



## Red Hat Virtualization 4.4

# Migrating from a standalone Manager to a self-hosted engine

How to migrate the Red Hat Virtualization Manager from a standalone server to a self-managed virtual machine



# Red Hat Virtualization 4.4 Migrating from a standalone Manager to a self-hosted engine

---

How to migrate the Red Hat Virtualization Manager from a standalone server to a self-managed virtual machine

Red Hat Virtualization Documentation Team  
Red Hat Customer Content Services  
rhev-docs@redhat.com

## Legal Notice

Copyright © 2022 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux<sup>®</sup> is the registered trademark of Linus Torvalds in the United States and other countries.

Java<sup>®</sup> is a registered trademark of Oracle and/or its affiliates.

XFS<sup>®</sup> is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL<sup>®</sup> is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js<sup>®</sup> is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack<sup>®</sup> Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## Abstract

This document describes how to migrate your Red Hat Virtualization environment from a Manager installed on a physical server (or a virtual machine running in a separate environment) to a Manager installed on a virtual machine running on the same hosts it manages.

---

## Table of Contents

<b>PREFACE</b> .....	<b>3</b>
STANDALONE MANAGER ARCHITECTURE	3
SELF-HOSTED ENGINE ARCHITECTURE	3
<b>CHAPTER 1. MIGRATION OVERVIEW</b> .....	<b>5</b>
<b>CHAPTER 2. INSTALLING THE SELF-HOSTED ENGINE DEPLOYMENT HOST</b> .....	<b>6</b>
2.1. INSTALLING RED HAT VIRTUALIZATION HOSTS	6
2.1.1. Enabling the Red Hat Virtualization Host Repository	8
2.2. INSTALLING RED HAT ENTERPRISE LINUX HOSTS	8
2.2.1. Enabling the Red Hat Enterprise Linux host Repositories	9
<b>CHAPTER 3. PREPARING STORAGE FOR RED HAT VIRTUALIZATION</b> .....	<b>12</b>
3.1. PREPARING NFS STORAGE	13
3.2. PREPARING ISCSI STORAGE	14
3.3. PREPARING FCP STORAGE	15
3.4. PREPARING RED HAT GLUSTER STORAGE	16
3.5. CUSTOMIZING MULTIPATH CONFIGURATIONS FOR SAN VENDORS	16
3.6. RECOMMENDED SETTINGS FOR MULTIPATH.CONF	17
<b>CHAPTER 4. UPDATING THE RED HAT VIRTUALIZATION MANAGER</b> .....	<b>19</b>
<b>CHAPTER 5. BACKING UP THE ORIGINAL MANAGER</b> .....	<b>21</b>
<b>CHAPTER 6. RESTORING THE BACKUP ON A NEW SELF-HOSTED ENGINE</b> .....	<b>22</b>
<b>CHAPTER 7. ENABLING THE RED HAT VIRTUALIZATION MANAGER REPOSITORIES</b> .....	<b>26</b>
<b>CHAPTER 8. REINSTALLING AN EXISTING HOST AS A SELF-HOSTED ENGINE NODE</b> .....	<b>28</b>
<b>APPENDIX A. PREVENTING KERNEL MODULES FROM LOADING AUTOMATICALLY</b> .....	<b>29</b>
A.1. REMOVING A MODULE TEMPORARILY	30
<b>APPENDIX B. LEGAL NOTICE</b> .....	<b>32</b>



## PREFACE

You can convert a standalone Red Hat Virtualization Manager to a self-hosted engine by backing up the standalone Manager and restoring it in a new self-hosted environment.

The difference between the two environment types is explained below:


### STANDALONE MANAGER ARCHITECTURE

The Red Hat Virtualization Manager runs on a physical server, or a virtual machine hosted in a separate virtualization environment. A standalone Manager is easier to deploy and manage, but requires an additional physical server. The Manager is only highly available when managed externally with a product such as Red Hat's High Availability Add-On.

The minimum setup for a standalone Manager environment includes:

- One Red Hat Virtualization Manager machine. The Manager is typically deployed on a physical server. However, it can also be deployed on a virtual machine, as long as that virtual machine is hosted in a separate environment. The Manager must run on Red Hat Enterprise Linux 8.
- A minimum of two hosts for virtual machine high availability. You can use Red Hat Enterprise Linux hosts or Red Hat Virtualization Hosts (RHVH). VDSM (the host agent) runs on all hosts to facilitate communication with the Red Hat Virtualization Manager.
- One storage service, which can be hosted locally or on a remote server, depending on the storage type used. The storage service must be accessible to all hosts.

**Figure 1. Standalone Manager Red Hat Virtualization Architecture**




### SELF-HOSTED ENGINE ARCHITECTURE

The Red Hat Virtualization Manager runs as a virtual machine on self-hosted engine nodes (specialized hosts) in the same environment it manages. A self-hosted engine environment requires one less physical server, but requires more administrative overhead to deploy and manage. The Manager is highly available without external HA management.

The minimum setup of a self-hosted engine environment includes:

- One Red Hat Virtualization Manager virtual machine that is hosted on the self-hosted engine nodes. The RHV-M Appliance is used to automate the installation of a Red Hat Enterprise Linux 8 virtual machine, and the Manager on that virtual machine.
- A minimum of two self-hosted engine nodes for virtual machine high availability. You can use Red Hat Enterprise Linux hosts or Red Hat Virtualization Hosts (RHVH). VDSM (the host agent) runs on all hosts to facilitate communication with the Red Hat Virtualization Manager. The HA services run on all self-hosted engine nodes to manage the high availability of the Manager virtual machine.
- One storage service, which can be hosted locally or on a remote server, depending on the storage type used. The storage service must be accessible to all hosts.

Figure 2. Self-Hosted Engine Red Hat Virtualization Architecture





## CHAPTER 1. MIGRATION OVERVIEW

When you specify a backup file during self-hosted engine deployment, the Manager backup is restored on a new virtual machine, with a dedicated self-hosted engine storage domain. Deploying on a fresh host is highly recommended; if the host used for deployment existed in the backed up environment, it will be removed from the restored database to avoid conflicts in the new environment. If you deploy on a new host, you must assign a unique name to the host. Reusing the name of an existing host included in the backup can cause conflicts in the new environment.

At least two self-hosted engine nodes are required for the Manager virtual machine to be highly available. You can add new nodes, or convert existing hosts.

The migration involves the following key steps:

1. [Install a new host to deploy the self-hosted engine on.](#) You can use either host type:
  - [Red Hat Virtualization Host](#)
  - [Red Hat Enterprise Linux](#)
2. [Prepare storage for the self-hosted engine storage domain.](#) You can use one of the following storage types:
  - [NFS](#)
  - [iSCSI](#)
  - [Fibre Channel \(FCP\)](#)
  - [Red Hat Gluster Storage](#)
3. [Update the original Manager to the latest minor version before you back it up.](#)
4. [Back up the original Manager using the `engine-backup` tool.](#)
5. [Deploy a new self-hosted engine and restore the backup.](#)
6. [Enable the Manager repositories on the new Manager virtual machine.](#)
7. [Convert regular hosts to self-hosted engine nodes that can host the new Manager.](#)


This procedure assumes that you have access and can make changes to the original Manager.

### Prerequisites

- FQDNs prepared for your Manager and the deployment host. Forward and reverse lookup records must both be set in the DNS. The new Manager must have the same FQDN as the original Manager.
- The management network (`ovirtmgmt` by default) must be configured as a **VM network**, so that it can manage the Manager virtual machine.

## CHAPTER 2. INSTALLING THE SELF-HOSTED ENGINE DEPLOYMENT HOST

A self-hosted engine can be deployed from a [Red Hat Virtualization Host](#) or a [Red Hat Enterprise Linux host](#).



### IMPORTANT

If you plan to use bonded interfaces for high availability or VLANs to separate different types of traffic (for example, for storage or management connections), you should configure them on the host before beginning the self-hosted engine deployment. See [Networking Recommendations](#) in the *Planning and Prerequisites Guide*.

### 2.1. INSTALLING RED HAT VIRTUALIZATION HOSTS

Red Hat Virtualization Host (RHVH) is a minimal operating system based on Red Hat Enterprise Linux that is designed to provide a simple method for setting up a physical machine to act as a hypervisor in a Red Hat Virtualization environment. The minimal operating system contains only the packages required for the machine to act as a hypervisor, and features a Cockpit web interface for monitoring the host and performing administrative tasks. See [Running Cockpit](#) for the minimum browser requirements.

RHVH supports NIST 800-53 partitioning requirements to improve security. RHVH uses a NIST 800-53 partition layout by default.

The host must meet the minimum [host requirements](#).



### WARNING

When installing or reinstalling the host's operating system, Red Hat strongly recommends that you first detach any existing non-OS storage that is attached to the host to avoid accidental initialization of these disks, and with that, potential data loss.


#### Procedure

1. Go to the [Get Started with Red Hat Virtualization](#) on the Red Hat Customer Portal and log in.
2. Click **Download Latest** to access the product download page.
3. Choose the appropriate **Hypervisor Image for RHV** from the list and click **Download Now**.
4. Start the machine on which you are installing RHVH, booting from the prepared installation media.
5. From the boot menu, select **Install RHVH 4.4** and press **Enter**.

**NOTE**

You can also press the **Tab** key to edit the kernel parameters. Kernel parameters must be separated by a space, and you can boot the system using the specified kernel parameters by pressing the **Enter** key. Press the **Esc** key to clear any changes to the kernel parameters and return to the boot menu.

6. Select a language, and click **Continue**.
7. Select a keyboard layout from the **Keyboard Layout** screen and click **Done**.
8. Select the device on which to install RHVH from the **Installation Destination** screen. Optionally, enable encryption. Click **Done**.

**IMPORTANT**

Use the **Automatically configure partitioning** option.

9. Select a time zone from the **Time & Date** screen and click **Done**.
10. Select a network from the **Network & Host Name** screen and click **Configure...** to configure the connection details.

**NOTE**

To use the connection every time the system boots, select the **Connect automatically with priority** check box. For more information, see [Configuring network and host name options](#) in the *Red Hat Enterprise Linux 8 Installation Guide*.


Enter a host name in the **Host Name** field, and click **Done**.

11. Optional: Configure **Security Policy** and **Kdump**. See [Customizing your RHEL installation using the GUI](#) in *Performing a standard RHEL installation* for Red Hat Enterprise Linux 8 for more information on each of the sections in the **Installation Summary** screen.
12. Click **Begin Installation**.
13. Set a root password and, optionally, create an additional user while RHVH installs.


**WARNING**

Do not create untrusted users on RHVH, as this can lead to exploitation of local security vulnerabilities.

14. Click **Reboot** to complete the installation.

**NOTE**

When RHVH restarts, **nodectl check** performs a health check on the host and displays the result when you log in on the command line. The message **node status: OK** or **node status: DEGRADED** indicates the health status. Run **nodectl check** to get more information.

**NOTE**

If necessary, you can [prevent kernel modules from loading automatically](#).

## 2.1.1. Enabling the Red Hat Virtualization Host Repository

Register the system to receive updates. Red Hat Virtualization Host only requires one repository. This section provides instructions for registering RHVH with the [Content Delivery Network](#), or with [Red Hat Satellite 6](#).

### Registering RHVH with the Content Delivery Network

1. Enable the **Red Hat Virtualization Host 8** repository to allow later updates to the Red Hat Virtualization Host:

```
# subscription-manager repos --enable=rhvh-4-for-rhel-8-x86_64-rpms
```

### Registering RHVH with Red Hat Satellite 6

1. Log in to the Cockpit web interface at **https://*HostFQDNorIP*:9090**.
2. Click **Terminal**.
3. Register RHVH with Red Hat Satellite 6:

```
# rpm -Uvh http://satellite.example.com/pub/katello-ca-consumer-latest.noarch.rpm
# subscription-manager register --org="org_id"
# subscription-manager list --available
# subscription-manager attach --pool=pool_id
# subscription-manager repos \
--disable='*' \
--enable=rhvh-4-for-rhel-8-x86_64-rpms
```

**NOTE**

You can also configure virtual machine subscriptions in Red Hat Satellite using `virt-who`. See [Using virt-who to manage host-based subscriptions](#).

## 2.2. INSTALLING RED HAT ENTERPRISE LINUX HOSTS

A Red Hat Enterprise Linux host is based on a standard basic installation of Red Hat Enterprise Linux 8 on a physical server, with the **Red Hat Enterprise Linux Server** and **Red Hat Virtualization** subscriptions attached.

For detailed installation instructions, see the [Performing a standard RHEL installation](#).

The host must meet the minimum [host requirements](#).



### WARNING

When installing or reinstalling the host's operating system, Red Hat strongly recommends that you first detach any existing non-OS storage that is attached to the host to avoid accidental initialization of these disks, and with that, potential data loss.



### IMPORTANT

Virtualization must be enabled in your host's BIOS settings. For information on changing your host's BIOS settings, refer to your host's hardware documentation.



### IMPORTANT

Do not install third-party watchdogs on Red Hat Enterprise Linux hosts. They can interfere with the watchdog daemon provided by VDSM.

## 2.2.1. Enabling the Red Hat Enterprise Linux host Repositories

To use a Red Hat Enterprise Linux machine as a host, you must register the system with the Content Delivery Network, attach the **Red Hat Enterprise Linux Server** and **Red Hat Virtualization** subscriptions, and enable the host repositories.

### Procedure

1. Register your system with the Content Delivery Network, entering your Customer Portal user name and password when prompted:


```
# subscription-manager register
```

2. Find the **Red Hat Enterprise Linux Server** and **Red Hat Virtualization** subscription pools and record the pool IDs:

```
# subscription-manager list --available
```

3. Use the pool IDs to attach the subscriptions to the system:

```
# subscription-manager attach --pool=poolid
```

**NOTE**

To view currently attached subscriptions:

```
# subscription-manager list --consumed
```

To list all enabled repositories:

```
# dnf repolist
```

## 4. Configure the repositories:

```
# subscription-manager repos \
  --disable='*' \
  --enable=rhel-8-for-x86_64-baseos-rpms \
  --enable=rhel-8-for-x86_64-appstream-rpms \
  --enable=rhv-4-mgmt-agent-for-rhel-8-x86_64-rpms \
  --enable=fast-datapath-for-rhel-8-x86_64-rpms \
  --enable=advanced-virt-for-rhel-8-x86_64-rpms \
  --enable=openstack-16.2-cinderlib-for-rhel-8-x86_64-rpms \
  --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms
```

5. Reset the **virt** module:

```
# dnf module reset virt
```

**NOTE**

If this module is already enabled in the Advanced Virtualization stream, this step is not necessary, but it has no negative impact.

You can see the value of the stream by entering:

```
# dnf module list virt
```

6. Enable the **virt** module in the Advanced Virtualization stream with the following command:

- For RHV 4.4.2:

```
# dnf module enable virt:8.2
```

- For RHV 4.4.3 to 4.4.5:

```
# dnf module enable virt:8.3
```

- For RHV 4.4.6 to 4.4.10:

```
# dnf module enable virt:av
```

- For RHV 4.4 and later:

```
# dnf module enable virt:rhel
```

**NOTE**

Starting with RHEL 8.6 the Advanced virtualization packages will use the standard **virt:rhel** module. For RHEL 8.4 and 8.5, only one Advanced Virtualization stream is used, **rhel:av**.

1. Ensure that all packages currently installed are up to date:

```
# dnf upgrade --nobest
```

2. Reboot the machine.

**NOTE**

If necessary, you can [prevent kernel modules from loading automatically](#).

Although the existing storage domains will be migrated from the standalone Manager, you must prepare additional storage for a self-hosted engine storage domain that is dedicated to the Manager virtual machine.

## CHAPTER 3. PREPARING STORAGE FOR RED HAT VIRTUALIZATION

You need to prepare storage to be used for storage domains in the new environment. A Red Hat Virtualization environment must have at least one data storage domain, but adding more is recommended.



### WARNING

When installing or reinstalling the host's operating system, Red Hat strongly recommends that you first detach any existing non-OS storage that is attached to the host to avoid accidental initialization of these disks, and with that, potential data loss.

A data domain holds the virtual hard disks and OVF files of all the virtual machines and templates in a data center, and cannot be shared across data centers while active (but can be migrated between data centers). Data domains of multiple storage types can be added to the same data center, provided they are all shared, rather than local, domains.

You can use one of the following storage types:

- [NFS](#)
- [iSCSI](#)
- [Fibre Channel \(FCP\)](#)
- [Red Hat Gluster Storage](#)

### Prerequisites

- Self-hosted engines must have an additional data domain with at least 74 GiB dedicated to the Manager virtual machine. The self-hosted engine installer creates this domain. Prepare the storage for this domain before installation.



### WARNING

Extending or otherwise changing the self-hosted engine storage domain after deployment of the self-hosted engine is not supported. Any such change might prevent the self-hosted engine from booting.

- When using a block storage domain, either FCP or iSCSI, a single target LUN is the only supported setup for a self-hosted engine.



- If you use iSCSI storage, the self-hosted engine storage domain must use a dedicated iSCSI target. Any additional storage domains must use a different iSCSI target.
- It is strongly recommended to create additional data storage domains in the same data center as the self-hosted engine storage domain. If you deploy the self-hosted engine in a data center with only one active data storage domain, and that storage domain is corrupted, you cannot add new storage domains or remove the corrupted storage domain. You must redeploy the self-hosted engine.

## 3.1. PREPARING NFS STORAGE

Set up NFS shares on your file storage or remote server to serve as storage domains on Red Hat Enterprise Virtualization Host systems. After exporting the shares on the remote storage and configuring them in the Red Hat Virtualization Manager, the shares will be automatically imported on the Red Hat Virtualization hosts.

For information on setting up, configuring, mounting and exporting NFS, see [Managing file systems](#) for Red Hat Enterprise Linux 8.

Specific system user accounts and system user groups are required by Red Hat Virtualization so the Manager can store data in the storage domains represented by the exported directories. The following procedure sets the permissions for one directory. You must repeat the **chown** and **chmod** steps for all of the directories you intend to use as storage domains in Red Hat Virtualization.

### Prerequisites

1. Install the NFS **utils** package.

```
# dnf install nfs-utils -y
```

2. To check the enabled versions:

```
# cat /proc/fs/nfsd/versions
```

3. Enable the following services:

```
# systemctl enable nfs-server  
# systemctl enable rpcbind
```

### Procedure

1. Create the group **kvm**:

```
# groupadd kvm -g 36
```

2. Create the user **vdsm** in the group **kvm**:

```
# useradd vdsm -u 36 -g kvm
```

3. Create the **storage** directory and modify the access rights.

```
# mkdir /storage
# chmod 0755 /storage
# chown 36:36 /storage/
```

4. Add the **storage** directory to **/etc/exports** with the relevant permissions.


```
# vi /etc/exports
# cat /etc/exports
/storage *(rw)
```

5. Restart the following services:

```
# systemctl restart rpcbind
# systemctl restart nfs-server
```

6. To see which export are available for a specific IP address:

```
# exportfs
/nfs_server/srv
      10.46.11.3/24
/nfs_server <world>
```




#### NOTE

If changes in **/etc/exports** have been made after starting the services, the **exportfs -ra** command can be used to reload the changes. After performing all the above stages, the exports directory should be ready and can be tested on a different host to check that it is usable.

## 3.2. PREPARING ISCSI STORAGE

Red Hat Virtualization supports iSCSI storage, which is a storage domain created from a volume group made up of LUNs. Volume groups and LUNs cannot be attached to more than one storage domain at a time.

For information on setting up and configuring iSCSI storage, see [Getting started with iSCSI](#) in *Managing storage devices* for Red Hat Enterprise Linux 8.



#### IMPORTANT

If you are using block storage and intend to deploy virtual machines on raw devices or direct LUNs and manage them with the Logical Volume Manager (LVM), you must create a filter to hide guest logical volumes. This will prevent guest logical volumes from being activated when the host is booted, a situation that could lead to stale logical volumes and cause data corruption. Use the **vdsm-tool config-lvm-filter** command to create filters for the LVM. See [Creating an LVM filter](#)



#### IMPORTANT

Red Hat Virtualization currently does not support block storage with a block size of 4K. You must configure block storage in legacy (512b block) mode.

 **IMPORTANT**

If your host is booting from SAN storage and loses connectivity to the storage, the storage file systems become read-only and remain in this state after connectivity is restored.

To prevent this situation, add a drop-in multipath configuration file on the root file system of the SAN for the boot LUN to ensure that it is queued when there is a connection:

```
# cat /etc/multipath/conf.d/host.conf
multipaths {
  multipath {
    wwid boot_LUN_wwid
    no_path_retry queue
  }
}
```

### 3.3. PREPARING FCP STORAGE

Red Hat Virtualization supports SAN storage by creating a storage domain from a volume group made of pre-existing LUNs. Neither volume groups nor LUNs can be attached to more than one storage domain at a time.

Red Hat Virtualization system administrators need a working knowledge of Storage Area Networks (SAN) concepts. SAN usually uses Fibre Channel Protocol (FCP) for traffic between hosts and shared external storage. For this reason, SAN may occasionally be referred to as FCP storage.


For information on setting up and configuring FCP or multipathing on Red Hat Enterprise Linux, see the [Storage Administration Guide](#) and [DM Multipath Guide](#).

 **IMPORTANT**

If you are using block storage and intend to deploy virtual machines on raw devices or direct LUNs and manage them with the Logical Volume Manager (LVM), you must create a filter to hide guest logical volumes. This will prevent guest logical volumes from being activated when the host is booted, a situation that could lead to stale logical volumes and cause data corruption. Use the **vdsm-tool config-lvm-filter** command to create filters for the LVM. See [Creating an LVM filter](#)

 **IMPORTANT**

Red Hat Virtualization currently does not support block storage with a block size of 4K. You must configure block storage in legacy (512b block) mode.



## IMPORTANT

If your host is booting from SAN storage and loses connectivity to the storage, the storage file systems become read-only and remain in this state after connectivity is restored.

To prevent this situation, add a drop-in multipath configuration file on the root file system of the SAN for the boot LUN to ensure that it is queued when there is a connection:

```
# cat /etc/multipath/conf.d/host.conf
multipaths {
  multipath {
    wwid boot_LUN_wwid
    no_path_retry queue
  }
}
```

## 3.4. PREPARING RED HAT GLUSTER STORAGE

For information on setting up and configuring Red Hat Gluster Storage, see the [Red Hat Gluster Storage Installation Guide](#).

For the Red Hat Gluster Storage versions that are supported with Red Hat Virtualization, see [Red Hat Gluster Storage Version Compatibility and Support](#).

## 3.5. CUSTOMIZING MULTIPATH CONFIGURATIONS FOR SAN VENDORS

If your RHV environment is configured to use multipath connections with SANs, you can customize the multipath configuration settings to meet requirements specified by your storage vendor. These customizations can override both the default settings and settings that are specified in **/etc/multipath.conf**.

To override the multipath settings, do not customize **/etc/multipath.conf**. Because VDSM owns **/etc/multipath.conf**, installing or upgrading VDSM or Red Hat Virtualization can overwrite this file including any customizations it contains. This overwriting can cause severe storage failures.

Instead, you create a file in the **/etc/multipath/conf.d** directory that contains the settings you want to customize or override.

VDSM executes the files in **/etc/multipath/conf.d** in alphabetical order. So, to control the order of execution, you begin the filename with a number that makes it come last. For example, **/etc/multipath/conf.d/90-myfile.conf**.

To avoid causing severe storage failures, follow these guidelines:

- Do not modify **/etc/multipath.conf**. If the file contains user modifications, and the file is overwritten, it can cause unexpected storage problems.

**WARNING**

Not following these guidelines can cause catastrophic storage errors.

**Prerequisites**


- VDSM is configured to use the multipath module. To verify this, enter:

```
# vdsmd-tool is-configured --module multipath
```

**Procedure**

1. Create a new configuration file in the **/etc/multipath/conf.d** directory.
2. Copy the individual setting you want to override from **/etc/multipath.conf** to the new configuration file in **/etc/multipath/conf.d/<my\_device>.conf**. Remove any comment marks, edit the setting values, and save your changes.
3. Apply the new configuration settings by entering:

```
# systemctl reload multipathd
```

**NOTE**

Do not restart the multipathd service. Doing so generates errors in the VDSM logs.

**Verification steps**

1. Test that the new configuration performs as expected on a non-production cluster in a variety of failure scenarios. For example, disable all of the storage connections.
2. Enable one connection at a time and verify that doing so makes the storage domain reachable.

**Additional resources**

- [Recommended Settings for Multipath.conf](#)
- [Red Hat Enterprise Linux DM Multipath](#)
- [Configuring iSCSI Multipathing](#)
- [How do I customize /etc/multipath.conf on my RHVH hypervisors? What values must not change and why?](#)

**3.6. RECOMMENDED SETTINGS FOR MULTIPATH.CONF**

Do not override the following settings:

**user\_friendly\_names no**

Device names must be consistent across all hypervisors. For example, `/dev/mapper/{WWID}`. The default value of this setting, **no**, prevents the assignment of arbitrary and inconsistent device names such as `/dev/mapper/mpath{N}` on various hypervisors, which can lead to unpredictable system behavior.

**WARNING**

Do not change this setting to **user\_friendly\_names yes**. User-friendly names are likely to cause unpredictable system behavior or failures, and are not supported.

**find\_multipaths no**

This setting controls whether RHVH tries to access devices through multipath only if more than one path is available. The current value, **no**, allows RHV to access devices through multipath even if only one path is available.

**WARNING**

Do not override this setting.

Avoid overriding the following settings unless required by the storage system vendor:

**no\_path\_retry 4**

This setting controls the number of polling attempts to retry when no paths are available. Before RHV version 4.2, the value of **no\_path\_retry** was **fail** because QEMU had trouble with the I/O queuing when no paths were available. The **fail** value made it fail quickly and paused the virtual machine. RHV version 4.2 changed this value to **4** so when multipathd detects the last path has failed, it checks all of the paths four more times. Assuming the default 5-second polling interval, checking the paths takes 20 seconds. If no path is up, multipathd tells the kernel to stop queuing and fails all outstanding and future I/O until a path is restored. When a path is restored, the 20-second delay is reset for the next time all paths fail. For more details, see [the commit that changed this setting](#).

**polling\_interval 5**

This setting determines the number of seconds between polling attempts to detect whether a path is open or has failed. Unless the vendor provides a clear reason for increasing the value, keep the VDSM-generated default so the system responds to path failures sooner.

Before backing up the Manager, ensure it is updated to the latest minor version. The Manager version in the backup file must match the version of the new Manager.

# CHAPTER 4. UPDATING THE RED HAT VIRTUALIZATION MANAGER

## Prerequisites

- The data center compatibility level must be set to the latest version to ensure compatibility with the updated storage version.

## Procedure

1. On the Manager machine, check if updated packages are available:

```
# engine-upgrade-check
```

2. Update the setup packages:

```
# yum update ovirt\*setup\* rh\*vm-setup-plugins
```

3. Update the Red Hat Virtualization Manager with the **engine-setup** script. The **engine-setup** script prompts you with some configuration questions, then stops the **ovirt-engine** service, downloads and installs the updated packages, backs up and updates the database, performs post-installation configuration, and starts the **ovirt-engine** service.

```
# engine-setup
```

When the script completes successfully, the following message appears:

```
Execution of setup completed successfully
```



### NOTE

The **engine-setup** script is also used during the Red Hat Virtualization Manager installation process, and it stores the configuration values supplied. During an update, the stored values are displayed when previewing the configuration, and might not be up to date if **engine-config** was used to update configuration after installation. For example, if **engine-config** was used to update **SANWipeAfterDelete** to **true** after installation, **engine-setup** will output "Default SAN wipe after delete: False" in the configuration preview. However, the updated values will not be overwritten by **engine-setup**.



### IMPORTANT

The update process might take some time. Do not stop the process before it completes.

4. Update the base operating system and any optional packages installed on the Manager:

```
# yum update --nobest
```



**IMPORTANT**

If you encounter a required Ansible package conflict during the update, see [Cannot perform yum update on my RHV manager \(ansible conflict\)](#) .



**IMPORTANT**

If any kernel packages were updated, reboot the machine to complete the update.



## CHAPTER 5. BACKING UP THE ORIGINAL MANAGER

Back up the original Manager using the **engine-backup** command, and copy the backup file to a separate location so that it can be accessed at any point during the process.

For more information about **engine-backup --mode=backup** options, see [Backing Up and Restoring the Red Hat Virtualization Manager](#) in the *Administration Guide*.

### Procedure

1. Log in to the original Manager and stop the **ovirt-engine** service:

```
# systemctl stop ovirt-engine
# systemctl disable ovirt-engine
```



### NOTE

Though stopping the original Manager from running is not obligatory, it is recommended as it ensures no changes are made to the environment after the backup is created. Additionally, it prevents the original Manager and the new Manager from simultaneously managing existing resources.

2. Run the **engine-backup** command, specifying the name of the backup file to create, and the name of the log file to create to store the backup log:

```
# engine-backup --mode=backup --file=file_name --log=log_file_name
```

3. Copy the files to an external server. In the following example, **storage.example.com** is the fully qualified domain name of a network storage server that will store the backup until it is needed, and **/backup/** is any designated folder or path.

```
# scp -p file_name log_file_name storage.example.com:/backup/
```

4. If you do not require the Manager machine for other purposes, unregister it from Red Hat Subscription Manager:

```
# subscription-manager unregister
```

After backing up the Manager, deploy a new self-hosted engine and restore the backup on the new virtual machine.

## CHAPTER 6. RESTORING THE BACKUP ON A NEW SELF-HOSTED ENGINE

Run the **hosted-engine** script on a new host, and use the **--restore-from-file=***path/to/file\_name* option to restore the Manager backup during the deployment.

### IMPORTANT

If you are using iSCSI storage, and your iSCSI target filters connections according to the initiator's ACL, the deployment may fail with a **STORAGE\_DOMAIN\_UNREACHABLE** error. To prevent this, you must update your iSCSI configuration before beginning the self-hosted engine deployment:

- If you are redeploying on an existing host, you must update the host's iSCSI initiator settings in **/etc/iscsi/initiatorname.iscsi**. The initiator IQN must be the same as was previously mapped on the iSCSI target, or updated to a new IQN, if applicable.
- If you are deploying on a fresh host, you must update the iSCSI target configuration to accept connections from that host.

Note that the IQN can be updated on the host side (iSCSI initiator), or on the storage side (iSCSI target).

### Procedure

1. Copy the backup file to the new host. In the following example, **host.example.com** is the FQDN for the host, and **/backup/** is any designated folder or path.

```
# scp -p file_name host.example.com:/backup/
```

2. Log in to the new host.
3. If you are deploying on Red Hat Virtualization Host, **ovirt-hosted-engine-setup** is already installed, so skip this step. If you are deploying on Red Hat Enterprise Linux, install the **ovirt-hosted-engine-setup** package:

```
# dnf install ovirt-hosted-engine-setup
```

4. Use the **tmux** window manager to run the script to avoid losing the session in case of network or terminal disruption.  
Install and run **tmux**:

```
# dnf -y install tmux
# tmux
```

5. Run the **hosted-engine** script, specifying the path to the backup file:

```
# hosted-engine --deploy --restore-from-file=backup/file_name
```

To escape the script at any time, use **CTRL+D** to abort deployment.

6. Select **Yes** to begin the deployment.

7. Configure the network. The script detects possible NICs to use as a management bridge for the environment.
8. If you want to use a custom appliance for the virtual machine installation, enter the path to the OVA archive. Otherwise, leave this field empty to use the RHV-M Appliance.
9. Enter the root password for the Manager.
10. Enter an SSH public key that will allow you to log in to the Manager as the root user, and specify whether to enable SSH access for the root user.
11. Enter the virtual machine's CPU and memory configuration.



#### NOTE

The virtual machine must have the same amount of RAM as the physical machine from which the Manager is being migrated. If you must migrate to a virtual machine that has less RAM than the physical machine from which the Manager is migrated, see [Configuring the amount of RAM in Red Hat Virtualization Hosted Engine](#).

12. Enter a MAC address for the Manager virtual machine, or accept a randomly generated one. If you want to provide the Manager virtual machine with an IP address via DHCP, ensure that you have a valid DHCP reservation for this MAC address. The deployment script will not configure the DHCP server for you.
13. Enter the virtual machine's networking details. If you specify **Static**, enter the IP address of the Manager.



#### IMPORTANT

The static IP address must belong to the same subnet as the host. For example, if the host is in 10.1.1.0/24, the Manager virtual machine's IP must be in the same subnet range (10.1.1.1-254/24).

14. Specify whether to add entries for the Manager virtual machine and the base host to the virtual machine's **/etc/hosts** file. You must ensure that the host names are resolvable.
15. Provide the name and TCP port number of the SMTP server, the email address used to send email notifications, and a comma-separated list of email addresses to receive these notifications:
16. Enter a password for the **admin@internal** user to access the Administration Portal. The script creates the virtual machine. This can take some time if the RHV-M Appliance needs to be installed.



## NOTE

If the host becomes non operational, due to a missing required network or a similar problem, the deployment pauses and a message such as the following is displayed:

```
[ INFO ] You can now connect to https://<host name>:6900/ovirt-engine/ and
check the status of this host and eventually remediate it, please continue only
when the host is listed as 'up'
[ INFO ] TASK [ovirt.ovirt.hosted_engine_setup : include_tasks]
[ INFO ] ok: [localhost]
[ INFO ] TASK [ovirt.ovirt.hosted_engine_setup : Create temporary lock file]
[ INFO ] changed: [localhost]
[ INFO ] TASK [ovirt.ovirt.hosted_engine_setup : Pause execution until
/tmp/ansible.<random>_he_setup_lock is removed, delete it once ready to
proceed]
```

Pausing the process allows you to:

- Connect to the Administration Portal using the provided URL.
- Assess the situation, find out why the host is non operational, and fix whatever is needed. For example, if this deployment was restored from a backup, and the backup included *required networks* for the host cluster, configure the networks, attaching the relevant host NICs to these networks.
- Once everything looks OK, and the host status is *Up*, remove the lock file presented in the message above. The deployment continues.

17. Select the type of storage to use:

- For NFS, enter the version, full address and path to the storage, and any mount options.
- For iSCSI, enter the portal details and select a target and LUN from the auto-detected lists. You can only select one iSCSI target during the deployment, but multipathing is supported to connect all portals of the same portal group.



## NOTE

To specify more than one iSCSI target, you must enable multipathing before deploying the self-hosted engine. See [Red Hat Enterprise Linux DM Multipath](#) for details. There is also a [Multipath Helper](#) tool that generates a script to install and configure multipath with different options.

- For Gluster storage, enter the full address and path to the storage, and any mount options.



## IMPORTANT

Only replica 1 and replica 3 Gluster storage are supported. Ensure you configure the volume as follows:

```
gluster volume set VOLUME_NAME group virt
gluster volume set VOLUME_NAME performance.strict-o-direct on
gluster volume set VOLUME_NAME network.remote-dio off
gluster volume set VOLUME_NAME storage.owner-uid 36
gluster volume set VOLUME_NAME storage.owner-gid 36
gluster volume set VOLUME_NAME network.ping-timeout 30
```

- For Fibre Channel, select a LUN from the auto-detected list. The host bus adapters must be configured and connected, and the LUN must not contain any existing data. To reuse an existing LUN, see [Reusing LUNs](#) in the *Administration Guide*.
18. Enter the Manager disk size.  
The script continues until the deployment is complete.
  19. The deployment process changes the Manager's SSH keys. To allow client machines to access the new Manager without SSH errors, remove the original Manager's entry from the **.ssh/known\_hosts** file on any client machines that accessed the original Manager.

When the deployment is complete, log in to the new Manager virtual machine and enable the required repositories.

## CHAPTER 7. ENABLING THE RED HAT VIRTUALIZATION MANAGER REPOSITORIES

You need to log in and register the Manager machine with Red Hat Subscription Manager, attach the **Red Hat Virtualization Manager** subscription, and enable the Manager repositories.

### Procedure

1. Register your system with the Content Delivery Network, entering your Customer Portal user name and password when prompted:

```
# subscription-manager register
```



#### NOTE

If you are using an IPv6 network, use an IPv6 transition mechanism to access the Content Delivery Network and subscription manager.

2. Find the **Red Hat Virtualization Manager** subscription pool and record the pool ID:

```
# subscription-manager list --available
```

3. Use the pool ID to attach the subscription to the system:

```
# subscription-manager attach --pool=pool_id
```



#### NOTE

To view currently attached subscriptions:

```
# subscription-manager list --consumed
```

To list all enabled repositories:

```
# dnf repolist
```

4. Configure the repositories:

```
# subscription-manager repos \
  --disable='*' \
  --enable=rhel-8-for-x86_64-baseos-rpms \
  --enable=rhel-8-for-x86_64-appstream-rpms \
  --enable=rhv-4.4-manager-for-rhel-8-x86_64-rpms \
  --enable=fast-datapath-for-rhel-8-x86_64-rpms \
  --enable=jb-eap-7.4-for-rhel-8-x86_64-rpms \
  --enable=openstack-16.2-cinderlib-for-rhel-8-x86_64-rpms \
  --enable=rhceph-4-tools-for-rhel-8-x86_64-rpms
```

5. Enable the **pki-deps** module.

```
# dnf module -y enable pki-deps
```

6. Enable version 12 of the **postgresql** module.

```
# dnf module -y enable postgresql:12
```

7. Enable version 14 of the **nodejs** module:

```
# dnf module -y enable nodejs:14
```

8. Synchronize installed packages to update them to the latest available versions.

```
# dnf distro-sync --nobest
```

### Additional resources

For information on modules and module streams, see the following sections in *Installing, managing, and removing user-space components*

- [Module streams](#)
- [Selecting a stream before installation of packages](#)
- [Resetting module streams](#)
- [Switching to a later stream](#)

The Red Hat Virtualization Manager has been migrated to a self-hosted engine setup. The Manager is now operating on a virtual machine on the new self-hosted engine node.

The hosts will be running in the new environment, but cannot host the Manager virtual machine. You can convert some or all of these hosts to self-hosted engine nodes.

## CHAPTER 8. REINSTALLING AN EXISTING HOST AS A SELF-HOSTED ENGINE NODE

You can convert an existing, standard host in a self-hosted engine environment to a self-hosted engine node capable of hosting the Manager virtual machine.



### WARNING

When installing or reinstalling the host's operating system, Red Hat strongly recommends that you first detach any existing non-OS storage that is attached to the host to avoid accidental initialization of these disks, and with that, potential data loss.

### Procedure

1. Click **Compute** → **Hosts** and select the host.
2. Click **Management** → **Maintenance** and **OK**.
3. Click **Installation** → **Reinstall**.
4. Click the **Hosted Engine** tab and select **DEPLOY** from the drop-down list.
5. Click **OK**.

The host is reinstalled with self-hosted engine configuration, and is flagged with a crown icon in the Administration Portal.

After reinstalling the hosts as self-hosted engine nodes, you can check the status of the new environment by running the following command on one of the nodes:

```
# hosted-engine --vm-status
```

If the new environment is running without issue, you can decommission the original Manager machine.



## APPENDIX A. PREVENTING KERNEL MODULES FROM LOADING AUTOMATICALLY

You can prevent a kernel module from being loaded automatically, whether the module is loaded directly, loaded as a dependency from another module, or during the boot process.

### Procedure

1. The module name must be added to a configuration file for the **modprobe** utility. This file must reside in the configuration directory **/etc/modprobe.d**.  
For more information on this configuration directory, see the man page **modprobe.d**.

2. Ensure the module is not configured to get loaded in any of the following:

- **/etc/modprobe.conf**
- **/etc/modprobe.d/\***
- **/etc/rc.modules**
- **/etc/sysconfig/modules/\***

```
# modprobe --showconfig <_configuration_file_name_>
```

3. If the module appears in the output, ensure it is ignored and not loaded:

```
# modprobe --ignore-install <_module_name_>
```

4. Unload the module from the running system, if it is loaded:

```
# modprobe -r <_module_name_>
```

5. Prevent the module from being loaded directly by adding the **blacklist** line to a configuration file specific to the system - for example **/etc/modprobe.d/local-dontload.conf**:

```
# echo "blacklist <_module_name_>" >> /etc/modprobe.d/local-dontload.conf
```



### NOTE

This step does not prevent a module from loading if it is a required or an optional dependency of another module.

6. Prevent optional modules from being loading on demand:

```
# echo "install <_module_name_>/bin/false" >> /etc/modprobe.d/local-dontload.conf
```



### IMPORTANT

If the excluded module is required for other hardware, excluding it might cause unexpected side effects.

7. Make a backup copy of your **initramfs**:

```
# cp /boot/initramfs-$(uname -r).img /boot/initramfs-$(uname -r).img.$(date +%m-%d-%H%M%S).bak
```

8. If the kernel module is part of the **initramfs**, rebuild your initial **ramdisk** image, omitting the module:

```
# dracut --omit-drivers <_module_name_> -f
```

9. Get the current kernel command line parameters:

```
# grub2-editenv - list | grep kernelopts
```

10. Append **<\_module\_name\_>.blacklist=1 rd.driver.blacklist=<\_module\_name\_>** to the generated output:

```
# grub2-editenv - set kernelopts="<> <_module_name_>.blacklist=1 rd.driver.blacklist=<_module_name_>"
```

For example:

```
# grub2-editenv - set kernelopts="root=/dev/mapper/rhel_example-root ro crashkernel=auto resume=/dev/mapper/rhel_example-swap rd.lvm.lv=rhel_example/root rd.lvm.lv=rhel_example/swap <_module_name_>.blacklist=1 rd.driver.blacklist=<_module_name_>"
```

11. Make a backup copy of the **kdump initramfs**:

```
# cp /boot/initramfs-$(uname -r)kdump.img /boot/initramfs-$(uname -r)kdump.img.$(date +%m-%d-%H%M%S).bak
```

12. Append **rd.driver.blacklist=<\_module\_name\_>** to the **KDUMP\_COMMANDLINE\_APPEND** setting in **/etc/sysconfig/kdump** to omit it from the **kdump initramfs**:

```
# sed -i '/^KDUMP_COMMANDLINE_APPEND=/s/"$/ rd.driver.blacklist=module_name"/ /etc/sysconfig/kdump
```

13. Restart the **kdump** service to pick up the changes to the **kdump initrd**:

```
# kdumpctl restart
```

14. Rebuild the **kdump** initial **ramdisk** image:

```
# mkdumprd -f /boot/initramfs-$(uname -r)kdump.img
```

15. Reboot the system.

## A.1. REMOVING A MODULE TEMPORARILY

You can remove a module temporarily.

## Procedure

1. Run **modprobe** to remove any currently-loaded module:

```
# modprobe -r <module name>
```

2. If the module cannot be unloaded, a process or another module might still be using the module. If so, terminate the process and run the **modprobe** command written above another time to unload the module.

## APPENDIX B. LEGAL NOTICE

Copyright © 2022 Red Hat, Inc.

Licensed under the ([Creative Commons Attribution–ShareAlike 4.0 International License](#)). Derived from documentation for the ([oVirt Project](#)). If you distribute this document or an adaptation of it, you must provide the URL for the original version.

Modified versions must remove all Red Hat trademarks.

Red Hat, Red Hat Enterprise Linux, the Red Hat logo, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux® is the registered trademark of Linus Torvalds in the United States and other countries.

Java® is a registered trademark of Oracle and/or its affiliates.

XFS® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.