



Red Hat OpenStack Platform

11

Overcloud Parameters

Parameters for customizing the core template collection for a Red Hat OpenStack Platform overcloud

OpenStack Team

Red Hat OpenStack Platform 11 Overcloud Parameters

Parameters for customizing the core template collection for a Red Hat OpenStack Platform overcloud

OpenStack Team
rhos-docs@redhat.com

Legal Notice

Copyright © 2017 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This guide provides parameters for customizing the overcloud in Red Hat OpenStack Platform. Use this guide in conjunction with the Advanced Overcloud Customization guide.

Table of Contents

CHAPTER 1. CORE OVERCLOUD PARAMETERS	3
CHAPTER 2. ROLE-BASED PARAMETERS	6
CHAPTER 3. CEPH STORAGE PARAMETERS	7
CHAPTER 4. CEPH RADOSGW PARAMETERS	9
CHAPTER 5. BLOCK STORAGE (CINDER) PARAMETERS	10
CHAPTER 6. IMAGE STORAGE (GLANCE) PARAMETERS	12
CHAPTER 7. ORCHESTRATION (HEAT) PARAMETERS	13
CHAPTER 8. DASHBOARD (HORIZON) PARAMETERS	15
CHAPTER 9. BARE METAL (IRONIC) PARAMETERS	16
CHAPTER 10. IDENTITY (KEYSTONE) PARAMETERS	17
CHAPTER 11. SHARED FILE SERVICE (MANILA) PARAMETERS	20
CHAPTER 12. NETWORKING (NEUTRON) PARAMETERS	21
CHAPTER 13. COMPUTE (NOVA) PARAMETERS	25
CHAPTER 14. CLUSTERING (SAHARA) PARAMETERS	28
CHAPTER 15. OBJECT STORAGE (SWIFT) PARAMETERS	29
CHAPTER 16. TELEMETRY (CEILOMETER, GNOCCHI, AODH) PARAMETERS	31
CHAPTER 17. TIME PARAMETERS	33

CHAPTER 1. CORE OVERCLOUD PARAMETERS

Parameter	Description
AddVipsToEtcHosts	Set to true to append per network VIPs to /etc/hosts on each node. The default value is: True
CloudDomain	The DNS domain used for the hosts. This should match the dhcp_domain configured in the undercloud. The default value is: localdomain
CloudName	The DNS name of this cloud. The default value is: overcloud.localdomain
CloudNameCtlplane	The DNS name of this cloud's storage management endpoint. The default value is: overcloud.ctlplane.localdomain
CloudNameInternal	The DNS name of this cloud's internal API endpoint. The default value is: overcloud.internalapi.localdomain
CloudNameStorage	The DNS name of this cloud's storage endpoint. E.g. <i>ci-overcloud.storage.tripleo.org</i> . The default value is: overcloud.storage.localdomain
CloudNameStorageManagement	The DNS name of this cloud's storage management endpoint. The default value is: overcloud.storagemgmt.localdomain
ControlFixedIPs	Defines a fixed VIP for the Control Plane. Value uses the following format: [{ip_address:'1.2.3.4'}]
DeployIdentifier	Setting this to a unique value will re-run any deployment tasks that perform configuration on a Heat stack-update .

Parameter	Description
HypervisorNeutronPhysicalBridge	An Open vSwitch bridge to create on each hypervisor. This defaults to br-ex , which is the same as the control plane nodes. This ensures uniform configuration of the Open vSwitch agent. Typically should not need to be changed. The default value is: br-ex
HypervisorNeutronPublicInterface	What interface to add to the HypervisorNeutronPhysicalBridge . The default value is: nic1
InternalApiVirtualFixedIPs	Control the IP allocation for the InternalApiVirtualInterface port. Value uses the following format: [{ip_address:'1.2.3.4'}]
NeutronControlPlaneID	ID or name for Control Plane ctlplane network. The default value is: ctlplane
NeutronPublicInterface	The interface to bridge onto the external bridge for network nodes. The default value is: nic1
PublicVirtualFixedIPs	Control the IP allocation for the PublicVirtualInterface port. Value uses the following format: [{ip_address:'1.2.3.4'}]
RabbitCookieSalt	Salt for the RabbitMQ cookie. Change to force the randomly generated RabbitMQ cookie to change. The default value is: unset
RedisVirtualFixedIPs	Control the IP allocation for the virtual IP used by Redis. Value uses the following format: [{ip_address:'1.2.3.4'}]
ServerMetadata	Extra properties or metadata passed to Nova for the created nodes in the overcloud. Accessible through the Nova metadata API.

Parameter	Description
StorageMgmtVirtualFixedIPs	Control the IP allocation for the StorageMgmtVirtualInterface port. Value uses the following format: [{ip_address: '1.2.3.4'}]
StorageVirtualFixedIPs	Control the IP allocation for the StorageVirtualInterface port. Value uses the following format: [{ip_address: '1.2.3.4'}]
UpdateIdentifier	Set to a previously unused value during stack-update triggers package update on all nodes.

CHAPTER 2. ROLE-BASED PARAMETERS

Substitute **_ROLE_** with the name of the role. For example, for **_ROLE_Count** use **ControllerCount**.

Parameter	Description
_ROLE_Count	The number of nodes to deploy in a role.
_ROLE_HostnameFormat	Format for node hostnames. Note that %index% is translated into the index of the node (e.g 0/1/2) and %stackname% is replaced with the stack name (e.g overcloud). The default value is: %stackname%-_ROLE_-%index%
_ROLE_RemovalPolicies	List of resources to be removed from the role's ResourceGroup when doing an update that requires removal of specific resources.
_ROLE_SchedulerHints	Optional scheduler hints to pass to OpenStack Compute (nova).
_ROLE_Services	A list of service resources (configured in the Heat resource_registry) which represent nested stacks for each service that should get installed on the <i>ROLE</i> role.

CHAPTER 3. CEPH STORAGE PARAMETERS

Parameter	Description
CephAdminKey	The Ceph admin client key. Can be created with: ceph-authtool --gen-print-key
CephClientKey	The Ceph client key. Currently only used for external Ceph deployments to create the openstack user keyring. Can be created with: ceph-authtool --gen-print-key
CephClusterFSID	The Ceph cluster FSID. Must be a UUID.
CephIPv6	Enables Ceph daemons to bind to IPv6 addresses. The default is: false
CephMonKey	The Ceph monitors key. Can be created with: ceph-authtool --gen-print-key
CephPools	Override settings for one of the predefined pools or to create additional ones. Example: { "volumes": { "size": 5, "pg_num": 128, "pgp_num": 128 } }
CephValidationDelay	Interval (in seconds) in between validation checks. The default value is: 30
CephValidationRetries	Number of retry attempts for Ceph validation. The default value is: 40
CinderBackupRbdPoolName	Pool to use if Block Storage (cinder) Backup is enabled. The default is: backups
CinderRbdPoolName	Pool to use for Block Storage (cinder) service. The default is: volumes

Parameter	Description
ControllerEnableCephStorage	Whether to deploy Ceph Storage (OSD) on the Controller. The default value is: False
GlanceBackend	The short name of the Glance backend to use. Set to rbd to use Ceph Storage.
GlanceRbdPoolName	Pool to use for Image Storage (glance) service. The default is: images
GnocchiRbdPoolName	Pool to use for Telemetry storage. The default is: metrics
IgnoreCephUpgradeWarnings	If enabled, Ceph upgrade will be forced even though cluster or PGs status is not clean. The default value is: False
ManilaCephFSDataPoolName	Pool to use for file share storage. The default is: manila_data
ManilaCephFSMetadataPoolName	Pool to use for file share metadata storage. The default is: manila_metadata
NovaEnableRbdBackend	Whether to enable the Ceph backend for Compute (nova). The default value is: False
NovaRbdPoolName	Pool to use for Compute storage. The default is: vms

CHAPTER 4. CEPH RADOSGW PARAMETERS

Parameter	Description
CephRgwKey	The cephx key for the radosgw client. Can be created with: ceph-authtool --gen-print-key

CHAPTER 5. BLOCK STORAGE (CINDER) PARAMETERS

Parameter	Description
CinderCronDbPurgeAge	Cron to move deleted instances to another table - Age. The default value is: 0
CinderCronDbPurgeDestination	Cron to move deleted instances to another table - Log destination. The default value is: /var/log/cinder/cinder-rowsflush.log
CinderCronDbPurgeHour	Cron to move deleted instances to another table - Hour. The default value is: 0
CinderCronDbPurgeMinute	Cron to move deleted instances to another table - Minute. The default value is: 1
CinderCronDbPurgeMonth	Cron to move deleted instances to another table - Month. The default value is: *
CinderCronDbPurgeMonthday	Cron to move deleted instances to another table - Month Day. The default value is: *
CinderCronDbPurgeUser	Cron to move deleted instances to another table - User. The default value is: keystone
CinderCronDbPurgeWeekday	Cron to move deleted instances to another table - Week Day. The default value is: *
CinderEnableDBPurge	Whether to create cron job for purging soft deleted rows in Cinder database. The default value is: True
CinderPassword	The password for the cinder service account, used by cinder-api.

Parameter	Description
CinderWorkers	Set the number of workers for the block storage service. The default value is equal to the number of CPU cores on the node. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.

CHAPTER 6. IMAGE STORAGE (GLANCE) PARAMETERS

Parameter	Description
GlanceBackend	The short name of the backend to use. Should be one of swift , rbd , or file . The default value is: swift
GlanceLogFile	The filepath of the file to use for logging messages from Glance.
GlanceNfsEnabled	When using GlanceBackend: file , mount NFS share for image storage. The default value is: False
GlanceNfsOptions	NFS mount options for image storage when GlanceNfsEnabled is true. The default value is: intr,context=system_u:object_r:glance_var_lib_t:s0
GlanceNfsShare	NFS share to mount for image storage when GlanceNfsEnabled is true.
GlanceNotifierStrategy	Strategy to use for Glance notification queue. The default value is: noop
GlancePassword	The password for the image storage service and database account.
GlanceWorkers	Set the number of workers for the image storage service. The default value is equal to the number of CPU cores on the node. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.

CHAPTER 7. ORCHESTRATION (HEAT) PARAMETERS

Parameter	Description
HeatAuthEncryptionKey	Auth encryption key for heat-engine.
HeatConvergenceEngine	Enables the heat engine with the convergence architecture. The default value is: True
HeatCronPurgeDeletedAge	Cron to purge db entries marked as deleted and older than \$age - Age. The default value is: 30
HeatCronPurgeDeletedAgeType	Cron to purge db entries marked as deleted and older than \$age - Age type. The default value is: days
HeatCronPurgeDeletedDestination	Cron to purge db entries marked as deleted and older than \$age - Log destination. The default value is: /dev/null
HeatCronPurgeDeletedEnsure	Cron to purge db entries marked as deleted and older than \$age - Ensure. The default value is: present
HeatCronPurgeDeletedHour	Cron to purge db entries marked as deleted and older than \$age - Hour. The default value is: 0
HeatCronPurgeDeletedMaxDelay	Cron to purge db entries marked as deleted and older than \$age - Max Delay. The default value is: 3600
HeatCronPurgeDeletedMinute	Cron to purge db entries marked as deleted and older than \$age - Minute. The default value is: 1
HeatCronPurgeDeletedMonth	Cron to purge db entries marked as deleted and older than \$age - Month. The default value is: *

Parameter	Description
HeatCronPurgeDeletedMonthday	Cron to purge db entries marked as deleted and older than \$age - Month Day. The default value is: *
HeatCronPurgeDeletedUser	Cron to purge db entries marked as deleted and older than \$age - User. The default value is: heat
HeatCronPurgeDeletedWeekday	Cron to purge db entries marked as deleted and older than \$age - Week Day. The default value is: *
HeatEnableDBPurge	Whether to create cron job for purging soft deleted rows in the Heat database. The default value is: True
HeatMaxResourcesPerStack	Maximum resources allowed per top-level stack. -1 stands for unlimited. The default value is: 1000
HeatPassword	The password for the Orchestration service and database account.
HeatStackDomainAdminPassword	The admin password for the OpenStack Orchestration (heat) domain in OpenStack Identity (keystone).
HeatWorkers	Number of workers for Heat service. The default value is: 0. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.

CHAPTER 8. DASHBOARD (HORIZON) PARAMETERS

Parameter	Description
HorizonAllowedHosts	A list of IP/Hostname for the server Horizon is running on. Used for header checks. The default value is: *
HorizonPasswordValidator	Regex for password validation.
HorizonPasswordValidatorHelp	Help text for password validation.
HorizonSecret	Secret key for the webserver.
MemcachedIPv6	Enable IPv6 features in Memcached. The default value is: False

CHAPTER 9. BARE METAL (IRONIC) PARAMETERS

Parameter	Description
IronicCleaningDiskErase	Type of disk cleaning before and between deployments. full for full cleaning. metadata to clean only disk metadata (partition table). The default value is: full
IronicCleaningNetwork	Name or UUID of the overcloud network used for cleaning bare metal nodes. The default value of provisioning can be left during the initial deployment (when no networks are created yet) and should be changed to an actual UUID in a post-deployment stack update.
IronicEnabledDrivers	Enabled Ironic drivers. The default value is: <code>['pxe_ipmitool', 'pxe_drac', 'pxe_ilc']</code>
IronicIPXEEnabled	Whether to use iPXE instead of PXE for deployment. The default value is: True
IronicIPXEPort	Port to use for serving images when iPXE is used. The default value is: 8088
IronicPassword	The password for the Bare Metal service and database account.

CHAPTER 10. IDENTITY (KEYSTONE) PARAMETERS

Parameter	Description
AdminEmail	The email for the OpenStack Identity (keystone) admin account. The default value is: admin@example.com
AdminPassword	The password for the OpenStack Identity (keystone) admin account.
AdminToken	The OpenStack Identity (keystone) secret and database password.
KeystoneCredential0	The first OpenStack Identity (keystone) credential key. Must be a valid key.
KeystoneCredential1	The second OpenStack Identity (keystone) credential key. Must be a valid key.
KeystoneCronTokenFlushDestination	Cron to purge expired tokens - Log destination. The default value is: /var/log/keystone/keystone-tokenflush.log
KeystoneCronTokenFlushEnsure	Cron to purge expired tokens - Ensure. The default value is: present
KeystoneCronTokenFlushHour	Cron to purge expired tokens - Hour. The default value is: 0
KeystoneCronTokenFlushMaxDelay	Cron to purge expired tokens - Max Delay. The default value is: 0
KeystoneCronTokenFlushMinute	Cron to purge expired tokens - Minute. The default value is: 1

Parameter	Description
KeystoneCronTokenFlushMonth	Cron to purge expired tokens - Month. The default value is: *
KeystoneCronTokenFlushMonthday	Cron to purge expired tokens - Month Day. The default value is: *
KeystoneCronTokenFlushUser	Cron to purge expired tokens - User. The default value is: keystone
KeystoneCronTokenFlushWeekday	Cron to purge expired tokens - Week Day. The default value is: *
KeystoneEnableDBPurge	Whether to create cron job for purging soft deleted rows in Keystone database. The default value is: True
KeystoneFernetKey0	The first OpenStack Identity (keystone) fernet key. Must be a valid key.
KeystoneFernetKey1	The second OpenStack Identity (keystone) fernet key. Must be a valid key.
KeystoneLDAPBackendConfigs	Hash containing the configurations for the LDAP backends configured in keystone.
KeystoneLDAPDomainEnable	Trigger to call ldap_backend puppet keystone define. The default value is: False
KeystoneNotificationDriver	Comma-separated list of Oslo notification drivers used by Keystone. The default value is: ['messaging']
KeystoneNotificationFormat	The OpenStack Identity (keystone) notification format. The default value is: basic

Parameter	Description
KeystoneSSLCertificate	Keystone certificate for verifying token validity.
KeystoneSSLCertificateKey	Keystone key for signing tokens.
KeystoneTokenProvider	The OpenStack Identity (keystone) token format. The default value is: uuid
KeystoneWorkers	Set the number of workers for the OpenStack Identity (keystone) service. The default value is equal to the number of CPU cores on the node. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.

CHAPTER 11. SHARED FILE SERVICE (MANILA) PARAMETERS

Parameter	Description
ManilaPassword	The password for the shared file service account.

CHAPTER 12. NETWORKING (NEUTRON) PARAMETERS

Parameter	Description
EnableConfigPurge	Remove configuration that is not generated by the director. Used to avoid configuration remnants after upgrades. The default value is: False
NeutronAgentExtensions	Comma-separated list of extensions enabled for the Neutron agents. The default value is: qos
NeutronAllowL3AgentFailover	Allow automatic l3-agent failover. The default value is: True
NeutronBridgeMappings	The logical to physical bridge mappings to use. The default (datacentre:br-ex) maps br-ex (the external bridge on hosts) to a physical name datacentre , which provider networks can use (for example, the default floating network). If changing this, either use different post-install network scripts or be sure to keep datacentre as a mapping network name.
NeutronCorePlugin	The core plugin for networking. The value should be the entrypoint to be loaded from neutron.core_plugins namespace. The default value is: ml2
NeutronDhcpAgentDnsmasqDnsServers	List of servers to use as dnsmasq forwarders.
NeutronDhcpAgentsPerNetwork	The number of DHCP agents to schedule per network. The default value is: 0
NeutronEnableARPResponder	Enable ARP responder feature in the OVS Agent. The default value is: False
NeutronEnableDVR	Enable Distributed Virtual Router. The default value is: False

Parameter	Description
NeutronEnableForceMetadata	If True, DHCP always provides metadata route to VM. The default value is: False
NeutronEnableIsolatedMetadata	If True, DHCP allows metadata support on isolated networks. The default value is: False
NeutronEnableL2Pop	Enable/disable the L2 population feature in the Neutron agents. The default value is: False
NeutronEnableMetadataNetwork	If True, DHCP provides metadata network. Requires either NeutronEnableIsolatedMetadata or NeutronEnableForceMetadata parameters to also be True. The default value is: False
NeutronExternalNetworkBridge	Name of bridge used for external network traffic. Usually L2 agent handles port wiring into external bridge, and hence the parameter should be unset.
NeutronFlatNetworks	Sets the flat network name to configure in plugins. The default value is: datacentre
NeutronGlobalPhysnetMtu	MTU of the underlying physical network. OpenStack Networking (neutron) uses this value to calculate MTU for all virtual network components. For flat and VLAN networks, OpenStack Networking uses this value without modification. For overlay networks such as VXLAN, OpenStack Networking automatically subtracts the overlay protocol overhead from this value. The default value is: 1500
NeutronL3AgentMode	Agent mode for L3 agent. Must be legacy or dvr_snat . The default value is: legacy
NeutronMechanismDrivers	The mechanism drivers for the tenant network. The default value is: openvswitch

Parameter	Description
NeutronMetadataProxySharedSecret	Shared secret to prevent spoofing.
NeutronNetworkType	The tenant network type. The default value is: vxlan
NeutronNetworkVLANRanges	The Neutron ML2 and Open vSwitch VLAN mapping range to support. Defaults to permitting any VLAN on the datacentre physical network (See NeutronBridgeMappings). The default value is: datacentre:1:1000
NeutronOVSFirewallDriver	Configure the classname of the firewall driver to use for implementing security groups. Possible values depend on system configuration. Some examples are: noop , openvswitch , iptables_hybrid . The default value of an empty string results in a default supported configuration.
NeutronPassword	The password for the OpenStack Networking (neutron) service and database account.
NeutronPluginExtensions	Comma-separated list of enabled extension plugins. The default value is: qos, port_security
NeutronServicePlugins	Comma-separated list of service plugin entrypoints. The default value is: router, qos, trunk
NeutronTunnelIdRanges	Comma-separated list of <tun_min>:<tun_max> tuples enumerating ranges of GRE tunnel IDs that are available for tenant network allocation. The default value is: ['1:4094']
NeutronTunnelTypes	The tunnel types for the tenant network. The default value is: vxlan

Parameter	Description
NeutronTypeDrivers	Comma-separated list of network type driver entrypoints to be loaded. The default value is: vxlan,vlan,flat,gre
NeutronVniRanges	Comma-separated list of <vni_min>:<vni_max> tuples enumerating ranges of VXLAN VNI IDs that are available for tenant network allocation. The default value is: ['1:4094']
NeutronWorkers	Sets the number of API and RPC workers for the OpenStack Networking service. The default value is equal to the number of CPU cores on the node. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.

CHAPTER 13. COMPUTE (NOVA) PARAMETERS

Parameter	Description
EnableConfigPurge	Remove configuration that is not generated by the director. Used to avoid configuration remnants after upgrades. The default value is: False
InstanceNameTemplate	Template string to be used to generate instance names. The default value is: instance-%08x
LibvirtEnabledPerfEvents	This is a performance event list which could be used as monitor. For example: cmt,mbml,mbmt .
MigrationSshKey	SSH key for migration. Expects a dictionary with keys <i>public_key</i> and <i>private_key</i> . Values should be identical to SSH public/private key files.
NeutronMetadataProxySharedSecret	Shared secret to prevent spoofing.
NovaComputeLibvirtType	Libvirt domain type. Defaults to <i>kvm</i> .
NovaComputeLibvirtVifDriver	Libvirt VIF driver configuration for the network.
NovaCronArchiveDeleteRowsDestination	Cron to move deleted instances to another table - Log destination. The default value is: /var/log/nova/nova-rowsflush.log
NovaCronArchiveDeleteRowsHour	Cron to move deleted instances to another table - Hour. The default value is: 0
NovaCronArchiveDeleteRowsMaxRows	Cron to move deleted instances to another table - Max Rows. The default value is: 100
NovaCronArchiveDeleteRowsMinute	Cron to move deleted instances to another table - Minute. The default value is: 1

Parameter	Description
NovaCronArchiveDeleteRowsMonth	Cron to move deleted instances to another table - Month. The default value is: *
NovaCronArchiveDeleteRowsMonthday	Cron to move deleted instances to another table - Month Day. The default value is: *
NovaCronArchiveDeleteRowsUntilComplete	Cron to move deleted instances to another table - Until complete. The default value is: False
NovaCronArchiveDeleteRowsUser	Cron to move deleted instances to another table - User. The default value is: nova
NovaCronArchiveDeleteRowsWeekday	Cron to move deleted instances to another table - Week Day. The default value is: *
NovaDbSyncTimeout	Timeout for OpenStack Compute (nova) database synchronization in seconds. The default value is: 300
NovaDefaultFloatingPool	Default pool for floating IP addresses. The default value is: public
NovaEnableDBPurge	Whether to create cron job for purging soft deleted rows in Nova database. The default value is: True
NovaIPv6	Enable IPv6 features for OpenStack Compute (nova). The default is: false
NovaOVSBridge	Name of integration bridge used by Open vSwitch. The default value is: br-int
NovaPCIPassthrough	YAML list of PCI passthrough whitelist parameters.

Parameter	Description
NovaPassword	The password for the OpenStack Compute (nova) service and database account.
NovaPlacementAPIInterface	Endpoint interface to be used for the placement API. The default value is: internal
NovaReservedHostMemory	Reserved RAM for host processes. The default value is: 2048
NovaSchedulerAvailableFilters	List of scheduler available filters.
NovaSchedulerDefaultFilters	An array of filters OpenStack Compute (nova) uses to filter a node. OpenStack Compute applies these filters in the order they are listed. Place your most restrictive filters first to make the filtering process more efficient.
NovaVcpuPinSet	A list or range of physical CPU cores to reserve for virtual machine processes. For example, NovaVcpuPinSet: [4-12,^8] reserves cores from 4-12 excluding 8.
NovaWorkers	Number of workers for the Compute's Conductor service. The default value is: 0 . Note that more workers creates a larger number of processes on systems, which results in excess memory consumption.
UpgradeLevelNovaCompute	OpenStack Compute upgrade level. The default value is: auto

CHAPTER 14. CLUSTERING (SAHARA) PARAMETERS

Parameter	Description
SaharaPassword	The password for the clusting service and database account.
SaharaPlugins	Clusting enabled plugin list. The default value is: ['ambari', 'cdh', 'mapr', 'vanilla', 'spark', 'storm']
SaharaWorkers	Set the number of workers for the clusting service. The default value is: 0 . Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.

CHAPTER 15. OBJECT STORAGE (SWIFT) PARAMETERS

Parameter	Description
ControllerEnableSwiftStorage	Whether to enable object storage on Controller nodes. The default value is: True
SwiftCeilometerPipelineEnabled	Set to False to disable the object storage proxy ceilometer pipeline. The default value is: True
SwiftHashSuffix	A random string to be used as a salt when hashing to determine mappings in the ring.
SwiftMinPartHours	The minimum time (in hours) before a partition in a ring can be moved following a rebalance. The default value is: 1
SwiftMountCheck	Check if the devices are mounted to prevent accidentally writing to the root device. The default value is: False
SwiftPartPower	Partition power to use when building object storage rings. The default value is: 10
SwiftPassword	The password for the object storage service account.
SwiftProxyNodeTimeout	Timeout for requests going from swift-proxy to account, container, and object services. The default value is: 60
SwiftRawDisks	Additional raw devices to use for the object storage backend. For example: {sdb: {}}
SwiftReplicas	Number of replicas to use in the object storage rings. The default value is: 3

Parameter	Description
SwiftRingBuild	Whether to manage object storage rings or not. The default value is: True
SwiftUseLocalDir	Use a local directory for object storage services when building rings. The default value is: True
SwiftWorkers	Number of workers for object storage service. The default value is: 0 . Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.

CHAPTER 16. TELEMETRY (CEILOMETER, GNOCCHI, AODH) PARAMETERS

Parameter	Description
AodhPassword	The password for the OpenStack Telemetry Alarming (aodh) services.
CeilometerApiEndpoint	Whether to create or skip legacy Telemetry API endpoint. Set this to false to disable legacy Telemetry API service. The default value is: True.
CeilometerBackend	The Telemetry backend type. The default value is: mongodb
CeilometerEventDispatcher	Comma-separated list of Dispatchers to process events data. The default value is: ['panko', 'gnocchi']
CeilometerMeterDispatcher	Comma-separated list of Dispatcher to process meter data. The default value is: ['gnocchi']
CeilometerMeteringSecret	Secret shared by the Telemetry services.
CeilometerPassword	The password for the Telemetry service account.
CeilometerWorkers	Number of workers for the Telemetry service. The default value is: 0 . Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.
GnocchiBackend	The short name of the OpenStack Telemetry Metrics (gnocchi) backend to use. Should be one of swift , rbd , or file . The default value is: swift

Parameter	Description
GnocchiIndexerBackend	The short name of the OpenStack Telemetry Metrics (gnocchi) indexer backend to use. The default value is: mysql
GnocchiMetricdWorkers	Number of workers for OpenStack Telemetry Metrics (gnocchi). The default value is equal to the number of CPU cores on the node. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts.
GnocchiPassword	The password for the OpenStack Telemetry Metrics (gnocchi) service and database account.
MongoDbIPv6	Enable IPv6 if MongoDB VIP is IPv6. The default value is: False
MongoDbNoJournal	Should MongoDB journaling be disabled. The default value is: False
PankoPassword	The password for the panko services.

CHAPTER 17. TIME PARAMETERS

Parameter	Description
NtpServer	NTP servers list. The default value is: ['pool.ntp.org']
TimeZone	The timezone to be set on the overcloud. The default value is: UTC