



Red Hat Satellite 6.5

Hammer CLI Guide

Using Hammer, the Satellite's CLI tool

Red Hat Satellite 6.5 Hammer CLI Guide

Using Hammer, the Satellite's CLI tool

Red Hat Satellite Documentation Team
satellite-doc-list@redhat.com

Legal Notice

Copyright © 2019 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document describes how to use the Hammer CLI tool to configure and manage Red Hat Satellite.

Table of Contents

CHAPTER 1. INTRODUCTION TO HAMMER	17
1.1. GETTING HELP	17
1.2. AUTHENTICATION	17
1.2.1. Hammer Authentication Session	18
1.2.2. Hammer Configuration File	18
1.2.3. Command Line	19
1.3. USING STANDALONE HAMMER	19
1.4. SETTING A DEFAULT ORGANIZATION AND LOCATION	20
1.5. CONFIGURING HAMMER	20
1.6. CONFIGURING HAMMER LOGGING	21
1.7. INVOKING THE HAMMER SHELL	22
1.8. GENERATING FORMATTED OUTPUT	22
1.9. HIDING HEADER OUTPUT FROM HAMMER COMMANDS	22
1.10. TROUBLESHOOTING WITH HAMMER	23
CHAPTER 2. MANAGING ORGANIZATIONS, LOCATIONS, AND REPOSITORIES	24
2.1. ORGANIZATIONS	24
2.1.1. Creating an Organization	24
2.1.2. Identifying an Organization in a Hammer Command	25
2.1.3. Uploading a Manifest	25
2.2. LOCATIONS	25
2.2.1. Creating a Location	25
2.3. REPOSITORIES	26
2.3.1. Enabling a Repository	26
2.3.2. Synchronizing a Repository	26
2.3.3. Creating a Synchronization Plan	28
2.3.4. Creating a Custom Repository	29
CHAPTER 3. MANAGING CONTENT LIFE CYCLE	31
3.1. CREATING A LIFE CYCLE ENVIRONMENT	31
3.2. CREATING A CONTENT VIEW	31
3.2.1. Adding Repositories to a Content View	32
3.2.2. Adding Puppet Modules to a Content View	34
3.2.3. Adding Docker Images to a Content View	35
3.3. PUBLISHING A CONTENT VIEW	35
3.4. PROMOTING A CONTENT VIEW	36
3.5. PERFORMING AN INCREMENTAL UPDATE OF A CONTENT VIEW	36
CHAPTER 4. MANAGING ACTIVATION KEYS	38
CHAPTER 5. CONFIGURING PROVISIONING ENVIRONMENT	41
5.1. DOMAINS	41
5.2. SUBNETS	41
5.3. ARCHITECTURES	41
5.4. COMPUTE RESOURCES	42
5.5. INSTALLATION MEDIA	42
5.6. PARTITION TABLES	42
5.7. PROVISIONING TEMPLATES	42
5.7.1. Importing Templates	43
5.7.2. Exporting templates	43
5.8. OPERATING SYSTEMS	43
5.9. PARAMETERS	44

CHAPTER 6. MANAGING HOSTS	46
6.1. CREATING A HOST GROUP	46
6.2. CREATING A HOST	47
6.3. CREATING A HOST COLLECTION	50
6.4. RUNNING REMOTE JOBS ON HOSTS	51
CHAPTER 7. MANAGING USERS AND PERMISSIONS	53
7.1. CREATING USERS	53
7.2. CREATING USER GROUPS	53
7.3. CREATING ROLES	53
7.4. ASSIGNING ROLES TO USERS	54
7.5. ADDING SSH KEYS TO A USER	54
7.6. DELETING SSH KEYS FROM A USER	55
7.7. VIEWING SSH KEYS OF A USER	55
CHAPTER 8. MANAGING ERRATA	56
8.1. INSPECTING AVAILABLE ERRATA	56
8.2. APPLYING ERRATA TO A HOST	56
8.3. APPLYING ERRATA TO A HOST COLLECTION	58
CHAPTER 9. MANAGING DOCKER CONTAINERS	59
CHAPTER 10. REFERENCE	60
10.1. HAMMER	60
10.2. HAMMER ACTIVATION-KEY	62
10.2.1. hammer activation-key add-host-collection	62
10.2.2. hammer activation-key add-subscription	63
10.2.3. hammer activation-key content-override	63
10.2.4. hammer activation-key copy	63
10.2.5. hammer activation-key create	64
10.2.6. hammer activation-key delete	64
10.2.7. hammer activation-key host-collections	64
10.2.8. hammer activation-key info	65
10.2.9. hammer activation-key list	65
10.2.10. hammer activation-key product-content	65
10.2.11. hammer activation-key remove-host-collection	66
10.2.12. hammer activation-key remove-subscription	66
10.2.13. hammer activation-key subscriptions	67
10.2.14. hammer activation-key update	67
10.3. HAMMER ADMIN	68
10.3.1. hammer admin logging	68
10.4. HAMMER ANSIBLE	68
10.4.1. hammer ansible roles	69
10.4.1.1. hammer ansible roles delete	69
10.4.1.2. hammer ansible roles import	69
10.4.1.3. hammer ansible roles info	70
10.4.1.4. hammer ansible roles list	70
10.4.1.5. hammer ansible roles obsolete	71
10.5. HAMMER ARCHITECTURE	71
10.5.1. hammer architecture add-operatingsystem	71
10.5.2. hammer architecture create	72
10.5.3. hammer architecture delete	72
10.5.4. hammer architecture info	72
10.5.5. hammer architecture list	73

10.5.6. hammer architecture remove-operatingsystem	73
10.5.7. hammer architecture update	73
10.6. HAMMER ARF-REPORT	74
10.6.1. hammer arf-report delete	74
10.6.2. hammer arf-report download	74
10.6.3. hammer arf-report download-html	75
10.6.4. hammer arf-report info	75
10.6.5. hammer arf-report list	75
10.7. HAMMER AUDIT	76
10.7.1. hammer audit info	76
10.7.2. hammer audit list	76
10.8. HAMMER AUTH	77
10.8.1. hammer auth login	77
10.8.2. hammer auth logout	77
10.8.3. hammer auth status	78
10.9. HAMMER AUTH-SOURCE	78
10.9.1. hammer auth-source ldap	78
10.9.1.1. hammer auth-source ldap create	78
10.9.1.2. hammer auth-source ldap delete	79
10.9.1.3. hammer auth-source ldap info	80
10.9.1.4. hammer auth-source ldap list	80
10.9.1.5. hammer auth-source ldap update	80
10.9.2. hammer auth-source list	81
10.10. HAMMER BOOTDISK	82
10.10.1. hammer bootdisk generic	82
10.10.2. hammer bootdisk host	83
10.10.3. hammer bootdisk subnet	83
10.11. HAMMER CAPSULE	83
10.11.1. hammer capsule content	84
10.11.1.1. hammer capsule content add-lifecycle-environment	84
10.11.1.2. hammer capsule content available-lifecycle-environments	85
10.11.1.3. hammer capsule content cancel-synchronization	85
10.11.1.4. hammer capsule content info	85
10.11.1.5. hammer capsule content lifecycle-environments	85
10.11.1.6. hammer capsule content remove-lifecycle-environment	86
10.11.1.7. hammer capsule content synchronization-status	86
10.11.1.8. hammer capsule content synchronize	86
10.11.2. hammer capsule create	87
10.11.3. hammer capsule delete	87
10.11.4. hammer capsule import-classes	88
10.11.5. hammer capsule info	88
10.11.6. hammer capsule list	88
10.11.7. hammer capsule refresh-features	89
10.11.8. hammer capsule update	89
10.12. HAMMER COMPUTE-RESOURCE	90
10.12.1. hammer compute-resource clusters	90
10.12.2. hammer compute-resource create	91
10.12.3. hammer compute-resource delete	92
10.12.4. hammer compute-resource flavors	92
10.12.5. hammer compute-resource folders	92
10.12.6. hammer compute-resource image	93
10.12.6.1. hammer compute-resource image available	93
10.12.6.2. hammer compute-resource image create	94

10.12.6.3. hammer compute-resource image delete	94
10.12.6.4. hammer compute-resource image info	94
10.12.6.5. hammer compute-resource image list	95
10.12.6.6. hammer compute-resource image update	95
10.12.7. hammer compute-resource images	96
10.12.8. hammer compute-resource info	96
10.12.9. hammer compute-resource list	97
10.12.10. hammer compute-resource networks	97
10.12.11. hammer compute-resource resource-pools	97
10.12.12. hammer compute-resource security-groups	98
10.12.13. hammer compute-resource storage-domains	98
10.12.14. hammer compute-resource storage-pods	98
10.12.15. hammer compute-resource update	99
10.12.16. hammer compute-resource zones	100
10.13. HAMMER CONFIG-GROUP	100
10.13.1. hammer config-group create	101
10.13.2. hammer config-group delete	101
10.13.3. hammer config-group info	101
10.13.4. hammer config-group list	102
10.13.5. hammer config-group update	102
10.14. HAMMER CONFIG-REPORT	102
10.14.1. hammer config-report delete	103
10.14.2. hammer config-report info	103
10.14.3. hammer config-report list	103
10.15. HAMMER CONTENT-VIEW	104
10.15.1. hammer content-view add-repository	104
10.15.2. hammer content-view add-version	105
10.15.3. hammer content-view component	105
10.15.3.1. hammer content-view component add	106
10.15.3.2. hammer content-view component list	106
10.15.3.3. hammer content-view component remove	106
10.15.3.4. hammer content-view component update	107
10.15.4. hammer content-view copy	107
10.15.5. hammer content-view create	108
10.15.6. hammer content-view delete	108
10.15.7. hammer content-view filter	109
10.15.7.1. hammer content-view filter add-repository	109
10.15.7.2. hammer content-view filter create	109
10.15.7.3. hammer content-view filter delete	110
10.15.7.4. hammer content-view filter info	110
10.15.7.5. hammer content-view filter list	111
10.15.7.6. hammer content-view filter remove-repository	111
10.15.7.7. hammer content-view filter rule	111
10.15.7.8. hammer content-view filter rule create	112
10.15.7.9. hammer content-view filter rule delete	113
10.15.7.10. hammer content-view filter rule info	113
10.15.7.11. hammer content-view filter rule list	113
10.15.7.12. hammer content-view filter rule update	114
10.15.7.13. hammer content-view filter update	114
10.15.8. hammer content-view info	115
10.15.9. hammer content-view list	115
10.15.10. hammer content-view publish	116
10.15.11. hammer content-view puppet-module	116

10.15.11.1. hammer content-view puppet-module add	116
10.15.11.2. hammer content-view puppet-module list	117
10.15.11.3. hammer content-view puppet-module remove	117
10.15.12. hammer content-view purge	118
10.15.13. hammer content-view remove	118
10.15.14. hammer content-view remove-from-environment	119
10.15.15. hammer content-view remove-repository	119
10.15.16. hammer content-view remove-version	119
10.15.17. hammer content-view update	120
10.15.18. hammer content-view version	120
10.15.18.1. hammer content-view version delete	121
10.15.18.2. hammer content-view version export	121
10.15.18.3. hammer content-view version export-legacy	121
10.15.18.4. hammer content-view version import	122
10.15.18.5. hammer content-view version incremental-update	122
10.15.18.6. hammer content-view version info	123
10.15.18.7. hammer content-view version list	123
10.15.18.8. hammer content-view version promote	124
10.15.18.9. hammer content-view version republish-repositories	125
10.16. HAMMER CSV	125
10.16.1. hammer csv activation-keys	126
10.16.2. hammer csv architectures	126
10.16.3. hammer csv compute-profiles	127
10.16.4. hammer csv compute-resources	127
10.16.5. hammer csv containers	127
10.16.6. hammer csv content-hosts	128
10.16.7. hammer csv content-view-filters	129
10.16.8. hammer csv content-views	129
10.16.9. hammer csv domains	129
10.16.10. hammer csv export	130
10.16.11. hammer csv host-collections	130
10.16.12. hammer csv host-groups	130
10.16.13. hammer csv hosts	131
10.16.14. hammer csv import	131
10.16.15. hammer csv installation-media	131
10.16.16. hammer csv job-templates	132
10.16.17. hammer csv lifecycle-environments	132
10.16.18. hammer csv locations	133
10.16.19. hammer csv operating-systems	133
10.16.20. hammer csv organizations	133
10.16.21. hammer csv partition-tables	134
10.16.22. hammer csv products	134
10.16.23. hammer csv provisioning-templates	134
10.16.24. hammer csv puppet-environments	135
10.16.25. hammer csv puppet-facts	135
10.16.26. hammer csv puppet-reports	136
10.16.27. hammer csv reports	136
10.16.28. hammer csv roles	136
10.16.29. hammer csv settings	137
10.16.30. hammer csv smart-proxies	137
10.16.31. hammer csv splice	137
10.16.32. hammer csv subnets	138
10.16.33. hammer csv subscriptions	138

10.16.34. hammer csv sync-plans	138
10.16.35. hammer csv users	139
10.17. HAMMER DEFAULTS	139
10.17.1. hammer defaults add	140
10.17.2. hammer defaults delete	140
10.17.3. hammer defaults list	140
10.17.4. hammer defaults providers	140
10.18. HAMMER DISCOVERY	140
10.18.1. hammer discovery auto-provision	141
10.18.2. hammer discovery delete	141
10.18.3. hammer discovery facts	142
10.18.4. hammer discovery info	142
10.18.5. hammer discovery list	142
10.18.6. hammer discovery provision	143
10.18.7. hammer discovery reboot	144
10.18.8. hammer discovery refresh-facts	144
10.19. HAMMER DISCOVERY-RULE	145
10.19.1. hammer discovery-rule create	145
10.19.2. hammer discovery-rule delete	146
10.19.3. hammer discovery-rule info	146
10.19.4. hammer discovery-rule list	146
10.19.5. hammer discovery-rule update	147
10.20. HAMMER DOCKER	148
10.20.1. hammer docker container	148
10.20.1.1. hammer docker container create	149
10.20.1.2. hammer docker container delete	150
10.20.1.3. hammer docker container info	150
10.20.1.4. hammer docker container list	150
10.20.1.5. hammer docker container logs	151
10.20.1.6. hammer docker container start	151
10.20.1.7. hammer docker container status	151
10.20.1.8. hammer docker container stop	152
10.20.2. hammer docker manifest	152
10.20.2.1. hammer docker manifest info	153
10.20.2.2. hammer docker manifest list	153
10.20.3. hammer docker registry	153
10.20.3.1. hammer docker registry create	154
10.20.3.2. hammer docker registry delete	154
10.20.3.3. hammer docker registry info	155
10.20.3.4. hammer docker registry list	155
10.20.3.5. hammer docker registry update	155
10.20.4. hammer docker tag	156
10.20.4.1. hammer docker tag info	156
10.20.4.2. hammer docker tag list	157
10.21. HAMMER DOMAIN	157
10.21.1. hammer domain create	158
10.21.2. hammer domain delete	158
10.21.3. hammer domain delete-parameter	159
10.21.4. hammer domain info	159
10.21.5. hammer domain list	159
10.21.6. hammer domain set-parameter	160
10.21.7. hammer domain update	160
10.22. HAMMER ENVIRONMENT	161

10.22.1. hammer environment create	161
10.22.2. hammer environment delete	162
10.22.3. hammer environment info	162
10.22.4. hammer environment list	162
10.22.5. hammer environment sc-params	163
10.22.6. hammer environment update	163
10.23. HAMMER ERRATUM	164
10.23.1. hammer erratum info	164
10.23.2. hammer erratum list	164
10.24. HAMMER EXPORT-TEMPLATES	165
10.25. HAMMER FACT	166
10.25.1. hammer fact list	166
10.26. HAMMER FILE	167
10.26.1. hammer file info	167
10.26.2. hammer file list	168
10.27. HAMMER FILTER	168
10.27.1. hammer filter available-permissions	169
10.27.2. hammer filter available-resources	169
10.27.3. hammer filter create	169
10.27.4. hammer filter delete	170
10.27.5. hammer filter info	170
10.27.6. hammer filter list	171
10.27.7. hammer filter update	171
10.28. HAMMER FOREIGN-INPUT-SET	172
10.28.1. hammer foreign-input-set create	172
10.28.2. hammer foreign-input-set delete	173
10.28.3. hammer foreign-input-set info	173
10.28.4. hammer foreign-input-set list	174
10.28.5. hammer foreign-input-set update	174
10.29. HAMMER FULL-HELP	174
10.30. HAMMER GLOBAL-PARAMETER	175
10.30.1. hammer global-parameter delete	175
10.30.2. hammer global-parameter list	175
10.30.3. hammer global-parameter set	176
10.31. HAMMER GPG	176
10.31.1. hammer gpg create	176
10.31.2. hammer gpg delete	177
10.31.3. hammer gpg info	177
10.31.4. hammer gpg list	177
10.31.5. hammer gpg update	178
10.32. HAMMER HOST	178
10.32.1. hammer host ansible-roles	179
10.32.2. hammer host boot	179
10.32.3. hammer host config-reports	179
10.32.4. hammer host create	180
10.32.5. hammer host delete	185
10.32.6. hammer host delete-parameter	185
10.32.7. hammer host disassociate	185
10.32.8. hammer host enc-dump	186
10.32.9. hammer host errata	186
10.32.9.1. hammer host errata apply	186
10.32.9.2. hammer host errata info	187
10.32.9.3. hammer host errata list	187

10.32.9.4. hammer host errata recalculate	187
10.32.10. hammer host facts	188
10.32.11. hammer host info	188
10.32.12. hammer host interface	188
10.32.12.1. hammer host interface create	189
10.32.12.2. hammer host interface delete	190
10.32.12.3. hammer host interface info	190
10.32.12.4. hammer host interface list	191
10.32.12.5. hammer host interface update	191
10.32.13. hammer host list	192
10.32.14. hammer host package	193
10.32.14.1. hammer host package install	193
10.32.14.2. hammer host package list	193
10.32.14.3. hammer host package remove	194
10.32.14.4. hammer host package upgrade	194
10.32.14.5. hammer host package upgrade-all	194
10.32.15. hammer host package-group	195
10.32.15.1. hammer host package-group install	195
10.32.15.2. hammer host package-group remove	195
10.32.16. hammer host puppet-classes	196
10.32.17. hammer host puppetrun	196
10.32.18. hammer host reboot	196
10.32.19. hammer host rebuild-config	197
10.32.20. hammer host reports	197
10.32.21. hammer host reset	197
10.32.22. hammer host sc-params	198
10.32.23. hammer host set-parameter	198
10.32.24. hammer host smart-variables	199
10.32.25. hammer host start	199
10.32.26. hammer host status	199
10.32.27. hammer host stop	200
10.32.28. hammer host subscription	200
10.32.28.1. hammer host subscription attach	200
10.32.28.2. hammer host subscription auto-attach	201
10.32.28.3. hammer host subscription content-override	201
10.32.28.4. hammer host subscription product-content	201
10.32.28.5. hammer host subscription register	202
10.32.28.6. hammer host subscription remove	202
10.32.28.7. hammer host subscription unregister	202
10.32.29. hammer host update	203
10.33. HAMMER HOST-COLLECTION	207
10.33.1. hammer host-collection add-host	208
10.33.2. hammer host-collection copy	208
10.33.3. hammer host-collection create	209
10.33.4. hammer host-collection delete	209
10.33.5. hammer host-collection erratum	209
10.33.5.1. hammer host-collection erratum install	210
10.33.6. hammer host-collection hosts	210
10.33.7. hammer host-collection info	211
10.33.8. hammer host-collection list	211
10.33.9. hammer host-collection package	211
10.33.9.1. hammer host-collection package install	212
10.33.9.2. hammer host-collection package remove	212

10.33.9.3. hammer host-collection package update	212
10.33.10. hammer host-collection package-group	213
10.33.10.1. hammer host-collection package-group install	213
10.33.10.2. hammer host-collection package-group remove	213
10.33.10.3. hammer host-collection package-group update	214
10.33.11. hammer host-collection remove-host	214
10.33.12. hammer host-collection update	214
10.34. HAMMER HOSTGROUP	215
10.34.1. hammer hostgroup ansible-roles	215
10.34.2. hammer hostgroup create	216
10.34.3. hammer hostgroup delete	218
10.34.4. hammer hostgroup delete-parameter	218
10.34.5. hammer hostgroup info	218
10.34.6. hammer hostgroup list	219
10.34.7. hammer hostgroup puppet-classes	219
10.34.8. hammer hostgroup sc-params	219
10.34.9. hammer hostgroup set-parameter	220
10.34.10. hammer hostgroup smart-variables	220
10.34.11. hammer hostgroup update	221
10.35. HAMMER IMPORT-TEMPLATES	222
10.36. HAMMER JOB-INVOCATION	223
10.36.1. hammer job-invocation cancel	224
10.36.2. hammer job-invocation create	224
10.36.3. hammer job-invocation info	225
10.36.4. hammer job-invocation list	225
10.36.5. hammer job-invocation output	226
10.36.6. hammer job-invocation rerun	226
10.37. HAMMER JOB-TEMPLATE	226
10.37.1. hammer job-template create	227
10.37.2. hammer job-template delete	228
10.37.3. hammer job-template dump	228
10.37.4. hammer job-template export	228
10.37.5. hammer job-template import	229
10.37.6. hammer job-template info	229
10.37.7. hammer job-template list	229
10.37.8. hammer job-template update	230
10.38. HAMMER LIFECYCLE-ENVIRONMENT	231
10.38.1. hammer lifecycle-environment create	231
10.38.2. hammer lifecycle-environment delete	232
10.38.3. hammer lifecycle-environment info	232
10.38.4. hammer lifecycle-environment list	232
10.38.5. hammer lifecycle-environment paths	233
10.38.6. hammer lifecycle-environment update	233
10.39. HAMMER LOCATION	233
10.39.1. hammer location add-compute-resource	234
10.39.2. hammer location add-config-template	234
10.39.3. hammer location add-domain	235
10.39.4. hammer location add-environment	235
10.39.5. hammer location add-hostgroup	235
10.39.6. hammer location add-medium	236
10.39.7. hammer location add-organization	236
10.39.8. hammer location add-smart-proxy	236
10.39.9. hammer location add-subnet	236

10.39.10. hammer location add-user	237
10.39.11. hammer location create	237
10.39.12. hammer location delete	239
10.39.13. hammer location delete-parameter	239
10.39.14. hammer location info	239
10.39.15. hammer location list	240
10.39.16. hammer location remove-compute-resource	240
10.39.17. hammer location remove-config-template	240
10.39.18. hammer location remove-domain	241
10.39.19. hammer location remove-environment	241
10.39.20. hammer location remove-hostgroup	241
10.39.21. hammer location remove-medium	241
10.39.22. hammer location remove-organization	242
10.39.23. hammer location remove-smart-proxy	242
10.39.24. hammer location remove-subnet	242
10.39.25. hammer location remove-user	243
10.39.26. hammer location set-parameter	243
10.39.27. hammer location update	243
10.40. HAMMER MEDIUM	245
10.40.1. hammer medium add-operatingsystem	245
10.40.2. hammer medium create	246
10.40.3. hammer medium delete	246
10.40.4. hammer medium info	247
10.40.5. hammer medium list	247
10.40.6. hammer medium remove-operatingsystem	248
10.40.7. hammer medium update	248
10.41. HAMMER MODEL	249
10.41.1. hammer model create	249
10.41.2. hammer model delete	249
10.41.3. hammer model info	250
10.41.4. hammer model list	250
10.41.5. hammer model update	251
10.42. HAMMER MODULE-STREAM	251
10.42.1. hammer module-stream info	251
10.42.2. hammer module-stream list	252
10.43. HAMMER ORGANIZATION	252
10.43.1. hammer organization add-compute-resource	253
10.43.2. hammer organization add-config-template	253
10.43.3. hammer organization add-domain	254
10.43.4. hammer organization add-environment	254
10.43.5. hammer organization add-hostgroup	254
10.43.6. hammer organization add-location	255
10.43.7. hammer organization add-medium	255
10.43.8. hammer organization add-smart-proxy	255
10.43.9. hammer organization add-subnet	255
10.43.10. hammer organization add-user	256
10.43.11. hammer organization create	256
10.43.12. hammer organization delete	258
10.43.13. hammer organization delete-parameter	258
10.43.14. hammer organization info	258
10.43.15. hammer organization list	259
10.43.16. hammer organization remove-compute-resource	259
10.43.17. hammer organization remove-config-template	259

10.43.18. hammer organization remove-domain	260
10.43.19. hammer organization remove-environment	260
10.43.20. hammer organization remove-hostgroup	260
10.43.21. hammer organization remove-location	261
10.43.22. hammer organization remove-medium	261
10.43.23. hammer organization remove-smart-proxy	261
10.43.24. hammer organization remove-subnet	261
10.43.25. hammer organization remove-user	262
10.43.26. hammer organization set-parameter	262
10.43.27. hammer organization update	262
10.44. HAMMER OS	264
10.44.1. hammer os add-architecture	265
10.44.2. hammer os add-config-template	265
10.44.3. hammer os add-ptable	265
10.44.4. hammer os create	265
10.44.5. hammer os delete	266
10.44.6. hammer os delete-default-template	267
10.44.7. hammer os delete-parameter	267
10.44.8. hammer os info	267
10.44.9. hammer os list	268
10.44.10. hammer os remove-architecture	268
10.44.11. hammer os remove-config-template	268
10.44.12. hammer os remove-ptable	269
10.44.13. hammer os set-default-template	269
10.44.14. hammer os set-parameter	269
10.44.15. hammer os update	269
10.45. HAMMER OSTREE-BRANCH	270
10.45.1. hammer ostree-branch info	271
10.45.2. hammer ostree-branch list	271
10.46. HAMMER PACKAGE	272
10.46.1. hammer package info	272
10.46.2. hammer package list	272
10.47. HAMMER PACKAGE-GROUP	273
10.47.1. hammer package-group info	273
10.47.2. hammer package-group list	274
10.48. HAMMER PARTITION-TABLE	274
10.48.1. hammer partition-table add-operatingsystem	275
10.48.2. hammer partition-table create	275
10.48.3. hammer partition-table delete	276
10.48.4. hammer partition-table dump	276
10.48.5. hammer partition-table info	277
10.48.6. hammer partition-table list	277
10.48.7. hammer partition-table remove-operatingsystem	278
10.48.8. hammer partition-table update	278
10.49. HAMMER PING	279
10.50. HAMMER POLICY	279
10.50.1. hammer policy create	279
10.50.2. hammer policy delete	280
10.50.3. hammer policy info	281
10.50.4. hammer policy list	281
10.50.5. hammer policy update	281
10.51. HAMMER PRODUCT	282
10.51.1. hammer product create	283

10.51.2. hammer product delete	283
10.51.3. hammer product info	283
10.51.4. hammer product list	284
10.51.5. hammer product remove-sync-plan	284
10.51.6. hammer product set-sync-plan	285
10.51.7. hammer product synchronize	285
10.51.8. hammer product update	285
10.52. HAMMER PROXY	286
10.52.1. hammer proxy content	286
10.52.1.1. hammer proxy content add-lifecycle-environment	287
10.52.1.2. hammer proxy content available-lifecycle-environments	287
10.52.1.3. hammer proxy content cancel-synchronization	287
10.52.1.4. hammer proxy content info	288
10.52.1.5. hammer proxy content lifecycle-environments	288
10.52.1.6. hammer proxy content remove-lifecycle-environment	288
10.52.1.7. hammer proxy content synchronization-status	288
10.52.1.8. hammer proxy content synchronize	289
10.52.2. hammer proxy create	289
10.52.3. hammer proxy delete	290
10.52.4. hammer proxy import-classes	290
10.52.5. hammer proxy info	291
10.52.6. hammer proxy list	291
10.52.7. hammer proxy refresh-features	291
10.52.8. hammer proxy update	292
10.53. HAMMER PUPPET-CLASS	292
10.53.1. hammer puppet-class info	293
10.53.2. hammer puppet-class list	293
10.53.3. hammer puppet-class sc-params	294
10.53.4. hammer puppet-class smart-variables	294
10.54. HAMMER PUPPET-MODULE	295
10.54.1. hammer puppet-module info	295
10.54.2. hammer puppet-module list	295
10.55. HAMMER REALM	296
10.55.1. hammer realm create	296
10.55.2. hammer realm delete	297
10.55.3. hammer realm info	297
10.55.4. hammer realm list	298
10.55.5. hammer realm update	298
10.56. HAMMER RECURRING-LOGIC	299
10.56.1. hammer recurring-logic cancel	299
10.56.2. hammer recurring-logic info	299
10.56.3. hammer recurring-logic list	300
10.57. HAMMER REMOTE-EXECUTION-FEATURE	300
10.57.1. hammer remote-execution-feature info	300
10.57.2. hammer remote-execution-feature list	301
10.57.3. hammer remote-execution-feature update	301
10.58. HAMMER REPORT	301
10.58.1. hammer report delete	302
10.58.2. hammer report info	302
10.58.3. hammer report list	302
10.59. HAMMER REPORT-TEMPLATE	303
10.59.1. hammer report-template clone	303
10.59.2. hammer report-template create	304

10.59.3. hammer report-template delete	304
10.59.4. hammer report-template dump	305
10.59.5. hammer report-template generate	305
10.59.6. hammer report-template info	305
10.59.7. hammer report-template list	306
10.59.8. hammer report-template update	306
10.60. HAMMER REPOSITORY	307
10.60.1. hammer repository create	307
10.60.2. hammer repository delete	309
10.60.3. hammer repository export	309
10.60.4. hammer repository info	309
10.60.5. hammer repository list	310
10.60.6. hammer repository remove-content	311
10.60.7. hammer repository synchronize	311
10.60.8. hammer repository update	312
10.60.9. hammer repository upload-content	313
10.61. HAMMER REPOSITORY-SET	313
10.61.1. hammer repository-set available-repositories	314
10.61.2. hammer repository-set disable	314
10.61.3. hammer repository-set enable	314
10.61.4. hammer repository-set info	315
10.61.5. hammer repository-set list	315
10.62. HAMMER ROLE	316
10.62.1. hammer role clone	316
10.62.2. hammer role create	317
10.62.3. hammer role delete	317
10.62.4. hammer role filters	318
10.62.5. hammer role info	318
10.62.6. hammer role list	318
10.62.7. hammer role update	319
10.63. HAMMER SC-PARAM	319
10.63.1. hammer sc-param add-matcher	320
10.63.2. hammer sc-param info	320
10.63.3. hammer sc-param list	321
10.63.4. hammer sc-param remove-matcher	321
10.63.5. hammer sc-param update	322
10.64. HAMMER SCAP-CONTENT	323
10.64.1. hammer scap-content create	323
10.64.2. hammer scap-content delete	323
10.64.3. hammer scap-content download	324
10.64.4. hammer scap-content info	324
10.64.5. hammer scap-content list	324
10.64.6. hammer scap-content update	325
10.65. HAMMER SETTINGS	325
10.65.1. hammer settings list	326
10.65.2. hammer settings set	326
10.66. HAMMER SHELL	326
10.67. HAMMER SMART-VARIABLE	327
10.67.1. hammer smart-variable add-matcher	327
10.67.2. hammer smart-variable create	327
10.67.3. hammer smart-variable delete	328
10.67.4. hammer smart-variable info	328
10.67.5. hammer smart-variable list	329

10.67.6. hammer smart-variable remove-matcher	329
10.67.7. hammer smart-variable update	330
10.68. HAMMER SUBNET	330
10.68.1. hammer subnet create	331
10.68.2. hammer subnet delete	332
10.68.3. hammer subnet delete-parameter	332
10.68.4. hammer subnet info	333
10.68.5. hammer subnet list	333
10.68.6. hammer subnet set-parameter	333
10.68.7. hammer subnet update	334
10.69. HAMMER SUBSCRIPTION	335
10.69.1. hammer subscription delete-manifest	335
10.69.2. hammer subscription list	336
10.69.3. hammer subscription manifest-history	336
10.69.4. hammer subscription refresh-manifest	336
10.69.5. hammer subscription upload	337
10.70. HAMMER SYNC-PLAN	337
10.70.1. hammer sync-plan create	337
10.70.2. hammer sync-plan delete	338
10.70.3. hammer sync-plan info	338
10.70.4. hammer sync-plan list	338
10.70.5. hammer sync-plan update	339
10.71. HAMMER TAILORING-FILE	339
10.71.1. hammer tailoring-file create	340
10.71.2. hammer tailoring-file delete	340
10.71.3. hammer tailoring-file download	341
10.71.4. hammer tailoring-file info	341
10.71.5. hammer tailoring-file list	341
10.71.6. hammer tailoring-file update	342
10.72. HAMMER TASK	342
10.72.1. hammer task info	342
10.72.2. hammer task list	343
10.72.3. hammer task progress	343
10.72.4. hammer task resume	343
10.73. HAMMER TEMPLATE	344
10.73.1. hammer template add-operatingsystem	344
10.73.2. hammer template build-pxe-default	345
10.73.3. hammer template clone	345
10.73.4. hammer template combination	345
10.73.4.1. hammer template combination create	346
10.73.4.2. hammer template combination delete	346
10.73.4.3. hammer template combination info	346
10.73.4.4. hammer template combination list	347
10.73.4.5. hammer template combination update	347
10.73.5. hammer template create	348
10.73.6. hammer template delete	348
10.73.7. hammer template dump	349
10.73.8. hammer template info	349
10.73.9. hammer template kinds	349
10.73.10. hammer template list	350
10.73.11. hammer template remove-operatingsystem	350
10.73.12. hammer template update	350
10.74. HAMMER TEMPLATE-INPUT	351

10.74.1. hammer template-input create	351
10.74.2. hammer template-input delete	352
10.74.3. hammer template-input info	352
10.74.4. hammer template-input list	353
10.75. HAMMER USER	353
10.75.1. hammer user access-token	354
10.75.1.1. hammer user access-token create	354
10.75.1.2. hammer user access-token info	354
10.75.1.3. hammer user access-token list	355
10.75.1.4. hammer user access-token revoke	355
10.75.2. hammer user add-role	356
10.75.3. hammer user create	356
10.75.4. hammer user delete	357
10.75.5. hammer user info	357
10.75.6. hammer user list	358
10.75.7. hammer user remove-role	358
10.75.8. hammer user ssh-keys	359
10.75.8.1. hammer user ssh-keys add	359
10.75.8.2. hammer user ssh-keys delete	359
10.75.8.3. hammer user ssh-keys info	360
10.75.8.4. hammer user ssh-keys list	360
10.75.9. hammer user update	360
10.76. HAMMER USER-GROUP	362
10.76.1. hammer user-group add-role	362
10.76.2. hammer user-group add-user	363
10.76.3. hammer user-group add-user-group	363
10.76.4. hammer user-group create	363
10.76.5. hammer user-group delete	364
10.76.6. hammer user-group external	364
10.76.6.1. hammer user-group external create	364
10.76.6.2. hammer user-group external delete	365
10.76.6.3. hammer user-group external info	365
10.76.6.4. hammer user-group external list	366
10.76.6.5. hammer user-group external refresh	366
10.76.6.6. hammer user-group external update	366
10.76.7. hammer user-group info	367
10.76.8. hammer user-group list	367
10.76.9. hammer user-group remove-role	367
10.76.10. hammer user-group remove-user	368
10.76.11. hammer user-group remove-user-group	368
10.76.12. hammer user-group update	368
10.77. HAMMER VIRT-WHO-CONFIG	369
10.77.1. hammer virt-who-config create	369
10.77.2. hammer virt-who-config delete	370
10.77.3. hammer virt-who-config deploy	371
10.77.4. hammer virt-who-config fetch	371
10.77.5. hammer virt-who-config info	371
10.77.6. hammer virt-who-config list	372
10.77.7. hammer virt-who-config update	372

CHAPTER 1. INTRODUCTION TO HAMMER

Hammer is a powerful command-line tool provided with Red Hat Satellite 6. You can use Hammer to configure and manage a Red Hat Satellite Server either through CLI commands or automation in shell scripts. Hammer also provides an interactive shell.

Hammer compared to Satellite web UI

Compared to navigating the web UI, using Hammer can result in much faster interaction with the Satellite Server, as common shell features such as environment variables and aliases are at your disposal. You can also incorporate Hammer commands into reusable scripts for automating tasks of various complexity. Output from Hammer commands can be redirected to other tools, which allows for integration with your existing environment. You can issue Hammer commands directly on the base operating system running Red Hat Satellite.

Access to Satellite Server's base operating system is required to issue Hammer commands, which can limit the number of potential users compared to the web UI. Although the parity between Hammer and the web UI is almost complete, the web UI has development priority and can be ahead especially for newly introduced features.

Hammer compared to Satellite API

For many tasks, both Hammer and Satellite API are equally applicable. Hammer can be used as a human friendly interface to Satellite API, for example to test responses to API calls before applying them in a script (use the **-d** option to inspect API calls issued by Hammer, for example **hammer -d organization list**). Changes in the API are automatically reflected in Hammer, while scripts using the API directly have to be updated manually.

In the background, each Hammer command first establishes a binding to the API, then sends a request. This can have performance implications when executing a large number of Hammer commands in sequence. In contrast, a script communicating directly with the API establishes the binding only once. See the [API Guide](#) for more information.

1.1. GETTING HELP

View the full list of **hammer** options and subcommands by executing:

```
$ hammer --help
```

Use **--help** to inspect any subcommand, for example:

```
$ hammer organization --help
```

You can search the help output using **grep**, or redirect it to a text viewer, for example:

```
$ hammer | less
```

1.2. AUTHENTICATION

A Satellite user must prove their identity to Red Hat Satellite when entering hammer commands. Hammer commands can be run manually or automatically. In either case, hammer requires Satellite credentials for authentication. There are three methods of hammer authentication:

- Hammer authentication session

- Storing credentials in the hammer configuration file
- Providing credentials with each hammer command

The hammer configuration file method is recommended when running commands automatically. For example, running Satellite maintenance commands from a cron job. When running commands manually, the hammer authentication session and providing credentials with each command are recommended.

1.2.1. Hammer Authentication Session

Hammer authentication session is a cache that stores your credentials, and you have to provide them only once, at the beginning of the session. This method is suited to running several hammer commands in succession, for example a script containing hammer commands. In this scenario, you enter your Satellite credentials once, and the script runs as expected. By using the hammer authentication session, you avoid storing your credentials in the script itself and in the `~/.hammer/cli.modules.d/foreman.yml` hammer configuration file.

See the instructions on how to use the sessions:

- To enable sessions, add **`:use_sessions: true`** to the `~/.hammer/cli.modules.d/foreman.yml` file:

```
:foreman:
:use_sessions: true
```

Note that if you enable sessions, credentials stored in the configuration file will be ignored.

- To start a session, enter the following command:

```
# hammer auth login
```

You are prompted for your Satellite credentials, and logged in. You will not be prompted for the credentials again until your session expires.

- The default length of a session is 60 minutes. You can change the time to suit your preference. For example, to change it to 30 minutes, enter the following command:

```
# hammer settings set --name idle_timeout --value 30
Setting [idle_timeout] updated to [30]
```

- To see the current status of the session, enter the following command:

```
# hammer auth status
```

- To end the session, enter the following command:

```
# hammer auth logout
```

1.2.2. Hammer Configuration File

If you ran the Satellite installation with **`--foreman-admin-username`** and **`--foreman-admin-password`** options, credentials you entered are stored in the `~/.hammer/cli.modules.d/foreman.yml` configuration file, and hammer does not prompt for your credentials.

You can also add your credentials to the `~/.hammer/cli.modules.d/foreman.yml` configuration file manually:

```
:foreman:
:username: 'username'
:password: 'password'
```



IMPORTANT

Use only spaces for indentation in hammer configuration files. Do not use tabs for indentation in hammer configuration files.

1.2.3. Command Line

If you do not have your Satellite credentials saved in the `~/.hammer/cli.modules.d/foreman.yml` configuration file, hammer prompts you for them each time you enter a command. You can specify your credentials when executing a command as follows:

```
$ hammer -u username -p password subcommands
```



NOTE

Examples in this guide assume having saved credentials in the configuration file, or using a hammer authentication session.

1.3. USING STANDALONE HAMMER

You can install **hammer** on a host that has no Satellite Server installed, and use it to connect the host to a remote Satellite.

Prerequisites

- Ensure that you register the host to Satellite Server or Capsule Server. For more information, see [Registering a Host](#) in the *Provisioning Guide*.
- Ensure that you synchronize the following repositories on Satellite Server or Capsule Server. For more information, see [Synchronizing Red Hat Repositories](#) in the *Content Management Guide*.
 - rhel-7-server-rpms
 - rhel-server-rhsc-7-rpms
 - rhel-7-server-satellite-tools-6.5-rpms

Procedure

On a host, complete the following steps to install **hammer**:

1. Enable the Red Hat Enterprise Linux, Red Hat Software Collections and Red Hat Satellite Tools repositories:

```
# subscription-manager repos --enable=rhel-7-server-rpms \  
--enable=rhel-server-rhsc-7-rpms \  
--enable=rhel-7-server-satellite-tools-6.5-rpms
```

2. Install **hammer**:

```
# yum install tfm-rubygem-hammer_cli_katello
```

3. Edit the **:host:** entry in the **/etc/hammer/cli.modules.d/foreman.yml** file to include the Satellite IP address or FQDN.

```
:host: 'https://satellite.example.com'
```

1.4. SETTING A DEFAULT ORGANIZATION AND LOCATION

Many **hammer** commands are organization specific. You can set a default organization and location for **hammer** commands so that you do not have to specify them every time with the **--organization** and **--location** options.

Specifying a default organization is useful when you mostly manage a single organization, as it makes your commands shorter. However, when you switch to a different organization, you must use **hammer** with the **--organization** option to specify it.

Procedure

To set a default organization and location, complete the following steps:

1. To set a default organization, enter the following command:

```
# hammer defaults add --param-name organization \  
--param-value "Your_Organization"
```

You can find the name of your organization with the **hammer organization list** command.

2. Optional: To set a default location, enter the following command:

```
# hammer defaults add --param-name location \  
--param-value "Your_Location"
```

You can find the name of your location with the **hammer location list** command.

3. To verify the currently specified default settings, enter the following command:

```
# hammer defaults list
```

1.5. CONFIGURING HAMMER

The default location for global **hammer** configuration is:

- **/etc/hammer/cli_config.yml** for general **hammer** settings
- **/etc/hammer/cli.modules.d/** for CLI module configuration files

You can set user specific directives for **hammer** (in `~/.hammer/cli_config.yml`) as well as for CLI modules (in respective `.yml` files under `~/.hammer/cli.modules.d/`).

To see the order in which configuration files are loaded, as well as versions of loaded modules, issue:

```
$ hammer -d --version
```



NOTE

Loading configuration for many CLI modules can slow down the execution of **hammer** commands. In such a case, consider disabling CLI modules that are not regularly used.

Apart from saving credentials as described in [Section 1.2, “Authentication”](#), you can set several other options in the `~/.hammer/` configuration directory. For example, you can change the default log level and set log rotation with the following directives in `~/.hammer/cli_config.yml`. Note that these directives affect only the current user and are not applied globally.

```
:log_level: 'warning'
:log_size: 5 #in MB
```

Similarly, you can configure user interface settings. For example, set the number of entries displayed per request in the Hammer output by changing the following line:


```
:per_page: 30
```

This setting is an equivalent of the `--per-page` Hammer option.

1.6. CONFIGURING HAMMER LOGGING

You can set **hammer** to log debugging information for various Satellite components.

You can set debug or normal configuration options for all Satellite components.



NOTE

After changing hammer’s logging behavior, you must restart Satellite services.

```
# satellite-maintain service restart
```

- To set debug level for all components, use the following command:

```
# hammer admin logging --all --level-debug
# satellite-maintain service restart
```

- To set production level logging, use the following command:

```
# hammer admin logging --all --level-production
# satellite-maintain service restart
```

- To list the currently recognized components, that you can set logging for:

```
# hammer admin logging --list
```

- To list all available logging options:

```
# hammer admin logging --help
```

```
Usage:  
hammer admin logging [OPTIONS]
```

1.7. INVOKING THE HAMMER SHELL

You can issue **hammer** commands through the interactive shell. To invoke the shell, issue the following command:

```
$ hammer shell
```

In the shell, you can enter subcommands directly without typing "hammer", which can be useful for testing commands before using them in a script. To exit the shell, type **exit** or press [Ctrl + D].

1.8. GENERATING FORMATTED OUTPUT

You can modify the default formatting of the output of **hammer** commands to simplify the processing of this output by other command line tools and applications. For example, to list organizations in a CSV format with a custom separator (in this case a semicolon), issue the following command:

```
$ hammer --csv --csv-separator ";" organization list
```

Output in CSV format is useful for example when you need to parse IDs and use them in a **for** loop (see [or xref:exam-CLI_Guide-Assigning_a_Synchronization_Plan_to_Multiple_Products\[\]](#)).

Several other formatting options are available with the **--output** option:

```
$ hammer --output output_format organization list
```

Replace *output_format* with one of:

- **table** – generates output in the form of a human readable table (default).
- **base** – generates output in the form of key-value pairs.
- **yaml** – generates output in the YAML format.
- **csv** – generates output in the Comma Separated Values format. To define a custom separator, use the **--csv** and **--csv-separator** options instead.
- **json** – generates output in the JavaScript Object Notation format.
- **silent** – suppresses the output.

1.9. HIDING HEADER OUTPUT FROM HAMMER COMMANDS

When you use any hammer command, you have the option of hiding headers from the output. If you want to pipe or use the output in custom scripts, hiding the output is useful.

- To hide the header output, add the **--no-headers** option to any hammer command.

1.10. TROUBLESHOOTING WITH HAMMER

You can use the **hammer ping** command to check the status of core Satellite services. Together with the **satellite-maintain service status** command, this can help you to diagnose and troubleshoot Satellite issues. If all services are running as expected, the output looks as follows:

```
$ hammer ping
candlepin:
  Status:      ok
  Server Response: Duration: 22ms
candlepin_auth:
  Status:      ok
  Server Response: Duration: 17ms
pulp:
  Status:      ok
  Server Response: Duration: 41ms
pulp_auth:
  Status:      ok
  Server Response: Duration: 23ms
foreman_tasks:
  Status:      ok
  Server Response: Duration: 33ms
```

CHAPTER 2. MANAGING ORGANIZATIONS, LOCATIONS, AND REPOSITORIES

You can use **hammer** to create, edit, and manage organizations, locations, and repositories. For web UI equivalents of the following procedures see [Managing Organizations](#) and [Importing Red Hat Content](#) in the *Content Management Guide*.

2.1. ORGANIZATIONS

Organization in Red Hat Satellite is an isolated collection of systems, content, and other functionality within a Satellite deployment. This section shows how to create and modify organizations using **hammer**.

2.1.1. Creating an Organization

Use the following command to create an organization:

```
$ hammer organization create \  
--name "org_name" \  
--label "org_label" \  
--description "org_description"
```

Where:

- *org_name* is the name of the organization. This parameter is required.
- *org_label* is the organization label used in command-line applications such as **subscription-manager**. Labels cannot contain white space and you cannot change them later. If not specified, label is generated automatically from the organization name (white space is replaced with underscores).
- *org_description* is a short description of the organization. This parameter is not required, but it can help you to manage a large number of organizations.

You can fully configure an organization while creating it (issue **hammer organization create --help** to see the options). Also, you can modify an existing organization using the **hammer organization update** command.

Example 2.1. Creating and Updating ACME Organization

The following example shows how to create an organization named ACME:

```
$ ORG="ACME"  
$ hammer organization create \  
--name $ORG \  
--description "Example_organization"
```

This command assigns a compute resource to the organization:

```
$ hammer organization update \  
--name $ORG \  
--compute-resource-ids 1
```

2.1.2. Identifying an Organization in a Hammer Command

Many tasks you can perform in the Satellite Server are specific to an organization. Hammer commands provide three ways to identify an organization: by using the **organization**, **organization-label**, or **organization-id** option. To find the organization ID, use the following command:

```
$ hammer organization list
```

If your organization name is long, consider storing it in a shell variable. You can use this variable in Hammer commands. For example:

```
$ ORG = "Red Hat Enterprise Linux Developer Team"
$ hammer product list --organization $ORG
```

This approach is used in examples in this guide.

If you mostly manage a single organization, you can set it as default. For information on how to do that, see [Section 1.4, "Setting a Default Organization and Location"](#).

2.1.3. Uploading a Manifest

A Subscription Manifest transfers subscriptions from the Red Hat Customer Portal to Satellite Server. First, generate the manifest on the Red Hat Customer portal as described in the [Creating a Subscription Manifest](#) in the *Content Management Guide*. Then upload the manifest to the organization as follows:

```
$ hammer subscription upload \
--organization-label org_label \
--file path_to_manifest
```

Example 2.2. Uploading a Manifest to ACME Organization

The following example shows how to upload a Subscription Manifest file to the ACME organization (assuming the organization name is stored in a shell variable):

```
$ hammer subscription upload --organization $ORG --file /tmp/manifest.zip
```

To view the subscriptions imported with the manifest, issue:

```
$ hammer subscription list --organization $ORG
```

2.2. LOCATIONS

Location in Red Hat Satellite is collection of default settings that represent a physical place. This section shows how to create locations using **hammer**.

2.2.1. Creating a Location

Use the following command to create a location:

```
$ hammer location create --name location_name
```

Example 2.3. Creating Multiple Locations Using a Script

The following Bash script creates three locations (london, munich, boston), and assigns them to the ACME organization.

```
ORG="ACME"
LOCATIONS="london munich boston"

for LOC in ${LOCATIONS}
do
    hammer location create --name "${LOC}"
    hammer location add-organization --name "${LOC}" --organization "${ORG}"
done
```

Run **hammer location --help** to view all possible location related operations.

2.3. REPOSITORIES

Repository provides storage for a collection of content. This section shows how to enable and synchronize repositories using **hammer**.

2.3.1. Enabling a Repository

Before enabling a Red Hat repository, you need to know its name, the name of the product it provides, the base architecture, and the release version. Use the following command to enable a repository:

```
$ hammer repository-set enable \
--organization-label org_label \
--product "product_name" \
--basearch "base_architecture" \
--releasever "release_version" \
--name "repository_name"
```

Example 2.4. Enabling a Red Hat Enterprise Linux Repository

The following command enables the Red Hat Enterprise Linux 7 Server repository for the organization:

```
$ hammer repository-set enable \
--organization $ORG \
--product "Red Hat Enterprise Linux Server" \
--basearch "x86_64" \
--releasever "7Server" \
--name "Red Hat Enterprise Linux 7 Server (RPMs)"
```

Run **hammer repository-set --help** to view all possible repository related operations. Also see **hammer repository --help**.

2.3.2. Synchronizing a Repository

By synchronizing a repository you pull its content from Red Hat Customer Portal to the Satellite Server. To synchronize a repository you need to specify its name and a product name:

```
$ hammer repository synchronize \
--product "product_name" \
--name "repo_name" \
--organization-label org_label \
--async
```

Note that if you have created Content Views, multiple repositories with the same name can exist within a single organization. In such a case, use the **--id** option to identify the repository you want to synchronize (issue **hammer repository list** to find repository IDs).

Example 2.5. Synchronizing a Red Hat Enterprise Linux Repository

The following command performs a single synchronization of the Red Hat Enterprise Linux 7 Server repository in the organization:

```
$ hammer repository synchronize \
--product "Red Hat Enterprise Linux Server" \
--name "Red Hat Enterprise Linux 7 Server (RPMs)" \
--organization $ORG \
--async
```

The task ID is displayed after executing the above command:

```
Repository is being synchronized in task 640bb71f-0ce5-40a3-a675-425a4acacceb
```

To view the progress of the task, issue:

```
$ hammer task progress --id 640bb71f-0ce5-40a3-a675-425a4acacceb
```

After finishing the first synchronization, the repository is added to the list of repositories mirrored on Satellite Server. Execute the following command to see the list:

```
$ hammer repository list --organization $ORG
```

You can also synchronize all repositories within a product as follows:

```
$ hammer product synchronize \
--organization-label org_label \
--name "product_name" \
--async
```

With the **--async** option, the repository synchronization runs in the background, which for example allows you to enable and synchronize several repositories in parallel.

Example 2.6. Synchronizing All Repositories in ACME Organization

The following Bash script synchronizes all repositories within the ACME organization.

```
ORG="ACME"
```

```
for i in $(hammer --csv repository list --organization $ORG | grep -vi '^ID' | awk -F, {'print $1'})
do
    hammer repository synchronize --id ${i} --organization $ORG --async
done
```

2.3.3. Creating a Synchronization Plan

Product in Red Hat Satellite is a collection of repositories that acts as the smallest unit of the synchronization process. You can create a synchronization plan to automatically update repositories of a selected product in a given time interval.

To define a synchronization plan, issue the following command:

```
$ hammer sync-plan create \
--name "sync_plan_name" \
--enabled=true \
--interval repetition_interval \
--organization-label org_label \
--sync-date "initial_sync"
```

Replace *repetition_interval* with **hourly**, **daily**, or **weekly**. Replace *initial_sync* with the date and time of the initial synchronization in the form of "YYYY-MM-DD HH:MM:SS".

Example 2.7. Creating a Synchronization Plan

The following command creates a daily synchronization schedule for the ACME organization, that runs at 3 a.m., starting from 15 January 2016:

```
$ hammer sync-plan create \
--name "daily sync at 3 a.m." \
--enabled=true \
--interval daily \
--organization $ORG \
--sync-date "2016-01-15 03:00:00"
```

To associate the synchronization plan with a product, issue the following command:

```
$ hammer product set-sync-plan \
--organization-label org_label \
--name "product_name" \
--sync-plan "sync_plan_name"
```

Example 2.8. Assigning a Synchronization Plan to Multiple Products

The following Bash script selects the products in the ACME organization that have been synchronized at least once and contain at least one repository and assigns them a synchronization plan named "daily sync at 3 a.m.".

```
ORG="ACME"
SYNC_PLAN="daily sync at 3 a.m."
```



```
for i in $(hammer --csv product list --organization $ORG --per-page 999 | grep -vi '^ID' | grep -vi
not_synced | awk -F, '{{ if ($5!=0) print $1}}')
do
    hammer product set-sync-plan --sync-plan $SYNC_PLAN --organization $ORG --id $i
done
```

After executing the script, issue the following command to see which products have been assigned the synchronization plan:

```
$ hammer product list --organization $ORG --sync-plan "daily sync at 3 a.m."
```

To view synchronization plans available for a selected organization, issue the following command:

```
$ hammer sync-plan list --organization-label org_label
```

For more details on working with products and synchronization plans see the output of **hammer sync-plan --help** and **hammer product --help**.

2.3.4. Creating a Custom Repository

After enabling a Red Hat repository, the corresponding product is created automatically. To enable a repository with custom packages, you first need to manually create a product for this repository.

Use the following command to create a custom product:

```
$ hammer product create --name "product_name" --organization-label org_label
```

The following command creates a new repository under the custom product:

```
$ hammer repository create \
--name "repo_name" \
--organization-label org_label \
--product "product_name" \
--content-type cont_type --publish-via-http true \
--url "repo_url"
```

Replace the example values with your own details, in particular:

- *cont_type* specifies the type of content in the repository, choose one of **yum**, **puppet**, or **docker**.
- *repo_url* specifies the URL on which the repository will be available, valid only if `--publish-via-http` is enabled.

To upload packages to a custom repository, issue the following command:

```
$ hammer repository upload-content \
--organization-label org_label \
--id "repo_id" \
--path path_to_dir
```

Replace *path_to_dir* with the path to the directory with content (RPM packages, Puppet modules, or Docker images) to be added to the custom repository.

CHAPTER 3. MANAGING CONTENT LIFE CYCLE

This section shows how to use **hammer** to create Content Views and to promote them through life cycle environments.

3.1. CREATING A LIFE CYCLE ENVIRONMENT

Life cycle environments represent stages of the content life cycle. This section shows how to view and create life cycle environments with **hammer**. By default, the Library environment is present for each organization. Use the following syntax to create a new life cycle environment:

```
$ hammer lifecycle-environment create \
--name env_name \
--description "env_description" \
--organization-label org_label \
--prior prior_env_name
```

Example 3.1. Creating a Life Cycle Environment

This example shows how to create a new environment based on Library for the ACME organization (assuming the organization name is stored in a shell variable):

```
$ hammer lifecycle-environment create \
--name Development \
--description "Initial testing" \
--organization $ORG \
--prior Library
```

You can create another life cycle environment based on **Development** using the **--prior** option.

To view existing life cycle environments, issue the following command:

```
$ hammer lifecycle-environment list --organization-label org_label
```

The output of the above command can look as follows:

```
---|-----|-----
ID | NAME      | PRIOR
---|-----|-----
2  | Library   |
5  | Development | Library
6  | Testing   | Development
---|-----|-----
```

For more information on commands related to life cycle environments, see the output of **hammer lifecycle-environment --help**.

3.2. CREATING A CONTENT VIEW

Content Views are subsets of content from the Library created by intelligent filtering. You can publish and promote Content Views into life cycle environments that make content available for different uses (typically Dev, QA, and Production). To create a Content View, issue the following command:

```
$ hammer content-view create \
--name cv_name \
--repository-ids repo_ID1,repo_ID2,repo_ID3 \
--description "cv_description" \
--organization-label org_label
```

The **--repository-ids** option adds the selected repositories to the Content View, use the **hammer repository list** command to find the IDs. It is also possible to omit this option to create an empty Content View that you can modify later using the **update** or **add-repository** subcommands.

Example 3.2. Creating a Content View

The following example creates a Content View under the ACME organization and assigns it three repositories:

```
$ hammer content-view create \
--name cv-rhel7-server \
--repository-ids 1,2,3 \
--description "Initial CV for RHEL 7" \
--organization $ORG
```

Example 3.3. Creating a Composite Content View

A Composite Content View is comprised of one or more Content Views. This example shows how to create a Composite Content View from two existing Content Views:

```
$ hammer content-view create \
--name ccv-rhel7-server-scl \
--description "CCV for RHEL7 and Software Collections" \
--organization $ORG \
--composite --component-ids 2,6 \
--auto-publish yes
```

Find the IDs for the **--component-ids** option by executing **hammer content-view list**. When the **--auto-publish** option is set to **yes**, the Composite Content View is automatically republished when a Content View it includes is republished.

There are three content types you can add to the Content View: RPM packages, Puppet modules, and Docker images.

3.2.1. Adding Repositories to a Content View

Use the following command to add repositories to an existing Content View:

```
$ hammer content-view update \
--repository-ids repo_ID1,repo_ID2... \
--name cv_name \
--organization-label org_label
```

The above command is useful for populating an empty Content View with repositories. Note that it will overwrite any existing repositories, therefore to increase the number of repositories in a Content View, use:

```
$ hammer content-view add-repository \
--organization-label org_label \
--name cv_name \
--repository-id repo_ID
```

Similarly, you can use the **remove-repository** subcommand to remove a repository from the Content View. Use **hammer content-view info** to inspect repositories in a Content View.

Example 3.4. Filtering Packages for a Content View – Excluding a Package

Filters allow you to select a subset of packages from a repository (either by including or excluding) to create customized Content Views. This example shows how to create a filter to exclude the **emacs** package from the **cv-rhel7-server** Content View.

First create a filter for the Content View in the organization:

```
$ hammer content-view filter create \
--type rpm \
--name exclude-emacs \
--description "Excluding emacs package" \
--inclusion false \
--organization $ORG \
--repository-ids 1,2,3 \
--content-view cv-rhel7-server
```

Find the repository IDs by executing **hammer repository list**. Create a rule to exclude packages with name starting with "emacs" and add it to the filter as follows:

```
$ hammer content-view filter rule create \
--name "emacs*" \
--organization $ORG \
--content-view cv-rhel7-server \
--content-view-filter exclude-emacs
```

As a result, hosts using the cv-rhel7-server Content View will not have access to the emacs package. You can add multiple rules to a filter, see the output **hammer content-view filter rule create --help** for the full list of filtering parameters. To inspect rules present in a filter, issue the following command:

```
$ hammer content-view filter rule list \
--content-view cv-rhel7-server \
--content-view-filter exclude-emacs \
--organization $ORG
```

Example 3.5. Filtering Packages for a Content View – Limiting Errata by Date

This example shows how to create a filter to exclude errata released before a specific date from the **cv-rhel7-server** Content View. For more information on errata management see [Chapter 8, Managing Errata](#). Create a filter for the Content View as follows:

```
$ hammer content-view filter create \
--type erratum \
--name limit-errata-by-date \
--description "Excluding errata by date" \
--inclusion false \
--organization $ORG \
--repository-ids 1,2,3 \
--content-view cv-rhel7-server
```

Create a rule to exclude errata with a name starting with "emacs" and add it to the filter as follows:

```
$ hammer content-view filter rule create \
--end-date YYYY-MM-DD \
--organization $ORG \
--content-view cv-rhel7-server \
--content-view-filter limit-errata-by-date \
--types enhancement,bugfix,security
```

3.2.2. Adding Puppet Modules to a Content View

To add a Puppet module to a Content View, first upload this module to a Puppet repository within a custom product. Use the commands from [Section 2.3.4, "Creating a Custom Repository"](#) to create a product with a repository, and to upload a Puppet module to the repository.

To add a Puppet module to a Content View, issue the following command:

```
$ hammer content-view puppet-module add \
--content-view cv_name \
--name module_name
```

Example 3.6. Adding a Puppet Module to a Content View

This example shows how to add a Puppet module from an external source to the cv-rhel7-server Content View.

1. Download the **concat** module (that constructs files from multiple text fragments) from Puppet Forge:

```
$ wget -O /tmp/puppetlabs-concat-1.2.5.tar.gz https://forgeapi.puppetlabs.com/v3/files/puppetlabs-concat-1.2.3.tar.gz
```

2. Create a Puppet repository under the ACME-puppet product and upload the module to this repository (the example assumes repository ID is 6):

```
$ hammer product create \
--name "ACME-puppet" \
--organization $ORG
```

```
$ hammer repository create \
--organization $ORG \
--product ACME-puppet \
```

```
--name "ACME Puppet Repository" \
--content-type puppet \
--url "https://forge.puppetlabs.com/"

$ hammer repository upload-content \
--organization $ORG \
--product ACME-puppet \
--id 6 \
--path /tmp/puppetlabs-concat-1.2.5.tar.gz
```

3. Add the module to the Content View using the **id**, **name**, or **author** parameters. To find the exact values, enter:

```
$ hammer puppet-module list --organization $ORG
---|-----|-----|-----
ID | NAME   | AUTHOR   | VERSION
---|-----|-----|-----
1  | concat | puppetlabs | 1.2.3
---|-----|-----|-----
```

To add the module to the Content View, issue:

```
$ hammer content-view puppet-module add \
--name concat \
--content-view cv-rhel7-server \
--organization $ORG
```

To verify if the module has been added successfully, issue the following command:

```
$ hammer content-view puppet-module list \
--content-view cv-rhel7-server \
--organization $ORG
```

3.2.3. Adding Docker Images to a Content View

You can upload Docker images directly to the dedicated repository as follows:

```
$ hammer repository upload-content --path image_archive --id repo_id
```

Replace *image_archive* with a path to the archive containing the Docker image. Use *repo_id* to identify the repository of docker content type. Then you can add this repository to the Content View.

3.3. PUBLISHING A CONTENT VIEW

By publishing a Content View you make it visible and usable by hosts. Use the following command to publish a selected Content View:

```
$ hammer content-view publish \
--id cv_ID \
--organization-label org_label \
--async
```

Find the *cv_ID* of the Content View to be published in the output of the **hammer content-view list** command. Published Content Views become available in the Library environment. To verify the Content View status, issue the following command:

```
$ hammer content-view info --id cv_ID
```

3.4. PROMOTING A CONTENT VIEW

Promoting is the act of moving a Content View from one life cycle environment to another. To do so, issue the following command.

```
$ hammer content-view version promote \
--content-view cv_name \
--organization-label org_label \
--to-lifecycle-environment env_name
```

Here, *env_name* stands for the name of target life cycle environment.

Example 3.7. Promoting a Content View Through the Life Cycle Environment Path

The following Bash script promotes the selected Content View from Library through all life cycle environments in the ACME organization:

```
ORG="ACME"
CV_ID=1

for i in $(hammer --csv lifecycle-environment list --organization $ORG | grep -vi '^ID' | awk -F,
{'print $1'} | sort -n)
do
    hammer content-view version promote --organization $ORG --to-lifecycle-environment-id $i --id
$CV_ID
done
```

To verify if the Content View has been promoted correctly, issue the following command:

```
$ hammer content-view version info --id 1
```

3.5. PERFORMING AN INCREMENTAL UPDATE OF A CONTENT VIEW

Incremental updates enable modifying a published Content View without the need to promote a new Content View version through the life cycle environment. As a result of the incremental update, a new minor Content View version is created. Incremental updates are useful for fast emergency updates, you can use them to add errata, packages, or Puppet modules.

To create an incremental update adding new packages to a Content View, issue:

```
$ hammer content-view version incremental-update \
--content-view-version-id cv_ID \
--packages pkg_name1, pkg_name2 \
--lifecycle-environment-ids env_ID1, env_ID2,... \
--organization-id org_ID
```


Find the Content View version ID in the output of **hammer Content View version list**. Instead of supplying packages with the **--packages** option, you can add Puppet modules with **--puppet-modules**, or errata with **--errata-ids** (see [Example 3.8, “Adding Errata to a Content View using an Incremental Update”](#)). For more information on working with incremental updates issue **hammer content-view version incremental-update --help**.

Example 3.8. Adding Errata to a Content View using an Incremental Update

This example shows how to apply an erratum to a host (named **auth01.example.com**) by creating an incremental update of its Content View:

```
$ hammer content-view version incremental-update \
--content-view-version-id 4 \
--errata-ids 8c3801f6-12a7-4a62-83f4-addbb1f34ce6 \
--lifecycle-environments Infrastructure \
--organization $ORG
```

To find the required information for the above command, perform the following steps:

1. Find the Organization ID and name by executing:

```
$ hammer organization list
```

2. Find the Content View your host is registered to as well as its life cycle environment by executing:

```
$ hammer host info --name auth01.example.com
```

3. Then find the current version of the Content View (assuming Content View name **RHEL7_Infra**):

```
$ hammer content-view info --name "RHEL7_Infra" --organization $ORG
```

4. Find the IDs of errata you want to apply in the list of applicable errata in **Library**:

```
$ hammer erratum list --content-view-version-id 4 --organization $ORG
$ hammer host errata list --host auth01.example.com
```

CHAPTER 4. MANAGING ACTIVATION KEYS

Activation keys define the subscription properties of a host. Using an activation key improves the speed of host registration. For web UI equivalents of the following procedures see [Managing Activation Keys](#) in the *Content Management Guide*.

There are three possible use cases for activation keys:

- **Activation key with no subscriptions specified**– hosts using the activation key search for the best fitting subscription. This is akin to running **subscription-manager --auto-attach**. See [Example 4.1, "Creating an Empty Activation Key"](#).
- **Activation key providing a custom subscription pool for auto attach**– hosts using the activation key select the best fitting subscription from the list specified in the activation key. See [Example 4.2, "Creating an Activation Key with Custom Subscription Pool"](#).
- **Activation key with the exact set of subscriptions**– hosts using the activation key are associated with all subscriptions specified in the activation key. See [Example 4.3, "Creating an Activation Key with Mandatory Subscription List"](#).



NOTE

Activation keys are only used when hosts are registered. If changes are made to an activation key, it is only applicable to hosts that are registered with the amended activation key in the future. The changes are not made to existing hosts.

To create an activation key, issue the following command:

```
$ hammer activation-key create --name ak_name \
--organization-label org_label \
--content-view cv_name \
--lifecycle-environment lc_name
```

Note that the Content View has to be published. To see the full list of operations related to activation keys, use the **hammer activation-key --help** command.

To add a subscription to the activation key, issue the following command:

```
$ hammer activation-key add-subscription \
--id ak_ID \
--subscription-id sub_ID
```

To find the activation key ID, use **hammer activation-key list**; to find the subscription ID, use **hammer subscription list**.

Example 4.1. Creating an Empty Activation Key

This example shows how to create an activation key that directs the associated hosts to automatically attach a best fitting subscription:

```
$ hammer activation-key create \
--name "automatically attach key" \
--organization $ORG \
```

```
--content-view cv-rhel7-server \
--lifecycle-environment Testing
```

As a result, hosts registered in the cv-rhel7-server Content View are associated with this activation key.

Example 4.2. Creating an Activation Key with Custom Subscription Pool

This example shows how to create an activation key that will direct the associated hosts to automatically attach a best fitting subscription from the list specified in the activation key.

First create an empty activation key:

```
$ hammer activation-key create \
--name "custom pool key" \
--organization $ORG \
--content-view cv-rhel7-server \
--lifecycle-environment Testing
```

Add a subscription to the activation key:

```
$ hammer activation-key add-subscription \
--name "custom pool key" \
--subscription-id 1
```

Keep repeating this step to add all required subscriptions to the activation key.

Example 4.3. Creating an Activation Key with Mandatory Subscription List

This example shows how to create an activation key that will direct the associated hosts to attach all subscriptions specified in the activation key.

First, create an activation key and add all required subscriptions to it. Follow the steps from [Example 4.2, “Creating an Activation Key with Custom Subscription Pool”](#).

Then disable the **auto-attach** property of the activation key:

```
$ hammer activation-key update \
--organization $ORG \
--name "mandatory subs key" \
--auto-attach false
```



IMPORTANT

You can assign several activation keys to a Content View. In case of conflicting settings, the values from the last specified key take precedence. You can specify the order of precedence by setting a host group parameter as follows:

```
$ hammer hostgroup set-parameter \  
--name kt_activation_keys \  
--value name_of_first_key, name_of_second_key,... \  
--hostgroup hostgroup_name
```

CHAPTER 5. CONFIGURING PROVISIONING ENVIRONMENT

This section shows how to configure various stages of your provisioning environment using **hammer**. For web UI equivalents of the following procedures see [Configuring Provisioning Resources](#) in the *Provisioning Guide*.

5.1. DOMAINS

Domains in Red Hat Satellite represent DNS zones. Satellite has the ability to assign domain names with Red Hat Satellite Capsule Server DNS. This provides users with a means to group and name hosts within a particular domain and associate them with parameters and Puppet variables.

To create a new domain, issue the following command:

```
$ hammer domain create --name domain_name
```

You can associate the newly created domain to organizations and locations using the **hammer organization add-domain** or **hammer location add-domain** commands. To view the status of a domain, issue the following command:

```
$ hammer domain info --name domain_name
```

5.2. SUBNETS

Subnets in Red Hat Satellite define networks specified for groups of systems. Subnets use standard IP-address settings to define the network and use the Red Hat Satellite Capsule Server's DHCP features to assign IP addresses to systems within the subnet. The following command contains the minimal set of options required for subnet creation:

```
$ hammer subnet create \
  --name subnet_name \
  --organization-ids org_ID1,org_ID2... \
  --location-ids loc_ID1,loc_ID2... \
  --domain-ids dom_ID1,dom_ID2... \
  --boot-mode boot_mode \
  --network network_address \
  --mask netmask \
  --ipam ipam
```

Here, *boot_mode* is one of **Static** or **DHCP**, *ipam* is one of **DHCP**, **Internal DB**, or **None**. If using DHCP, you can set the IP range with the **--from** and **--to** options. For the full list of configurable options, see the output of the **hammer subnet create --help** command.

5.3. ARCHITECTURES

Architecture in Satellite represents a logical grouping of hosts and operating systems. To view the architectures, issue the following command:

```
$ hammer architecture list
```

Architectures are created by Satellite automatically when hosts are registered in Puppet, therefore it is rarely needed to create them manually (even though **hammer** provides this option).

5.4. COMPUTE RESOURCES

Compute resources are hardware abstractions from virtualization and cloud providers. Satellite uses compute resources to provision virtual machines and containers. Run the following command to create a compute resource:

```
$ hammer compute-resource create \  
--name cr_name \  
--organization-ids org_ID1,org_ID2... \  
--location-ids loc_ID1,loc_ID2... \  
--provider provider
```

Here, *provider* is one of: **RHEV**, **RHEL OpenStack Platform**, **Libvirt**, **Docker**, **Rackspace**, **Google**, **EC2**, or **VMware**. Depending on the provider type, other options such as **--url**, or **--user** may be required. See the output of the **hammer compute-resource create --help** command for details.

5.5. INSTALLATION MEDIA

Installation media (ISO images) provide content for kickstart trees and new host installations in Red Hat Satellite. To list the media, issue the following command:

```
$ hammer medium list
```

To add a new medium, issue the following command:

```
$ hammer medium create --name medium_name --path path_to_medium
```

You can make the medium available to organizations and locations directly when adding it (see the output of the **hammer medium create --help** command), or later by using the **hammer organization add-medium** or **hammer location add-medium** commands.

5.6. PARTITION TABLES

Partition tables define the partitions and file system layout for new installations when provisioning systems. Red Hat Satellite provides default partition tables associated with operating system families, to view them, issue the following command:

```
$ hammer partition-table list
```

To create a new partition table, issue the following command:

```
$ hammer partition-table create \  
--name table_name \  
--file path_to_layout_file \  
--os-family os_family
```

See the output of the **hammer partition-table --help** command for other subcommands.

5.7. PROVISIONING TEMPLATES

Provisioning templates provide the systematic means to run unattended installations. To view the provisioning templates provided by Satellite, enter the following command:

```
$ hammer template list
```

To add a new template, enter the following command:

```
$ hammer template create --name template_name --file path_to_template_file
```

See the output of the **hammer template --help** command for other subcommands.

5.7.1. Importing Templates

You can use the **hammer import-templates** command to import templates from a repository of your choice. You can use different protocols to point to your repository, for example `/tmp/dir`, `git://example.com`, `https://example.com`, and `ssh://example.com`.

For better indexing and management of your templates, use **--prefix** to set a category for your templates. To select certain templates from a large repository, use **--filter** to define the title of the templates that you want to import. For example **--filter '*.Ansible Default\$'** imports various Ansible Default templates.

To import a template from a repository, enter the following command:

```
$ hammer import-templates \
  --prefix '[Custom Index]' \
  --filter '*.Template Name$' \
  --repo https://github.com/examplerepo/templatedirectory \
  --branch my_branch \
  --organization 'Default Organization'
```

5.7.2. Exporting templates

You can use the **hammer export-templates** command to export templates to a Git repository.

1. Clone a local copy of your Git repository:

```
$ git clone https://github.com/foreman/community-templates /custom/templates
```

2. Change the owner of your local directory to the foreman user, and change the SELinux context with the following commands:

```
# chown -R foreman:foreman /custom/templates
# chcon -R -t httpd_sys_rw_content_t /custom/templates
```

3. To export the templates to your local repository, enter the following command:

```
hammer export-templates --organization 'Default Organization' --repo /custom/templates
```

5.8. OPERATING SYSTEMS

Operating systems define combinations of installation methods and media and are grouped within families. As a default, Red Hat Satellite uses a Red Hat family. Families allow Satellite to change certain behaviors when provisioning hosts. To list operating systems, issue the following command:

```
$ hammer os list
```

To create a new operating system, issue the following command:

```
$ hammer os create --name os_name --major version_number
```

Then you can add architectures, partition tables, installation media, and configuration templates to the operating system. See the output of the **hammer os --help** command for details.

Example 5.1. Updating Multiple Operating Systems

The following Bash script assigns each operating system a partition table (**Kickstart default**), configuration template (**Kickstart default PXELinux**), and provisioning template (**Satellite Kickstart Default**).

```
PARTID=$(hammer --csv partition-table list | grep "Kickstart default" | cut -d, -f1)
PXEID=$(hammer --csv template list --per-page=1000 | grep "Kickstart default PXELinux" | cut -d, -f1)
SATID=$(hammer --csv template list --per-page=1000 | grep "provision" | grep "Satellite Kickstart Default" | cut -d, -f1)

for i in $(hammer --csv os list | grep -vi '^ID' | awk -F, {'print $1'})
do
    hammer partition-table add-operatingsystem --id="{PARTID}" --operatingsystem-id="{i}"
    hammer template add-operatingsystem --id="{PXEID}" --operatingsystem-id="{i}"
    hammer os set-default-template --id="{i}" --config-template-id="{PXEID}"
    hammer os add-config-template --id="{i}" --config-template-id="{SATID}"
    hammer os set-default-template --id="{i}" --config-template-id="{SATID}"
done
```

You can add **grep** commands to the **for** statement to further specify the affected operating systems. To verify if the assignment was performed correctly, use the **hammer os info** command.

5.9. PARAMETERS

Parameters define the behavior of Red Hat Satellite during provisioning. There are several types of parameters, see [Parameters](#) in the *Puppet Guide* for details. Use the following example to set a global parameter:

```
$ hammer global-parameter set --name param_name --value param_value
```

Example 5.2. Setting a Global Parameter to Disable the Firewall

Run the following command to set the **firewall** global option to disabled:

```
$ hammer global-parameter set --name firewall --value --disabled
```

To verify the setting, issue the following command:

```
$ hammer global-parameter list
-----|-----
NAME   | VALUE
```



```

-----|-----
firewall | --disabled
-----|-----

```

Similarly, you can use **hammer** to set other parameter types:

- To set domain parameters, use:

```

$ hammer domain set-parameter \
--name param_name \
--value param_value \
--domain domain_name

```

- To set host group parameters, use:

```

$ hammer hostgroup set-parameter \
--name param_name \
--value param_value \
--hostgroup hg_name

```

- To set host parameters, use:

```

$ hammer host set-parameter \
--name param_name \
--value param_value \
--host h_name

```

- To update smart class parameters, use:

```

$ hammer sc-param \
--name param_name \
--default-value param_value

```

CHAPTER 6. MANAGING HOSTS

Host refers to any physical or virtual system Red Hat Satellite manages. This section shows how to create and configure hosts and host groups using **hammer**. For web UI equivalents of the following procedures see [Managing Hosts](#).

6.1. CREATING A HOST GROUP

A host group is a collection of hosts or host groups. It is recommended to create host groups to hold shared host parameters. Members of the host group inherit these parameters, therefore you do not have to set them individually during host creation. Note that you can nest host groups in a hierarchical manner.

The following command demonstrates a basic set of options for creating a host group:

```
$ hammer hostgroup create \
--name "hostgroup_name" \
--environment "environment_name" \
--architecture "architecture_name" \
--domain domain_name \
--subnet subnet_name \
--puppet-proxy proxy_name \
--puppet-ca-proxy ca-proxy_name \
--operatingsystem "os_name" \
--partition-table "table_name" \
--medium "medium_name" \
--organization-ids org_ID1,org_ID2... \
--location-ids loc_ID1,loc_ID2...
```

See **hammer hostgroup create --help** for the full list of configurable options. There are two settings that cannot be configured during host group creation:

- An activation key has to be added afterwards using:

```
$ hammer hostgroup set-parameter \
--hostgroup "hostgroup_name" \
--name "kt_activation_keys" \
--value key_name
```

Run **hammer activation-key list** to find the activation key name (see [Chapter 4, Managing Activation Keys](#) for details on activation keys).

- The **root** password has to be specified when adding a host to the host group.

Example 6.1. Creating Host Groups for Multiple Content Views

The following Bash script creates a host group for each life cycle environment.

```
MAJOR="7"
OS=$(hammer --output csv os list | awk -F "," "/RedHat ${MAJOR}/ {print \$2;exit}")
ARCH="x86_64"
ORG="ACME"
LOCATIONS="london,munich"
PTABLE_NAME="ptable-acme-os-rhel-server"
```

```

DOMAIN="example.com"

hammer lifecycle-environment list --organization "${ORG}" | awk -F "|" '/[[:digit:]]/{print $2}' | sed
s/ /" | while read LC_ENV
do
  if [[ ${LC_ENV} == "Library" ]]; then
    continue
  fi

  LC_ENV_LOWER=$(echo ${LC_ENV} | tr '[:upper:]' '[:lower:]')
  ParentID=$(hammer --output csv hostgroup list --per-page 999 | awk -F"," "(\${3} ~
/^${LC_ENV_LOWER}$/) {print \$1}")

  hammer hostgroup create --name "rhel-${MAJOR}server-${ARCH}" \
    --medium
"${ORG}/Library/Red_Hat_Server/Red_Hat_Enterprise_Linux_${MAJOR}_Server_Kickstart_${AR
CH}_${MAJOR}
  Server" \
    --parent-id ${ParentID} \
    --architecture "${ARCH}" \
    --operatingsystem "${OS}" \
    --partition-table "${PTABLE_NAME}" \
    --subnet "${DOMAIN}" \
    --domain "${DOMAIN}" \
    --organizations "${ORG}" \
    --locations "${LOCATIONS}" \
    --content-view "cv-os-rhel-${MAJOR}Server" \
    --environment-id $(hammer --output csv environment list --per-page 999 | awk -F"," "(\${3} ~
${ORG}_${LC_ENV}_cv_os_rhel_${MAJOR}Server/ {print \$1}")

  HgID=$(hammer --output csv hostgroup list --per-page 999 | awk -F"," "(\${3} ~
/^${LC_ENV_LOWER}\rhel-${MAJOR}server-${ARCH}$/) {print \$1}")

  hammer hostgroup set-parameter \
    --hostgroup-id "${HgID}" \
    --name "kt_activation_keys" \
    --value "act-${LC_ENV_LOWER}-os-rhel-${MAJOR}server-${ARCH}"
done

```

6.2. CREATING A HOST

It is recommended to set general parameters in a host group to reduce the number of required options when creating a host. The following command creates a basic host associated to a host group:

```

$ hammer host create \
--name "host_name" \
--hostgroup "hostgroup_name" \
--interface="primary=true, \
  provision=true, \
  mac=mac_address, \
  ip=ip_address" \
--organization-id org_ID \
--location-id loc_ID \
--ask-root-password yes

```

After executing the above command you will be prompted to specify the root password. It is required to specify the host's IP and MAC address, other properties of the primary network interface can be inherited from the host group or set using the **subnet**, and **domain** parameters. You can set additional interfaces using the **--interface** option, which accepts a list of key-value pairs. For the list of available interface settings, see [Table 6.1, "Available Keys for the --interface Option"](#).

If you decide to create a host without host group membership, specify additional options described in [\[\]](#). There is a wide range of available host parameters, for details see the output of **hammer host create --help**. The value of certain parameters depends on the type of compute resource the host is provisioned on, see [xref:tabl-CLI_Guide-Host_Options_Specific_to_Provider\[\]](#) for reference.

Table 6.1. Available Keys for the --interface Option

Keys	Description
type	Defines the interface type, one of Nic::Managed , Nic::BMC , Nic::Bond .
name, identifier	Identification of the interface.
mac, ip, domain (or domain_id), subnet (or subnet_id)	Network settings, domain and subnet identification can be inherited from the host group.
primary, provision, managed, virtual	Accept true or false . Managed hosts needs to have one primary and provisioning interface.
Specific to virtual interfaces	
tag	VLAN tag, this attribute has precedence over the subnet VLAN ID.
attached_to	Identifier of the interface to which the virtual interface belongs, for example eth1 .
Specific to bonded interfaces	
mode	Bonding mode, one of balance-rr , active-backup , balance-xor , broadcast , 802.3ad , balance-tlb , balance-alb .
Specific to BMC interfaces	
provider	BMC provider, set to IPMI .
username, password	BMC access credentials.
Specific to hosts provisioned on Libvirt	
compute_type	Interface type, one of bridge , network .

Keys	Description
compute_network or compute_bridge	Specifies interface name, pick one depending on the interface type.
compute_model	One of virtio , rtl8139 , ne2k_pci , pcnet , e1000 .
Specific to hosts provisioned on RHEV	
compute_name	Interface name, for example eth0 .
compute_network	Select one of the available networks for a cluster, use UUID from RHEV.
Specific to hosts provisioned on VMware	
compute_type	Type of the network adapter, depends on your version of vSphere.
compute_network	Network ID form VMware.

Table 6.2. Host Options Specific to Provider

Provider	Keys
Keys for the --compute-attributes option	
EC2	flavor_id, image_id, availability_zone, security_group_ids, managed_ip
GCE	machine_type, image_id, network, external_ip
Libvirt	cpus, memory, start
OpenStack	flavor_ref, image_ref, tenant_id, security_groups, network
RHEV	cluster, template, cores, memory, start
VMware	cpus, corespersocket, memory_mb, cluster, path, guest_id, scsi_controller_type, hardware_version, start
Keys for the --volume option	
Libvirt	poll_name, capacity, format_type

Provider	Keys
RHEV	size_gb, storage_domain, bootable
VMware	datastore, name, size_gb, thin, eager_zero

Example 6.2. Creating a Host with a Bonded Interface Pair

The following example shows how to create a host with a bonded interface pair. For more information on interface bonding see [Configure Network Bonding](#) in the *Red Hat Enterprise Linux Networking Guide*.

```
$ hammer host create --name bondtest \
--hostgroup-id 1 \
--ip=192.168.100.123 \
--mac=52:54:00:14:92:2a \
--subnet-id=1 \
--managed true \
  --interface="identifier=eth1, \
    mac=52:54:00:62:43:06, \
    managed=true, \
    type=Nic::Managed, \
    domain_id=1, \
    subnet_id=1" \
  --interface="identifier=eth2, \
    mac=52:54:00:d3:87:8f, \
    managed=true, \
    type=Nic::Managed, \
    domain_id=1, \
    subnet_id=1" \
  --interface="identifier=bond0, \
    ip=172.25.18.123, \
    type=Nic::Bond, \
    mode=active-backup, \
    attached_devices=[eth1,eth2], \
    managed=true, \
    domain_id=1, \
    subnet_id=1" \
--organization-id 1 \
--location-id 1 \
--ask-root-password yes
```

6.3. CREATING A HOST COLLECTION

A host collection in Red Hat Satellite is a group of hosts. The following command shows the minimal set of options required to create a host collection:

```
$ hammer host-collection create \
--organization-label org_label \
--name hc_name
```

To add hosts to a host collection, issue the following command:

```
$ hammer host-collection add-host \
--id hc_ID \
--host-ids ch_ID1,ch_ID2...
```

Run the following command to associate a host collection with an activation key (see [Chapter 4, Managing Activation Keys](#) for details on activation keys):

```
$ hammer activation-key add-host-collection \
--id ak_ID \
--host-collection hc_name
```

Hosts grouped in the host collection now inherit the configuration from the activation key.

6.4. RUNNING REMOTE JOBS ON HOSTS

The remote execution feature enables defining arbitrary commands on the Satellite Server and executing them on remote hosts. Commands are defined in job templates that are similar to provisioning templates. Several job templates are included by default, you can use them or define a custom template for example to manipulate software packages or start a Puppet process on remote hosts. To use this feature in Hammer, install the remote execution CLI module by executing the following command as **root**:

```
# yum install tfm-rubygem-hammer_cli_foreman_remote_execution
```

To list job templates available, issue:

```
$ hammer job-template list
```

To create a job template using a template-definition file, use a command as follows:

```
$ hammer job-template create \
--file "template" \
--name "template_name" \
--provider-type SSH \
--job-category "category_name"
```

Replace *template* with the path to the file containing the template definition. Specify a custom *category_name* or select one of the existing categories (**Commands**, **Katello**, **Packages**, **Power**, **Puppet**, or **Services**). See the output of **hammer job-template create --help** for information on other available parameters.

To invoke a job with custom parameters, issue:

```
$ hammer job-invocation create \
--job-template "template_name" \
--inputs key1="value",key2="value",... \
--search-query "query"
```

Specify the template name you want to use for the remote job. Specify inputs as a comma separated list of key-value pairs. Run **hammer job-template info** to see what parameters are required by your template. Replace *query* with the filter expression defining which hosts will be affected (for example

"name ~ rex01").

Example 6.3. Starting the httpd Service on Selected Hosts

This example shows how to execute a remote job based on the default **Service Action - SSH Default** template, that will start the **httpd** service on hosts that have a name that contains "target".

```
$ hammer job-invocation create \  
--job-template "Service Action - SSH Default" \  
--inputs service="httpd",action="start" \  
--search-query "name ~ target"
```

To find the ID of a job output, issue:

```
$ hammer job-invocation list
```

To monitor a job output, issue:

```
$ hammer job-invocation output \  
--id job_ID \  
--host host_name
```

To cancel a job output, issue:

```
$ hammer job-invocation cancel \  
--id job_ID
```

For more information on executing remote commands with hammer, issue **hammer job-template --help** or **hammer job-invocation --help**.

CHAPTER 7. MANAGING USERS AND PERMISSIONS

For the administrator, Red Hat Satellite provides the ability to create, modify, and remove users. Also, it is possible to configure access permissions through assigning roles to users. This section shows how to perform these tasks using **hammer**. For web UI equivalents of the following procedures see [Managing Users and Roles](#) in *Administering Red Hat Satellite*.

7.1. CREATING USERS

User in Red Hat Satellite defines a set of details for individuals using the system. To configure a user in Red Hat Satellite, **hammer** provides the **user create** and **user update** commands. Create a new user with the following command:

```
$ hammer user create \
--login user_name \
--password user_password \
--mail user_mail \
--auth-source-id 1 \
--organization-ids org_ID1,org_ID2...
```

The **--auth-source-id 1** setting means that the user is authenticated internally, you can specify an external authentication source as an alternative. Add the **--admin** option to grant administrator privileges to the user. Specifying organization IDs is not required, you can modify the user details later using the **update** subcommand.

For more information on user related subcommands see the output of **hammer user --help**.

7.2. CREATING USER GROUPS

You can manage permissions of several users at once by organizing them into user groups. User groups themselves can be further grouped to create a hierarchy of permissions. Use the following command to create a new user group:

```
$ hammer user-group create --name usergroup_name
```

To add a user to a user group, issue the following command:

```
$ hammer user-group add-user --user user_name --id usergroup_id
```

Find the user group ID by executing **hammer user-group list**. Similarly, you can add user groups using the **add-user-group** subcommand. For more information on operations related to user groups see the output of **hammer user-group --help**.

7.3. CREATING ROLES

Roles in Red Hat Satellite define a set of permissions and access levels. Satellite provides a number of predefined roles, to view them, enter the following command:

```
$ hammer role list
```

To view permissions associated with a role, issue the following command:

```
$ hammer role filters --id role_id
```

Here, *role_id* is the ID of the role from the output of **hammer role list**.

To create a custom role, issue the following command:

```
$ hammer role create --name role_name
```

Add a permission filter to the role with the following command:

```
$ hammer filter create \
  --role role_name \
  --permission-ids perm_ID1,perm_ID2...
```

Find the permissions to be added to the role by using **hammer filter available-permissions**. For details on roles and permissions see the output of **hammer role --help** and **hammer filter --help**.

Example 7.1. Granular Permission Filtering

Red Hat Satellite provides the ability to limit the configured user permissions to selected instances of a resource type. Use the **--search** option to limit permission filters, for example:

```
$ hammer filter create \
  --permission-ids 91 \
  --search "name ~ ccv*" \
  --role qa-user
```

The above command adds to the **qa-user** role a permission to view, create, edit, and destroy Content Views that only applies to Content Views with name starting with **ccv**. See [Granular Permission Filtering](#) in *Administering Red Hat Satellite* for more information.

7.4. ASSIGNING ROLES TO USERS

To assign a role to a user, issue the following command:

```
$ hammer user add-role --id user_id --role role_name
```

Similarly, you can assign a role to a user group:

```
$ hammer user-group add-role --id usergroup_id --role role_name
```

7.5. ADDING SSH KEYS TO A USER

The following steps show how to add public SSH keys to an existing user using the **hammer**. To create SSH keys or for more information, see [Generating Key Pairs](#) in the *Red Hat Enterprise Linux 7 System Administrator's Guide*.

For web UI equivalents of the following procedures see [Adding SSH keys to a User](#) in *Administering Red Hat Satellite*.

Prerequisite

You need either the path to the public SSH key file, or the content of the public SSH key copied to the clipboard.

If you have the public SSH key file:

```
$ hammer user ssh-keys add --user-id user_id --name key_name --key-file ~/.ssh/id_rsa.pub
```

If you have the content of the public SSH key:

```
$ hammer user ssh-keys add --user-id user_id --name key_name --key ecdsa-sha2-nistp256  
AAAAE2VjZHNhLXNoYTltbmlzdHAyNTYAAAAIbmlzdHAyNtYAAABBBHHS2KmNyIYa27Qaa7EHp+2l9  
9ucGStx4P77e03ZvE3yVRJEFikpoP3MJtYYfle8k 1/46MTIZo9CPTX4CYUHeN8= host@user
```

7.6. DELETING SSH KEYS FROM A USER

To delete an SSH key from a user:

```
$ hammer user ssh-keys delete --id key_id --user-id user_id
```

7.7. VIEWING SSH KEYS OF A USER

To view an SSH key attached to a user:

```
$ hammer user ssh-keys info --id key_id --user-id user_id
```

To list SSH keys attached to a user:

```
$ hammer user ssh-keys list --user-id user_id
```

CHAPTER 8. MANAGING ERRATA

Software packages in Red Hat products are subject to updates, referred to as errata, that are released at regular intervals as well as asynchronously. This section shows how to inspect and apply errata using **hammer**. For web UI equivalents of the following procedures see [Managing Errata](#) in the *Content Management Guide*.

8.1. INSPECTING AVAILABLE ERRATA

To view errata that are available for all organizations, issue the following command:

```
$ hammer erratum list
```

Example 8.1. Filtering Errata

The **hammer erratum list** command provides numerous options for filtering and ordering the output list. For example, to find an erratum that contains a specific security fix, issue:

```
$ hammer erratum list --cve CVE-2014-0453
```

The following command displays applicable errata for the selected product that contain the specified bugs ordered so that the security errata are displayed on top:

```
$ hammer erratum list \  
--product-id 7 \  
--search "bug = 1213000 or bug = 1207972" \  
--errata-restrict-applicable 1 \  
--order "type desc"
```

For more information on syntax used in the **--search** option, see [Inspecting Available Errata](#) in the *Content Management Guide*. For more information on filtering options implemented in hammer, see the output of **hammer erratum list --help**.

To view details of a specific erratum, issue the following command:

```
$ hammer erratum info --id erratum_ID
```

Replace *erratum_ID* with a unique identifier of the erratum found in the output of the **hammer erratum list** command. You can identify errata also by name and repository name, see the output of **hammer erratum info --help** for details.

8.2. APPLYING ERRATA TO A HOST

To list errata available for a host, issue the following command:

```
$ hammer host errata list --host hostname
```

To apply selected errata to the host, issue the following command:

```
$ hammer host errata apply \
--host hostname \
--errata-ids erratum_ID1,erratum_ID2...
```

Example 8.2. Applying All Available Errata to a Host

The following Bash script applies all errata available to a host (auth01.example.com):

```
HOST="auth01.example.com"
for i in $(hammer --csv host errata list --host $HOST | grep -vi '^ID' | awk -F, {'print $2'})
do
    hammer host errata apply --host $HOST --errata-ids $i
done
```

Example 8.3. Applying a Security Advisory

This example shows how to apply a security fix to hosts using **hammer**:

1. Find the erratum that contains a fix for a selected issue (CVE-2015-3238):

```
$ hammer erratum list --cve CVE-2015-3238
-----|-----|-----|-----
ID    | ERRATA ID    | TYPE    | TITLE
-----|-----|-----|-----
f30e66 | RHSA-2015:1640 | security | Moderate: pam security update
-----|-----|-----|-----
```

2. Verify if the security erratum (RHSA-2015:1640) is applicable for your host (auth01.example.com):

```
$ hammer host errata list \
--host auth01.example.com \
--search "RHSA-2015:1640"
```

3. Apply the erratum to the host:

```
$ hammer host errata apply \
--host auth01.example.com \
--errata-ids "RHSA-2015:1640"
```

You can use the following Bash script to apply a security erratum (for example RHSA-2015:1640) to all hosts where it is applicable:

```
ORG="ACME"
RHSA="RHSA-2015:1640"

for i in $(hammer --csv host list --organization $ORG | grep -vi '^ID' | awk -F, {'print $2'})
do
    hammer host errata apply --host $i --errata-ids $RHSA
done
```

To see if errata were applied successfully, find the corresponding task in the output of the following command:

```
$ hammer task list
```

To review the state of a selected task, issue the following command:

```
$ hammer task progress --id task_ID
```

8.3. APPLYING ERRATA TO A HOST COLLECTION

To apply selected errata to a Host Collection, enter a command as follows:

```
$ hammer host-collection erratum install \  
--errata "erratum_ID1,erratum_ID2,..." \  
--name "my-collection" --organization $ORG
```

This command is available in Red Hat Satellite 6.2.8 or later.

CHAPTER 9. MANAGING DOCKER CONTAINERS

A Docker container is a sandbox for isolating applications. The container image stores the configuration for the container. This section shows how to use **hammer** to provision Docker containers. For web UI equivalents of the following procedures see [Managing Containers](#) in *Managing Hosts*.

In Red Hat Satellite, you can deploy containers only on a compute resource of the Docker provider type. See [Preparing Container Hosts](#) in *Managing Hosts* for instructions on how to prepare a container host. To register this host as a compute resource, issue the following command:

```
$ hammer compute-resource create
--name cr_name \
--organization-ids org_ID1,org_ID2... \
--location-ids loc_ID1,loc_ID2... \
--url cr_url \
--provider docker
```

Use the following syntax to provision a container on the compute resource:

```
$ hammer docker container create \
--name container_name \
--compute-resource-id cr_ID \
--repository-name repo_name \
--tag tag \
--command command
```

Find the compute resource ID in the output of **hammer compute-resource list**. Replace *repo_name* with the name of the synchronized repository that contains your docker images. This can be a custom repository pointing to Docker Hub or your internal registry (see [J](#)), or the [official Red Hat image repository](#). If you provision from a Content View, replace *repo_name* with the name of the Content View. See [xref:sect-CLI_Guide-Adding_Docker_Images_to_a_Content_View](#) for details on adding images to a Content View.

By starting a container you start the process specified with the **--command** option during the container creation. To start a container, issue the following command:

```
$ hammer docker container start --id container_ID
```

For the full list of container related options, see the output of the **hammer docker container --help** command.

CHAPTER 10. REFERENCE

This chapter provides a list of Hammer usage statements. These usage statements are current to the versions of Hammer and its components released for Satellite 6.5.

10.1. HAMMER

Usage:

```
hammer [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

activation-key	Manipulate activation keys
admin	Administrative server-side tasks
ansible	Manage foreman ansible
architecture	Manipulate architectures
arf-report	Manipulate compliance reports
audit	Search audit trails.
auth	Foreman connection login/logout
auth-source	Manipulate auth sources
bootdisk	Download boot disks
capsule	Manipulate capsule
compute-resource	Manipulate compute resources
config-group	Manipulate config groups
config-report	Browse and read reports
content-view	Manipulate content views
csv	Import to or export from a running foreman server
defaults	Defaults management
discovery	Manipulate discovered hosts.
discovery-rule	Manipulate discovered rules.
docker	Manipulate docker content
domain	Manipulate domains
environment	Manipulate environments
erratum	Manipulate errata
export-templates	Export templates to a git repo or a directory on the server
fact	Search facts
file	Manipulate files
filter	Manage permission filters
foreign-input-set	Manage foreign input sets
full-help	Print help for all hammer commands
global-parameter	Manipulate global parameters
gpg	Manipulate GPG Key actions on the server
host	Manipulate hosts
host-collection	Manipulate host collections
hostgroup	Manipulate hostgroups
import-templates	Import templates from a git repo or a directory on the server
job-invocation	Manage job invocations
job-template	Manage job templates
lifecycle-environment	Manipulate lifecycle_environments on the server
location	Manipulate locations
medium	Manipulate installation media
model	Manipulate hardware models

module-stream	View Module Streams
organization	Manipulate organizations
os	Manipulate operating system
ostree-branch	Manipulate ostree branches
package	Manipulate packages
package-group	Manipulate package groups
partition-table	Manipulate partition tables
ping	Get the status of the server
policy	Manipulate policies
product	Manipulate products
proxy	Manipulate smart proxies
puppet-class	Search puppet modules
puppet-module	View Puppet Module details
realm	Manipulate realms
recurring-logic	Recurring logic related actions
remote-execution-feature	Manage remote execution features
report	Browse and read reports
report-template	Manipulate report templates
repository	Manipulate repositories
repository-set	Manipulate repository sets on the server
role	Manage user roles
sc-param	Manipulate smart class parameters
scap-content	Manipulate SCAP contents
settings	Change server settings
shell	Interactive shell
smart-variable	Manipulate smart variables
subnet	Manipulate subnets
subscription	Manipulate subscriptions
sync-plan	Manipulate sync plans
tailoring-file	Manipulate Tailoring files
task	Tasks related actions.
template	Manipulate config templates
template-input	Manage template inputs
user	Manipulate users
user-group	Manage user groups
virt-who-config	Manage Virt Who configurations

Options:

--[no-]use-defaults	Enable/disable stored defaults. Enabled by default
--autocomplete LINE	Get list of possible endings
--csv	Output as CSV (same as --output=csv)
--csv-separator SEPARATOR	Character to separate the values
--fetch-ca-cert SERVER	Fetch CA certificate from server and exit
--interactive INTERACTIVE	Explicitly turn interactive mode on/off One of true/false, yes/no, 1/0.
--no-headers	Hide headers from output
--output ADAPTER	Set output format. One of [base, table, silent, csv, yaml, json]
--output-file OUTPUT_FILE	Path to custom output file
--show-ids	Show ids of associated resources
--ssl-ca-file CA_FILE	Configure the file containing the CA certificates
--ssl-ca-path CA_PATH	Configure the directory containing the CA certificates
--ssl-client-cert CERT_FILE	Configure the client's public certificate
--ssl-client-key KEY_FILE	Configure the client's private key
--ssl-with-basic-auth	Use standard authentication in addition to client certificate authentication
--verify-ssl VERIFY_SSL	Configure SSL verification of remote system One of true/false, yes/no, 1/0.

```

--version          Show version
-c, --config CFG_FILE  Path to custom config file
-d, --debug        Show debugging output
-h, --help         Print help
-p, --password PASSWORD Password to access the remote system
-q, --quiet        Completely silent
-r, --reload-cache  Force reload of Apipie cache
-s, --server SERVER  Remote system address
-u, --username USERNAME Username to access the remote system
-v, --[no-]verbose  Be verbose (or not). True by default

```

10.2. HAMMER ACTIVATION-KEY

Manipulate activation keys

Usage:

```
hammer activation-key [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```

SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments

```

Subcommands:

```

add-host-collection  Associate a resource
add-subscription     Add subscription
content-override     Override product content defaults
copy                Copy an activation key
create              Create an activation key
delete              Destroy an activation key
host-collections     List associated host collections
info                Show an activation key
list                List activation keys
product-content      List associated products
remove-host-collection Disassociate a resource
remove-subscription  Remove subscription
subscriptions        List associated subscriptions
update              Update an activation key

```

Options:

```
-h, --help          Print help
```

10.2.1. hammer activation-key add-host-collection

Associate a resource

Usage:

```
hammer activation-key add-host-collection [OPTIONS]
```

Options:

```

--host-collection HOST_COLLECTION_NAME  Host collection name to search by
--host-collection-id HOST_COLLECTION_ID Id of the host collection
--id ID                                ID of the activation key
--name NAME                            Activation key name to search by
--organization ORGANIZATION_NAME      Organization name to search by

```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                          Print help
```

10.2.2. hammer activation-key add-subscription

Add subscription

```
Usage:
  hammer activation-key add-subscription [OPTIONS]

Options:
  --id ID                ID of the activation key
  --name NAME            Activation key name to search by
  --organization ORGANIZATION_NAME  Organization name to search by
  --organization-id ORGANIZATION_ID  Organization ID
  --organization-label ORGANIZATION_LABEL Organization label to search by
  --quantity QUANTITY    Quantity of this subscription to add
  --subscription-id SUBSCRIPTION_ID  ID of subscription
  -h, --help            Print help
```

10.2.3. hammer activation-key content-override

Override product content defaults

```
Usage:
  hammer activation-key content-override [OPTIONS]

Options:
  --content-label CONTENT_LABEL  Label of the content
  --id ID                        ID of the activation key
  --name NAME                    Activation key name to search by
  --organization ORGANIZATION_NAME  Organization name to search by
  --organization-id ORGANIZATION_ID  Organization ID
  --organization-label ORGANIZATION_LABEL Organization label to search by
  --override-name OVERRIDE_NAME    Override parameter key or name.
                                   To enable or disable a repo select 'enabled'.
                                   Default value: enabled
                                   Default: "enabled"
  --remove                      Remove a content override
  --value VALUE                  Override value. Note for repo enablement you can use a boolean
value
  -h, --help                    Print help
```

10.2.4. hammer activation-key copy

Copy an activation key

```
Usage:
  hammer activation-key copy [OPTIONS]

Options:
  --id ID                ID of the activation key
```

```

--name NAME                Activation key name to search by
--new-name NEW_NAME        Name of new activation key
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
-h, --help                Print help

```

10.2.5. hammer activation-key create

Create an activation key

Usage:

```
hammer activation-key create [OPTIONS]
```

Options:

```

--content-view CONTENT_VIEW_NAME        Content view name to search by
--content-view-id CONTENT_VIEW_ID        Content view numeric identifier
--description DESCRIPTION                Description
--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME  Environment name
--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
--max-hosts MAX_HOSTS                    Maximum number of registered content hosts
--name NAME                              Name
--organization ORGANIZATION_NAME          Organization name to search by
--organization-id ORGANIZATION_ID          Organization ID
--organization-label ORGANIZATION_LABEL    Organization label to search by
--unlimited-hosts                          Set hosts max to unlimited
-h, --help                                Print help

```

10.2.6. hammer activation-key delete

Destroy an activation key

Usage:

```
hammer activation-key delete [OPTIONS]
```

Options:

```

--id ID                ID of the activation key
--name NAME            Activation key name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
-h, --help            Print help

```

10.2.7. hammer activation-key host-collections

List associated host collections

Usage:

```
hammer activation-key host-collections [OPTIONS]
```

Options:

```

--available-for AVAILABLE_FOR  Interpret specified object to return only Host Collections that
can be

```

```

Associated with specified object. The value 'host' is supported.
--full-result FULL_RESULT      Whether or not to show all results
                                One of true/false, yes/no, 1/0.
--host-id HOST_ID              Filter products by host id
--id ID                        ID of activation key
--name NAME                    Name of activation key
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--sort-by SORT_BY              Field to sort the results on
--sort-order SORT_ORDER        How to order the sorted results (e.g. ASC for ascending)
-h, --help                    Print help

```

10.2.8. hammer activation-key info

Show an activation key

```

Usage:
  hammer activation-key info [OPTIONS]

Options:
--id ID                ID of the activation key
--name NAME            Activation key name to search by
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help            Print help

```

10.2.9. hammer activation-key list

List activation keys

```

Usage:
  hammer activation-key list [OPTIONS]

Options:
--content-view CONTENT_VIEW_NAME      Content view name to search by
--content-view-id CONTENT_VIEW_ID      Content view numeric identifier
--full-result FULL_RESULT              Whether or not to show all results
                                        One of true/false, yes/no, 1/0.
--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Environment name
--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
--name NAME                            Activation key name to filter by
--order ORDER                          Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME        Organization name to search by
--organization-id ORGANIZATION_ID        Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
--page PAGE                             Page number, starting at 1
--per-page PER_PAGE                     Number of results per page to return
--search SEARCH                         Search string
-h, --help                             Print help

```

10.2.10. hammer activation-key product-content

List associated products

Usage:

hammer activation-key product-content [OPTIONS]

Options:

--content-access-mode-all CONTENT_ACCESS_MODE_ALL Get all content available, not just that provided by subscriptions

One of true/false, yes/no, 1/0.

--content-access-mode-env CONTENT_ACCESS_MODE_ENV Limit content to just that available in the activation key's content

View version

One of true/false, yes/no, 1/0.

--id ID

ID of the activation key

--name NAME

Activation key name to search by

--organization ORGANIZATION_NAME

Organization name to search by

--organization-id ORGANIZATION_ID

Organization ID

--organization-label ORGANIZATION_LABEL

Organization label to search by

-h, --help

Print help

10.2.11. hammer activation-key remove-host-collection

Disassociate a resource

Usage:

hammer activation-key remove-host-collection [OPTIONS]

Options:

--host-collection HOST_COLLECTION_NAME Host collection name to search by

--host-collection-id HOST_COLLECTION_ID Id of the host collection

--id ID

ID of the activation key

--name NAME

Activation key name to search by

--organization ORGANIZATION_NAME

Organization name to search by

--organization-id ORGANIZATION_ID

Organization ID

--organization-label ORGANIZATION_LABEL

Organization label to search by

-h, --help

Print help

10.2.12. hammer activation-key remove-subscription

Remove subscription

Usage:

hammer activation-key remove-subscription [OPTIONS]

Options:

--id ID

ID of the activation key

--name NAME

Activation key name to search by

--organization ORGANIZATION_NAME

Organization name to search by

--organization-id ORGANIZATION_ID

Organization ID

--organization-label ORGANIZATION_LABEL

Organization label to search by

--subscription-id SUBSCRIPTION_ID

ID of subscription

-h, --help

Print help

10.2.13. hammer activation-key subscriptions

List associated subscriptions

Usage:

hammer activation-key subscriptions [OPTIONS]

Options:

--activation-key ACTIVATION_KEY_NAME Activation key name to search by
 --activation-key-id ACTIVATION_KEY_ID ID of the activation key
 --available-for AVAILABLE_FOR Object to show subscriptions available for, either 'host' or
 'activation_key'
 --full-result FULL_RESULT Whether or not to show all results
 One of true/false, yes/no, 1/0.
 --host HOST_NAME Host name
 --host-id HOST_ID
 --id ACTIVATION_KEY_ID ID of the activation key
 --match-host MATCH_HOST Ignore subscriptions that are unavailable to the specified host
 One of true/false, yes/no, 1/0.
 --match-installed MATCH_INSTALLED Return subscriptions that match installed products of the
 specified host
 One of true/false, yes/no, 1/0.
 --name ACTIVATION_KEY_NAME Activation key name to search by
 --no-overlap NO_OVERLAP Return subscriptions which do not overlap with a currently-
 attached
 Subscription
 One of true/false, yes/no, 1/0.
 --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --page PAGE Page number, starting at 1
 --per-page PER_PAGE Number of results per page to return
 --search SEARCH Search string
 -h, --help Print help

10.2.14. hammer activation-key update

Update an activation key

Usage:

hammer activation-key update [OPTIONS]

Options:

--auto-attach AUTO_ATTACH Auto attach subscriptions upon registration
 One of true/false, yes/no, 1/0.
 --content-view CONTENT_VIEW_NAME Content view name to search by
 --content-view-id CONTENT_VIEW_ID Content view numeric identifier
 --description DESCRIPTION Description
 --id ID ID of the activation key
 --lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Environment name
 --lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
 --max-hosts MAX_HOSTS Maximum number of registered content hosts
 --name NAME Activation key name to search by
 --new-name NEW_NAME Name

```

--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID      Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--release-version RELEASE_VERSION      Content release version
--service-level SERVICE_LEVEL          Service level
--unlimited-hosts                       Set hosts max to unlimited
-h, --help                             Print help

```

10.3. HAMMER ADMIN

Administrative server-side tasks

```

Usage:
  hammer admin [OPTIONS] SUBCOMMAND [ARG] ...

```

```

Parameters:
  SUBCOMMAND      Subcommand
  [ARG] ...       Subcommand arguments

```

```

Subcommands:
  logging          Logging verbosity level setup

```

```

Options:
  -h, --help      Print help

```

10.3.1. hammer admin logging

Logging verbosity level setup

```

Usage:
  hammer admin logging [OPTIONS]

```

```

Options:
  --no-backup          Skip configuration backups creation.
  --prefix PATH        Operate on prefixed environment (e.g. chroot).
  -a, --all            Apply to all components.
  -c, --components COMPONENTS Components to apply, use --list to get them.
                        Comma separated list of values. Values containing comma should be quoted or
escaped with backslash
  -d, --level-debug    Increase verbosity level to debug.
  -h, --help           Print help
  -l, --list           List available components.
  -n, --dry-run        Do not apply specified changes.
  -p, --level-production Decrease verbosity level to standard.

```

10.4. HAMMER ANSIBLE

Manage foreman ansible

```

Usage:
  hammer ansible [OPTIONS] SUBCOMMAND [ARG] ...

```

```

Parameters:

```


SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

roles	Manage ansible roles
-------	----------------------

Options:

-h, --help	Print help
------------	------------

10.4.1. hammer ansible roles

Manage ansible roles

Usage:

```
hammer ansible roles [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

delete	Deletes Ansible role
import	Import Ansible roles
info	Show role
list	List Ansible roles
obsolete	Obsolete Ansible roles

Options:

-h, --help	Print help
------------	------------

10.4.1.1. hammer ansible roles delete

Deletes Ansible role

Usage:

```
hammer ansible roles delete [OPTIONS]
```

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Name to search by
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.4.1.2. hammer ansible roles import

Import Ansible roles

Usage:

```
hammer ansible roles import [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--proxy-id PROXY_ID           Capsule to import from
--role-names ROLE_NAMES       Ansible role names to import
                               Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
-h, --help                    Print help
-h, --help                    Print help
```

10.4.1.3. hammer ansible roles info

Show role

Usage:

```
hammer ansible roles info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.4.1.4. hammer ansible roles list

List Ansible roles

Usage:

```
hammer ansible roles list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                    Print help
```

10.4.1.5. hammer ansible roles obsolete

Obsolete Ansible roles

Usage:

```
hammer ansible roles obsolete [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--proxy-id PROXY_ID           Capsule to import from
-h, --help                    Print help
-h, --help                    Print help
```

10.5. HAMMER ARCHITECTURE

Manipulate architectures

Usage:

```
hammer architecture [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND      Subcommand
[ARG] ...        Subcommand arguments
```

Subcommands:

```
add-operatingsystem Associate an operating system
create              Create an architecture
delete             Delete an architecture
info               Show an architecture
list               List all architectures
remove-operatingsystem Disassociate an operating system
update             Update an architecture
```

Options:

```
-h, --help      Print help
```

10.5.1. hammer architecture add-operatingsystem

Associate an operating system

Usage:

```
hammer architecture add-operatingsystem [OPTIONS]
```

Options:

```
--id ID
--name NAME      Architecture name
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
-h, --help      Print help
```

10.5.2. hammer architecture create

Create an architecture

Usage:

hammer architecture create [OPTIONS]

Options:

--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME
--operatingsystem-ids OPERATINGSYSTEM_IDS Operating system IDs
 Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.5.3. hammer architecture delete

Delete an architecture

Usage:

hammer architecture delete [OPTIONS]

Options:

--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Architecture name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.5.4. hammer architecture info

Show an architecture

Usage:

hammer architecture info [OPTIONS]

Options:

--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title

```
--name NAME                Architecture name
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                  Print help
```

10.5.5. hammer architecture list

List all architectures

```
Usage:
  hammer architecture list [OPTIONS]

Options:
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--order ORDER                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                   Paginate results
--per-page PER_PAGE           Number of entries per request
--search SEARCH               Filter results
-h, --help                    Print help
```

10.5.6. hammer architecture remove-operatingsystem

Disassociate an operating system

```
Usage:
  hammer architecture remove-operatingsystem [OPTIONS]

Options:
--id ID
--name NAME                Architecture name
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
-h, --help                  Print help
```

10.5.7. hammer architecture update

Update an architecture

```
Usage:
  hammer architecture update [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
```

```

--location-title LOCATION_TITLE      Location title
--name NAME                          Architecture name
--new-name NEW_NAME
--operatingsystem-ids OPERATINGSYSTEM_IDS Operating system IDs
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help

```

10.6. HAMMER ARF-REPORT

Manipulate compliance reports

```

Usage:
  hammer arf-report [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  delete              Delete an ARF Report
  download            Download bzipped ARF report
  download-html       Download ARF report in HTML
  info               Show an ARF report
  list               List ARF reports

Options:
  -h, --help          Print help

```

10.6.1. hammer arf-report delete

Delete an ARF Report

```

Usage:
  hammer arf-report delete [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Name to search by
  --location-id LOCATION_ID
  --organization ORGANIZATION_NAME Name to search by
  --organization-id ORGANIZATION_ID Organization ID
  -h, --help                    Print help

```

10.6.2. hammer arf-report download

Download bzipped ARF report

Usage:

```
hammer arf-report download [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Name to search by
--location-id LOCATION_ID
--organization ORGANIZATION_NAME Name to search by
--organization-id ORGANIZATION_ID Organization ID
--path PATH                   Path to directory where downloaded file will be saved
-h, --help                    Print help
```

10.6.3. hammer arf-report download-html

Download ARF report in HTML

Usage:

```
hammer arf-report download-html [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Name to search by
--location-id LOCATION_ID
--organization ORGANIZATION_NAME Name to search by
--organization-id ORGANIZATION_ID Organization ID
--path PATH                   Path to directory where downloaded file will be saved
-h, --help                    Print help
```

10.6.4. hammer arf-report info

Show an ARF report

Usage:

```
hammer arf-report info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Name to search by
--location-id LOCATION_ID
--organization ORGANIZATION_NAME Name to search by
--organization-id ORGANIZATION_ID Organization ID
-h, --help                    Print help
```

10.6.5. hammer arf-report list

List ARF reports

Usage:

```
hammer arf-report list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
```

```
--location-title LOCATION_TITLE    Location title
--order ORDER                      Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID   Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                        Paginate results
--per-page PER_PAGE                Number of entries per request
--search SEARCH                    Filter results
-h, --help                          Print help
```

10.7. HAMMER AUDIT

Search audit trails.

```
Usage:
  hammer audit [OPTIONS] SUBCOMMAND [ARG] ...
```

```
Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments
```

```
Subcommands:
  info                Show an audit
  list                List all audits
```

```
Options:
  -h, --help          Print help
```

10.7.1. hammer audit info

Show an audit

```
Usage:
  hammer audit info [OPTIONS]
```

```
Options:
  --id ID
  --location LOCATION_NAME    Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                  Print help
```

10.7.2. hammer audit list

List all audits

```
Usage:
  hammer audit list [OPTIONS]
```

```
Options:
```



```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                   Paginate results
--per-page PER_PAGE           Number of entries per request
--search SEARCH               Filter results
-h, --help                   Print help
```

10.8. HAMMER AUTH

Foreman connection login/logout

```
Usage:
  hammer auth [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND      Subcommand
  [ARG] ...       Subcommand arguments

Subcommands:
  login           Set credentials
  logout          Wipe your credentials
  status          Information about current connections

Options:
  -h, --help      Print help
```

10.8.1. hammer auth login

Set credentials

```
Usage:
  hammer auth login [OPTIONS]

Options:
  -h, --help      Print help
  -p, --password PASSWORD Password to access the remote system
  -u, --username USERNAME Username to access the remote system
```

10.8.2. hammer auth logout

Wipe your credentials

```
Usage:
  hammer auth logout [OPTIONS]

Options:
  -h, --help      Print help
```

10.8.3. hammer auth status

Information about current connections

Usage:
hammer auth status [OPTIONS]

Options:
-h, --help Print help

10.9. HAMMER AUTH-SOURCE

Manipulate auth sources

Usage:
hammer auth-source [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
SUBCOMMAND Subcommand
[ARG] ... Subcommand arguments

Subcommands:
ldap Manage LDAP auth sources
list List all auth sources.

Options:
-h, --help Print help

10.9.1. hammer auth-source ldap

Manage LDAP auth sources

Usage:
hammer auth-source ldap [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
SUBCOMMAND Subcommand
[ARG] ... Subcommand arguments

Subcommands:
create Create an LDAP authentication source
delete Delete an LDAP authentication source
info Show an LDAP authentication source
list List all LDAP authentication sources
update Update an LDAP authentication source

Options:
-h, --help Print help

10.9.1.1. hammer auth-source ldap create

Create an LDAP authentication source

Usage:

```
hammer auth-source ldap create [OPTIONS]
```

Options:

```
--account ACCOUNT
--account-password ACCOUNT_PASSWORD    Required if onthefly_register is true
--attr-firstname ATTR_FIRSTNAME        Required if onthefly_register is true
--attr-lastname ATTR_LASTNAME          Required if onthefly_register is true
--attr-login ATTR_LOGIN                Required if onthefly_register is true
--attr-mail ATTR_MAIL                  Required if onthefly_register is true
--attr-photo ATTR_PHOTO
--base-dn BASE_DN
--groups-base GROUPS_BASE              Groups base DN
--host HOST
--ldap-filter LDAP_FILTER               LDAP filter
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS             REPLACE locations with given ids
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE         Location title
--location-titles LOCATION_TITLES      Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--name NAME
--onthefly-register ONTHEFLY_REGISTER  One of true/false, yes/no, 1/0.
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID        Organization ID
--organization-ids ORGANIZATION_IDS      REPLACE organizations with given ids.
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--port PORT                             Defaults to 389
--server-type SERVER_TYPE                Type of the LDAP server
                                         Possible value(s): 'free_ipa', 'active_directory', 'posix'
--tls TLS                                One of true/false, yes/no, 1/0.
--use-netgroups USE_NETGROUPS            Use NIS netgroups instead of posix groups, applicable
only when server_type
                                         Is posix or free_ipa
                                         One of true/false, yes/no, 1/0.
--usergroup-sync USERGROUP_SYNC         Sync external user groups on login
                                         One of true/false, yes/no, 1/0.
-h, --help                               Print help
```

10.9.1.2. hammer auth-source ldap delete

Delete an LDAP authentication source

Usage:

```
hammer auth-source ldap delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.9.1.3. hammer auth-source ldap info

Show an LDAP authentication source

Usage:

```
hammer auth-source ldap info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.9.1.4. hammer auth-source ldap list

List all LDAP authentication sources

Usage:

```
hammer auth-source ldap list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                    Print help
```

10.9.1.5. hammer auth-source ldap update

Update an LDAP authentication source

■

Usage:

```
hammer auth-source ldap update [OPTIONS]
```

Options:

```
--account ACCOUNT
--account-password ACCOUNT_PASSWORD    Required if onthefly_register is true
--attr-firstname ATTR_FIRSTNAME         Required if onthefly_register is true
--attr-lastname ATTR_LASTNAME           Required if onthefly_register is true
--attr-login ATTR_LOGIN                  Required if onthefly_register is true
--attr-mail ATTR_MAIL                   Required if onthefly_register is true
--attr-photo ATTR_PHOTO
--base-dn BASE_DN
--groups-base GROUPS_BASE               Groups base DN
--host HOST
--id ID
--ldap-filter LDAP_FILTER               LDAP filter
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS             REPLACE locations with given ids
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE         Location title
--location-titles LOCATION_TITLES       Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--name NAME                             Name to search by
--new-name NEW_NAME
--onthefly-register ONTHEFLY_REGISTER   One of true/false, yes/no, 1/0.
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID        Organization ID
--organization-ids ORGANIZATION_IDS      REPLACE organizations with given ids.
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--port PORT                             Defaults to 389
--server-type SERVER_TYPE                Type of the LDAP server
                                         Possible value(s): 'free_ipa', 'active_directory', 'posix'
--tls TLS                               One of true/false, yes/no, 1/0.
--use-netgroups USE_NETGROUPS            Use NIS netgroups instead of posix groups, applicable
only when server_type
                                         Is posix or free_ipa
                                         One of true/false, yes/no, 1/0.
--usergroup-sync USERGROUP_SYNC         Sync external user groups on login
                                         One of true/false, yes/no, 1/0.
-h, --help                               Print help
```

10.9.2. hammer auth-source list

List all auth sources.

Usage:

```
hammer auth-source list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                    Print help
```

10.10. HAMMER BOOTDISK

Download boot disks

Usage:

```
hammer bootdisk [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND      Subcommand
[ARG] ...        Subcommand arguments
```

Subcommands:

```
generic          Download generic image
host             Download host image
subnet          Download subnet generic image
```

Options:

```
-h, --help      Print help
```

10.10.1. hammer bootdisk generic

Download generic image

Usage:

```
hammer bootdisk generic [OPTIONS]
```

Options:

```
--file PATH          File or device to write image to
--force              Force writing to existing destination (device etc.)
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--sudo               Use sudo to write to device
-h, --help           Print help
```

10.10.2. hammer bootdisk host

Download host image

Usage:

hammer bootdisk host [OPTIONS]

Options:

--file PATH	File or device to write image to
--force	Force writing to existing destination (device etc.)
--full FULL	True for full, false for basic reusable image
	One of true/false, yes/no, 1/0.
--host HOST_NAME	Host name
--host-id HOST_ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--sudo	Use sudo to write to device
-h, --help	Print help

10.10.3. hammer bootdisk subnet

Download subnet generic image

Usage:

hammer bootdisk subnet [OPTIONS]

Options:

--file PATH	File or device to write image to
--force	Force writing to existing destination (device etc.)
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--subnet SUBNET_NAME	Subnet name
--subnet-id SUBNET_ID	
--sudo	Use sudo to write to device
-h, --help	Print help

10.11. HAMMER CAPSULE

Manipulate capsule

Usage:

hammer capsule [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

content	Manage the capsule content
create	Create a capsule
delete	Delete a capsule
import-classes	Import puppet classes from puppet Capsule
info	Show a capsule
list	List all capsules
refresh-features	Refresh capsule features
update	Update a capsule

Options:

-h, --help	Print help
------------	------------

10.11.1. hammer capsule content

Manage the capsule content

Usage:

```
hammer capsule content [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

add-lifecycle-environment	Add lifecycle environments to the capsule
available-lifecycle-environments	List the lifecycle environments not attached to the capsule
cancel-synchronization	Cancel running capsule synchronization
info	Get current capsule synchronization status
lifecycle-environments	List the lifecycle environments attached to the capsule
remove-lifecycle-environment	Remove lifecycle environments from the capsule
synchronization-status	Get current capsule synchronization status
synchronize	Synchronize the content to the capsule

Options:

-h, --help	Print help
------------	------------

10.11.1.1. hammer capsule content add-lifecycle-environment

Add lifecycle environments to the capsule

Usage:

```
hammer capsule content add-lifecycle-environment [OPTIONS]
```

Options:

--environment ENVIRONMENT_NAME	Environment name
--environment-id ENVIRONMENT_ID	
--id ID	Id of the capsule
--name NAME	Name to search by
--organization NAME	Organization name
--organization-id ID	Organization ID
-h, --help	Print help

10.11.1.2. hammer capsule content available-lifecycle-environments

List the lifecycle environments not attached to the capsule

Usage:

hammer capsule content available-lifecycle-environments [OPTIONS]

Options:

--id ID Id of the capsule
 --name NAME Name to search by
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 -h, --help Print help

10.11.1.3. hammer capsule content cancel-synchronization

Cancel running capsule synchronization

Usage:

hammer capsule content cancel-synchronization [OPTIONS]

Options:

--id ID Id of the capsule
 --name NAME Name to search by
 -h, --help Print help

10.11.1.4. hammer capsule content info

Get current capsule synchronization status

Usage:

hammer capsule content info [OPTIONS]

Options:

--id ID Id of the capsule
 --name NAME Name to search by
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 -h, --help Print help

10.11.1.5. hammer capsule content lifecycle-environments

List the lifecycle environments attached to the capsule

Usage:

hammer capsule content lifecycle-environments [OPTIONS]

Options:

--id ID Id of the capsule
 --name NAME Name to search by
 --organization ORGANIZATION_NAME Organization name to search by

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                            Print help
```

10.11.1.6. hammer capsule content remove-lifecycle-environment

Remove lifecycle environments from the capsule

```
Usage:
  hammer capsule content remove-lifecycle-environment [OPTIONS]
```

```
Options:
--environment ENVIRONMENT_NAME  Environment name
--environment-id ENVIRONMENT_ID
--id ID                          Id of the capsule
--name NAME                      Name to search by
--organization NAME              Organization name
--organization-id ID             Organization ID
-h, --help                       Print help
```

10.11.1.7. hammer capsule content synchronization-status

Get current capsule synchronization status

```
Usage:
  hammer capsule content synchronization-status [OPTIONS]
```

```
Options:
--id ID                          Id of the capsule
--name NAME                      Name to search by
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                       Print help
```

10.11.1.8. hammer capsule content synchronize

Synchronize the content to the capsule

```
Usage:
  hammer capsule content synchronize [OPTIONS]
```

```
Options:
--async                Do not wait for the task
--environment ENVIRONMENT_NAME  Environment name
--environment-id ENVIRONMENT_ID
--id ID                  Id of the capsule
--name NAME              Name to search by
--organization NAME       Organization name
--organization-id ID      Organization ID
--skip-metadata-check SKIP_METADATA_CHECK Skip metadata check on each repository on the
```

capsule	One of true/false, yes/no, 1/0.
-h, --help	Print help

10.11.2. hammer capsule create

Create a capsule

Usage:

hammer capsule create [OPTIONS]

Options:

--download-policy DOWNLOAD_POLICY	Download Policy of the capsule, must be one of immediate, on_demand,
	Background, inherit
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-ids LOCATION_IDS	REPLACE locations with given ids
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--location-title LOCATION_TITLE	Location title
--location-titles LOCATION_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--locations LOCATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--name NAME	
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-ids ORGANIZATION_IDS	REPLACE organizations with given ids.
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE	Organization title
--organization-titles ORGANIZATION_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--url URL	
-h, --help	Print help

10.11.3. hammer capsule delete

Delete a capsule

Usage:

hammer capsule delete [OPTIONS]

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Name to search by
--organization ORGANIZATION_NAME	Organization name

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help
```

10.11.4. hammer capsule import-classes

Import puppet classes from puppet Capsule

```
Usage:
  hammer capsule import-classes [OPTIONS]

Options:
  --dryrun                Do not run the import
  --environment ENVIRONMENT_NAME    Environment name
  --environment-id ENVIRONMENT_ID
  --except EXCEPT              Optional comma-delimited string containing either 'new',
                                'updated', or 'obsolete' that is used to limit the imported
                                Puppet classes
  --id ID
  --location LOCATION_NAME        Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE    Location title
  --name NAME                    Name to search by
  --organization ORGANIZATION_NAME    Organization name
  --organization-id ORGANIZATION_ID    Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                    Print help
```

10.11.5. hammer capsule info

Show a capsule

```
Usage:
  hammer capsule info [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME        Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE    Location title
  --name NAME                    Name to search by
  --organization ORGANIZATION_NAME    Organization name
  --organization-id ORGANIZATION_ID    Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                    Print help
```

10.11.6. hammer capsule list

List all capsules

```
Usage:
  hammer capsule list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                     Paginate results
--per-page PER_PAGE             Number of entries per request
--search SEARCH                 Filter results
-h, --help                      Print help
```

10.11.7. hammer capsule refresh-features

Refresh capsule features

Usage:

```
hammer capsule refresh-features [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help
```

10.11.8. hammer capsule update

Update a capsule

Usage:

```
hammer capsule update [OPTIONS]
```

Options:

```
--download-policy DOWNLOAD_POLICY Download Policy of the capsule, must be one of
immediate, on_demand,
                                Background, inherit
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS   REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--name NAME                    Name to search by
```

```

--new-name NEW_NAME
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-ids ORGANIZATION_IDS    REPLACE organizations with given ids.
                                       Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES     Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--url URL
-h, --help                             Print help

```

10.12. HAMMER COMPUTE-RESOURCE

Manipulate compute resources

```

Usage:
  hammer compute-resource [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND      Subcommand
  [ARG] ...       Subcommand arguments

Subcommands:
  clusters      List available clusters for a compute resource
  create        Create a compute resource
  delete        Delete a compute resource
  flavors       List available flavors for a compute resource
  folders       List available folders for a compute resource
  image         View and manage compute resource's images
  images        List available images for a compute resource
  info          Show a compute resource
  list          List all compute resources
  networks      List available networks for a compute resource
  resource-pools List resource pools for a compute resource cluster
  security-groups List available security groups for a compute resource
  storage-domains List storage domains for a compute resource
  storage-pods  List storage pods for a compute resource
  update        Update a compute resource
  zones        List available zone for a compute resource

Options:
  -h, --help      Print help

```

10.12.1. hammer compute-resource clusters

List available clusters for a compute resource

```

Usage:
  hammer compute-resource clusters [OPTIONS]

Options:

```

```

--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Compute resource name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                      Print help

```

10.12.2. hammer compute-resource create

Create a compute resource

Usage:

```
hammer compute-resource create [OPTIONS]
```

Options:

```

--caching-enabled CACHING_ENABLED      Enable caching, for VMware only
                                         One of true/false, yes/no, 1/0.
--datacenter DATACENTER                 For RHEV, VMware Datacenter
--description DESCRIPTION
--display-type DISPLAY_TYPE             For Libvirt only
                                         Possible value(s): 'VNC', 'SPICE'
--domain DOMAIN                         For RHEL OpenStack Platform only
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS             REPLACE locations with given ids
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE         Location title
--location-titles LOCATION_TITLES       Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--locations LOCATION_NAMES              Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--name NAME
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID       Organization ID
--organization-ids ORGANIZATION_IDS     REPLACE organizations with given ids.
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--ovirt-quota OVIRT_QUOTA                For RHEV only, ID of quota to use
--password PASSWORD                     Password for RHEV, EC2, VMware, RHEL OpenStack
Platform. Secret key for EC2
--provider PROVIDER                     Providers include Libvirt, Ovirt, EC2, VMware, Openstack,
Rackspace, GCE,
                                         Docker
--region REGION                         For EC2 only, use 'us-gov-west-1' for GovCloud region
--server SERVER                         For VMware
--set-console-password SET_CONSOLE_PASSWORD For Libvirt and VMware only

```

	One of true/false, yes/no, 1/0.
--tenant TENANT	For RHEL OpenStack Platform only
--url URL	URL for Docker, Libvirt, RHEV, RHEL OpenStack Platform and Rackspace
--use-v4 USE_V4	For RHEV only
	One of true/false, yes/no, 1/0.
--user USER	Username for RHEV, EC2, VMware, RHEL OpenStack Platform.
Access Key for	
	EC2.
--uuid UUID	Deprecated, please use datacenter
-h, --help	Print help

10.12.3. hammer compute-resource delete

Delete a compute resource

```
Usage:
  hammer compute-resource delete [OPTIONS]

Options:
  --id ID                                Location name
  --location LOCATION_NAME               Location name
  --location-id LOCATION_ID              Location title
  --location-title LOCATION_TITLE        Location title
  --name NAME                            Compute resource name
  --organization ORGANIZATION_NAME       Organization name
  --organization-id ORGANIZATION_ID       Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                             Print help
```

10.12.4. hammer compute-resource flavors

List available flavors for a compute resource

```
Usage:
  hammer compute-resource flavors [OPTIONS]

Options:
  --id ID                                Location name
  --location LOCATION_NAME               Location name
  --location-id LOCATION_ID              Location title
  --location-title LOCATION_TITLE        Location title
  --name NAME                            Compute resource name
  --organization ORGANIZATION_NAME       Organization name
  --organization-id ORGANIZATION_ID       Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                             Print help
```

10.12.5. hammer compute-resource folders

List available folders for a compute resource

```
Usage:
```



```
hammer compute-resource folders [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Compute resource name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.12.6. hammer compute-resource image

View and manage compute resource's images

Usage:

```
hammer compute-resource image [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND      Subcommand
[ARG] ...        Subcommand arguments
```

Subcommands:

```
available      Show images available for addition
create         Create an image
delete         Delete an image
info           Show an image
list           List all images for a compute resource
update         Update an image
```

Options:

```
-h, --help      Print help
```

10.12.6.1. hammer compute-resource image available

Show images available for addition

Usage:

```
hammer compute-resource image available [OPTIONS]
```

Options:

```
--compute-resource NAME      Compute resource name
--compute-resource-id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.12.6.2. hammer compute-resource image create

Create an image

Usage:

```
hammer compute-resource image create [OPTIONS]
```

Options:

```
--architecture ARCHITECTURE_NAME      Architecture name
--architecture-id ARCHITECTURE_ID
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE          Location title
--name NAME
--operatingsystem OPERATINGSYSTEM_TITLE  Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID        Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
--password PASSWORD
--user-data USER_DATA                   Whether or not the image supports user data
                                         One of true/false, yes/no, 1/0.
--username USERNAME
--uuid UUID
-h, --help                               Print help
```

10.12.6.3. hammer compute-resource image delete

Delete an image

Usage:

```
hammer compute-resource image delete [OPTIONS]
```

Options:

```
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE            Location title
--name NAME                               Name to search by
--organization ORGANIZATION_NAME          Organization name
--organization-id ORGANIZATION_ID          Organization ID
--organization-title ORGANIZATION_TITLE    Organization title
-h, --help                               Print help
```

10.12.6.4. hammer compute-resource image info

Show an image

Usage:

```
hammer compute-resource image info [OPTIONS]
```

Options:

```
--architecture ARCHITECTURE_NAME      Architecture name
--architecture-id ARCHITECTURE_ID
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE          Location title
--name NAME                             Name to search by
--operatingsystem OPERATINGSYSTEM_TITLE  Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--organization ORGANIZATION_NAME         Organization name
--organization-id ORGANIZATION_ID         Organization ID
--organization-title ORGANIZATION_TITLE   Organization title
-h, --help                               Print help
```

10.12.6.5. hammer compute-resource image list

List all images for a compute resource

Usage:

```
hammer compute-resource image list [OPTIONS]
```

Options:

```
--architecture ARCHITECTURE_NAME      Architecture name
--architecture-id ARCHITECTURE_ID
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE          Location title
--operatingsystem OPERATINGSYSTEM_TITLE  Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--order ORDER                           Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME         Organization name
--organization-id ORGANIZATION_ID         Organization ID
--organization-title ORGANIZATION_TITLE   Organization title
--page PAGE                              Paginate results
--per-page PER_PAGE                       Number of entries per request
--search SEARCH                           Filter results
-h, --help                               Print help
```

10.12.6.6. hammer compute-resource image update

Update an image

Usage:

```
hammer compute-resource image update [OPTIONS]
```

Options:

```
--architecture ARCHITECTURE_NAME      Architecture name
--architecture-id ARCHITECTURE_ID
```

```

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Name to search by
--new-name NEW_NAME
--operatingsystem OPERINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERINGSYSTEM_ID
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--password PASSWORD
--user-data USER_DATA Whether or not the image supports user data
                        One of true/false, yes/no, 1/0.
--username USERNAME
--uuid UUID
-h, --help Print help

```

10.12.7. hammer compute-resource images

List available images for a compute resource

```

Usage:
  hammer compute-resource images [OPTIONS]

Options:
--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Compute resource name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

```

10.12.8. hammer compute-resource info

Show a compute resource

```

Usage:
  hammer compute-resource info [OPTIONS]

Options:
--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Compute resource name
--organization ORGANIZATION_NAME Organization name

```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help
```

10.12.9. hammer compute-resource list

List all compute resources

```
Usage:
  hammer compute-resource list [OPTIONS]

Options:
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                   Paginate results
--per-page PER_PAGE           Number of entries per request
--search SEARCH               Filter results
-h, --help                    Print help
```

10.12.10. hammer compute-resource networks

List available networks for a compute resource

```
Usage:
  hammer compute-resource networks [OPTIONS]

Options:
--cluster-id CLUSTER_ID
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Compute resource name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.12.11. hammer compute-resource resource-pools

List resource pools for a compute resource cluster

```
Usage:
  hammer compute-resource resource-pools [OPTIONS]

Options:
--cluster-id CLUSTER_ID
--id ID
```

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Compute resource name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help
```

10.12.12. hammer compute-resource security-groups

List available security groups for a compute resource

```
Usage:
  hammer compute-resource security-groups [OPTIONS]
```

```
Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Compute resource name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help
```

10.12.13. hammer compute-resource storage-domains

List storage domains for a compute resource

```
Usage:
  hammer compute-resource storage-domains [OPTIONS]
```

```
Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Compute resource name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--storage-domain STORAGE_DOMAIN
-h, --help                     Print help
```

10.12.14. hammer compute-resource storage-pods

List storage pods for a compute resource

```
Usage:
  hammer compute-resource storage-pods [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Compute resource name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--storage-pod STORAGE_POD
-h, --help                    Print help
```

10.12.15. hammer compute-resource update

Update a compute resource

Usage:

```
hammer compute-resource update [OPTIONS]
```

Options:

```
--caching-enabled CACHING_ENABLED      Enable caching, for VMware only
                                         One of true/false, yes/no, 1/0.
--datacenter DATACENTER                 For RHEV, VMware Datacenter
--description DESCRIPTION
--display-type DISPLAY_TYPE             For Libvirt only
                                         Possible value(s): 'VNC', 'SPICE'
--domain DOMAIN                        For RHEL OpenStack Platform only
--id ID
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS             REPLACE locations with given ids
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE         Location title
--location-titles LOCATION_TITLES       Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--locations LOCATION_NAMES              Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--name NAME                             Compute resource name
--new-name NEW_NAME
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID       Organization ID
--organization-ids ORGANIZATION_IDS     REPLACE organizations with given ids.
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--ovirt-quota OVIRT_QUOTA               For RHEV only, ID of quota to use
--password PASSWORD                    Password for RHEV, EC2, VMware, RHEL OpenStack
Platform. Secret key for EC2
--provider PROVIDER                    Providers include Libvirt, Ovirt, EC2, VMware, Openstack,
Rackspace, GCE,
```

	Docker	
--region REGION		For EC2 only, use 'us-gov-west-1' for GovCloud region
--server SERVER		For VMware
--set-console-password SET_CONSOLE_PASSWORD		For Libvirt and VMware only
		One of true/false, yes/no, 1/0.
--tenant TENANT		For RHEL OpenStack Platform only
--url URL		URL for Docker, Libvirt, RHEV, RHEL OpenStack Platform and Rackspace
--use-v4 USE_V4		For RHEV only
		One of true/false, yes/no, 1/0.
--user USER		Username for RHEV, EC2, VMware, RHEL OpenStack Platform.
Access Key for		
	EC2.	
--uuid UUID		Deprecated, please use datacenter
-h, --help		Print help

10.12.16. hammer compute-resource zones

List available zone for a compute resource

```
Usage:
  hammer compute-resource zones [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE       Location title
  --name NAME                           Compute resource name
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                            Print help
```

10.13. HAMMER CONFIG-GROUP

Manipulate config groups

```
Usage:
  hammer config-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  create              Create a config group
  delete              Delete a config group
  info                Show a config group
  list                List of config groups
  update              Update a config group

Options:
  -h, --help          Print help
```


10.13.1. hammer config-group create

Create a config group

Usage:

```
hammer config-group create [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--puppet-class-ids PUPPET_CLASS_IDS Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
-h, --help                    Print help
```

10.13.2. hammer config-group delete

Delete a config group

Usage:

```
hammer config-group delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                  Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.13.3. hammer config-group info

Show a config group

Usage:

```
hammer config-group info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                  Name to search by
--organization ORGANIZATION_NAME Organization name
```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help
```

10.13.4. hammer config-group list

List of config groups

Usage:

```
hammer config-group list [OPTIONS]
```

Options:

```
--location LOCATION_NAME          Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE    Location title
--order ORDER                      Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME   Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                        Paginate results
--per-page PER_PAGE                Number of entries per request
--search SEARCH                    Filter results
-h, --help                          Print help
```

10.13.5. hammer config-group update

Update a config group

Usage:

```
hammer config-group update [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME          Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE    Location title
--name NAME                       Name to search by
--new-name NEW_NAME
--organization ORGANIZATION_NAME   Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--puppet-class-ids PUPPET_CLASS_IDS Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
-h, --help                          Print help
```

10.14. HAMMER CONFIG-REPORT

Browse and read reports

Usage:

```
hammer config-report [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

delete	Delete a report
info	Show a report
list	List all reports

Options:

-h, --help	Print help
------------	------------

10.14.1. hammer config-report delete

Delete a report

Usage:

```
hammer config-report delete [OPTIONS]
```

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.14.2. hammer config-report info

Show a report

Usage:

```
hammer config-report info [OPTIONS]
```

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.14.3. hammer config-report list

List all reports

Usage:

```
hammer config-report list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                     Print help
```

10.15. HAMMER CONTENT-VIEW

Manipulate content views

Usage:

```
hammer content-view [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...            Subcommand arguments
```

Subcommands:

```
add-repository      Associate a resource
add-version          Add a content view version to a composite view
component            View and manage components
copy                 Copy a content view
create               Create a content view
delete               Delete a content view
filter               View and manage filters
info                 Show a content view
list                 List content views
publish              Publish a content view
puppet-module        View and manage puppet modules
purge                Delete old versions of a content view
remove               Remove versions and/or environments from a content view and reassign
systems and keys
remove-from-environment Remove a content view from an environment
remove-repository    Disassociate a resource
remove-version        Remove a content view version from a composite view
update               Update a content view
version              View and manage content view versions
```

Options:

```
-h, --help          Print help
```

10.15.1. hammer content-view add-repository

Associate a resource

Usage:

```
hammer content-view add-repository [OPTIONS]
```

Options:

```
--id ID                      Content view numeric identifier
--name NAME                  Content view name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL  Organization label to search by
--product PRODUCT_NAME        Product name to search by
--product-id PRODUCT_ID       Product numeric identifier
--repository REPOSITORY_NAME   Repository name to search by
--repository-id REPOSITORY_ID  Repository ID
-h, --help                    Print help
```

10.15.2. hammer content-view add-version

Add a content view version to a composite view

Usage:

```
hammer content-view add-version [OPTIONS]
```

Options:

```
--content-view CONTENT_VIEW_NAME      Content view name to search by
--content-view-id CONTENT_VIEW_ID      Content view numeric identifier
--content-view-version CONTENT_VIEW_VERSION_VERSION  Content view version number
--content-view-version-id CONTENT_VIEW_VERSION_ID  Content view version identifier
--id ID                      Content view numeric identifier
--name NAME                  Content view name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL  Organization label to search by
-h, --help                    Print help
```

10.15.3. hammer content-view component

View and manage components

Usage:

```
hammer content-view component [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments
```

Subcommands:

```
add                Add components to the content view
list               List components attached to this content view
remove             Remove components from the content view
update             Update a component associated with the content view
```

Options:

```
-h, --help          Print help
```

10.15.3.1. hammer content-view component add

Add components to the content view

Usage:

```
hammer content-view component add [OPTIONS]
```

Options:

```
--component-content-view COMPONENT_CONTENT_VIEW_NAME      Content View
name of the component who's latest version is desired
--component-content-view-id COMPONENT_CONTENT_VIEW_ID      Content View
identifier of the component who's latest version is desired
--component-content-view-version COMPONENT_CONTENT_VIEW_VERSION_VERSION Content
View Version number of the component. Either use this or --component-content-view-version-id
option
--component-content-view-version-id COMPONENT_CONTENT_VIEW_VERSION_ID Content
View Version identifier of the component
--composite-content-view COMPOSITE_CONTENT_VIEW_NAME      Name of the
composite content view
--composite-content-view-id COMPOSITE_CONTENT_VIEW_ID      Composite content
view identifier
--latest                                                    Select the latest version of the components content
view is desired
--organization ORGANIZATION_NAME                          Organization name to search by
--organization-id ORGANIZATION_ID                          Organization ID to search by
--organization-label ORGANIZATION_LABEL                    Organization label to search by
-h, --help                                                  Print help
```

10.15.3.2. hammer content-view component list

List components attached to this content view

Usage:

```
hammer content-view component list [OPTIONS]
```

Options:

```
--composite-content-view COMPOSITE_CONTENT_VIEW_NAME      Name of the composite content
view
--composite-content-view-id COMPOSITE_CONTENT_VIEW_ID      Composite content view identifier
--organization ORGANIZATION_NAME                          Organization name to search by
--organization-id ORGANIZATION_ID                          Organization ID to search by
--organization-label ORGANIZATION_LABEL                    Organization label to search by
-h, --help                                                  Print help
```

10.15.3.3. hammer content-view component remove

Remove components from the content view

Usage:

```
hammer content-view component remove [OPTIONS]
```

Options:

```
--component-content-view-ids COMPONENT_CONTENT_VIEW_IDS Array of component content
view identifiers to remove. Comma separated list of values
```

```

--component-content-views COMPONENT_CONTENT_VIEW_NAMES  Array of component content
view names to remove. Comma separated list of values
--component-ids COMPONENT_IDS                          Array of content view component IDs to
remove. Identifier of the component
                                     Association
                                     Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--composite-content-view COMPOSITE_CONTENT_VIEW_NAME    Name of the composite content
view
--composite-content-view-id COMPOSITE_CONTENT_VIEW_ID    Composite content view identifier
--organization ORGANIZATION_NAME                        Organization name to search by
--organization-id ORGANIZATION_ID                       Organization ID to search by
--organization-label ORGANIZATION_LABEL                 Organization label to search by
-h, --help                                              Print help

```

10.15.3.4. hammer content-view component update

Update a component associated with the content view

```

Usage:
  hammer content-view component update [OPTIONS]

Options:
--component-content-view COMPONENT_CONTENT_VIEW_NAME    Content View
name of the component who's latest version is desired
--component-content-view-id COMPONENT_CONTENT_VIEW_ID    Content View
identifier of the component who's latest version is desired
--component-content-view-version COMPONENT_CONTENT_VIEW_VERSION_VERSION Content
View Version number of the component. Either use this or --component-content-view-version-id
option
--component-content-view-version-id COMPONENT_CONTENT_VIEW_VERSION_ID Content
View Version identifier of the component
--composite-content-view COMPOSITE_CONTENT_VIEW_NAME    Name of the
composite content view
--composite-content-view-id COMPOSITE_CONTENT_VIEW_ID    Composite content
view identifier
--id ID                                                  Content view component ID. Identifier of the
component association
--latest                                                Select the latest version of the components content
view is desired
--organization ORGANIZATION_NAME                        Organization name to search by
--organization-id ORGANIZATION_ID                       Organization ID to search by
--organization-label ORGANIZATION_LABEL                 Organization label to search by
-h, --help                                              Print help

```

10.15.4. hammer content-view copy

Copy a content view

```

Usage:
  hammer content-view copy [OPTIONS]

Options:
--id ID          Content view numeric identifier

```

```

--name NAME                Content view name to search by
--new-name NEW_NAME        New content view name
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL  Organization label to search by
-h, --help                Print help

```

10.15.5. hammer content-view create

Create a content view

Usage:

```
hammer content-view create [OPTIONS]
```

Options:

```

--auto-publish AUTO_PUBLISH  Enable/Disable auto publish of composite view
                              One of true/false, yes/no, 1/0.
--component-ids COMPONENT_IDS  List of component content view version ids for composite
views
                              Comma separated list of values. Values containing comma should be
                              quoted or escaped with backslash
--composite                  Create a composite content view
--description DESCRIPTION    Description for the content view
--label LABEL                Content view label
--name NAME                  Name of the content view
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
--product PRODUCT_NAME       Product name to search by
--product-id PRODUCT_ID       Product numeric identifier
--repositories REPOSITORY_NAMES  Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--repository-ids REPOSITORY_IDS  List of repository ids
                              Comma separated list of values. Values containing comma should be
                              quoted or escaped with backslash
-h, --help                  Print help

```

10.15.6. hammer content-view delete

Delete a content view

Usage:

```
hammer content-view delete [OPTIONS]
```

Options:

```

--async                    Do not wait for the task
--id ID                    Content view numeric identifier
--name NAME                Content view name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL  Organization label to search by
-h, --help                Print help

```


10.15.7. hammer content-view filter

View and manage filters

Usage:

hammer content-view filter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

add-repository	Associate a resource
create	Create a filter for a content view
delete	Delete a filter
info	Show filter info
list	List filters
remove-repository	Disassociate a resource
rule	View and manage filter rules
update	Update a filter

Options:

-h, --help	Print help
------------	------------

10.15.7.1. hammer content-view filter add-repository

Associate a resource

Usage:

hammer content-view filter add-repository [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME	Content view name to search by
--content-view-id CONTENT_VIEW_ID	Content view numeric identifier
--id ID	Filter identifier
--name NAME	Name to search by
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID to search by
--organization-label ORGANIZATION_LABEL	Organization label to search by
--product PRODUCT_NAME	Product name to search by
--product-id PRODUCT_ID	Product numeric identifier
--repository REPOSITORY_NAME	Repository name to search by
--repository-id REPOSITORY_ID	Repository ID
-h, --help	Print help

10.15.7.2. hammer content-view filter create

create a filter for a content view

Usage:

hammer content-view filter create [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME	Content view name to search by
----------------------------------	--------------------------------

```

--content-view-id CONTENT_VIEW_ID    Content view numeric identifier
--description DESCRIPTION             Description of the filter
--inclusion INCLUSION                 Specifies if content should be included or excluded, default:
                                     Inclusion=false
                                     One of true/false, yes/no, 1/0.
--name NAME                           Name of the filter
--organization ORGANIZATION_NAME     Organization name to search by
--organization-id ORGANIZATION_ID    Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
--original-packages ORIGINAL_PACKAGES Add all packages without errata to the
included/excluded list. (package
                                     Filter only)
                                     One of true/false, yes/no, 1/0.
--product PRODUCT_NAME               Product name to search by
--product-id PRODUCT_ID              Product numeric identifier
--repositories REPOSITORY_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--repository-ids REPOSITORY_IDS      List of repository ids
                                     Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--type TYPE                           Type of filter (e.g. rpm, package_group, erratum, docker)
-h, --help                           Print help

```

10.15.7.3. hammer content-view filter delete

delete a filter

```

Usage:
  hammer content-view filter delete [OPTIONS]

Options:
--content-view CONTENT_VIEW_NAME    Content view name to search by
--content-view-id CONTENT_VIEW_ID   Content view numeric identifier
--id ID                             Filter identifier
--name NAME                         Name to search by
--organization ORGANIZATION_NAME    Organization name to search by
--organization-id ORGANIZATION_ID   Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                           Print help

```

10.15.7.4. hammer content-view filter info

show filter info

```

Usage:
  hammer content-view filter info [OPTIONS]

Options:
--content-view CONTENT_VIEW_NAME    Content view name to search by
--content-view-id CONTENT_VIEW_ID   Content view numeric identifier
--id ID                             Filter identifier
--name NAME                         Name to search by
--organization ORGANIZATION_NAME    Organization name to search by

```

```
--organization-id ORGANIZATION_ID    Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                            Print help
```

10.15.7.5. hammer content-view filter list

list filters

Usage:

```
hammer content-view filter list [OPTIONS]
```

Options:

```
--content-view CONTENT_VIEW_NAME    Content view name to search by
--content-view-id CONTENT_VIEW_ID    Content view numeric identifier
--full-result FULL_RESULT            Whether or not to show all results
                                     One of true/false, yes/no, 1/0.
--name NAME                          Filter content view filters by name
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME     Organization name to search by
--organization-id ORGANIZATION_ID    Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
--page PAGE                          Page number, starting at 1
--per-page PER_PAGE                  Number of results per page to return
--search SEARCH                      Search string
--types TYPES                        Types of filters
                                     Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
-h, --help                            Print help
```

10.15.7.6. hammer content-view filter remove-repository

Disassociate a resource

Usage:

```
hammer content-view filter remove-repository [OPTIONS]
```

Options:

```
--content-view CONTENT_VIEW_NAME    Content view name to search by
--content-view-id CONTENT_VIEW_ID    Content view numeric identifier
--id ID                              Filter identifier
--name NAME                          Name to search by
--organization ORGANIZATION_NAME     Organization name to search by
--organization-id ORGANIZATION_ID    Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
--product PRODUCT_NAME               Product name to search by
--product-id PRODUCT_ID              Product numeric identifier
--repository REPOSITORY_NAME         Repository name to search by
--repository-id REPOSITORY_ID        Repository ID
-h, --help                            Print help
```

10.15.7.7. hammer content-view filter rule

View and manage filter rules

■

Usage:

```
hammer content-view filter rule [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...            Subcommand arguments
```

Subcommands:

```
create              Create a filter rule. The parameters included should be based upon the filter
type.
delete             Delete a filter rule
info               Show filter rule info
list               List filter rules
update             Update a filter rule. The parameters included should be based upon the filter
type.
```

Options:

```
-h, --help          Print help
```

10.15.7.8. hammer content-view filter rule create

Create a filter rule. The parameters included should be based upon the filter type.

Usage:

```
hammer content-view filter rule create [OPTIONS]
```

Options:

```
--architecture ARCHITECTURE      Package: architecture
--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-filter CONTENT_VIEW_FILTER_NAME  Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID  Filter identifier
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--date-type DATE_TYPE             Erratum: search using the 'Issued On' or 'Updated On'
                                  Column of the errata. Values are 'issued'/'updated'
--end-date END_DATE               Erratum: end date (YYYY-MM-DD)
--errata-id ERRATA_ID             Erratum: id
--errata-ids ERRATA_IDS           Erratum: IDs or a select all object
                                  Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--max-version MAX_VERSION         Package: maximum version
--min-version MIN_VERSION         Package: minimum version
--name NAME                       Package, package group, or docker tag names
                                  Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--names NAMES                     Package and package group names
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL  Organization label to search by
--start-date START_DATE           Erratum: start date (YYYY-MM-DD)
--types TYPES                     Erratum: types (enhancement, bugfix, security)
                                  Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--uuid UUID                       Package group: uuid
--version VERSION                 Package: version
-h, --help                       Print help
```

10.15.7.9. hammer content-view filter rule delete

Delete a filter rule

Usage:

```
hammer content-view filter rule delete [OPTIONS]
```

Options:

```
--content-view CONTENT_VIEW_NAME      Content view name to search by
--content-view-filter CONTENT_VIEW_FILTER_NAME  Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID  Filter identifier
--content-view-id CONTENT_VIEW_ID          Content view numeric identifier
--id ID                                    Rule identifier
--name NAME                                Name to search by
--organization ORGANIZATION_NAME          Organization name to search by
--organization-id ORGANIZATION_ID          Organization ID to search by
--organization-label ORGANIZATION_LABEL    Organization label to search by
-h, --help                                Print help
```

10.15.7.10. hammer content-view filter rule info

Show filter rule info

Usage:

```
hammer content-view filter rule info [OPTIONS]
```

Options:

```
--content-view CONTENT_VIEW_NAME      Content view name to search by
--content-view-filter CONTENT_VIEW_FILTER_NAME  Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID  Filter identifier
--content-view-id CONTENT_VIEW_ID          Content view numeric identifier
--id ID                                    Rule identifier
--name NAME                                Name to search by
--organization ORGANIZATION_NAME          Organization name to search by
--organization-id ORGANIZATION_ID          Organization ID to search by
--organization-label ORGANIZATION_LABEL    Organization label to search by
-h, --help                                Print help
```

10.15.7.11. hammer content-view filter rule list

List filter rules

Usage:

```
hammer content-view filter rule list [OPTIONS]
```

Options:

```
--content-view CONTENT_VIEW_NAME      Content view name to search by
--content-view-filter CONTENT_VIEW_FILTER_NAME  Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID  Filter identifier
--content-view-id CONTENT_VIEW_ID          Content view numeric identifier
--errata-id ERRATA_ID                  Errata_id of the content view filter rule
--full-result FULL_RESULT              Whether or not to show all results
                                         One of true/false, yes/no, 1/0.
--name NAME                            Name of the content view filter rule
```

```

--order ORDER                Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL  Organization label to search by
--page PAGE                  Page number, starting at 1
--per-page PER_PAGE          Number of results per page to return
--search SEARCH              Search string
-h, --help                  Print help

```

10.15.7.12. hammer content-view filter rule update

Update a filter rule. The parameters included should be based upon the filter type.

Usage:

```
hammer content-view filter rule update [OPTIONS]
```

Options:

```

--architecture ARCHITECTURE      Package: architecture
--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-filter CONTENT_VIEW_FILTER_NAME  Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID  Filter identifier
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--end-date END_DATE              Erratum: end date (YYYY-MM-DD)
--errata-id ERRATA_ID            Erratum: id
--id ID                          Rule identifier
--max-version MAX_VERSION         Package: maximum version
--min-version MIN_VERSION         Package: minimum version
--name NAME                      Name to search by
--new-name NEW_NAME              Package, package group, or docker tag: name
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL  Organization label to search by
--start-date START_DATE          Erratum: start date (YYYY-MM-DD)
--types TYPES                    Erratum: types (enhancement, bugfix, security)
                                Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash
--version VERSION                Package: version
-h, --help                      Print help

```

10.15.7.13. hammer content-view filter update

update a filter

Usage:

```
hammer content-view filter update [OPTIONS]
```

Options:

```

--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--id ID                          Filter identifier
--inclusion INCLUSION              Specifies if content should be included or excluded, default:
                                Inclusion=false
                                One of true/false, yes/no, 1/0.
--name NAME                      Name to search by

```

```

--new-name NEW_NAME          New name for the filter
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
--original-packages ORIGINAL_PACKAGES Add all packages without errata to the
included/excluded list. (package
                                Filter only)
                                One of true/false, yes/no, 1/0.
--repositories REPOSITORY_NAMES  Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--repository-ids REPOSITORY_IDS  List of repository ids
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
-h, --help                    Print help

```

10.15.8. hammer content-view info

Show a content view

```

Usage:
  hammer content-view info [OPTIONS]

Options:
--id ID                Content view numeric identifier
--name NAME            Content view name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help            Print help

```

10.15.9. hammer content-view list

List content views

```

Usage:
  hammer content-view list [OPTIONS]

Options:
--composite COMPOSITE          Filter only composite content views
                                One of true/false, yes/no, 1/0.
--full-result FULL_RESULT      Whether or not to show all results
                                One of true/false, yes/no, 1/0.
--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Environment name
--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
--name NAME                    Name of the content view
--noncomposite NONCOMPOSITE    Filter out composite content views
                                One of true/false, yes/no, 1/0.
--nondefault NONDEFAULT        Filter out default content views
                                One of true/false, yes/no, 1/0.
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--page PAGE                    Page number, starting at 1

```

```

--per-page PER_PAGE      Number of results per page to return
--search SEARCH          Search string
--without WITHOUT        Do not include this array of content views
                          Comma separated list of values. Values containing comma should
                          be quoted or escaped with backslash
-h, --help              Print help

```

10.15.10. hammer content-view publish

Publish a content view

```

Usage:
  hammer content-view publish [OPTIONS]

Options:
  --async                Do not wait for the task
  --description DESCRIPTION  Description for the new published content view version
  --id ID                Content view identifier
  --major MAJOR           Override the major version number
  --minor MINOR           Override the minor version number
  --name NAME             Content view name to search by
  --organization ORGANIZATION_NAME  Organization name to search by
  --organization-id ORGANIZATION_ID  Organization ID to search by
  --organization-label ORGANIZATION_LABEL  Organization label to search by
  --repos-units REPOS_UNITS  Specify the list of units in each repo
                          Comma separated list of values. Values containing comma should be
                          quoted or escaped with backslash
-h, --help              Print help

```

10.15.11. hammer content-view puppet-module

View and manage puppet modules

```

Usage:
  hammer content-view puppet-module [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND      Subcommand
  [ARG] ...       Subcommand arguments

Subcommands:
  add      Add a puppet module to the content view
  list     List content view puppet modules
  remove   Remove a puppet module from the content view

Options:
  -h, --help      Print help

```

10.15.11.1. hammer content-view puppet-module add

Add a puppet module to the content view

```

Usage:

```



```
hammer content-view puppet-module add [OPTIONS]
```

Options:

```
--author AUTHOR          Puppet module's author to search by
--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--id ID                    The id of the puppet module to associate
--name NAME                Puppet module name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
--uuid UUID                Puppet module's UUID to search by
-h, --help                Print help
```

10.15.11.2. hammer content-view puppet-module list

List content view puppet modules

Usage:

```
hammer content-view puppet-module list [OPTIONS]
```

Options:

```
--author AUTHOR          Author of the puppet module
--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--full-result FULL_RESULT  Whether or not to show all results
                          One of true/false, yes/no, 1/0.
--name NAME                Name of the puppet module
--order ORDER              Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
--page PAGE                Page number, starting at 1
--per-page PER_PAGE        Number of results per page to return
--search SEARCH            Search string
--uuid UUID                The uuid of the puppet module to associate
-h, --help                Print help
```

10.15.11.3. hammer content-view puppet-module remove

Remove a puppet module from the content view

Usage:

```
hammer content-view puppet-module remove [OPTIONS]
```

Options:

```
--author AUTHOR          Puppet module's author to search by
--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--id ID                    Puppet module ID
--name NAME                Puppet module name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID to search by
```

```
--organization-label ORGANIZATION_LABEL Organization label to search by
--uuid UUID                               Puppet module's UUID to search by
-h, --help                               Print help
```

10.15.12. hammer content-view purge

Delete old versions of a content view

```
Usage:
  hammer content-view purge [OPTIONS]

Options:
  --async                Do not wait for the task
  --count COUNT          Count of unused versions to keep
                        Default: 3
  --id ID                Content View numeric identifier
  --name NAME            Content View name
  --organization ORGANIZATION_NAME Organization name to search by
  --organization-id ORGANIZATION_ID Organization ID to search by
  --organization-label ORGANIZATION_LABEL Organization label to search by
  -h, --help            Print help
```

Unfortunately the server does not support such operation.

10.15.13. hammer content-view remove

Remove versions and/or environments from a content view and reassign systems and keys

```
Usage:
  hammer content-view remove [OPTIONS]

Options:
  --async                Do not wait for the task
  --content-view-version-ids VERSION_IDS Version ids to remove
                        Comma separated list of values. Values containing comma should
                        be quoted or escaped with backslash
  --content-view-versions CONTENT_VIEW_VERSION_VERSIONS Comma separated list of values.
                        Values containing comma should be quoted or escaped with backslash
  --environment-ids ENVIRONMENT_IDS Environment ids to remove
                        Comma separated list of values. Values containing comma should
                        be quoted or escaped with backslash
  --environments ENVIRONMENT_NAMES Comma separated list of values. Values
                        containing comma should be quoted or escaped with backslash
  --id ID                Content view numeric identifier
  --key-content-view-id KEY_CONTENT_VIEW_ID Content view to reassign orphaned
                        activation keys to
  --key-environment-id KEY_ENVIRONMENT_ID Environment to reassign orphaned
                        activation keys to
  --name NAME            Content view name to search by
  --organization ORGANIZATION_NAME Organization name to search by
  --organization-id ORGANIZATION_ID Organization ID to search by
  --organization-label ORGANIZATION_LABEL Organization label to search by
  --system-content-view-id SYSTEM_CONTENT_VIEW_ID Content view to reassign orphaned
                        systems to
```

```
--system-environment-id SYSTEM_ENVIRONMENT_ID  Environment to reassign orphaned
systems to
-h, --help                                     Print help
```

10.15.14. hammer content-view remove-from-environment

Remove a content view from an environment

```
Usage:
  hammer content-view remove-from-environment [OPTIONS]

Options:
  --async                Do not wait for the task
  --id ID                Content view numeric identifier
  --lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME  Environment name
  --lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
  --name NAME            Content view name to search by
  --organization ORGANIZATION_NAME  Organization name to search by
  --organization-id ORGANIZATION_ID  Organization ID to search by
  --organization-label ORGANIZATION_LABEL  Organization label to search by
  -h, --help            Print help
```

10.15.15. hammer content-view remove-repository

Disassociate a resource

```
Usage:
  hammer content-view remove-repository [OPTIONS]

Options:
  --id ID                Content view numeric identifier
  --name NAME            Content view name to search by
  --organization ORGANIZATION_NAME  Organization name to search by
  --organization-id ORGANIZATION_ID  Organization ID to search by
  --organization-label ORGANIZATION_LABEL  Organization label to search by
  --product PRODUCT_NAME  Product name to search by
  --product-id PRODUCT_ID  Product numeric identifier
  --repository REPOSITORY_NAME  Repository name to search by
  --repository-id REPOSITORY_ID  Repository ID
  -h, --help            Print help
```

10.15.16. hammer content-view remove-version

Remove a content view version from a composite view

```
Usage:
  hammer content-view remove-version [OPTIONS]

Options:
  --content-view CONTENT_VIEW_NAME  Content view name to search by
  --content-view-id CONTENT_VIEW_ID  Content view numeric identifier
  --content-view-version CONTENT_VIEW_VERSION_VERSION  Content view version number
  --content-view-version-id CONTENT_VIEW_VERSION_ID  Content view version identifier
```

--id ID	Content view numeric identifier
--name NAME	Content view name to search by
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID to search by
--organization-label ORGANIZATION_LABEL	Organization label to search by
-h, --help	Print help

10.15.17. hammer content-view update

Update a content view

Usage:

hammer content-view update [OPTIONS]

Options:

--auto-publish AUTO_PUBLISH	Enable/Disable auto publish of composite view
	One of true/false, yes/no, 1/0.
--component-ids COMPONENT_IDS	List of component content view version ids for composite views
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--description DESCRIPTION	Description for the content view
--id ID	Content view identifier
--name NAME	Content view name to search by
--new-name NEW_NAME	New name for the content view
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID to search by
--organization-label ORGANIZATION_LABEL	Organization label to search by
--repositories REPOSITORY_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--repository-ids REPOSITORY_IDS	List of repository ids
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
-h, --help	Print help

10.15.18. hammer content-view version

View and manage content view versions

Usage:

hammer content-view version [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

delete	Remove content view version
export	Export a content view version
export-legacy	Export a content view
import	Import a content view version
incremental-update	Perform an Incremental Update on one or more Content View Versions
info	Show content view version
list	List content view versions

```

promote                Promote a content view version
republish-repositories Forces a republish of the version's repositories' metadata

Options:
-h, --help            Print help

```

10.15.18.1. hammer content-view version delete

Remove content view version

```

Usage:
  hammer content-view version delete [OPTIONS]

Options:
--async                Do not wait for the task
--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--environment ENVIRONMENT_NAME    Environment name
--environment-id ENVIRONMENT_ID
--id ID                  Content view version identifier
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
--version VERSION        Content view version number
-h, --help              Print help

```

10.15.18.2. hammer content-view version export

Export a content view version

```

Usage:
  hammer content-view version export [OPTIONS]

Options:
--export-dir EXPORT_DIR  Directory to put content view version export into.
--id ID                 Content View Version numeric identifier
-h, --help              Print help

```

10.15.18.3. hammer content-view version export-legacy

Export a content view

```

Usage:
  hammer content-view version export-legacy [OPTIONS]

Options:
--async                Do not wait for the task
--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--environment ENVIRONMENT_NAME    Environment name
--environment-id ENVIRONMENT_ID
--export-to-iso EXPORT_TO_ISO    Export to ISO format
                                One of true/false, yes/no, 1/0.

```

```

--id ID                      Content view version identifier
--iso-mb-size ISO_MB_SIZE    Maximum size of each ISO in MB
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--since SINCE                Optional date of last export (ex: 2010-01-01T12:00:00Z)
--version VERSION            Content view version number
-h, --help                  Print help

```

10.15.18.4. hammer content-view version import

Import a content view version

```

Usage:
  hammer content-view version import [OPTIONS]

```

```

Options:
  --async                Do not wait for the task
  --export-tar EXPORT_TAR Location of export tar on disk
  --organization-id ORGANIZATION_ID Organization numeric identifier
  -h, --help            Print help

```

10.15.18.5. hammer content-view version incremental-update

Perform an Incremental Update on one or more Content View Versions

```

Usage:
  hammer content-view version incremental-update [OPTIONS]

```

```

Options:
  --async                Do not wait for the task
  --content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
  --content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier
  --deb-ids DEB_IDS      Deb Package ids or uuids to copy into the new versions
                        Comma separated list of values. Values containing comma should
                        be quoted or escaped with backslash
  --debs DEB_NAMES       Comma separated list of values. Values containing
                        comma should be quoted or escaped with backslash
  --description DESCRIPTION The description for the new generated Content View
                        Versions
  --errata-ids ERRATA_IDS Errata ids or uuids to copy into the new versions
                        Comma separated list of values. Values containing comma should
                        be quoted or escaped with backslash
  --host-ids HOST_IDS    IDs of hosts to update
                        Comma separated list of values. Values containing comma should
                        be quoted or escaped with backslash
  --lifecycle-environment-ids ENVIRONMENT_IDS List of lifecycle environment IDs to update the
                        content view version in
                        Comma separated list of values. Values containing comma should
                        be quoted or escaped with backslash
  --lifecycle-environments ENVIRONMENTS List of lifecycle environment names to update
                        the content view version in
                        Comma separated list of values. Values containing comma should
                        be quoted or escaped with backslash

```

```

--organization ORGANIZATION_NAME      Organization name for resolving lifecycle
environment names
--organization-id ORGANIZATION_ID      Organization id for resolving lifecycle environment
names
--package-ids PACKAGE_IDS              Package ids or uuids to copy into the new versions
                                      Comma separated list of values. Values containing comma should
                                      be quoted or escaped with backslash
--packages PACKAGE_NAMES                Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--propagate-all-composites PROPAGATE_ALL_COMPOSITES If true, will publish a new composite
version using any specified
                                      Content_view_version_id that has been promoted to a lifecycle
environment
                                      One of true/false, yes/no, 1/0.
--puppet-module-ids PUPPET_MODULE_IDS    Puppet Module ids or uuids to copy into the
new versions
                                      Comma separated list of values. Values containing comma should
                                      be quoted or escaped with backslash
--puppet-modules PUPPET_MODULE_NAMES      Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--resolve-dependencies RESOLVE_DEPENDENCIES If true, when adding the specified errata
or packages, any needed
                                      Dependencies will be copied as well
                                      One of true/false, yes/no, 1/0.
--update-all-hosts UPDATE                Update all editable and applicable hosts within the
specified Content View and \
                                      Lifecycle Environments
                                      One of true/false, yes/no, 1/0.
-h, --help                               Print help

```

10.15.18.6. hammer content-view version info

Show content view version

```

Usage:
  hammer content-view version info [OPTIONS]

Options:
--content-view CONTENT_VIEW_NAME      Content view name to search by
--content-view-id CONTENT_VIEW_ID      Content view numeric identifier
--environment ENVIRONMENT_NAME        Environment name
--environment-id ENVIRONMENT_ID
--id ID                               Content view version identifier
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID      Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--version VERSION                     Content view version number
-h, --help                             Print help

```

10.15.18.7. hammer content-view version list

List content view versions

```

Usage:

```

```
hammer content-view version list [OPTIONS]
```

Options:

```
--composite-version-id COMPOSITE_VERSION_ID  Filter versions that are components in the
specified composite version
--content-view CONTENT_VIEW_NAME              Content view name to search by
--content-view-id CONTENT_VIEW_ID             Content view numeric identifier
--environment ENVIRONMENT_NAME                Environment name
--environment-id ENVIRONMENT_ID
--full-result FULL_RESULT                     Whether or not to show all results
                                              One of true/false, yes/no, 1/0.
--order ORDER                                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME              Organization name to search by
--organization-id ORGANIZATION_ID             Organization ID
--organization-label ORGANIZATION_LABEL        Organization label to search by
--page PAGE                                    Page number, starting at 1
--per-page PER_PAGE                           Number of results per page to return
--puppet-module PUPPET_MODULE_NAME            Name to search by
--puppet-module-id PUPPET_MODULE_ID            A puppet module identifier
--search SEARCH                               Search string
--triggered-by-id TRIGGERED_BY_ID             Filter composite versions whose publish was triggered
by the specified
                                              Component version
--version VERSION                             Filter versions by version number
-h, --help                                    Print help
```

10.15.18.8. hammer content-view version promote

Promote a content view version

Usage:

```
hammer content-view version promote [OPTIONS]
```

Options:

```
--async                                         Do not wait for the task
--content-view CONTENT_VIEW_NAME              Content view name to search by
--content-view-id CONTENT_VIEW_ID             Content view numeric identifier
--description DESCRIPTION                     The description for the content view version promotion
--environment-ids ENVIRONMENT_IDS              Identifiers for Lifecycle Environment
                                              Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--force                                         Force content view promotion and bypass lifecycle environment
restriction
--from-lifecycle-environment FROM_ENVIRONMENT_ID  Environment name from where to
promote its version from (if version is unknown)
--from-lifecycle-environment-id FROM_ENVIRONMENT_ID  Id of the environment from where to
promote its version from (if version is unknown)
--id ID                                         Content view version identifier
--organization ORGANIZATION_NAME              Organization name to search by
--organization-id ORGANIZATION_ID             Organization ID
--organization-label ORGANIZATION_LABEL        Organization label to search by
--to-lifecycle-environment TO_ENVIRONMENT       Name of the target environment
--to-lifecycle-environment-id TO_ENVIRONMENT_ID  Id of the target environment
--version VERSION                             Content view version number
-h, --help                                    Print help
```


10.15.18.9. hammer content-view version republish-repositories

Forces a republish of the version's repositories' metadata

Usage:

```
hammer content-view version republish-repositories [OPTIONS]
```

Options:

```
--async           Do not wait for the task
--content-view CONTENT_VIEW_NAME  Content view name to search by
--content-view-id CONTENT_VIEW_ID  Content view numeric identifier
--id ID           Content view version identifier
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--version VERSION          Content view version number
-h, --help           Print help
```

10.16. HAMMER CSV

import to or export from a running foreman server

Usage:

```
hammer csv [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments
```

Subcommands:

```
activation-keys      Import or export activation keys
architectures        Import or export architectures
compute-profiles     Import or export compute profiles
compute-resources    Import or export compute resources
containers           Import or export containers
content-hosts        Import or export content hosts
content-view-filters Import or export content-view-filters
content-views        Import or export content-views
domains              Import or export domains
export               Export into directory
host-collections     Import or export host collections
host-groups          Import or export host-groups
hosts                Import or export hosts
import               Import by directory
installation-media    Import or export media
job-templates        Import or export job templates
lifecycle-environments Import or export lifecycle environments
locations            Import or export locations
operating-systems    Import or export operating systems
organizations        Import or export organizations
partition-tables     Import or export partition tables
products             Import or export products
provisioning-templates Import or export provisioning templates
puppet-environments  Import or export puppet environments
puppet-facts         Import or export puppet facts
```

```

puppet-reports      Import or export puppet reports
reports             Import or export reports
roles               Import or export roles
settings            Import or export settings
smart-proxies       Import or export smart proxies
splice              Import Satellite-5 splice data
subnets            Import or export subnets
subscriptions       Import or export subscriptions
sync-plans          Import or export repository sync plans
users               Import or export users

Options:
-h, --help          Print help

```

10.16.1. hammer csv activation-keys

import or export activation keys

```

Usage:
  hammer csv activation-keys [OPTIONS]

Options:
--continue-on-error  Continue processing even if individual resource error
--export             Export current data instead of importing
--file FILE_NAME     CSV file (default to /dev/stdout with --export, otherwise required)
--itemized-subscriptions  Export one subscription per row, only process update subscriptions on
import
--organization ORGANIZATION  Only process organization matching this name
--search SEARCH       Only export search results
-h, --help           Print help
-v, --verbose        Be verbose

```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.2. hammer csv architectures

import or export architectures

```

Usage:
  hammer csv architectures [OPTIONS]

Options:
--continue-on-error  Continue processing even if individual resource error
--export             Export current data instead of importing
--file FILE_NAME     CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION  Only process organization matching this name
--search SEARCH       Only export search results
-h, --help           Print help
-v, --verbose        Be verbose

```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.3. hammer csv compute-profiles

import or export compute profiles

Usage:

```
hammer csv compute-profiles [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.4. hammer csv compute-resources

import or export compute resources

Usage:

```
hammer csv compute-resources [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.5. hammer csv containers

import or export containers

Usage:

```
hammer csv containers [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
```

```
--search SEARCH      Only export search results
-h, --help           Print help
-v, --verbose        Be verbose
```

Unfortunately the server does not support such operation.

10.16.6. hammer csv content-hosts

import or export content hosts

Usage:

```
hammer csv content-hosts [OPTIONS]
```

Options:

```
--clear-subscriptions  When processing --itemized-subscriptions, clear existing subscriptions first
--columns COLUMN_NAMES  Comma separated list of column names to export
--continue-on-error    Continue processing even if individual resource error
--export              Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--itemized-subscriptions  Export one subscription per row, only process update subscriptions on
import
--organization ORGANIZATION  Only process organization matching this name
--search SEARCH          Only export search results
-h, --help              Print help
-v, --verbose           Be verbose
```

Unfortunately the server does not support such operation.

Columns:

```
Name - Name of resource
Search - Search for matching names during import (overrides 'Name' column)
Organization - Organization name
Environment - Lifecycle environment name
Content View - Content view name
Host Collections - Comma separated list of host collection names
Virtual - Is a virtual host, Yes or No
Guest of Host - Hypervisor host name for virtual hosts
OS - Operating system
Arch - Architecture
Sockets - Number of sockets
RAM - Quantity of RAM in bytes
Cores - Number of cores
SLA - Service Level Agreement value
Products - Comma separated list of products, each of the format "<sku>|<name>"
Subscriptions - Comma separated list of subscriptions, each of the format "<quantity>|<sku>|
<name>|<contract>|<account>"
Subscription Name - Subscription name (only applicable for --itemized-subscriptions)
Subscription Type - Subscription type (only applicable for --itemized-subscriptions)
Subscription Quantity - Subscription quantity (only applicable for --itemized-subscriptions)
Subscription SKU - Subscription SKU (only applicable for --itemized-subscriptions)
Subscription Contract - Subscription contract number (only applicable for --itemized-subscriptions)
Subscription Account - Subscription account number (only applicable for --itemized-subscriptions)
Subscription Start - Subscription start date (only applicable for --itemized-subscriptions)
Subscription End - Subscription end date (only applicable for --itemized-subscriptions)
```

This command is unsupported and is provided as tech preview.

10.16.7. hammer csv content-view-filters

import or export content-view-filters

Usage:

```
hammer csv content-view-filters [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.8. hammer csv content-views

import or export content-views

Usage:

```
hammer csv content-views [OPTIONS]
```

Options:

```
--[no-]promote         Publish and promote content view on import (default false)
--[no-]publish         Publish content view on import (default false)
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.9. hammer csv domains

import or export domains

Usage:

```
hammer csv domains [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
```

```
--file FILE_NAME          CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION  Only process organization matching this name
--search SEARCH            Only export search results
-h, --help                Print help
-v, --verbose              Be verbose
```

Unfortunately the server does not support such operation.

10.16.10. hammer csv export

export into directory

Usage:

```
hammer csv export [OPTIONS]
```

Options:

```
--dir DIRECTORY          Directory to export to
--organization ORGANIZATION  Only process organization matching this name
--settings FILE           Csv file for settings
-h, --help                Print help
-v, --verbose              Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.11. hammer csv host-collections

import or export host collections

Usage:

```
hammer csv host-collections [OPTIONS]
```

Options:

```
--continue-on-error      Continue processing even if individual resource error
--export                  Export current data instead of importing
--file FILE_NAME          CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION  Only process organization matching this name
--search SEARCH            Only export search results
-h, --help                Print help
-v, --verbose              Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.12. hammer csv host-groups

import or export host-groups

Usage:

```
hammer csv host-groups [OPTIONS]
```

Options:

```

--continue-on-error    Continue processing even if individual resource error
--export              Export current data instead of importing
--file FILE_NAME      CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH       Only export search results
-h, --help           Print help
-v, --verbose        Be verbose

```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.13. hammer csv hosts

import or export hosts

```

Usage:
  hammer csv hosts [OPTIONS]

Options:
--continue-on-error    Continue processing even if individual resource error
--export              Export current data instead of importing
--file FILE_NAME      CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH       Only export search results
-h, --help           Print help
-v, --verbose        Be verbose

```

Unfortunately the server does not support such operation.

10.16.14. hammer csv import

import by directory

```

Usage:
  hammer csv import [OPTIONS]

Options:
--dir DIRECTORY      Directory to import from
--organization ORGANIZATION Only process organization matching this name
--settings FILE      Csv file for settings
-h, --help           Print help
-v, --verbose        Be verbose

```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.15. hammer csv installation-media

import or export media

```

Usage:
  hammer csv installation-media [OPTIONS]

```

Options:

<code>--continue-on-error</code>	Continue processing even if individual resource error
<code>--export</code>	Export current data instead of importing
<code>--file FILE_NAME</code>	CSV file (default to /dev/stdout with <code>--export</code> , otherwise required)
<code>--organization ORGANIZATION</code>	Only process organization matching this name
<code>--search SEARCH</code>	Only export search results
<code>-h, --help</code>	Print help
<code>-v, --verbose</code>	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.16. hammer csv job-templates

import or export job templates

Usage:

hammer csv job-templates [OPTIONS]

Options:

<code>--continue-on-error</code>	Continue processing even if individual resource error
<code>--export</code>	Export current data instead of importing
<code>--file FILE_NAME</code>	CSV file (default to /dev/stdout with <code>--export</code> , otherwise required)
<code>--organization ORGANIZATION</code>	Only process organization matching this name
<code>--search SEARCH</code>	Only export search results
<code>-h, --help</code>	Print help
<code>-v, --verbose</code>	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.17. hammer csv lifecycle-environments

import or export lifecycle environments

Usage:

hammer csv lifecycle-environments [OPTIONS]

Options:

<code>--continue-on-error</code>	Continue processing even if individual resource error
<code>--export</code>	Export current data instead of importing
<code>--file FILE_NAME</code>	CSV file (default to /dev/stdout with <code>--export</code> , otherwise required)
<code>--organization ORGANIZATION</code>	Only process organization matching this name
<code>--search SEARCH</code>	Only export search results
<code>-h, --help</code>	Print help
<code>-v, --verbose</code>	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.18. hammer csv locations

import or export locations

Usage:

hammer csv locations [OPTIONS]

Options:

--continue-on-error	Continue processing even if individual resource error
--export	Export current data instead of importing
--file FILE_NAME	CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION	Only process organization matching this name
--search SEARCH	Only export search results
-h, --help	Print help
-v, --verbose	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.19. hammer csv operating-systems

import or export operating systems

Usage:

hammer csv operating-systems [OPTIONS]

Options:

--continue-on-error	Continue processing even if individual resource error
--export	Export current data instead of importing
--file FILE_NAME	CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION	Only process organization matching this name
--search SEARCH	Only export search results
-h, --help	Print help
-v, --verbose	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.20. hammer csv organizations

import or export organizations

Usage:

hammer csv organizations [OPTIONS]

Options:

--continue-on-error	Continue processing even if individual resource error
--export	Export current data instead of importing
--file FILE_NAME	CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION	Only process organization matching this name
--search SEARCH	Only export search results
-h, --help	Print help

`-v, --verbose` Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.21. hammer csv partition-tables

import or export partition tables

Usage:
hammer csv partition-tables [OPTIONS]

Options:

<code>--continue-on-error</code>	Continue processing even if individual resource error
<code>--export</code>	Export current data instead of importing
<code>--file FILE_NAME</code>	CSV file (default to /dev/stdout with --export, otherwise required)
<code>--organization ORGANIZATION</code>	Only process organization matching this name
<code>--search SEARCH</code>	Only export search results
<code>-h, --help</code>	Print help
<code>-v, --verbose</code>	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.22. hammer csv products

import or export products

Usage:
hammer csv products [OPTIONS]

Options:

<code>--[no-]sync</code>	Sync product repositories (default true) Default: true
<code>--continue-on-error</code>	Continue processing even if individual resource error
<code>--export</code>	Export current data instead of importing
<code>--file FILE_NAME</code>	CSV file (default to /dev/stdout with --export, otherwise required)
<code>--organization ORGANIZATION</code>	Only process organization matching this name
<code>--search SEARCH</code>	Only export search results
<code>-h, --help</code>	Print help
<code>-v, --verbose</code>	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.23. hammer csv provisioning-templates

import or export provisioning templates

Usage:
hammer csv provisioning-templates [OPTIONS]

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--include-locked       Include locked templates (will fail if re-imported)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.24. hammer csv puppet-environments

import or export puppet environments

Usage:

```
hammer csv puppet-environments [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.25. hammer csv puppet-facts

import or export puppet facts

Usage:

```
hammer csv puppet-facts [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.26. hammer csv puppet-reports

import or export puppet reports

Usage:

hammer csv puppet-reports [OPTIONS]

Options:

--continue-on-error	Continue processing even if individual resource error
--export	Export current data instead of importing
--file FILE_NAME	CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION	Only process organization matching this name
--search SEARCH	Only export search results
-h, --help	Print help
-v, --verbose	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.27. hammer csv reports

import or export reports

Usage:

hammer csv reports [OPTIONS]

Options:

--continue-on-error	Continue processing even if individual resource error
--export	Export current data instead of importing
--file FILE_NAME	CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION	Only process organization matching this name
--search SEARCH	Only export search results
-h, --help	Print help
-v, --verbose	Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.28. hammer csv roles

import or export roles

Usage:

hammer csv roles [OPTIONS]

Options:

--continue-on-error	Continue processing even if individual resource error
--export	Export current data instead of importing
--file FILE_NAME	CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION	Only process organization matching this name
--search SEARCH	Only export search results
-h, --help	Print help

`-v, --verbose` Be verbose

Unfortunately the server does not support such operation.

10.16.29. hammer csv settings

import or export settings

Usage:
hammer csv settings [OPTIONS]

Options:

- `--continue-on-error` Continue processing even if individual resource error
- `--export` Export current data instead of importing
- `--file FILE_NAME` CSV file (default to /dev/stdout with --export, otherwise required)
- `--organization ORGANIZATION` Only process organization matching this name
- `--search SEARCH` Only export search results
- `-h, --help` Print help
- `-v, --verbose` Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.30. hammer csv smart-proxies

import or export smart proxies

Usage:
hammer csv smart-proxies [OPTIONS]

Options:

- `--continue-on-error` Continue processing even if individual resource error
- `--export` Export current data instead of importing
- `--file FILE_NAME` CSV file (default to /dev/stdout with --export, otherwise required)
- `--organization ORGANIZATION` Only process organization matching this name
- `--search SEARCH` Only export search results
- `-h, --help` Print help
- `-v, --verbose` Be verbose

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.31. hammer csv splice

import Satellite-5 splice data

Usage:
hammer csv splice [OPTIONS]

Options:

- `--continue-on-error` Continue processing even if individual resource error
- `--dir DIR` Directory of Splice exported CSV files (default pwd)

```

--export          Export current data instead of importing
--file FILE_NAME  CSV file (default to /dev/stdout with --export, otherwise required)
--mapping-dir DIR  Directory of Splice product mapping files (default
/usr/share/rhsm/product/RHEL-6)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH    Only export search results
-h, --help        Print help
-v, --verbose      Be verbose

```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.32. hammer csv subnets

import or export subnets

```

Usage:
  hammer csv subnets [OPTIONS]

```

```

Options:
--continue-on-error  Continue processing even if individual resource error
--export            Export current data instead of importing
--file FILE_NAME    CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH      Only export search results
-h, --help          Print help
-v, --verbose        Be verbose

```

Unfortunately the server does not support such operation.

10.16.33. hammer csv subscriptions

import or export subscriptions

```

Usage:
  hammer csv subscriptions [OPTIONS]

```

```

Options:
--continue-on-error  Continue processing even if individual resource error
--export            Export current data instead of importing
--file FILE_NAME    CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH      Only export search results
-h, --help          Print help
-v, --verbose        Be verbose

```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.34. hammer csv sync-plans

import or export repository sync plans

Usage:

```
hammer csv sync-plans [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

This command is unsupported and is provided as tech preview.

10.16.35. hammer csv users

import or export users

Usage:

```
hammer csv users [OPTIONS]
```

Options:

```
--continue-on-error    Continue processing even if individual resource error
--export               Export current data instead of importing
--file FILE_NAME       CSV file (default to /dev/stdout with --export, otherwise required)
--organization ORGANIZATION Only process organization matching this name
--search SEARCH        Only export search results
-h, --help             Print help
-v, --verbose          Be verbose
```

Unfortunately the server does not support such operation.

10.17. HAMMER DEFAULTS

Defaults management

Usage:

```
hammer defaults [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND            Subcommand
[ARG] ...              Subcommand arguments
```

Subcommands:

```
add                  Add a default parameter to config
delete              Delete a default param
list                List all the default parameters
providers           List all the providers
```

Options:

```
-h, --help           Print help
```

10.17.1. hammer defaults add

Add a default parameter to config

Usage:

hammer defaults add [OPTIONS]

Options:

--param-name OPTION_NAME The name of the default option (e.g. organization_id)
--param-value OPTION_VALUE The value for the default option
--provider OPTION_PROVIDER The name of the provider providing the value. For list available providers see `hammer defaults providers`
-h, --help Print help

10.17.2. hammer defaults delete

Delete a default param

Usage:

hammer defaults delete [OPTIONS]

Options:

--param-name OPTION_NAME The name of the default option
-h, --help Print help

10.17.3. hammer defaults list

List all the default parameters

Usage:

hammer defaults list [OPTIONS]

Options:

-h, --help Print help

10.17.4. hammer defaults providers

List all the providers

Usage:

hammer defaults providers [OPTIONS]

Options:

-h, --help Print help

10.18. HAMMER DISCOVERY

Manipulate discovered hosts.

Usage:

hammer discovery [OPTIONS] SUBCOMMAND [ARG] ...


```

Parameters:
SUBCOMMAND                Subcommand
[ARG] ...                 Subcommand arguments

Subcommands:
auto-provision            Auto provision a host
delete                   Delete a discovered host
facts                    List all fact values
info                     Show a discovered host
list                     List all discovered hosts
provision                 Provision a discovered host
reboot                   Reboot a host
refresh-facts            Refresh the facts of a host

Options:
-h, --help               Print help

```

10.18.1. hammer discovery auto-provision

Auto provision a host

```

Usage:
  hammer discovery auto-provision [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                   Print help

```

10.18.2. hammer discovery delete

Delete a discovered host

```

Usage:
  hammer discovery delete [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                   Print help

```

10.18.3. hammer discovery facts

List all fact values

```
Usage:
  hammer discovery facts [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --name NAME                           Name to search by
  --order ORDER                         Sort field and order, eg. 'id DESC'
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --page PAGE                           Paginate results
  --per-page PER_PAGE                   Number of entries per request
  --search SEARCH                       Filter results
  -h, --help                           Print help
```

10.18.4. hammer discovery info

Show a discovered host

```
Usage:
  hammer discovery info [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --name NAME                           Name to search by
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                           Print help
```

10.18.5. hammer discovery list

List all discovered hosts

```
Usage:
  hammer discovery list [OPTIONS]

Options:
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --order ORDER                         Sort results
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
```

```
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                               Paginate results
--per-page PER_PAGE                       Number of entries per request
--search SEARCH                           Filter results
-h, --help                                Print help
```

10.18.6. hammer discovery provision

Provision a discovered host

Usage:

```
hammer discovery provision [OPTIONS]
```

Options:

```
--architecture ARCHITECTURE_NAME          Architecture name
--architecture-id ARCHITECTURE_ID
--ask-root-password ASK_ROOT_PW           One of true/false, yes/no, 1/0.
--build BUILD                             One of true/false, yes/no, 1/0.
--capabilities CAPABILITIES
--domain DOMAIN_NAME                     Domain name
--domain-id DOMAIN_ID                   Numerical ID or domain name
--enabled ENABLED                       One of true/false, yes/no, 1/0.
--environment ENVIRONMENT_NAME          Environment name
--environment-id ENVIRONMENT_ID
--host-parameters-attributes HOST_PARAMETERS_ATTRIBUTES Comma separated list of values.
Values containing comma should be quoted or escaped with backslash
--hostgroup HOSTGROUP_NAME              Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE        Hostgroup title
--id ID
--image IMAGE_NAME                      Name to search by
--image-id IMAGE_ID
--interface INTERFACE                  Interface parameters
                                       Comma-separated list of key=value
                                       Can be specified multiple times.
--ip IP                                Not required if using a subnet with DHCP Capsule
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE          Location title
--mac MAC                               Not required if it's a virtual machine
--managed MANAGED                       One of true/false, yes/no, 1/0.
--medium MEDIUM_NAME                   Medium name
--medium-id MEDIUM_ID
--model MODEL_NAME                      Model name
--model-id MODEL_ID
--name NAME                             Name to search by
--new-name NEW_NAME
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID        Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--overwrite OVERWRITE                   One of true/false, yes/no, 1/0.
--owner-id OWNER_ID
--parameters PARAMS                     Host parameters
```

```

                                Comma-separated list of key=value
--partition-table PARTITION_TABLE_NAME      Partition table name
--partition-table-id PARTITION_TABLE_ID
--progress-report-id PROGRESS_REPORT_ID      UUID to track orchestration tasks status,
GET
                                /api/orchestration/:UUID/tasks
--provision-method METHOD                    Possible value(s): 'build', 'image'
--puppet-ca-proxy-id PUPPET_CA_PROXY_ID
--puppet-proxy-id PUPPET_PROXY_ID
--puppetclass-ids PUPPETCLASS_IDS            Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--pxe-loader PXE_LOADER                     DHCP filename option (Grub2 or PXELinux by
default)
                                Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI',
'Grub UEFI', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded', 'iPXE Chain BIOS', 'iPXE
Chain UEFI'
--root-password ROOT_PW
--sp-subnet-id SP_SUBNET_ID
--subnet SUBNET_NAME                        Subnet name
--subnet-id SUBNET_ID
-h, --help                                  Print help

```

10.18.7. hammer discovery reboot

Reboot a host

```

Usage:
  hammer discovery reboot [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help

```

10.18.8. hammer discovery refresh-facts

Refresh the facts of a host

```

Usage:
  hammer discovery refresh-facts [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name

```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help
```

10.19. HAMMER DISCOVERY-RULE

Manipulate discovered rules.

Usage:

```
hammer discovery-rule [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments
```

Subcommands:

```
create              Create a discovery rule
delete              Delete a rule
info                Show a discovery rule
list                List all discovery rules
update              Update a rule
```

Options:

```
-h, --help          Print help
```

10.19.1. hammer discovery-rule create

Create a discovery rule

Usage:

```
hammer discovery-rule create [OPTIONS]
```

Options:

```
--enabled ENABLED          Flag is used for temporary shutdown of rules
                             One of true/false, yes/no, 1/0.
--hostgroup HOSTGROUP_NAME  Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE  Hostgroup title
--hostname HOSTNAME         Defines a pattern to assign human-readable hostnames to the
matching hosts
--hosts-limit HOSTS_LIMIT
--location LOCATION_NAME    Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS  Location ID for provisioned hosts
                             Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE  Location title
--location-titles LOCATION_TITLES  Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--max-count MAX_COUNT        Enables to limit maximum amount of provisioned hosts per
rule
--name NAME                  Represents rule name shown to the users
```

```

--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-ids ORGANIZATION_IDS    Organization ID for provisioned hosts
                                       Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES    Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--priority PRIORITY                   Puts the rules in order, low numbers go first. Must be greater then
zero
--search SEARCH                       Query to match discovered hosts for the particular rule
-h, --help                           Print help

```

10.19.2. hammer discovery-rule delete

Delete a rule

```

Usage:
  hammer discovery-rule delete [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                   Name to search by
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                   Print help

```

10.19.3. hammer discovery-rule info

Show a discovery rule

```

Usage:
  hammer discovery-rule info [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                   Name to search by
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                   Print help

```

10.19.4. hammer discovery-rule list

List all discovery rules

Usage:

```
hammer discovery-rule list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort results
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                    Print help
```

10.19.5. hammer discovery-rule update

Update a rule

Usage:

```
hammer discovery-rule update [OPTIONS]
```

Options:

```
--enabled ENABLED              Flag is used for temporary shutdown of rules
                                One of true/false, yes/no, 1/0.
--hostgroup HOSTGROUP_NAME      Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--hostname HOSTNAME             Defines a pattern to assign human-readable hostnames to the
matching hosts
--hosts-limit HOSTS_LIMIT
--id ID
--location LOCATION_NAME        Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS     Location ID for provisioned hosts
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES      Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--max-count MAX_COUNT           Enables to limit maximum amount of provisioned hosts per
rule
--name NAME                     Name to search by
--new-name NEW_NAME             Represents rule name shown to the users
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS Organization ID for provisioned hosts
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
```

```

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--priority PRIORITY                      Puts the rules in order, low numbers go first. Must be greater then
zero
--search SEARCH                          Query to match discovered hosts for the particular rule
-h, --help                               Print help

```

10.20. HAMMER DOCKER

Manipulate docker content

```

Usage:
  hammer docker [OPTIONS] SUBCOMMAND [ARG] ...

```

```

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

```

```

Subcommands:
  container          Manage docker containers
  manifest           Manage docker manifests
  registry           Manage docker registries
  tag                Manage docker tags

```

```

Options:
  -h, --help         Print help

```

Unfortunately the server does not support such operation.

10.20.1. hammer docker container

Manage docker containers

```

Usage:
  hammer docker container [OPTIONS] SUBCOMMAND [ARG] ...

```

```

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

```

```

Subcommands:
  create            Create a container
  delete           Delete a container
  info             Show a container
  list             List all containers
  logs            Show container logs
  start           Power a container on
  status          Run power operation on a container
  stop           Power a container off

```

```

Options:
  -h, --help         Print help

```


10.20.1.1. hammer docker container create

Create a container

Usage:

```
hammer docker container create [OPTIONS]
```

Options:

```
--attach-stderr ATTACH_STDERR      One of true/false, yes/no, 1/0.
--attach-stdin ATTACH_STDIN         One of true/false, yes/no, 1/0.
--attach-stdout ATTACH_STDOUT       One of true/false, yes/no, 1/0.
--capsule CAPSULE_NAME              Name to search by
--capsule-id CAPSULE_ID              Id of the capsule
--command COMMAND
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--cpu-set CPU_SET
--cpu-shares CPU_SHARES
--entrypoint ENTRYPOINT
--environment-variables ENVIRONMENT_VARIABLES Optional array of environment variables
hashes. e.g.
    'environment_variables': [{'name' => 'example',
                              'value' => '123'}]
    Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location LOCATION_NAME            Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS         REPLACE locations with given ids
    Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE     Location title
--location-titles LOCATION_TITLES   Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--locations LOCATION_NAMES          Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--memory MEMORY
--name NAME
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID     Organization ID
--organization-ids ORGANIZATION_IDS   REPLACE organizations with given ids.
    Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE  Organization title
--organization-titles ORGANIZATION_TITLES  Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES     Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--registry REGISTRY_NAME              Name to search by
--registry-id REGISTRY_ID
--repository-name REPOSITORY_NAME      Name of the repository to use to create the
container. e.g. centos
--tag TAG                             Tag to use to create the container. e.g. latest
--tty TTY                             One of true/false, yes/no, 1/0.
-h, --help                             Print help
```

10.20.1.2. hammer docker container delete

Delete a container

Usage:

```
hammer docker container delete [OPTIONS]
```

Options:

```
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE          Location title
--name NAME                              Name to search by
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID        Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
-h, --help                                Print help
```

10.20.1.3. hammer docker container info

Show a container

Usage:

```
hammer docker container info [OPTIONS]
```

Options:

```
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE          Location title
--name NAME                              Name to search by
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID        Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
-h, --help                                Print help
```

10.20.1.4. hammer docker container list

List all containers

Usage:

```
hammer docker container list [OPTIONS]
```

Options:

```
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE          Location title
--order ORDER                            Sort field and order, eg. 'id DESC'
```

```
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                            Paginate results
--per-page PER_PAGE                    Number of entries per request
--search SEARCH                        Filter results
-h, --help                            Print help
```

10.20.1.5. hammer docker container logs

Show container logs

```
Usage:
  hammer docker container logs [OPTIONS]

Options:
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE           Location title
--name NAME                              Name to search by
--organization ORGANIZATION_NAME          Organization name
--organization-id ORGANIZATION_ID          Organization ID
--organization-title ORGANIZATION_TITLE    Organization title
--stderr STDERR                           One of true/false, yes/no, 1/0.
--stdout STDOUT                           One of true/false, yes/no, 1/0.
--tail TAIL                              Number of lines to tail. Default: 100
-h, --help                                Print help
```

10.20.1.6. hammer docker container start

Power a container on

```
Usage:
  hammer docker container start [OPTIONS]

Options:
--compute-resource COMPUTE_RESOURCE_NAME  Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE           Location title
--name NAME                              Name to search by
--organization ORGANIZATION_NAME          Organization name
--organization-id ORGANIZATION_ID          Organization ID
--organization-title ORGANIZATION_TITLE    Organization title
-h, --help                                Print help
```

10.20.1.7. hammer docker container status

Run power operation on a container

Usage:

hammer docker container status [OPTIONS]

Options:

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.20.1.8. hammer docker container stop

Power a container off

Usage:

hammer docker container stop [OPTIONS]

Options:

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.20.2. hammer docker manifest

Manage docker manifests

Usage:

hammer docker manifest [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand
[ARG] ... Subcommand arguments

Subcommands:

info Show a docker manifest
list List docker_manifests

Options:

-h, --help Print help

10.20.2.1. hammer docker manifest info

Show a docker manifest

Usage:

hammer docker manifest info [OPTIONS]

Options:

--id ID A docker manifest identifier
 --name NAME Name to search by
 --repository REPOSITORY_NAME Repository name to search by
 --repository-id REPOSITORY_ID Repository ID
 -h, --help Print help

10.20.2.2. hammer docker manifest list

List docker_manifests

Usage:

hammer docker manifest list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by
 --content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by
 --content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier
 --content-view-id CONTENT_VIEW_ID Content view numeric identifier
 --content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
 --content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier
 --environment ENVIRONMENT_NAME Environment name
 --environment-id ENVIRONMENT_ID
 --full-result FULL_RESULT Whether or not to show all results
 One of true/false, yes/no, 1/0.
 --ids IDS Ids to filter content by
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --page PAGE Page number, starting at 1
 --per-page PER_PAGE Number of results per page to return
 --product PRODUCT_NAME Product name to search by
 --product-id PRODUCT_ID Product numeric identifier
 --repository REPOSITORY_NAME Repository name to search by
 --repository-id REPOSITORY_ID Repository ID
 --search SEARCH Search string
 -h, --help Print help

10.20.3. hammer docker registry

Manage docker registries

Usage:

hammer docker registry [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

create	Create a docker registry
delete	Delete a docker registry
info	Show a docker registry
list	List all docker registries
update	Update a docker registry

Options:

-h, --help	Print help
------------	------------

10.20.3.1. hammer docker registry create

Create a docker registry

Usage:

hammer docker registry create [OPTIONS]

Options:

--description DESCRIPTION	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-ids LOCATION_IDS	REPLACE locations with given ids
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--location-title LOCATION_TITLE	Location title
--location-titles LOCATION_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--locations LOCATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--name NAME	
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-ids ORGANIZATION_IDS	REPLACE organizations with given ids.
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE	Organization title
--organization-titles ORGANIZATION_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--password PASSWORD	
--url URL	
--username USERNAME	
-h, --help	Print help

10.20.3.2. hammer docker registry delete

Delete a docker registry

Usage:

```
hammer docker registry delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.20.3.3. hammer docker registry info

Show a docker registry

Usage:

```
hammer docker registry info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.20.3.4. hammer docker registry list

List all docker registries

Usage:

```
hammer docker registry list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                    Print help
```

10.20.3.5. hammer docker registry update

Update a docker registry

Usage:

```
hammer docker registry update [OPTIONS]
```

Options:

```
--description DESCRIPTION
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS   REPLACE locations with given ids
                               Comma separated list of values. Values containing comma should be
                               quoted or escaped with backslash
--location-title LOCATION_TITLE      Location title
--location-titles LOCATION_TITLES   Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES        Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--name NAME                      Name to search by
--new-name NEW_NAME
--organization ORGANIZATION_NAME   Organization name
--organization-id ORGANIZATION_ID   Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                               Comma separated list of values. Values containing comma should be
                               quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE      Organization title
--organization-titles ORGANIZATION_TITLES   Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES        Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--password PASSWORD
--url URL
--username USERNAME
-h, --help                        Print help
```

10.20.4. hammer docker tag

Manage docker tags

Usage:

```
hammer docker tag [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND      Subcommand
[ARG] ...       Subcommand arguments
```

Subcommands:

```
info           Show a docker tag
list           List docker_tags
```

Options:

```
-h, --help      Print help
```

10.20.4.1. hammer docker tag info

Show a docker tag

Usage:

hammer docker tag info [OPTIONS]

Options:

--id ID A docker tag identifier
 --name NAME Name to search by
 --repository REPOSITORY_NAME Repository name to search by
 --repository-id REPOSITORY_ID Repository ID
 -h, --help Print help

10.20.4.2. hammer docker tag list

List docker_tags

Usage:

hammer docker tag list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by
 --content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by
 --content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier
 --content-view-id CONTENT_VIEW_ID Content view numeric identifier
 --content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
 --content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier
 --environment ENVIRONMENT_NAME Environment name
 --environment-id ENVIRONMENT_ID
 --full-result FULL_RESULT Whether or not to show all results
 One of true/false, yes/no, 1/0.
 --ids IDS Ids to filter content by
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --page PAGE Page number, starting at 1
 --per-page PER_PAGE Number of results per page to return
 --product PRODUCT_NAME Product name to search by
 --product-id PRODUCT_ID Product numeric identifier
 --repository REPOSITORY_NAME Repository name to search by
 --repository-id REPOSITORY_ID Repository ID
 --search SEARCH Search string
 -h, --help Print help

10.21. HAMMER DOMAIN

Manipulate domains

Usage:

hammer domain [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

create	Create a domain
delete	Delete a domain
delete-parameter	Delete parameter for a domain
info	Show a domain
list	List of domains
set-parameter	Create or update parameter for a domain
update	Update a domain

Options:

-h, --help	Print help
------------	------------

10.21.1. hammer domain create

Create a domain

Usage:

```
hammer domain create [OPTIONS]
```

Options:

--description DESC	Full name describing the domain
--dns DNS_NAME	Name of DNS proxy to use within this domain
--dns-id DNS_ID	ID of DNS proxy to use within this domain
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-ids LOCATION_IDS	REPLACE locations with given ids
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--location-title LOCATION_TITLE	Location title
--location-titles LOCATION_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--locations LOCATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--name NAME	The full DNS domain name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-ids ORGANIZATION_IDS	REPLACE organizations with given ids.
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE	Organization title
--organization-titles ORGANIZATION_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
-h, --help	Print help

10.21.2. hammer domain delete

Delete a domain

Usage:

```
hammer domain delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Domain name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.21.3. hammer domain delete-parameter

Delete parameter for a domain

Usage:

```
hammer domain delete-parameter [OPTIONS]
```

Options:

```
--domain DOMAIN_NAME      Domain name
--domain-id DOMAIN_ID      Numerical ID or domain name
--name NAME                Parameter name
-h, --help                Print help
```

10.21.4. hammer domain info

Show a domain

Usage:

```
hammer domain info [OPTIONS]
```

Options:

```
--id ID                    Numerical ID or domain name
--location LOCATION_NAME    Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                Domain name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values
                                One of true/false, yes/no, 1/0.
-h, --help                Print help
```

10.21.5. hammer domain list

List of domains

Usage:

```
hammer domain list [OPTIONS]
```

Options:

--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--order ORDER	Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--page PAGE	Paginate results
--per-page PER_PAGE	Number of entries per request
--search SEARCH	Filter results
--subnet SUBNET_NAME	Subnet name
--subnet-id SUBNET_ID	
-h, --help	Print help

10.21.6. hammer domain set-parameter

Create or update parameter for a domain

Usage:

hammer domain set-parameter [OPTIONS]

Options:

--domain DOMAIN_NAME	Domain name
--domain-id DOMAIN_ID	Numerical ID or domain name
--hidden-value HIDDEN_VALUE	Should the value be hidden
	One of true/false, yes/no, 1/0.
--name NAME	Parameter name
--value VALUE	Parameter value
-h, --help	Print help

10.21.7. hammer domain update

Update a domain

Usage:

hammer domain update [OPTIONS]

Options:

--description DESC	Full name describing the domain
--dns DNS_NAME	Name of DNS proxy to use within this domain
--dns-id DNS_ID	ID of DNS proxy to use within this domain
--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-ids LOCATION_IDS	REPLACE locations with given ids
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--location-title LOCATION_TITLE	Location title
--location-titles LOCATION_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--locations LOCATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--name NAME	Domain name

```

--new-name NEW_NAME          The full DNS domain name
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-ids ORGANIZATION_IDS  REPLACE organizations with given ids.
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE  Organization title
--organization-titles ORGANIZATION_TITLES  Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES  Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
-h, --help                    Print help

```

10.22. HAMMER ENVIRONMENT

Manipulate environments

```

Usage:
  hammer environment [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  create              Create an environment
  delete              Delete an environment
  info                Show an environment
  list                List all environments
  sc-params            List all smart class parameters
  update              Update an environment

Options:
  -h, --help          Print help

```

10.22.1. hammer environment create

Create an environment

```

Usage:
  hammer environment create [OPTIONS]

Options:
  --location LOCATION_NAME          Location name
  --location-id LOCATION_ID
  --location-ids LOCATION_IDS       REPLACE locations with given ids
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
  --location-title LOCATION_TITLE    Location title
  --location-titles LOCATION_TITLES  Comma separated list of values. Values containing comma
                                   should be quoted or escaped with backslash
  --locations LOCATION_NAMES        Comma separated list of values. Values containing comma
                                   should be quoted or escaped with backslash
  --name NAME

```

```
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-ids ORGANIZATION_IDS    REPLACE organizations with given ids.
                                       Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES     Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
-h, --help                             Print help
```

10.22.2. hammer environment delete

Delete an environment

```
Usage:
  hammer environment delete [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Environment name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.22.3. hammer environment info

Show an environment

```
Usage:
  hammer environment info [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Environment name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.22.4. hammer environment list

List all environments

```
Usage:
```

```
hammer environment list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                     Paginate results
--per-page PER_PAGE             Number of entries per request
--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET_CLASS_ID ID of Puppet class
--search SEARCH                 Filter results
-h, --help                      Print help
```

10.22.5. hammer environment sc-params

List all smart class parameters

Usage:

```
hammer environment sc-params [OPTIONS]
```

Options:

```
--environment ENVIRONMENT_NAME Environment name
--environment-id ENVIRONMENT_ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                     Paginate results
--per-page PER_PAGE             Number of entries per request
--search SEARCH                 Filter results
--show-hidden SHOW_HIDDEN      Display hidden values
                                One of true/false, yes/no, 1/0.
-h, --help                      Print help
```

10.22.6. hammer environment update

Update an environment

Usage:

```
hammer environment update [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS    REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
```

```

quoted or escaped with backslash
--location-title LOCATION_TITLE      Location title
--location-titles LOCATION_TITLES    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES           Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--name NAME                          Environment name
--new-name NEW_NAME
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID     Organization ID
--organization-ids ORGANIZATION_IDS   REPLACE organizations with given ids.
                                     Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES    Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
-h, --help                            Print help

```

10.23. HAMMER ERRATUM

Manipulate errata

```

Usage:
  hammer erratum [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  info                Show an erratum
  list                List errata

Options:
  -h, --help          Print help

```

10.23.1. hammer erratum info

Show an erratum

```

Usage:
  hammer erratum info [OPTIONS]

Options:
  --id ID              An erratum identifier
  --name NAME          Name to search by
  --repository REPOSITORY_NAME Repository name to search by
  --repository-id REPOSITORY_ID Repository ID
  -h, --help          Print help

```

10.23.2. hammer erratum list

List errata

Usage:

```
hammer erratum list [OPTIONS]
```

Options:

```
--available-for AVAILABLE_FOR      Return errata that can be added to the specified
object. The values

                                     'content_view_version' and 'content_view_filter' are supported.
--content-view CONTENT_VIEW_NAME    Content view name to search by
--content-view-filter CONTENT_VIEW_FILTER_NAME    Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID    Filter identifier
--content-view-id CONTENT_VIEW_ID      Content view numeric identifier
--content-view-version CONTENT_VIEW_VERSION_VERSION    Content view version number
--content-view-version-id CONTENT_VIEW_VERSION_ID    Content view version identifier
--cve CVE                            CVE identifier
--environment ENVIRONMENT_NAME        Environment name
--environment-id ENVIRONMENT_ID
--errata-restrict-applicable ERRATA_RESTRICT_APPLICABLE    Return errata that are applicable to
one or more hosts (defaults to true if
                                     Host_id is specified)
                                     One of true/false, yes/no, 1/0.
--errata-restrict-installable ERRATA_RESTRICT_INSTALLABLE    Return errata that are upgradable
on one or more hosts
                                     One of true/false, yes/no, 1/0.
--full-result FULL_RESULT            Whether or not to show all results
                                     One of true/false, yes/no, 1/0.
--host HOST_NAME                     Host name
--host-id HOST_ID
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID      Organization ID
--organization-label ORGANIZATION_LABEL    Organization label to search by
--page PAGE                          Page number, starting at 1
--per-page PER_PAGE                  Number of results per page to return
--product PRODUCT_NAME               Product name to search by
--product-id PRODUCT_ID               Product numeric identifier
--repository REPOSITORY_NAME           Repository name to search by
--repository-id REPOSITORY_ID          Repository ID
--search SEARCH                      Search string
-h, --help                          Print help
```

10.24. HAMMER EXPORT-TEMPLATES

Export templates to a git repo or a directory on the server

Usage:

```
hammer export-templates [OPTIONS]
```

Options:

```
--branch BRANCH                    Branch in Git repo.
--dirname DIRNAME                  The directory within Git repo containing the templates
--filter FILTER                    Export templates with names matching this regex (case-insensitive;
snippets
                                     Are not filtered).
```

```

--location LOCATION_NAME          Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS       REPLACE locations with given ids
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--location-title LOCATION_TITLE   Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--locations LOCATION_NAMES        Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--metadata-export-mode METADATA_EXPORT_MODE Specify how to handle metadata
                                   Possible value(s): 'refresh', 'keep', 'remove'
--negate NEGATE                   Negate the prefix (for purging).
                                   One of true/false, yes/no, 1/0.
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--repo REPO                       Override the default repo from settings.
--verbose BE_VERBOSE              Be verbose
                                   One of true/false, yes/no, 1/0.
-h, --help                       Print help

```

10.25. HAMMER FACT

Search facts

```

Usage:
  hammer fact [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  list                List all fact values

Options:
  -h, --help          Print help

```

10.25.1. hammer fact list

List all fact values

```

Usage:
  hammer fact list [OPTIONS]

Options:

```

```

--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                     Print help

```

10.26. HAMMER FILE

Manipulate files

Usage:
hammer file [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
SUBCOMMAND Subcommand
[ARG] ... Subcommand arguments

Subcommands:
info Show a file
list List files

Options:
-h, --help Print help

10.26.1. hammer file info

Show a file

Usage:
hammer file info [OPTIONS]

Options:
--content-view CONTENT_VIEW_NAME Content view name to search by
--content-view-id CONTENT_VIEW_ID Content view numeric identifier
--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
--content-view-version-id CONTENT_VIEW_VERSION_ID Content View Version ID
--id ID A file identifier
--name NAME File name to search by
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID Product numeric identifier
--repository REPOSITORY_NAME Repository name to search by
--repository-id REPOSITORY_ID Repository ID
-h, --help Print help

10.26.2. hammer file list

List files

Usage:

hammer file list [OPTIONS]

Options:

```
--content-view CONTENT_VIEW_NAME          Content view name to search by
--content-view-filter CONTENT_VIEW_FILTER_NAME  Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID  Filter identifier
--content-view-id CONTENT_VIEW_ID            Content view numeric identifier
--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier
--environment ENVIRONMENT_NAME              Environment name
--environment-id ENVIRONMENT_ID
--full-result FULL_RESULT                    Whether or not to show all results
                                           One of true/false, yes/no, 1/0.
--ids IDS                                    Ids to filter content by
                                           Comma separated list of values. Values containing comma should
                                           be quoted or escaped with backslash
--order ORDER                               Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME            Organization name to search by
--organization-id ORGANIZATION_ID           Organization ID
--organization-label ORGANIZATION_LABEL      Organization label to search by
--page PAGE                                  Page number, starting at 1
--per-page PER_PAGE                          Number of results per page to return
--product PRODUCT_NAME                      Product name to search by
--product-id PRODUCT_ID                     Product numeric identifier
--repository REPOSITORY_NAME                Repository name to search by
--repository-id REPOSITORY_ID               Repository ID
--search SEARCH                             Search string
-h, --help                                  Print help
```

10.27. HAMMER FILTER

Manage permission filters

Usage:

hammer filter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...            Subcommand arguments
```

Subcommands:

```
available-permissions  List all permissions
available-resources     List available resource types
create                 Create a filter
delete                 Delete a filter
info                   Show a filter
list                   List all filters
update                 Update a filter
```

Options:

-h, --help Print help

10.27.1. hammer filter available-permissions

List all permissions

Usage:

hammer filter available-permissions [OPTIONS]

Options:

--location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-title LOCATION_TITLE Location title
 --name NAME
 --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION_TITLE Organization title
 --page PAGE Paginate results
 --per-page PER_PAGE Number of entries per request
 --resource-type RESOURCE_TYPE
 --search SEARCH Filter results
 -h, --help Print help

10.27.2. hammer filter available-resources

List available resource types

Usage:

hammer filter available-resources [OPTIONS]

Options:

--location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-title LOCATION_TITLE Location title
 --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION_TITLE Organization title
 -h, --help Print help

10.27.3. hammer filter create

Create a filter

Usage:

hammer filter create [OPTIONS]

Options:

--location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-ids LOCATION_IDS Comma separated list of values. Values containing comma

should be quoted or escaped with backslash

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--override OVERRIDE One of true/false, yes/no, 1/0.

--permission-ids PERMISSION_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--permissions PERMISSION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--role ROLE_NAME User role name

--role-id ROLE_ID

--search SEARCH

-h, --help Print help

Overriding organizations and locations:

Filters inherit organizations and locations from its role by default. This behavior can be changed by setting `--override=true`.

Therefore options `--organization[s]-ids` and `--location[s]-ids` are applicable only when the override flag is set.

10.27.4. hammer filter delete

Delete a filter

Usage:

hammer filter delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

10.27.5. hammer filter info

Show a filter

Usage:

```
hammer filter info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.27.6. hammer filter list

List all filters

Usage:

```
hammer filter list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                    Print help
```

10.27.7. hammer filter update

Update a filter

Usage:

```
hammer filter update [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES     Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
```

```

--organization-title ORGANIZATION_TITLE  Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--override OVERRIDE                     One of true/false, yes/no, 1/0.
--permission-ids PERMISSION_IDS         Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--permissions PERMISSION_NAMES          Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--role ROLE_NAME                        User role name
--role-id ROLE_ID
--search SEARCH
-h, --help                               Print help

```

Overriding organizations and locations:

Filters inherit organizations and locations from its role by default. This behavior can be changed by setting `--override=true`.

Therefore options `--organization[s]-ids` and `--location[s]-ids` are applicable only when the override flag is set.

10.28. HAMMER FOREIGN-INPUT-SET

Manage foreign input sets

Usage:

```
hammer foreign-input-set [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```

SUBCOMMAND          Subcommand
[ARG] ...            Subcommand arguments

```

Subcommands:

```

create              Create a foreign input set
delete              Delete a foreign input set
info                Show foreign input set details
list                List foreign input sets
update              Update a foreign input set

```

Options:

```
-h, --help          Print help
```

10.28.1. hammer foreign-input-set create

Create a foreign input set

Usage:

```
hammer foreign-input-set create [OPTIONS]
```

Options:

```

--description DESCRIPTION      Input set description
--exclude EXCLUDE              A comma separated list of input names to be included from the
foreign

```



```

                                Template.
--include INCLUDE              A comma separated list of input names to be included from the
foreign
                                Template.
--include-all INCLUDE_ALL      Include all inputs from the foreign template
                                One of true/false, yes/no, 1/0.
--location LOCATION_NAME       Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--target-template-id TARGET_TEMPLATE_ID Target template ID
--template-id TEMPLATE_ID
-h, --help                     Print help

```

10.28.2. hammer foreign-input-set delete

Delete a foreign input set

```

Usage:
  hammer foreign-input-set delete [OPTIONS]

Options:
--id ID
--location LOCATION_NAME       Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--template-id TEMPLATE_ID
-h, --help                     Print help

```

10.28.3. hammer foreign-input-set info

Show foreign input set details

```

Usage:
  hammer foreign-input-set info [OPTIONS]

Options:
--id ID
--location LOCATION_NAME       Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--template-id TEMPLATE_ID
-h, --help                     Print help

```

10.28.4. hammer foreign-input-set list

List foreign input sets

Usage:

```
hammer foreign-input-set list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
--template-id TEMPLATE_ID
-h, --help                    Print help
```

10.28.5. hammer foreign-input-set update

Update a foreign input set

Usage:

```
hammer foreign-input-set update [OPTIONS]
```

Options:

```
--description DESCRIPTION      Input set description
--exclude EXCLUDE              A comma separated list of input names to be included from the
foreign
                                Template.
--id ID
--include INCLUDE              A comma separated list of input names to be included from the
foreign
                                Template.
--include-all INCLUDE_ALL      Include all inputs from the foreign template
                                One of true/false, yes/no, 1/0.
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--new-name NEW_NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--target-template-id TARGET_TEMPLATE_ID Target template ID
--template-id TEMPLATE_ID
-h, --help                    Print help
```

10.29. HAMMER FULL-HELP

Print help for all hammer commands

Usage:
hammer full-help [OPTIONS]

Options:
--md Format output in markdown
-h, --help Print help

10.30. HAMMER GLOBAL-PARAMETER

Manipulate global parameters

Usage:
hammer global-parameter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
SUBCOMMAND Subcommand
[ARG] ... Subcommand arguments

Subcommands:
delete Delete a global parameter
list List all global parameters
set Set a global parameter

Options:
-h, --help Print help

10.30.1. hammer global-parameter delete

Delete a global parameter

Usage:
hammer global-parameter delete [OPTIONS]

Options:
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Common parameter name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.30.2. hammer global-parameter list

List all global parameters

Usage:
hammer global-parameter list [OPTIONS]

Options:
--location LOCATION_NAME Location name
--location-id LOCATION_ID

```
--location-title LOCATION_TITLE      Location title
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                   Number of entries per request
--search SEARCH                       Filter results
--show-hidden SHOW_HIDDEN             Display hidden values
                                     One of true/false, yes/no, 1/0.
-h, --help                           Print help
```

10.30.3. hammer global-parameter set

Set a global parameter

```
Usage:
  hammer global-parameter set [OPTIONS]

Options:
--hidden-value HIDDEN_VALUE  Should the value be hidden
                             One of true/false, yes/no, 1/0.
--name NAME                  Parameter name
--value VALUE                Parameter value
-h, --help                   Print help
```

10.31. HAMMER GPG

Manipulate GPG Key actions on the server

```
Usage:
  hammer gpg [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments

Subcommands:
create              Create a gpg key
delete              Destroy a gpg key
info                Show a gpg key
list                List gpg keys
update              Update a repository

Options:
-h, --help          Print help
```

10.31.1. hammer gpg create

Create a gpg key

```
Usage:
  hammer gpg create [OPTIONS]
```

Options:

```
--key GPG_KEY_FILE          GPG Key file
--name NAME                  Identifier of the gpg key
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                  Print help
```

10.31.2. hammer gpg delete

Destroy a gpg key

Usage:

```
hammer gpg delete [OPTIONS]
```

Options:

```
--id ID                      Gpg key numeric identifier
--name NAME                  Name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                  Print help
```

10.31.3. hammer gpg info

Show a gpg key

Usage:

```
hammer gpg info [OPTIONS]
```

Options:

```
--id ID                      Gpg key numeric identifier
--name NAME                  Name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                  Print help
```

10.31.4. hammer gpg list

List gpg keys

Usage:

```
hammer gpg list [OPTIONS]
```

Options:

```
--full-result FULL_RESULT  Whether or not to show all results
                           One of true/false, yes/no, 1/0.
--name NAME                Name of the GPG key
--order ORDER              Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
```

```
--organization-label ORGANIZATION_LABEL Organization label to search by
--page PAGE                               Page number, starting at 1
--per-page PER_PAGE                       Number of results per page to return
--search SEARCH                           Search string
-h, --help                                Print help
```

10.31.5. hammer gpg update

Update a repository

Usage:

```
hammer gpg update [OPTIONS]
```

Options:

```
--id ID                                Gpg key numeric identifier
--key GPG_KEY_FILE                     GPG Key file
--name NAME                            Name to search by
--new-name NEW_NAME                    Identifier of the gpg key
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID      Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                             Print help
```

10.32. HAMMER HOST

Manipulate hosts

Usage:

```
hammer host [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND                            Subcommand
[ARG] ...                             Subcommand arguments
```

Subcommands:

```
ansible-roles    List all Ansible roles for a host
boot             Boot host from specified device
config-reports   List all reports
create           Create a host
delete           Delete a host
delete-parameter Delete parameter for a host
disassociate     Disassociate a host
enc-dump         Dump host's ENC YAML
errata           Manage errata on your hosts
facts            List all fact values
info             Show a host
interface        View and manage host's network interfaces
list             List all hosts
package          Manage packages on your hosts
package-group    Manage package-groups on your hosts
puppet-classes   List all Puppet classes
puppetrun        Force a Puppet agent run on the host
reboot           Reboot a host
rebuild-config    Rebuild orchestration related configurations for host
```

reports	List all reports
reset	Reset a host
sc-params	List all smart class parameters
set-parameter	Create or update parameter for a host
smart-variables	List all smart variables
start	Power a host on
status	Get configuration status of host
stop	Power a host off
subscription	Manage subscription information on your hosts
update	Update a host

Options:

-h, --help	Print help
------------	------------

10.32.1. hammer host ansible-roles

List all Ansible roles for a host

Usage:

```
hammer host ansible-roles [OPTIONS]
```

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Host name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.32.2. hammer host boot

Boot host from specified device

Usage:

```
hammer host boot [OPTIONS]
```

Options:

--device DEVICE	Boot device, valid devices are disk, cdrom, pxe, bios
--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Host name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.32.3. hammer host config-reports

List all reports

Usage:

```
hammer host config-reports [OPTIONS]
```

Options:

```
--id ID                Host id
--location LOCATION_NAME    Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE    Location title
--name NAME                Host name
--order ORDER              Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE    Organization title
--page PAGE                Paginate results
--per-page PER_PAGE        Number of entries per request
--search SEARCH            Filter results
-h, --help                Print help
```

10.32.4. hammer host create

Create a host

Usage:

```
hammer host create [OPTIONS]
```

Options:

```
--ansible-role-ids ANSIBLE_ROLE_IDS    IDs of associated ansible roles
                                         Comma separated list of values. Values containing comma
                                         should be quoted or escaped with backslash
--ansible-roles ANSIBLE_ROLE_NAMES    Comma separated list of values. Values
                                         containing comma should be quoted or escaped with backslash
--architecture ARCHITECTURE_NAME    Architecture name
--architecture-id ARCHITECTURE_ID
--ask-root-password ASK_ROOT_PW        One of true/false, yes/no, 1/0.
--autoheal AUTOHEAL                  Sets whether the Host will autoheal subscriptions
                                         upon checkin
                                         One of true/false, yes/no, 1/0.
--build BUILD                        One of true/false, yes/no, 1/0.
--comment COMMENT                    Additional information about this host
--compute-attributes COMPUTE_ATTRS    Compute resource attributes
                                         Comma-separated list of key=value
--compute-profile COMPUTE_PROFILE_NAME    Name to search by
--compute-profile-id COMPUTE_PROFILE_ID
--compute-resource COMPUTE_RESOURCE_NAME    Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--config-group-ids CONFIG_GROUP_IDS    IDs of associated config groups
                                         Comma separated list of values. Values containing comma
                                         should be quoted or escaped with backslash
--config-groups CONFIG_GROUP_NAMES    Comma separated list of values. Values
                                         containing comma should be quoted or escaped with backslash
--content-source CONTENT_SOURCE_NAME    Content Source name
--content-source-id CONTENT_SOURCE_ID
--content-view CONTENT_VIEW_NAME    Name to search by
```


--content-view-id CONTENT_VIEW_ID	Content view numeric identifier
--domain DOMAIN_NAME	Domain name
--domain-id DOMAIN_ID	Numerical ID or domain name
--enabled ENABLED	Include this host within Satellite reporting
	One of true/false, yes/no, 1/0.
--environment ENVIRONMENT_NAME	Environment name
--environment-id ENVIRONMENT_ID	
--hostgroup HOSTGROUP_NAME	Hostgroup name
--hostgroup-id HOSTGROUP_ID	
--hostgroup-title HOSTGROUP_TITLE	Hostgroup title
--hypervisor-guest-uuids HYPERVISOR_GUEST_UUIDS	List of hypervisor guest uuids
	Comma separated list of values. Values containing comma
should be quoted or escaped with backslash	
--image IMAGE_NAME	Name to search by
--image-id IMAGE_ID	
--installed-products-attributes INSTALLED_PRODUCTS_ATTRIBUTES	List of products installed on the host
	Comma separated list of values. Values containing comma
should be quoted or escaped with backslash	
--interface INTERFACE	Interface parameters
	Comma-separated list of key=value
	Can be specified multiple times.
--ip IP	Not required if using a subnet with DHCP Capsule
--kickstart-repository REPOSITORY_NAME	Kickstart repository name
--kickstart-repository-id KICKSTART_REPOSITORY_ID	Repository Id associated with the kickstart repo used for provisioning
--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME	Name to search by
--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID	ID of the environment
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--mac MAC	Required for managed host that is bare metal, not required if it's a
	Virtual machine
--managed MANAGED	True/False flag whether a host is managed or unmanaged. Note: this value
	Also determines whether several parameters are required or not
	One of true/false, yes/no, 1/0.
--medium MEDIUM_NAME	Medium name
--medium-id MEDIUM_ID	
--model MODEL_NAME	Model name
--model-id MODEL_ID	
--name NAME	
--openscap-proxy-id OPENSAP_PROXY_ID	ID of OpenSCAP Capsule
--operatingsystem OPERATINGSYSTEM_TITLE	Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID	
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--overwrite OVERWRITE	One of true/false, yes/no, 1/0.
	Default: "true"
--owner OWNER_LOGIN	Login of the owner
--owner-id OWNER_ID	ID of the owner
--owner-type OWNER_TYPE	Host's owner type
	Possible value(s): 'User', 'Usergroup'

```

--parameters PARAMS                                Host parameters
                                                    Comma-separated list of key=value
--partition-table PARTITION_TABLE_NAME              Partition table name
--partition-table-id PARTITION_TABLE_ID
--product PRODUCT_NAME                               Name to search by
--product-id PRODUCT_ID                             Product numeric identifier
--progress-report-id PROGRESS_REPORT_ID              UUID to track orchestration tasks
status, GET
                                                    /api/orchestration/:UUID/tasks
--provision-method PROVISION_METHOD                  The method used to provision the host.
                                                    Possible value(s): 'build', 'image', 'bootdisk'
--puppet-ca-proxy PUPPET_CA_PROXY_NAME
--puppet-ca-proxy-id PUPPET_CA_PROXY_ID              Puppet CA Capsule ID
--puppet-class-ids PUPPET_CLASS_IDS                  Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--puppet-classes PUPPET_CLASS_NAMES                  Comma separated list of values.
Values containing comma should be quoted or escaped with backslash
--puppet-proxy PUPPET_PROXY_NAME
--puppet-proxy-id PUPPET_PROXY_ID                    Puppet Capsule ID
--purpose-addons PURPOSE_ADDONS                      Sets the system add-ons
                                                    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--purpose-role PURPOSE_ROLE                          Sets the system purpose usage
--purpose-usage PURPOSE_USAGE                        Sets the system purpose usage
--pxe-loader PXE_LOADER                             DHCP filename option (Grub2/PXELinux by
default)
                                                    Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI',
'Grub UEFI', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded', 'iPXE Chain BIOS', 'iPXE
Chain UEFI'
--realm REALM_NAME                                   Name to search by
--realm-id REALM_ID                                  Numerical ID or realm name
--release-version RELEASE_VERSION                    Release version for this Host to use
(7Server, 7.1, etc)
--root-password ROOT_PW                             Required if host is managed and value is not
inherited from host group or default password in settings
--service-level SERVICE_LEVEL                       Service level to be used for autoheal
--subnet SUBNET_NAME                                 Subnet name
--subnet-id SUBNET_ID
--volume VOLUME                                       Volume parameters
                                                    Comma-separated list of key=value
                                                    Can be specified multiple times.
-h, --help                                           Print help

```

Available keys for --interface:

```

mac
ip
type          Possible values: interface, bmc, bond, bridge
name
subnet_id
domain_id
identifier
managed       true/false
primary       true/false, each managed hosts needs to have one primary interface.
provision     true/false
virtual       true/false

```

For virtual=true:

- tag VLAN tag, this attribute has precedence over the subnet VLAN ID. Only for virtual interfaces.
- attached_to Identifier of the interface to which this interface belongs, e.g. eth1.

For type=bond:

- mode Possible values: balance-rr, active-backup, balance-xor, broadcast, 802.3ad, balance-tlb, balance-alb
- attached_devices Identifiers of slave interfaces, e.g. [eth1,eth2]
- bond_options

For type=bmc:

- provider always IPMI
- username
- password

Provider specific options:

EC2:

- compute-attributes:
 - flavor_id
 - image_id
 - availability_zone
 - security_group_ids
 - managed_ip

GCE:

- compute-attributes:
 - machine_type
 - image_id
 - network
 - external_ip

Libvirt:

- compute-attributes:
 - cpus Number of CPUs
 - memory String, amount of memory, value in bytes
 - start Boolean (expressed as 0 or 1), whether to start the machine or not
- interface:
 - compute_type Possible values: bridge, network
 - compute_network / compute_bridge Name of interface according to type
 - compute_model Possible values: virtio, rtl8139, ne2k_pci, pcnet, e1000
- volume:
 - pool_name One of available storage pools
 - capacity String value, eg. 10G
 - format_type Possible values: raw, qcow2

OpenStack:

- compute-attributes:
 - flavor_ref
 - image_ref
 - tenant_id
 - security_groups
 - network

oVirt:**--compute-attributes:**

cluster ID of cluster to use
 template Hardware profile to use
 cores Integer value, number of cores
 memory Amount of memory, integer value in bytes
 start Boolean (expressed as 0 or 1), whether to start the machine or not

--interface:

compute_name Eg. eth0
 compute_network Select one of available networks for a cluster, must be an ID

--volume:

size_gb Volume size in GB, integer value
 storage_domain ID of storage domain
 bootable Boolean, only one volume can be bootable

Rackspace:**--compute-attributes:**

flavor_id
 image_id

VMware:**--compute-attributes:**

cpus CPU count
 corespersocket Number of cores per socket (applicable to hardware versions < 10 only)
 memory_mb Integer number, amount of memory in MB
 firmware automatic/bios/efi
 cluster Cluster ID from VMware
 resource_pool Resource Pool ID from VMware
 path Path to folder
 guest_id Guest OS ID from VMware
 scsi_controller_type ID of the controller from VMware
 hardware_version Hardware version ID from VMware
 add_cdrom Must be a 1 or 0, Add a CD-ROM drive to the virtual machine
 cpuHotAddEnabled Must be a 1 or 0, lets you add memory resources while the machine is on
 memoryHotAddEnabled Must be a 1 or 0, lets you add CPU resources while the machine is on
 start Must be a 1 or 0, whether to start the machine or not
 annotation Annotation Notes

--interface:

compute_type Type of the network adapter, for example one of:
 VirtualVmxnet3,
 VirtualE1000
 See documentation center for your version of vSphere to find more details about

available adapter types:

<https://www.vmware.com/support/pubs/>

compute_network Network ID from VMware

--volume:

name
 storage_pod Storage Pod ID from VMware
 datastore Datastore ID from VMware
 size_gb Integer number, volume size in GB

thin	true/false
eager_zero	true/false
mode	persistent/independent_persistent/independent_nonpersistent

10.32.5. hammer host delete

Delete a host

```
Usage:
  hammer host delete [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                   Host name
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                   Print help
```

10.32.6. hammer host delete-parameter

Delete parameter for a host

```
Usage:
  hammer host delete-parameter [OPTIONS]

Options:
  --host HOST_NAME      Host name
  --host-id HOST_ID
  --name NAME           Parameter name
  -h, --help           Print help
```

10.32.7. hammer host disassociate

Disassociate a host

```
Usage:
  hammer host disassociate [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                   Host name
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                   Print help
```

10.32.8. hammer host enc-dump

Dump host's ENC YAML

```
Usage:
  hammer host enc-dump [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --name NAME                           Host name
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                            Print help
```

10.32.9. hammer host errata

Manage errata on your hosts

```
Usage:
  hammer host errata [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  apply              Schedule errata for installation
  info              Retrieve a single errata for a host
  list              List errata available for the content host
  recalculate        Force regenerate applicability.

Options:
  -h, --help        Print help
```

Unfortunately the server does not support such operation.

10.32.9.1. hammer host errata apply

Schedule errata for installation

```
Usage:
  hammer host errata apply [OPTIONS]

Options:
  --async          Do not wait for the task
  --errata-ids ERRATA_IDS  List of Errata ids to install
                        Comma separated list of values. Values containing comma should be quoted or
                        escaped with backslash
```

```
--host HOST_NAME      Host name
--host-id HOST_ID
-h, --help            Print help
```

10.32.9.2. hammer host errata info

Retrieve a single errata for a host

```
Usage:
  hammer host errata info [OPTIONS]

Options:
--host HOST_NAME      Host name
--host-id HOST_ID
--id ID               Errata id of the erratum (RHSA-2012:108)
--name NAME           Name to search by
-h, --help            Print help
```

10.32.9.3. hammer host errata list

List errata available for the content host

```
Usage:
  hammer host errata list [OPTIONS]

Options:
--content-view CONTENT_VIEW_NAME Content view name to search by
--content-view-id CONTENT_VIEW_ID Content view numeric identifier
--environment ENVIRONMENT_NAME  Environment name
--environment-id ENVIRONMENT_ID
--full-result FULL_RESULT       Whether or not to show all results
                                One of true/false, yes/no, 1/0.
--host HOST_NAME                Host name
--host-id HOST_ID
--order ORDER                   Sort field and order, eg. 'id DESC'
--page PAGE                     Page number, starting at 1
--per-page PER_PAGE             Number of results per page to return
--search SEARCH                 Search string
-h, --help                      Print help
```

10.32.9.4. hammer host errata recalculate

Force regenerate applicability.

```
Usage:
  hammer host errata recalculate [OPTIONS]

Options:
--async              Do not wait for the task
--host HOST_NAME     Host name
--host-id HOST_ID
-h, --help           Print help
```

10.32.10. hammer host facts

List all fact values

```
Usage:
  hammer host facts [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --name NAME                           Host name
  --order ORDER                         Sort field and order, eg. 'id DESC'
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID      Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --page PAGE                           Paginate results
  --per-page PER_PAGE                   Number of entries per request
  --search SEARCH                       Filter results
  -h, --help                           Print help
```

10.32.11. hammer host info

Show a host

```
Usage:
  hammer host info [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --name NAME                           Host name
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID      Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values
                                              One of true/false, yes/no, 1/0.
  -h, --help                           Print help
```

10.32.12. hammer host interface

View and manage host's network interfaces

```
Usage:
  hammer host interface [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
```


create	Create an interface on a host
delete	Delete a host's interface
info	Show an interface for host
list	List all interfaces for host
update	Update a host's interface
Options:	
-h, --help	Print help

10.32.12.1. hammer host interface create

Create an interface on a host

Usage:

hammer host interface create [OPTIONS]

Options:

--attached-devices ATTACHED_DEVICES Identifiers of attached interfaces, e.g. `[eth1', 'eth2']`. For bond interfaces those are the slaves. Only for bond And bridges interfaces.
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--attached-to ATTACHED_TO Identifier of the interface to which this interface belongs, e.g. eth1.
Only for virtual interfaces.

--bond-options BOND_OPTIONS Space separated options, e.g. miimon=100. Only for bond interfaces.

--compute-attributes COMPUTE_ATTRS Compute resource specific attributes
Comma-separated list of key=value

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID Numerical ID or domain name

--host HOST_NAME Host name

--host-id HOST_ID

--identifier IDENTIFIER Device identifier, e.g. eth0 or eth1.1

--ip IP IPv4 address of interface

--ip6 IP6 IPv6 address of interface

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--mac MAC MAC address of interface. Required for managed interfaces on bare metal.

--managed MANAGED Should this interface be managed via DHCP and DNS capsule and should it be
Configured during provisioning?
One of true/false, yes/no, 1/0.

--mode MODE Bond mode of the interface, e.g. balance-rr. Only for bond interfaces.
Possible value(s): 'balance-rr', 'active-backup', 'balance-xor', 'broadcast', '802.3ad', 'balance-tlb', 'balance-alb'

--mtu MTU MTU, this attribute has precedence over the subnet MTU.

--name NAME Interface's DNS name

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--password PASSWORD Only for BMC interfaces.

```

--primary                Should this interface be used for constructing the FQDN of the host?
Each managed hosts needs to have one primary interface
--provider PROVIDER      Interface provider, e.g. IPMI. Only for BMC interfaces.
                        Possible value(s): 'IPMI', 'SSH'
--provision              Should this interface be used for TFTP of PXELinux (or SSH for image-
based hosts)? Each managed hosts needs to have one provision interface
--subnet SUBNET_NAME     Subnet name
--subnet-id SUBNET_ID
--subnet6-id SUBNET6_ID  Satellite subnet ID of IPv6 interface
--tag TAG                VLAN tag, this attribute has precedence over the subnet VLAN ID. Only
for
                        Virtual interfaces.
--type TYPE              Interface type, e.g. bmc. Default is interface
                        Possible value(s): 'interface', 'bmc', 'bond', 'bridge'
--username USERNAME     Only for BMC interfaces.
--virtual VIRTUAL        Alias or VLAN device
                        One of true/false, yes/no, 1/0.
-h, --help               Print help

```

10.32.12.2. hammer host interface delete

Delete a host's interface

```

Usage:
  hammer host interface delete [OPTIONS]

Options:
  --host HOST_NAME      Host name
  --host-id HOST_ID
  --id ID               ID of interface
  --location LOCATION_NAME  Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE  Location title
  --organization ORGANIZATION_NAME  Organization name
  --organization-id ORGANIZATION_ID  Organization ID
  --organization-title ORGANIZATION_TITLE  Organization title
  -h, --help           Print help

```

10.32.12.3. hammer host interface info

Show an interface for host

```

Usage:
  hammer host interface info [OPTIONS]

Options:
  --host HOST_NAME      Host name
  --host-id HOST_ID
  --id ID               ID or name of interface
  --location LOCATION_NAME  Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE  Location title
  --organization ORGANIZATION_NAME  Organization name

```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help
```

10.32.12.4. hammer host interface list

List all interfaces for host

Usage:

```
hammer host interface list [OPTIONS]
```

Options:

```
--domain DOMAIN_NAME                Domain name
--domain-id DOMAIN_ID                Numerical ID or domain name
--host HOST_NAME                     Host name
--host-id HOST_ID
--location LOCATION_NAME             Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                           Paginate results
--per-page PER_PAGE                  Number of entries per request
--subnet SUBNET_NAME                 Subnet name
--subnet-id SUBNET_ID
-h, --help                            Print help
```

10.32.12.5. hammer host interface update

Update a host's interface

Usage:

```
hammer host interface update [OPTIONS]
```

Options:

```
--attached-devices ATTACHED_DEVICES Identifiers of attached interfaces, e.g. `['eth1',
                                     'eth2']`. For bond interfaces those are the slaves. Only for bond
                                     And bridges interfaces.
                                     Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--attached-to ATTACHED_TO            Identifier of the interface to which this interface belongs, e.g.
eth1.
                                     Only for virtual interfaces.
--bond-options BOND_OPTIONS          Space separated options, e.g. miimon=100. Only for bond
interfaces.
--compute-attributes COMPUTE_ATTRS   Compute resource specific attributes
                                     Comma-separated list of key=value
--domain DOMAIN_NAME                Domain name
--domain-id DOMAIN_ID                Numerical ID or domain name
--host HOST_NAME                     Host name
--host-id HOST_ID
--id ID                              ID of interface
--identifier IDENTIFIER              Device identifier, e.g. eth0 or eth1.1
```

```

--ip IP                      IPv4 address of interface
--ip6 IP6                    IPv6 address of interface
--location LOCATION_NAME    Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE    Location title
--mac MAC                    MAC address of interface. Required for managed interfaces on bare
metal.
--managed MANAGED            Should this interface be managed via DHCP and DNS capsule
and should it be
                             Configured during provisioning?
                             One of true/false, yes/no, 1/0.
--mode MODE                  Bond mode of the interface, e.g. balance-rr. Only for bond
interfaces.
                             Possible value(s): 'balance-rr', 'active-backup', 'balance-xor', 'broadcast',
'802.3ad', 'balance-tlb', 'balance-alb'
--mtu MTU                    MTU, this attribute has precedence over the subnet MTU.
--name NAME                  Interface's DNS name
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE    Organization title
--password PASSWORD          Only for BMC interfaces.
--primary                    Should this interface be used for constructing the FQDN of the host?
Each managed hosts needs to have one primary interface
--provider PROVIDER          Interface provider, e.g. IPMI. Only for BMC interfaces.
                             Possible value(s): 'IPMI', 'SSH'
--provision                  Should this interface be used for TFTP of PXELinux (or SSH for image-
based hosts)? Each managed hosts needs to have one provision interface
--subnet SUBNET_NAME        Subnet name
--subnet-id SUBNET_ID
--subnet6-id SUBNET6_ID      Satellite subnet ID of IPv6 interface
--tag TAG                    VLAN tag, this attribute has precedence over the subnet VLAN ID. Only
for
                             Virtual interfaces.
--type TYPE                  Interface type, e.g. bmc. Default is interface
                             Possible value(s): 'interface', 'bmc', 'bond', 'bridge'
--username USERNAME          Only for BMC interfaces.
--virtual VIRTUAL            Alias or VLAN device
                             One of true/false, yes/no, 1/0.
-h, --help                  Print help

```

10.32.13. hammer host list

List all hosts

Usage:

```
hammer host list [OPTIONS]
```

Options:

```

--environment ENVIRONMENT_NAME    Environment name
--environment-id ENVIRONMENT_ID
--hostgroup HOSTGROUP_NAME        Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE    Hostgroup title
--location LOCATION_NAME          Location name
--location-id LOCATION_ID

```

```
--location-title LOCATION_TITLE      Location title
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                  Number of entries per request
--search SEARCH                      Filter results
--thin THIN                          Only list ID and name of hosts
                                   One of true/false, yes/no, 1/0.
-h, --help                          Print help
```

10.32.14. hammer host package

Manage packages on your hosts

Usage:

hammer host package [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

install	Install packages remotely
list	List packages installed on the host
remove	Uninstall packages remotely
upgrade	Update packages remotely
upgrade-all	Update packages remotely

Options:

-h, --help Print help

Unfortunately the server does not support such operation.

10.32.14.1. hammer host package install

Install packages remotely

Usage:

```
hammer host package install [OPTIONS]
```

Options:

```
--async          Do not wait for the task
--host HOST_NAME      Host name
--host-id HOST_ID
--packages PACKAGES    List of package names
                        Comma separated list of values. Values containing comma should be quoted or
                        escaped with backslash
-h, --help          Print help
```

10.32.14.2. hammer host package list

List packages installed on the host

Usage:

hammer host package list [OPTIONS]

Options:

--full-result FULL_RESULT Whether or not to show all results
 One of true/false, yes/no, 1/0.
--host HOST_NAME Host name
--host-id HOST_ID
--order ORDER Sort field and order, eg. 'id DESC'
--page PAGE Page number, starting at 1
--per-page PER_PAGE Number of results per page to return
--search SEARCH Search string
-h, --help Print help

10.32.14.3. hammer host package remove

Uninstall packages remotely

Usage:

hammer host package remove [OPTIONS]

Options:

--async Do not wait for the task
--host HOST_NAME Host name
--host-id HOST_ID
--packages PACKAGES List of package names
 Comma separated list of values. Values containing comma should be quoted or
escaped with backslash
-h, --help Print help

10.32.14.4. hammer host package upgrade

Update packages remotely

Usage:

hammer host package upgrade [OPTIONS]

Options:

--async Do not wait for the task
--host HOST_NAME Host name
--host-id HOST_ID
--packages PACKAGES List of packages names
 Comma separated list of values. Values containing comma should be quoted or
escaped with backslash
-h, --help Print help

10.32.14.5. hammer host package upgrade-all

Update packages remotely

Usage:

hammer host package upgrade-all [OPTIONS]

```
Options:
--async          Do not wait for the task
--host HOST_NAME      Host name
--host-id HOST_ID
-h, --help        Print help
```

10.32.15. hammer host package-group

Manage package-groups on your hosts

```
Usage:
  hammer host package-group [OPTIONS] SUBCOMMAND [ARG] ...
```

```
Parameters:
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments
```

```
Subcommands:
install            Install packages remotely
remove            Uninstall packages remotely
```

```
Options:
-h, --help        Print help
```

Unfortunately the server does not support such operation.

10.32.15.1. hammer host package-group install

Install packages remotely

```
Usage:
  hammer host package-group install [OPTIONS]
```

```
Options:
--async          Do not wait for the task
--groups GROUPS  List of package group names
                  Comma separated list of values. Values containing comma should be quoted or
                  escaped with backslash
--host HOST_NAME      Host name
--host-id HOST_ID
-h, --help        Print help
```

10.32.15.2. hammer host package-group remove

Uninstall packages remotely

```
Usage:
  hammer host package-group remove [OPTIONS]
```

```
Options:
--async          Do not wait for the task
--groups GROUPS  List of package group names
                  Comma separated list of values. Values containing comma should be quoted or
```

```
escaped with backslash
--host HOST_NAME      Host name
--host-id HOST_ID
-h, --help            Print help
```

10.32.16. hammer host puppet-classes

List all Puppet classes

```
Usage:
  hammer host puppet-classes [OPTIONS]

Options:
--host HOST_NAME      Host name
--host-id HOST_ID
--location-id LOCATION_ID  Scope by locations
--order ORDER         Sort field and order, eg. 'id DESC'
--organization-id ORGANIZATION_ID  Scope by organizations
--page PAGE           Paginate results
--per-page PER_PAGE   Number of entries per request
--search SEARCH       Filter results
-h, --help            Print help
```

10.32.17. hammer host puppetrun

Force a Puppet agent run on the host

```
Usage:
  hammer host puppetrun [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
-h, --help                    Print help
```

10.32.18. hammer host reboot

Reboot a host

```
Usage:
  hammer host reboot [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
```



```
--name NAME                Host name
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                Print help
```

10.32.19. hammer host rebuild-config

Rebuild orchestration related configurations for host

Usage:

```
hammer host rebuild-config [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--name NAME                  Host name
--only ONLY                  Limit rebuild steps, valid steps are DHCP, DNS, TFTP
                              Comma separated list of values. Values containing comma should be
                              quoted or escaped with backslash
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                  Print help
```

10.32.20. hammer host reports

List all reports

Usage:

```
hammer host reports [OPTIONS]
```

Options:

```
--id ID                Host id
--location LOCATION_NAME  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--name NAME              Host name
--order ORDER            Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE              Paginate results
--per-page PER_PAGE      Number of entries per request
--search SEARCH          Filter results
-h, --help              Print help
```

10.32.21. hammer host reset

Reset a host

Usage:

hammer host reset [OPTIONS]

Options:

--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Host name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.32.22. hammer host sc-params

List all smart class parameters

Usage:

hammer host sc-params [OPTIONS]

Options:

--host HOST_NAME Host name
--host-id HOST_ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE Paginate results
--per-page PER_PAGE Number of entries per request
--search SEARCH Filter results
--show-hidden SHOW_HIDDEN Display hidden values
One of true/false, yes/no, 1/0.
-h, --help Print help

10.32.23. hammer host set-parameter

Create or update parameter for a host

Usage:

hammer host set-parameter [OPTIONS]

Options:

--hidden-value HIDDEN_VALUE Should the value be hidden
One of true/false, yes/no, 1/0.
--host HOST_NAME Host name
--host-id HOST_ID
--name NAME Parameter name
--value VALUE Parameter value
-h, --help Print help

10.32.24. hammer host smart-variables

List all smart variables

Usage:

hammer host smart-variables [OPTIONS]

Options:

--host HOST_NAME	Host name
--host-id HOST_ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--order ORDER	Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--page PAGE	Paginate results
--per-page PER_PAGE	Number of entries per request
--search SEARCH	Filter results
--show-hidden SHOW_HIDDEN	Display hidden values
	One of true/false, yes/no, 1/0.
-h, --help	Print help

10.32.25. hammer host start

Power a host on

Usage:

hammer host start [OPTIONS]

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Host name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.32.26. hammer host status

Get configuration status of host

Usage:

hammer host status [OPTIONS]

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title

```
--name NAME                Host name
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                  Print help
```

10.32.27. hammer host stop

Power a host off

```
Usage:
  hammer host stop [OPTIONS]

Options:
  --force                Force turning off a host
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE  Location title
  --name NAME                Host name
  --organization ORGANIZATION_NAME  Organization name
  --organization-id ORGANIZATION_ID  Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                Print help
```

10.32.28. hammer host subscription

Manage subscription information on your hosts

```
Usage:
  hammer host subscription [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  attach              Add a subscription to a host
  auto-attach         Trigger an auto-attach of subscriptions
  content-override    Override product content defaults
  product-content     List associated products
  register            Register a host with subscription and information
  remove
  unregister          Unregister the host as a subscription consumer

Options:
  -h, --help          Print help
```

Unfortunately the server does not support such operation.

10.32.28.1. hammer host subscription attach

Add a subscription to a host

-

Usage:
hammer host subscription attach [OPTIONS]

Options:

--host HOST_NAME	Host name
--host-id HOST_ID	
--quantity Quantity	Quantity of this subscriptions to add. Defaults to 1
--subscription-id SUBSCRIPTION_ID	ID of subscription
-h, --help	Print help

10.32.28.2. hammer host subscription auto-attach

Trigger an auto-attach of subscriptions

Usage:
hammer host subscription auto-attach [OPTIONS]

Options:

--host HOST_NAME	Host name
--host-id HOST_ID	
-h, --help	Print help

10.32.28.3. hammer host subscription content-override

Override product content defaults

Usage:

```
hammer host subscription content-override [OPTIONS]
```

Options:

- content-label CONTENT_LABEL Label of the content
- host HOST_NAME Host name
- host-id HOST_ID
- override-name OVERRIDE_NAME Override parameter key or name.
 - To enable or disable a repo select 'enabled'.
 - Default value: enabled
 - Default: "enabled"
- remove Remove a content override
- value VALUE Override value. Note for repo enablement you can use a boolean value
- h, --help Print help

10.32.28.4. hammer host subscription product-content

List associated products

Usage:
hammer host subscription product-content [OPTIONS]

Options:

- content-access-mode-all CONTENT_ACCESS_MODE_ALL Get all content available, not just that provided by subscriptions
- content-access-mode-env CONTENT_ACCESS_MODE_ENV Limit content to just that available in

the host's content view version

One of true/false, yes/no, 1/0.

--host HOST_NAME Host name

--host-id HOST_ID

-h, --help Print help

10.32.28.5. hammer host subscription register

Register a host with subscription and information

Usage:

hammer host subscription register [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-id CONTENT_VIEW_ID Content view numeric identifier

--hypervisor-guest-uuids HYPERVISOR_GUEST_UUIDS UUIDs of the virtual guests from the host's hypervisor

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID ID of the environment

--name NAME Name of the host

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--release-version RELEASE_VERSION Release version of the content host

--service-level SERVICE_LEVEL A service level for auto-healing process, e.g. SELF-SUPPORT

--uuid UUID UUID to use for registered host, random uuid is generated if not provided

-h, --help Print help

10.32.28.6. hammer host subscription remove

Usage:

hammer host subscription remove [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--quantity Quantity Remove the first instance of a subscription with matching id and quantity

--subscription-id SUBSCRIPTION_ID ID of subscription

-h, --help Print help

10.32.28.7. hammer host subscription unregister

Unregister the host as a subscription consumer

Usage:

hammer host subscription unregister [OPTIONS]

Options:

```
--host HOST_NAME           Host name
--host-id HOST_ID
-h, --help                 Print help
```

10.32.29. hammer host update

Update a host

Usage:

hammer host update [OPTIONS]

Options:

```
--ansible-role-ids ANSIBLE_ROLE_IDS           IDs of associated ansible roles
                                                Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--ansible-roles ANSIBLE_ROLE_NAMES             Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--architecture ARCHITECTURE_NAME              Architecture name
--architecture-id ARCHITECTURE_ID
--ask-root-password ASK_ROOT_PW               One of true/false, yes/no, 1/0.
--autoheal AUTOHEAL                          Sets whether the Host will autoheal subscriptions
upon checkin
                                                One of true/false, yes/no, 1/0.
--build BUILD                                 One of true/false, yes/no, 1/0.
--comment COMMENT                            Additional information about this host
--compute-attributes COMPUTE_ATTRS            Compute resource attributes
                                                Comma-separated list of key=value
--compute-profile COMPUTE_PROFILE_NAME        Name to search by
--compute-profile-id COMPUTE_PROFILE_ID
--compute-resource COMPUTE_RESOURCE_NAME      Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--config-group-ids CONFIG_GROUP_IDS           IDs of associated config groups
                                                Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--config-groups CONFIG_GROUP_NAMES            Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--content-source CONTENT_SOURCE_NAME          Content Source name
--content-source-id CONTENT_SOURCE_ID
--content-view CONTENT_VIEW_NAME              Name to search by
--content-view-id CONTENT_VIEW_ID             Content view numeric identifier
--domain DOMAIN_NAME                         Domain name
--domain-id DOMAIN_ID                       Numerical ID or domain name
--enabled ENABLED                            Include this host within Satellite reporting
                                                One of true/false, yes/no, 1/0.
--environment ENVIRONMENT_NAME               Environment name
--environment-id ENVIRONMENT_ID
--hostgroup HOSTGROUP_NAME                   Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE             Hostgroup title
--hypervisor-guest-uuids HYPERVISOR_GUEST_UUIDS List of hypervisor guest uuids
                                                Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--id ID
--image IMAGE_NAME                           Name to search by
```

--image-id IMAGE_ID
 --installed-products-attributes INSTALLED_PRODUCTS_ATTRIBUTES List of products installed on the host
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --interface INTERFACE Interface parameters
 Comma-separated list of key=value
 Can be specified multiple times.
 --ip IP Not required if using a subnet with DHCP Capsule
 --kickstart-repository REPOSITORY_NAME Kickstart repository name
 --kickstart-repository-id KICKSTART_REPOSITORY_ID Repository Id associated with the kickstart repo used for provisioning
 --lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by
 --lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID ID of the environment
 --location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-title LOCATION_TITLE Location title
 --mac MAC Required for managed host that is bare metal, not required if it's a
 Virtual machine
 --managed MANAGED True/False flag whether a host is managed or unmanaged. Note: this value
 Also determines whether several parameters are required or not
 One of true/false, yes/no, 1/0.
 --medium MEDIUM_NAME Medium name
 --medium-id MEDIUM_ID
 --model MODEL_NAME Model name
 --model-id MODEL_ID
 --name NAME Host name
 --new-name NEW_NAME
 --openscap-proxy-id OPENSAP_PROXY_ID ID of OpenSCAP Capsule
 --operatingsystem OPERATINGSYSTEM_TITLE Operating system title
 --operatingsystem-id OPERATINGSYSTEM_ID
 --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION_TITLE Organization title
 --overwrite OVERWRITE One of true/false, yes/no, 1/0.
 --owner OWNER_LOGIN Login of the owner
 --owner-id OWNER_ID ID of the owner
 --owner-type OWNER_TYPE Host's owner type
 Possible value(s): 'User', 'Usergroup'
 --parameters PARAMS Host parameters
 Comma-separated list of key=value
 --partition-table PARTITION_TABLE_NAME Partition table name
 --partition-table-id PARTITION_TABLE_ID
 --product PRODUCT_NAME Name to search by
 --product-id PRODUCT_ID Product numeric identifier
 --progress-report-id PROGRESS_REPORT_ID UUID to track orchestration tasks
 status, GET
 /api/orchestration/:UUID/tasks
 --provision-method PROVISION_METHOD The method used to provision the host.
 Possible value(s): 'build', 'image', 'bootdisk'
 --puppet-ca-proxy PUPPET_CA_PROXY_NAME
 --puppet-ca-proxy-id PUPPET_CA_PROXY_ID Puppet CA Capsule ID
 --puppet-class-ids PUPPET_CLASS_IDS Comma separated list of values. Values

containing comma should be quoted or escaped with backslash

--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values.

Values containing comma should be quoted or escaped with backslash

--puppet-proxy PUPPET_PROXY_NAME

--puppet-proxy-id PUPPET_PROXY_ID Puppet Capsule ID

--purpose-addons PURPOSE_ADDONS Sets the system add-ons

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--purpose-role PURPOSE_ROLE Sets the system purpose usage

--purpose-usage PURPOSE_USAGE Sets the system purpose usage

--pxe-loader PXE_LOADER DHCP filename option (Grub2/PXELinux by default)

Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI', 'Grub UEFI', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded', 'iPXE Chain BIOS', 'iPXE Chain UEFI'

--realm REALM_NAME Name to search by

--realm-id REALM_ID Numerical ID or realm name

--release-version RELEASE_VERSION Release version for this Host to use (7Server, 7.1, etc)

--root-password ROOT_PW Required if host is managed and value is not inherited from host group or default password in settings

--service-level SERVICE_LEVEL Service level to be used for autoheal

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

--volume VOLUME Volume parameters

Comma-separated list of key=value

Can be specified multiple times.

-h, --help Print help

Available keys for --interface:

mac

ip

type Possible values: interface, bmc, bond, bridge

name

subnet_id

domain_id

identifier

managed true/false

primary true/false, each managed hosts needs to have one primary interface.

provision true/false

virtual true/false

For virtual=true:

tag VLAN tag, this attribute has precedence over the subnet VLAN ID. Only for virtual interfaces.

attached_to Identifier of the interface to which this interface belongs, e.g. eth1.

For type=bond:

mode Possible values: balance-rr, active-backup, balance-xor, broadcast, 802.3ad, balance-tlb, balance-alb

attached_devices Identifiers of slave interfaces, e.g. [eth1,eth2]

bond_options

For type=bmc:

provider always IPMI

username

password

Provider specific options:

EC2:

--compute-attributes:
 flavor_id
 image_id
 availability_zone
 security_group_ids
 managed_ip

GCE:

--compute-attributes:
 machine_type
 image_id
 network
 external_ip

Libvirt:

--compute-attributes:
 cpus Number of CPUs
 memory String, amount of memory, value in bytes
 start Boolean (expressed as 0 or 1), whether to start the machine or not

--interface:
 compute_type Possible values: bridge, network
 compute_network / compute_bridge Name of interface according to type
 compute_model Possible values: virtio, rtl8139, ne2k_pci, pcnet, e1000

--volume:
 pool_name One of available storage pools
 capacity String value, eg. 10G
 format_type Possible values: raw, qcow2

OpenStack:

--compute-attributes:
 flavor_ref
 image_ref
 tenant_id
 security_groups
 network

oVirt:

--compute-attributes:
 cluster ID of cluster to use
 template Hardware profile to use
 cores Integer value, number of cores
 memory Amount of memory, integer value in bytes
 start Boolean (expressed as 0 or 1), whether to start the machine or not

--interface:
 compute_name Eg. eth0
 compute_network Select one of available networks for a cluster, must be an ID

--volume:
 size_gb Volume size in GB, integer value

storage_domain ID of storage domain
 bootable Boolean, only one volume can be bootable

Rackspace:

--compute-attributes:

flavor_id
 image_id

VMware:

--compute-attributes:

cpus CPU count
 corespersocket Number of cores per socket (applicable to hardware versions < 10 only)
 memory_mb Integer number, amount of memory in MB
 firmware automatic/bios/efi
 cluster Cluster ID from VMware
 resource_pool Resource Pool ID from VMware
 path Path to folder
 guest_id Guest OS ID form VMware
 scsi_controller_type ID of the controller from VMware
 hardware_version Hardware version ID from VMware
 add_cdrom Must be a 1 or 0, Add a CD-ROM drive to the virtual machine
 cpuHotAddEnabled Must be a 1 or 0, lets you add memory resources while the machine is on
 memoryHotAddEnabled Must be a 1 or 0, lets you add CPU resources while the machine is on
 start Must be a 1 or 0, whether to start the machine or not
 annotation Annotation Notes

--interface:

compute_type Type of the network adapter, for example one of:
 VirtualVmxnet3,
 VirtualE1000
 See documentation center for your version of vSphere to find more details about

available adapter types:

<https://www.vmware.com/support/pubs/>

compute_network Network ID from VMware

--volume:

name
 storage_pod Storage Pod ID from VMware
 datastore Datastore ID from VMware
 size_gb Integer number, volume size in GB
 thin true/false
 eager_zero true/false
 mode persistent/independent_persistent/independent_nonpersistent

10.33. HAMMER HOST-COLLECTION

Manipulate host collections

Usage:

hammer host-collection [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand
 [ARG] ... Subcommand arguments

Subcommands:

<code>add-host</code>	Add host to the host collection
<code>copy</code>	Copy a host collection
<code>create</code>	Create a host collection
<code>delete</code>	Destroy a host collection
<code>erratum</code>	Manipulate errata for a host collection
<code>hosts</code>	List all hosts
<code>info</code>	Show a host collection
<code>list</code>	List host collections
<code>package</code>	Manipulate packages for a host collection
<code>package-group</code>	Manipulate package-groups for a host collection
<code>remove-host</code>	Remove hosts from the host collection
<code>update</code>	Update a host collection

Options:

<code>-h, --help</code>	Print help
-------------------------	------------

10.33.1. hammer host-collection add-host

Add host to the host collection

Usage:

```
hammer host-collection add-host [OPTIONS]
```

Options:

<code>--host-ids HOST_IDS</code>	Array of host ids
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
<code>--hosts HOST_NAMES</code>	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
<code>--id ID</code>	Id of the host collection
<code>--name NAME</code>	Host collection name to search by
<code>--organization ORGANIZATION_NAME</code>	Organization name to search by
<code>--organization-id ORGANIZATION_ID</code>	Organization ID
<code>--organization-label ORGANIZATION_LABEL</code>	Organization label to search by
<code>-h, --help</code>	Print help

10.33.2. hammer host-collection copy

Copy a host collection

Usage:

```
hammer host-collection copy [OPTIONS]
```

Options:

<code>--id ID</code>	ID of the host collection
<code>--name NAME</code>	Host collection name to search by
<code>--new-name NEW_NAME</code>	New host collection name
<code>--organization ORGANIZATION_NAME</code>	Organization name to search by
<code>--organization-id ORGANIZATION_ID</code>	Organization ID
<code>--organization-label ORGANIZATION_LABEL</code>	Organization label to search by
<code>-h, --help</code>	Print help

10.33.3. hammer host-collection create

Create a host collection

Usage:

```
hammer host-collection create [OPTIONS]
```

Options:

```
--description DESCRIPTION      List of host ids to replace the hosts in host collection
--host-ids HOST_IDS              Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash
--hosts HOST_NAMES              Comma separated list of values. Values containing comma
                                should be quoted or escaped with backslash
--max-hosts MAX_HOSTS           Maximum number of hosts in the host collection
--name NAME                     Host Collection name
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--unlimited-hosts UNLIMITED_HOSTS Whether or not the host collection may have unlimited
                                hosts
                                One of true/false, yes/no, 1/0.
-h, --help                      Print help
```

10.33.4. hammer host-collection delete

Destroy a host collection

Usage:

```
hammer host-collection delete [OPTIONS]
```

Options:

```
--id ID                        Id of the host collection
--name NAME                    Host collection name to search by
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                    Print help
```

10.33.5. hammer host-collection erratum

Manipulate errata for a host collection

Usage:

```
hammer host-collection erratum [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND                    Subcommand
[ARG] ...                     Subcommand arguments
```

Subcommands:

```
install                      Install errata on content hosts contained within a host collection
```

Options:

-h, --help Print help

Unfortunately the server does not support such operation.

10.33.5.1. hammer host-collection erratum install

Install errata on content hosts contained within a host collection

Usage:

hammer host-collection erratum install [OPTIONS]

Options:

--errata ERRATA	List of Errata to install
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash

```
--id HOST_COLLECTION_ID          Host Collection ID
--name HOST_COLLECTION_NAME      Host Collection Name
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                      Print help
```

10.33.6. hammer host-collection hosts

List all hosts

Usage:

hammer host-collection hosts [OPTIONS]

Options:

```
--environment ENVIRONMENT_NAME      Environment name
--environment-id ENVIRONMENT_ID
--hostgroup HOSTGROUP_NAME          Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE    Hostgroup title
--id HOST_COLLECTION_ID              Host Collection ID
--include INCLUDE                    Array of extra information types to include
                                     Possible value(s): 'parameters', 'all_parameters'
--location LOCATION_NAME             Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE       Location title
--name HOST_COLLECTION_NAME           Host Collection Name
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID      Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--page PAGE                           Paginate results
--per-page PER_PAGE                   Number of entries per request
--search SEARCH                       Filter results
--thin THIN                           Only list ID and name of hosts
                                     One of true/false, yes/no, 1/0.
-h, --help                            Print help
```

10.33.7. hammer host-collection info

Show a host collection

Usage:

hammer host-collection info [OPTIONS]

Options:

--id ID Id of the host collection
 --name NAME Host collection name to search by
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 -h, --help Print help

10.33.8. hammer host-collection list

List host collections

Usage:

hammer host-collection list [OPTIONS]

Options:

--activation-key ACTIVATION_KEY_NAME Activation key name to search by
 --activation-key-id ACTIVATION_KEY_ID ID of the activation key
 --available-for AVAILABLE_FOR Interpret specified object to return only Host Collections that can be
 Associated with specified object. The value 'host' is supported.
 --full-result FULL_RESULT Whether or not to show all results
 One of true/false, yes/no, 1/0.
 --host HOST_NAME Host name
 --host-id HOST_ID
 --name NAME Host collection name to filter by
 --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --page PAGE Page number, starting at 1
 --per-page PER_PAGE Number of results per page to return
 --search SEARCH Search string
 -h, --help Print help

10.33.9. hammer host-collection package

Manipulate packages for a host collection

Usage:

hammer host-collection package [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand
 [ARG] ... Subcommand arguments

Subcommands:

install	Install packages on content hosts contained within a host collection
remove	Remove packages on content hosts contained within a host collection
update	Update packages on content hosts contained within a host collection

Options:

-h, --help	Print help
------------	------------

Unfortunately the server does not support such operation.

10.33.9.1. hammer host-collection package install

Install packages on content hosts contained within a host collection

Usage:

```
hammer host-collection package install [OPTIONS]
```

Options:

--id HOST_COLLECTION_ID	Host Collection ID
--name HOST_COLLECTION_NAME	Host Collection Name
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--packages PACKAGES	Comma-separated list of packages to install
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
-h, --help	Print help

10.33.9.2. hammer host-collection package remove

Remove packages on content hosts contained within a host collection

Usage:

```
hammer host-collection package remove [OPTIONS]
```

Options:

--id HOST_COLLECTION_ID	Host Collection ID
--name HOST_COLLECTION_NAME	Host Collection Name
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--packages PACKAGES	Comma-separated list of packages to install
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
-h, --help	Print help

10.33.9.3. hammer host-collection package update

Update packages on content hosts contained within a host collection

Usage:

```
hammer host-collection package update [OPTIONS]
```

Options:


```

--id HOST_COLLECTION_ID      Host Collection ID
--name HOST_COLLECTION_NAME   Host Collection Name
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--packages PACKAGES           Comma-separated list of packages to install
                               Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
-h, --help                    Print help

```

10.33.10. hammer host-collection package-group

Manipulate package-groups for a host collection

Usage:

```
hammer host-collection package-group [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```

SUBCOMMAND      Subcommand
[ARG] ...       Subcommand arguments

```

Subcommands:

```

install          Install package-groups on content hosts contained within a host collection
remove           Remove package-groups on content hosts contained within a host collection
update           Update package-groups on content hosts contained within a host collection

```

Options:

```
-h, --help      Print help
```

Unfortunately the server does not support such operation.

10.33.10.1. hammer host-collection package-group install

Install package-groups on content hosts contained within a host collection

Usage:

```
hammer host-collection package-group install [OPTIONS]
```

Options:

```

--id HOST_COLLECTION_ID      Host Collection ID
--name HOST_COLLECTION_NAME   Host Collection Name
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--package-groups PACKAGE-GROUPS Comma-separated list of package-groups to install
                               Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
-h, --help                    Print help

```

10.33.10.2. hammer host-collection package-group remove

Remove package-groups on content hosts contained within a host collection

Usage:

```
hammer host-collection package-group remove [OPTIONS]
```

Options:

```
--id HOST_COLLECTION_ID          Host Collection ID
--name HOST_COLLECTION_NAME       Host Collection Name
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--package-groups PACKAGE-GROUPS   Comma-separated list of package-groups to install
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
-h, --help                        Print help
```

10.33.10.3. hammer host-collection package-group update

Update package-groups on content hosts contained within a host collection

Usage:

```
hammer host-collection package-group update [OPTIONS]
```

Options:

```
--id HOST_COLLECTION_ID          Host Collection ID
--name HOST_COLLECTION_NAME       Host Collection Name
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--package-groups PACKAGE-GROUPS   Comma-separated list of package-groups to install
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
-h, --help                        Print help
```

10.33.11. hammer host-collection remove-host

Remove hosts from the host collection

Usage:

```
hammer host-collection remove-host [OPTIONS]
```

Options:

```
--host-ids HOST_IDS              Array of host ids
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--hosts HOST_NAMES                Comma separated list of values. Values containing comma
                                   should be quoted or escaped with backslash
--id ID                           Id of the host collection
--name NAME                       Host collection name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                        Print help
```

10.33.12. hammer host-collection update

Update a host collection

Usage:

hammer host-collection update [OPTIONS]

Options:

--description DESCRIPTION
 --host-ids HOST_IDS List of host ids to replace the hosts in host collection
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --id ID Id of the host collection
 --max-hosts MAX_HOSTS Maximum number of hosts in the host collection
 --name NAME Host collection name to search by
 --new-name NEW_NAME Host Collection name
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --unlimited-hosts UNLIMITED_HOSTS Whether or not the host collection may have unlimited hosts
 One of true/false, yes/no, 1/0.
 -h, --help Print help

10.34. HAMMER HOSTGROUP

Manipulate hostgroups

Usage:

hammer hostgroup [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand
 [ARG] ... Subcommand arguments

Subcommands:

ansible-roles List all Ansible roles for a hostgroup
 create Create a host group
 delete Delete a host group
 delete-parameter Delete parameter for a hostgroup
 info Show a host group
 list List all host groups
 puppet-classes List all Puppet classes
 sc-params List all smart class parameters
 set-parameter Create or update parameter for a hostgroup
 smart-variables List all smart variables
 update Update a host group

Options:

-h, --help Print help

10.34.1. hammer hostgroup ansible-roles

List all Ansible roles for a hostgroup

Usage:

```
hammer hostgroup ansible-roles [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Hostgroup name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--title TITLE                 Hostgroup title
-h, --help                    Print help
```

10.34.2. hammer hostgroup create

Create a host group

Usage:

```
hammer hostgroup create [OPTIONS]
```

Options:

```
--ansible-role-ids ANSIBLE_ROLE_IDS      IDs of associated ansible roles
                                         Comma separated list of values. Values containing comma
                                         should be quoted or escaped with backslash
--ansible-roles ANSIBLE_ROLE_NAMES        Comma separated list of values. Values
                                         containing comma should be quoted or escaped with backslash
--architecture ARCHITECTURE_NAME          Architecture name
--architecture-id ARCHITECTURE_ID
--ask-root-pass ASK_ROOT_PW               One of true/false, yes/no, 1/0.
--compute-profile COMPUTE_PROFILE_NAME     Name to search by
--compute-profile-id COMPUTE_PROFILE_ID
--compute-resource COMPUTE_RESOURCE_NAME   Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--config-group-ids CONFIG_GROUP_IDS        IDs of associated config groups
                                         Comma separated list of values. Values containing comma
                                         should be quoted or escaped with backslash
--config-groups CONFIG_GROUP_NAMES        Comma separated list of values. Values
                                         containing comma should be quoted or escaped with backslash
--content-source CONTENT_SOURCE_NAME       Content Source name
--content-source-id CONTENT_SOURCE_ID      Content source ID
--content-view CONTENT_VIEW_NAME          Name to search by
--content-view-id CONTENT_VIEW_ID          Content view numeric identifier
--description DESCRIPTION                  Host group description
--domain DOMAIN_NAME                      Domain name
--domain-id DOMAIN_ID                     Numerical ID or domain name
--environment ENVIRONMENT_NAME             Environment name
--environment-id ENVIRONMENT_ID
--group-parameters-attributes GROUP_PARAMETERS_ATTRIBUTES Array of parameters
                                         Comma separated list of values. Values containing comma
                                         should be quoted or escaped with backslash
--kickstart-repository REPOSITORY_NAME     Kickstart repository name
--kickstart-repository-id KICKSTART_REPOSITORY_ID Kickstart repository ID
--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by
```

```

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID    ID of the environment
--location LOCATION_NAME                               Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS                            REPLACE locations with given ids
                                                         Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--location-title LOCATION_TITLE                       Location title
--location-titles LOCATION_TITLES                     Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--locations LOCATION_NAMES                             Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--medium MEDIUM_NAME                                  Medium name
--medium-id MEDIUM_ID
--name NAME                                             Name of the host group
--openscap-proxy-id OPENSAP_PROXY_ID                   ID of OpenSCAP Capsule
--operatingsystem OPERATINGSYSTEM_TITLE               Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--organization ORGANIZATION_NAME                      Organization name
--organization-id ORGANIZATION_ID                     Organization ID
--organization-ids ORGANIZATION_IDS                   REPLACE organizations with given ids.
                                                         Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE                Organization title
--organization-titles ORGANIZATION_TITLES             Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES                   Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--parent PARENT_NAME                                  Name of parent hostgroup
--parent-id PARENT_ID                                 Parent ID of the host group
--partition-table PARTITION_TABLE_NAME                Partition table name
--partition-table-id PARTITION_TABLE_ID
--puppet-ca-proxy PUPPET_CA_PROXY_NAME                Name of puppet CA proxy
--puppet-ca-proxy-id PUPPET_CA_PROXY_ID                Puppet CA Capsule ID
--puppet-class-ids PUPPETCLASS_IDS                    List of puppetclass ids
                                                         Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--puppet-classes PUPPET_CLASS_NAMES                   Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--puppet-proxy PUPPET_PROXY_NAME                      Name of puppet proxy
--puppet-proxy-id PUPPET_PROXY_ID                     Puppet Capsule ID
--pxe-loader PXE_LOADER                               DHCP filename option (Grub2/PXELinux by
default)
                                                         Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI',
'Grub UEFI', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded', 'iPXE Chain BIOS', 'iPXE
Chain UEFI'
--query-organization ORGANIZATION_NAME                Organization name to search by
--query-organization-id ORGANIZATION_ID                Organization ID to search by
--query-organization-label ORGANIZATION_LABEL          Organization label to search by
--realm REALM_NAME                                    Name to search by
--realm-id REALM_ID                                   Numerical ID or realm name
--root-pass ROOT_PASSWORD                             Root password
--subnet SUBNET_NAME                                  Subnet name
--subnet-id SUBNET_ID
-h, --help                                             Print help

```

10.34.3. hammer hostgroup delete

Delete a host group

```
Usage:
  hammer hostgroup delete [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                   Hostgroup name
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --title TITLE                 Hostgroup title
  -h, --help                   Print help
```

10.34.4. hammer hostgroup delete-parameter

Delete parameter for a hostgroup

```
Usage:
  hammer hostgroup delete-parameter [OPTIONS]

Options:
  --hostgroup HOSTGROUP_NAME      Hostgroup name
  --hostgroup-id HOSTGROUP_ID
  --hostgroup-title HOSTGROUP_TITLE Hostgroup title
  --name NAME                     Parameter name
  -h, --help                     Print help
```

10.34.5. hammer hostgroup info

Show a host group

```
Usage:
  hammer hostgroup info [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                   Hostgroup name
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values
                                                    One of true/false, yes/no, 1/0.
  --title TITLE                 Hostgroup title
  -h, --help                   Print help
```

10.34.6. hammer hostgroup list

List all host groups

Usage:

hammer hostgroup list [OPTIONS]

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET_CLASS_ID ID of Puppet class
--search SEARCH                Filter results
-h, --help                     Print help
```

10.34.7. hammer hostgroup puppet-classes

List all Puppet classes

Usage:

hammer hostgroup puppet-classes [OPTIONS]

Options:

```
--hostgroup HOSTGROUP_NAME      Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--location-id LOCATION_ID        Scope by locations
--order ORDER                    Sort field and order, eg. 'id DESC'
--organization-id ORGANIZATION_ID Scope by organizations
--page PAGE                      Paginate results
--per-page PER_PAGE              Number of entries per request
--search SEARCH                  Filter results
-h, --help                      Print help
```

10.34.8. hammer hostgroup sc-params

List all smart class parameters

Usage:

hammer hostgroup sc-params [OPTIONS]

Options:

```
--hostgroup HOSTGROUP_NAME      Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--location LOCATION_NAME        Location name
--location-id LOCATION_ID
```

```
--location-title LOCATION_TITLE      Location title
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                  Number of entries per request
--search SEARCH                      Filter results
--show-hidden SHOW_HIDDEN            Display hidden values
                                     One of true/false, yes/no, 1/0.
-h, --help                          Print help
```

10.34.9. hammer hostgroup set-parameter

Create or update parameter for a hostgroup

```
Usage:
  hammer hostgroup set-parameter [OPTIONS]

Options:
--hidden-value HIDDEN_VALUE      Should the value be hidden
                                  One of true/false, yes/no, 1/0.
--hostgroup HOSTGROUP_NAME      Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--name NAME                      Parameter name
--value VALUE                    Parameter value
-h, --help                      Print help
```

10.34.10. hammer hostgroup smart-variables

List all smart variables

```
Usage:
  hammer hostgroup smart-variables [OPTIONS]

Options:
--hostgroup HOSTGROUP_NAME      Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--location LOCATION_NAME        Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
--show-hidden SHOW_HIDDEN      Display hidden values
                                  One of true/false, yes/no, 1/0.
-h, --help                    Print help
```


10.34.11. hammer hostgroup update

Update a host group

Usage:

```
hammer hostgroup update [OPTIONS]
```

Options:

```
--ansible-role-ids ANSIBLE_ROLE_IDS          IDs of associated ansible roles
                                              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--ansible-roles ANSIBLE_ROLE_NAMES           Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--architecture ARCHITECTURE_NAME             Architecture name
--architecture-id ARCHITECTURE_ID
--ask-root-pass ASK_ROOT_PW                  One of true/false, yes/no, 1/0.
--compute-profile COMPUTE_PROFILE_NAME       Name to search by
--compute-profile-id COMPUTE_PROFILE_ID
--compute-resource COMPUTE_RESOURCE_NAME     Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--config-group-ids CONFIG_GROUP_IDS          IDs of associated config groups
                                              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--config-groups CONFIG_GROUP_NAMES           Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--content-source CONTENT_SOURCE_NAME        Content Source name
--content-source-id CONTENT_SOURCE_ID        Content source ID
--content-view CONTENT_VIEW_NAME            Name to search by
--content-view-id CONTENT_VIEW_ID           Content view numeric identifier
--description DESCRIPTION                   Host group description
--domain DOMAIN_NAME                        Domain name
--domain-id DOMAIN_ID                       Numerical ID or domain name
--environment ENVIRONMENT_NAME              Environment name
--environment-id ENVIRONMENT_ID
--group-parameters-attributes GROUP_PARAMETERS_ATTRIBUTES Array of parameters
                                              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--id ID
--kickstart-repository REPOSITORY_NAME       Kickstart repository name
--kickstart-repository-id KICKSTART_REPOSITORY_ID Kickstart repository ID
--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by
--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID ID of the environment
--location LOCATION_NAME                     Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS                  REPLACE locations with given ids
                                              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--location-title LOCATION_TITLE              Location title
--location-titles LOCATION_TITLES           Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--locations LOCATION_NAMES                  Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--medium MEDIUM_NAME                        Medium name
--medium-id MEDIUM_ID
--name NAME                                  Hostgroup name
--new-name NEW_NAME                          Name of the host group
```

```

--openscap-proxy-id OPENSAP_PROXY_ID          ID of OpenSCAP Capsule
--operatingsystem OPERATINGSYSTEM_TITLE       Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--organization ORGANIZATION_NAME              Organization name
--organization-id ORGANIZATION_ID              Organization ID
--organization-ids ORGANIZATION_IDS            REPLACE organizations with given ids.
                                              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE        Organization title
--organization-titles ORGANIZATION_TITLES      Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES            Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--parent PARENT_NAME                          Name of parent hostgroup
--parent-id PARENT_ID                         Parent ID of the host group
--partition-table PARTITION_TABLE_NAME        Partition table name
--partition-table-id PARTITION_TABLE_ID
--puppet-ca-proxy PUPPET_CA_PROXY_NAME         Name of puppet CA proxy
--puppet-ca-proxy-id PUPPET_CA_PROXY_ID        Puppet CA Capsule ID
--puppet-class-ids PUPPETCLASS_IDS             List of puppetclass ids
                                              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--puppet-classes PUPPET_CLASS_NAMES            Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--puppet-proxy PUPPET_PROXY_NAME              Name of puppet proxy
--puppet-proxy-id PUPPET_PROXY_ID              Puppet Capsule ID
--pxe-loader PXE_LOADER                       DHCP filename option (Grub2/PXELinux by
default)
                                              Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI',
'Grub UEFI', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded', 'iPXE Chain BIOS', 'iPXE
Chain UEFI'
--query-organization ORGANIZATION_NAME         Organization name to search by
--query-organization-id ORGANIZATION_ID         Organization ID to search by
--query-organization-label ORGANIZATION_LABEL   Organization label to search by
--realm REALM_NAME                             Name to search by
--realm-id REALM_ID                             Numerical ID or realm name
--root-pass ROOT_PASSWORD                       Root password
--subnet SUBNET_NAME                           Subnet name
--subnet-id SUBNET_ID
--title TITLE                                  Hostgroup title
-h, --help                                     Print help

```

10.35. HAMMER IMPORT-TEMPLATES

Import templates from a git repo or a directory on the server

Usage:

```
hammer import-templates [OPTIONS]
```

Options:

```

--associate ASSOCIATE          Associate to OS's, Locations & Organizations. Options are:
always,
                                New or never.
                                Possible value(s): 'always', 'new', 'never'
--branch BRANCH                Branch in Git repo.

```

<code>--dirname DIRNAME</code>	The directory within Git repo containing the templates
<code>--filter FILTER</code>	Export templates with names matching this regex (case-insensitive; snippets
	Are not filtered).
<code>--force FORCE</code>	Update templates that are locked
	One of true/false, yes/no, 1/0.
<code>--location LOCATION_NAME</code>	Location name
<code>--location-id LOCATION_ID</code>	
<code>--location-ids LOCATION_IDS</code>	REPLACE locations with given ids
	Comma separated list of values. Values containing comma should be
	quoted or escaped with backslash
<code>--location-title LOCATION_TITLE</code>	Location title
<code>--location-titles LOCATION_TITLES</code>	Comma separated list of values. Values containing comma
	should be quoted or escaped with backslash
<code>--locations LOCATION_NAMES</code>	Comma separated list of values. Values containing comma
	should be quoted or escaped with backslash
<code>--lock LOCK</code>	Lock imported templates
	One of true/false, yes/no, 1/0.
<code>--negate NEGATE</code>	Negate the prefix (for purging).
	One of true/false, yes/no, 1/0.
<code>--organization ORGANIZATION_NAME</code>	Organization name
<code>--organization-id ORGANIZATION_ID</code>	Organization ID
<code>--organization-ids ORGANIZATION_IDS</code>	REPLACE organizations with given ids.
	Comma separated list of values. Values containing comma should be
	quoted or escaped with backslash
<code>--organization-title ORGANIZATION_TITLE</code>	Organization title
<code>--organization-titles ORGANIZATION_TITLES</code>	Comma separated list of values. Values containing
	comma should be quoted or escaped with backslash
<code>--organizations ORGANIZATION_NAMES</code>	Comma separated list of values. Values containing
	comma should be quoted or escaped with backslash
<code>--prefix PREFIX</code>	The string all imported templates should begin with.
<code>--repo REPO</code>	Override the default repo from settings.
<code>--verbose VERBOSE</code>	Show template diff in response
	One of true/false, yes/no, 1/0.
<code>-h, --help</code>	Print help

10.36. HAMMER JOB-INVOCATION

Manage job invocations

Usage:

hammer job-invocation [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

cancel	Cancel the job
create	Create a job invocation
info	Show job invocation
list	List job invocations
output	View the output for a host
rerun	Rerun the job

Options:

-h, --help Print help

10.36.1. hammer job-invocation cancel

Cancel the job

Usage:

hammer job-invocation cancel [OPTIONS]

Options:

--force FORCE One of true/false, yes/no, 1/0.
 --id ID
 --location-id LOCATION_ID Scope by locations
 --organization-id ORGANIZATION_ID Scope by organizations
 -h, --help Print help

10.36.2. hammer job-invocation create

Create a job invocation

Usage:

hammer job-invocation create [OPTIONS]

Options:

--async Do not wait for the task
 --bookmark BOOKMARK_NAME Name to search by
 --bookmark-id BOOKMARK_ID
 --concurrency-level CONCURRENCY_LEVEL Run at most N tasks at a time
 --cron-line CRONLINE Create a recurring execution
 Cron line format 'a b c d e', where:
 a. is minute (range: 0-59)
 b. is hour (range: 0-23)
 c. is day of month (range: 1-31)
 d. is month (range: 1-12)
 e. is day of week (range: 0-6)
 --description-format DESCRIPTION_FORMAT Override the description format from the
 template for this invocation only
 --dynamic Dynamic search queries are evaluated at run time
 --effective-user EFFECTIVE_USER What user should be used to run the script (using
 sudo-like mechanisms).
 Defaults to a template parameter or global setting.
 --end-time DATETIME Perform no more executions after this time, used with -
 --cron-line
 Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format
 --execution-timeout-interval EXECUTION_TIMEOUT_INTERVAL Override the timeout interval from
 the template for this invocation only
 --feature FEATURE Remote execution feature label that should be triggered,
 job template
 Assigned to this feature will be used
 --input-files INPUT_FILES Read input values from files
 Comma-separated list of key=file, where file is a path to a text file
 to be read

```

--inputs INPUTS                Specify inputs from command line
                                Comma-separated list of key=value
--job-template JOB_TEMPLATE_NAME  Name to search by
--job-template-id JOB_TEMPLATE_ID
--location LOCATION_NAME        Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--max-iteration MAX_ITERATION     Repeat a maximum of N times
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--search-query SEARCH_QUERY
--start-at DATETIME              Schedule the execution for a later time
                                Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format
--start-before DATETIME          Execution should be cancelled if it cannot be started
before --start-at
                                Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format
--time-span TIME_SPAN            Distribute tasks over N seconds
-h, --help                      Print help

```

10.36.3. hammer job-invocation info

Show job invocation

```

Usage:
  hammer job-invocation info [OPTIONS]

Options:
  --id ID
  --location-id LOCATION_ID  Scope by locations
  --organization-id ORGANIZATION_ID Scope by organizations
  -h, --help                Print help

```

10.36.4. hammer job-invocation list

List job invocations

```

Usage:
  hammer job-invocation list [OPTIONS]

Options:
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --order ORDER                 Sort field and order, eg. 'id DESC'
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --page PAGE                   Paginate results
  --per-page PER_PAGE           Number of entries per request
  --search SEARCH               Filter results
  -h, --help                   Print help

```

10.36.5. hammer job-invocation output

View the output for a host

```
Usage:
  hammer job-invocation output [OPTIONS]

Options:
  --async                Do not wait for job to complete, shows current output only
  --host HOST_NAME       Host name
  --host-id HOST_ID
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE    Location title
  --name NAME                Name to search by
  --organization ORGANIZATION_NAME    Organization name
  --organization-id ORGANIZATION_ID    Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                Print help
```

10.36.6. hammer job-invocation rerun

Rerun the job

```
Usage:
  hammer job-invocation rerun [OPTIONS]

Options:
  --failed-only FAILED_ONLY    One of true/false, yes/no, 1/0.
  --id ID
  --location-id LOCATION_ID    Scope by locations
  --organization-id ORGANIZATION_ID Scope by organizations
  -h, --help                Print help
```

10.37. HAMMER JOB-TEMPLATE

Manage job templates

```
Usage:
  hammer job-template [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  create              Create a job template
  delete              Delete a job template
  dump                View job template content
  export              Export a template including all metadata
  import              Import a job template from ERB
  info                Show job template details
  list                List job templates
```

update Update a job template

Options:

-h, --help Print help

10.37.1. hammer job-template create

Create a job template

Usage:

hammer job-template create [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--current-user CURRENT_USER Whether the current user login should be used as the effective user

One of true/false, yes/no, 1/0.

--description-format DESCRIPTION_FORMAT This template is used to generate the description. Input values can be used

Using the syntax %{package}. You may also include the job category and Template name using %{job_category} and %{template_name}.

--file TEMPLATE Path to a file that contains the template

--job-category JOB_CATEGORY Job category

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Template name

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--overridable OVERRIDABLE Whether it should be allowed to override the effective user from the

Invocation form.

One of true/false, yes/no, 1/0.

--provider-type PROVIDER_TYPE Provider type

Possible value(s): 'SSH', 'Ansible'

--snippet SNIPPET One of true/false, yes/no, 1/0.

```
--value VALUE          What user should be used to run the script (using sudo-like
mechanisms)
-h, --help              Print help
```

10.37.2. hammer job-template delete

Delete a job template

```
Usage:
  hammer job-template delete [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
-h, --help                    Print help
```

10.37.3. hammer job-template dump

View job template content

```
Usage:
  hammer job-template dump [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
-h, --help                    Print help
```

10.37.4. hammer job-template export

Export a template including all metadata

```
Usage:
  hammer job-template export [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--name NAME                   Name to search by
```



```
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                          Print help
```

10.37.5. hammer job-template import

Import a job template from ERB

```
Usage:
  hammer job-template import [OPTIONS]

Options:
  --file TEMPLATE          Path to a file that contains the template - must include ERB
  metadata
  --location LOCATION_NAME    Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --organization ORGANIZATION_NAME    Organization name
  --organization-id ORGANIZATION_ID    Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --overwrite OVERWRITE          Overwrite template if it already exists
                                  One of true/false, yes/no, 1/0.
  -h, --help                    Print help
```

10.37.6. hammer job-template info

Show job template details

```
Usage:
  hammer job-template info [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME    Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                 Name to search by
  --organization ORGANIZATION_NAME    Organization name
  --organization-id ORGANIZATION_ID    Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                  Print help
```

10.37.7. hammer job-template list

List job templates

```
Usage:
  hammer job-template list [OPTIONS]

Options:
  --location LOCATION_NAME    Location name
  --location-id LOCATION_ID
```

```

--location-title LOCATION_TITLE    Location title
--order ORDER                      Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                        Paginate results
--per-page PER_PAGE                Number of entries per request
--search SEARCH                    Filter results
-h, --help                        Print help

```

10.37.8. hammer job-template update

Update a job template

Usage:

```
hammer job-template update [OPTIONS]
```

Options:

```

--audit-comment AUDIT_COMMENT
--current-user CURRENT_USER    Whether the current user login should be used as the
effective user
                                One of true/false, yes/no, 1/0.
--description-format DESCRIPTION_FORMAT This template is used to generate the description.
Input values can be used
                                Using the syntax %{package}. You may also include the job category and
                                Template name using %{job_category} and %{template_name}.
--file TEMPLATE                Path to a file that contains the template
--id ID
--job-category JOB_CATEGORY    Job category
--location LOCATION_NAME       Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS    REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES     Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locked LOCKED                Whether or not the template is locked for editing
                                One of true/false, yes/no, 1/0.
--name NAME                    Name to search by
--new-name NEW_NAME            Template name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--overridable OVERRIDABLE     Whether it should be allowed to override the effective user
from the

```

	Invocation form.
	One of true/false, yes/no, 1/0.
--provider-type PROVIDER_TYPE	Provider type
	Possible value(s): 'SSH', 'Ansible'
--snippet SNIPPET	One of true/false, yes/no, 1/0.
--value VALUE	What user should be used to run the script (using sudo-like mechanisms)
-h, --help	Print help

10.38. HAMMER LIFECYCLE-ENVIRONMENT

Manipulate lifecycle_environments on the server

Usage:
hammer lifecycle-environment [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

create	Create an environment
delete	Destroy an environment
info	Show an environment
list	List environments in an organization
paths	List environment paths
update	Update an environment

Options:

-h, --help	Print help
------------	------------

10.38.1. hammer lifecycle-environment create

Create an environment

Usage:
hammer lifecycle-environment create [OPTIONS]

Options:

--description DESCRIPTION	Description of the environment
--label LABEL	Label of the environment
--name NAME	Name of the environment
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--prior PRIOR	Name of the prior environment
--prior-id PRIOR_ID	ID of an environment that is prior to the new environment in the chain. It
	Has to be either the ID of Library or the ID of an environment at the end
	Of a chain.
--registry-name-pattern REGISTRY_NAME_PATTERN	Pattern for container image names
--registry-unauthenticated-pull REGISTRY_UNAUTHENTICATED_PULL	Allow unauthenticated pull of

container images

One of true/false, yes/no, 1/0.

-h, --help

Print help

10.38.2. hammer lifecycle-environment delete

Destroy an environment

Usage:

hammer lifecycle-environment delete [OPTIONS]

Options:

--id ID ID of the environment
 --name NAME Lifecycle environment name to search by
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 -h, --help Print help

10.38.3. hammer lifecycle-environment info

Show an environment

Usage:

hammer lifecycle-environment info [OPTIONS]

Options:

--id ID ID of the environment
 --name NAME Lifecycle environment name to search by
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 -h, --help Print help

10.38.4. hammer lifecycle-environment list

List environments in an organization

Usage:

hammer lifecycle-environment list [OPTIONS]

Options:

--full-result FULL_RESULT Whether or not to show all results
 One of true/false, yes/no, 1/0.
 --library LIBRARY Set true if you want to see only library environments
 Possible value(s): 'true', 'false'
 --name NAME Filter only environments containing this name
 --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --page PAGE Page number, starting at 1

```
--per-page PER_PAGE      Number of results per page to return
--search SEARCH          Search string
-h, --help               Print help
```

10.38.5. hammer lifecycle-environment paths

List environment paths

```
Usage:
  hammer lifecycle-environment paths [OPTIONS]

Options:
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
--permission-type PERMISSION_TYPE  The associated permission type. One of (readable |
promotable) Default:
                                     Readable
-h, --help                        Print help
```

10.38.6. hammer lifecycle-environment update

Update an environment

```
Usage:
  hammer lifecycle-environment update [OPTIONS]

Options:
--async ASYNC              Do not wait for the update action to finish. Default: true
                           One of true/false, yes/no, 1/0.
--description DESCRIPTION  Description of the environment
--id ID                    ID of the environment
--name NAME                Lifecycle environment name to search by
--new-name NEW_NAME        New name to be given to the environment
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
--registry-name-pattern REGISTRY_NAME_PATTERN  Pattern for container image names
--registry-unauthenticated-pull REGISTRY_UNAUTHENTICATED_PULL Allow unauthenticated pull of
container images
                           One of true/false, yes/no, 1/0.
-h, --help                Print help
```

10.39. HAMMER LOCATION

Manipulate locations

```
Usage:
  hammer location [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
SUBCOMMAND      Subcommand
[ARG] ...       Subcommand arguments
```

Subcommands:

add-compute-resource	Associate a compute resource
add-config-template	Associate a configuration template
add-domain	Associate a domain
add-environment	Associate an environment
add-hostgroup	Associate a hostgroup
add-medium	Associate a medium
add-organization	Associate an organization
add-smart-proxy	Associate a smart proxy
add-subnet	Associate a subnet
add-user	Associate an user
create	Create a location
delete	Delete a location
delete-parameter	Delete parameter for a location
info	Show a location
list	List all locations
remove-compute-resource	Disassociate a compute resource
remove-config-template	Disassociate a configuration template
remove-domain	Disassociate a domain
remove-environment	Disassociate an environment
remove-hostgroup	Disassociate a hostgroup
remove-medium	Disassociate a medium
remove-organization	Disassociate an organization
remove-smart-proxy	Disassociate a smart proxy
remove-subnet	Disassociate a subnet
remove-user	Disassociate an user
set-parameter	Create or update parameter for a location
update	Update a location

Options:

-h, --help	Print help
------------	------------

10.39.1. hammer location add-compute-resource

Associate a compute resource

Usage:

hammer location add-compute-resource [OPTIONS]

Options:

--compute-resource COMPUTE_RESOURCE_NAME	Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID	
--id ID	
--name NAME	Location name
--title TITLE	Location title
-h, --help	Print help

10.39.2. hammer location add-config-template

Associate a configuration template

Usage:

hammer location add-config-template [OPTIONS]

Options:

```
--config-template CONFIG_TEMPLATE_NAME Name to search by
--config-template-id CONFIG_TEMPLATE_ID
--id ID
--name NAME                Location name
--title TITLE              Location title
-h, --help                Print help
```

10.39.3. hammer location add-domain

Associate a domain

Usage:

```
hammer location add-domain [OPTIONS]
```

Options:

```
--domain DOMAIN_NAME      Domain name
--domain-id DOMAIN_ID     Numerical ID or domain name
--id ID
--name NAME                Location name
--title TITLE              Location title
-h, --help                Print help
```

10.39.4. hammer location add-environment

Associate an environment

Usage:

```
hammer location add-environment [OPTIONS]
```

Options:

```
--environment ENVIRONMENT_NAME Environment name
--environment-id ENVIRONMENT_ID
--id ID
--name NAME                Location name
--title TITLE              Location title
-h, --help                Print help
```

10.39.5. hammer location add-hostgroup

Associate a hostgroup

Usage:

```
hammer location add-hostgroup [OPTIONS]
```

Options:

```
--hostgroup HOSTGROUP_NAME Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--id ID
```

```
--name NAME           Location name
--title TITLE         Location title
-h, --help            Print help
```

10.39.6. hammer location add-medium

Associate a medium

```
Usage:
  hammer location add-medium [OPTIONS]
```

```
Options:
--id ID
--medium MEDIUM_NAME      Medium name
--medium-id MEDIUM_ID
--name NAME                Location name
--title TITLE              Location title
-h, --help                 Print help
```

10.39.7. hammer location add-organization

Associate an organization

```
Usage:
  hammer location add-organization [OPTIONS]
```

```
Options:
--id ID
--name NAME                Location name
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
--title TITLE              Location title
-h, --help                 Print help
```

10.39.8. hammer location add-smart-proxy

Associate a smart proxy

```
Usage:
  hammer location add-smart-proxy [OPTIONS]
```

```
Options:
--id ID
--name NAME                Location name
--smart-proxy SMART_PROXY_NAME  Name to search by
--smart-proxy-id SMART_PROXY_ID
--title TITLE              Location title
-h, --help                 Print help
```

10.39.9. hammer location add-subnet

Associate a subnet

```
Usage:
  hammer location add-subnet [OPTIONS]

Options:
  --id ID
  --name NAME           Location name
  --subnet SUBNET_NAME  Subnet name
  --subnet-id SUBNET_ID
  --title TITLE         Location title
  -h, --help           Print help
```

10.39.10. hammer location add-user

Associate an user

```
Usage:
  hammer location add-user [OPTIONS]

Options:
  --id ID
  --name NAME           Location name
  --title TITLE         Location title
  --user USER_LOGIN     User's login to search by
  --user-id USER_ID
  -h, --help           Print help
```

10.39.11. hammer location create

Create a location

```
Usage:
  hammer location create [OPTIONS]

Options:
  --compute-resource-ids COMPUTE_RESOURCE_IDS  Compute resource IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
  --compute-resources COMPUTE_RESOURCE_NAMES    Comma separated list of values.
Values containing comma should be quoted or escaped with backslash
  --config-template-ids CONFIG_TEMPLATE_IDS     Provisioning template IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
  --config-templates CONFIG_TEMPLATE_NAMES      Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
  --description DESCRIPTION
  --domain-ids DOMAIN_IDS                      Domain IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
  --domains DOMAIN_NAMES                      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
  --environment-ids ENVIRONMENT_IDS            Environment IDs
                                                Comma separated list of values. Values containing comma should
```

be quoted or escaped with backslash
 --environments ENVIRONMENT_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroup-ids HOSTGROUP_IDS Host group IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --ignore-types IGNORE_TYPES List of resources types that will be automatically associated
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-title LOCATION_TITLE Location title
 --media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --medium-ids MEDIUM_IDS Medium IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --name NAME
 --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION_TITLE Organization title
 --parent-id PARENT_ID Parent ID
 --partition-table-ids PARTITION_TABLE_IDS Partition template IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --provisioning-template-ids PROVISIONING_TEMPLATE_IDS Provisioning template IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --realm-ids REALM_IDS Realm IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --realms REALM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --smart-proxies SMART_PROXY_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --smart-proxy-ids SMART_PROXY_IDS Capsule IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --subnet-ids SUBNET_IDS Subnet IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --subnets SUBNET_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --user-ids USER_IDS User IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash

```
--users USER_LOGINS          Comma separated list of values. Values containing
                              comma should be quoted or escaped with backslash
-h, --help                    Print help
```

10.39.12. hammer location delete

Delete a location

```
Usage:
  hammer location delete [OPTIONS]

Options:
  --id ID                      Location numeric id to search by
  --location LOCATION_NAME     Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                  Organization name
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --title TITLE                Organization title
  -h, --help                  Print help
```

10.39.13. hammer location delete-parameter

Delete parameter for a location

```
Usage:
  hammer location delete-parameter [OPTIONS]

Options:
  --location LOCATION_NAME     Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                  Parameter name
  -h, --help                  Print help
```

10.39.14. hammer location info

Show a location

```
Usage:
  hammer location info [OPTIONS]

Options:
  --id ID                      Location numeric id to search by
  --location LOCATION_NAME     Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                  Organization name
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
```

```
--show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values
                                     One of true/false, yes/no, 1/0.
--title TITLE                        Organization title
-h, --help                          Print help
```

10.39.15. hammer location list

List all locations

```
Usage:
  hammer location list [OPTIONS]

Options:
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                   Paginate results
--per-page PER_PAGE           Number of entries per request
--search SEARCH               Filter results
-h, --help                    Print help
```

10.39.16. hammer location remove-compute-resource

Disassociate a compute resource

```
Usage:
  hammer location remove-compute-resource [OPTIONS]

Options:
--compute-resource COMPUTE_RESOURCE_NAME Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID
--name NAME                    Location name
--title TITLE                  Location title
-h, --help                    Print help
```

10.39.17. hammer location remove-config-template

Disassociate a configuration template

```
Usage:
  hammer location remove-config-template [OPTIONS]

Options:
--config-template CONFIG_TEMPLATE_NAME Name to search by
--config-template-id CONFIG_TEMPLATE_ID
--id ID
```

```
--name NAME           Location name
--title TITLE         Location title
-h, --help           Print help
```

10.39.18. hammer location remove-domain

Disassociate a domain

```
Usage:
  hammer location remove-domain [OPTIONS]

Options:
--domain DOMAIN_NAME      Domain name
--domain-id DOMAIN_ID     Numerical ID or domain name
--id ID
--name NAME               Location name
--title TITLE             Location title
-h, --help               Print help
```

10.39.19. hammer location remove-environment

Disassociate an environment

```
Usage:
  hammer location remove-environment [OPTIONS]

Options:
--environment ENVIRONMENT_NAME Environment name
--environment-id ENVIRONMENT_ID
--id ID
--name NAME               Location name
--title TITLE             Location title
-h, --help               Print help
```

10.39.20. hammer location remove-hostgroup

Disassociate a hostgroup

```
Usage:
  hammer location remove-hostgroup [OPTIONS]

Options:
--hostgroup HOSTGROUP_NAME      Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--id ID
--name NAME                     Location name
--title TITLE                   Location title
-h, --help                     Print help
```

10.39.21. hammer location remove-medium

Disassociate a medium

```
Usage:
  hammer location remove-medium [OPTIONS]
```

```
Options:
  --id ID
  --medium MEDIUM_NAME      Medium name
  --medium-id MEDIUM_ID
  --name NAME                Location name
  --title TITLE              Location title
  -h, --help                 Print help
```

10.39.22. hammer location remove-organization

Disassociate an organization

```
Usage:
  hammer location remove-organization [OPTIONS]
```

```
Options:
  --id ID
  --name NAME                Location name
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --title TITLE              Location title
  -h, --help                 Print help
```

10.39.23. hammer location remove-smart-proxy

Disassociate a smart proxy

```
Usage:
  hammer location remove-smart-proxy [OPTIONS]
```

```
Options:
  --id ID
  --name NAME                Location name
  --smart-proxy SMART_PROXY_NAME Name to search by
  --smart-proxy-id SMART_PROXY_ID
  --title TITLE              Location title
  -h, --help                 Print help
```

10.39.24. hammer location remove-subnet

Disassociate a subnet

```
Usage:
  hammer location remove-subnet [OPTIONS]
```

```
Options:
  --id ID
```

```
--name NAME           Location name
--subnet SUBNET_NAME  Subnet name
--subnet-id SUBNET_ID
--title TITLE         Location title
-h, --help            Print help
```

10.39.25. hammer location remove-user

Disassociate an user

```
Usage:
  hammer location remove-user [OPTIONS]

Options:
  --id ID
  --name NAME           Location name
  --title TITLE         Location title
  --user USER_LOGIN     User's login to search by
  --user-id USER_ID
  -h, --help            Print help
```

10.39.26. hammer location set-parameter

Create or update parameter for a location

```
Usage:
  hammer location set-parameter [OPTIONS]

Options:
  --hidden-value HIDDEN_VALUE  Should the value be hidden
                                One of true/false, yes/no, 1/0.
  --location LOCATION_NAME     Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                  Parameter name
  --value VALUE                Parameter value
  -h, --help                    Print help
```

10.39.27. hammer location update

Update a location

```
Usage:
  hammer location update [OPTIONS]

Options:
  --compute-resource-ids COMPUTE_RESOURCE_IDS      Compute resource IDs
                                                    Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
  --compute-resources COMPUTE_RESOURCE_NAMES      Comma separated list of values.
Values containing comma should be quoted or escaped with backslash
  --config-template-ids CONFIG_TEMPLATE_IDS        Provisioning template IDs
                                                    Comma separated list of values. Values containing comma should
```

be quoted or escaped with backslash
 --config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --description DESCRIPTION
 --domain-ids DOMAIN_IDS Domain IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --domains DOMAIN_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --environment-ids ENVIRONMENT_IDS Environment IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --environments ENVIRONMENT_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroup-ids HOSTGROUP_IDS Host group IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --id ID Location numeric id to search by
 --ignore-types IGNORE_TYPES List of resources types that will be automatically associated
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-title LOCATION_TITLE Location title
 --media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --medium-ids MEDIUM_IDS Medium IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --name NAME Location name
 --new-name NEW_NAME
 --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION_TITLE Organization title
 --parent-id PARENT_ID Parent ID
 --partition-table-ids PARTITION_TABLE_IDS Partition template IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --provisioning-template-ids PROVISIONING_TEMPLATE_IDS Provisioning template IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --realm-ids REALM_IDS Realm IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --realms REALM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --smart-proxies SMART_PROXY_NAMES Comma separated list of values. Values


```

containing comma should be quoted or escaped with backslash
--smart-proxy-ids SMART_PROXY_IDS          Capsule IDs
                                         Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--subnet-ids SUBNET_IDS                    Subnet IDs
                                         Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--subnets SUBNET_NAMES                    Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--title TITLE                             Location title
--user-ids USER_IDS                       User IDs
                                         Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--users USER_LOGINS                       Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
-h, --help                                Print help

```

10.40. HAMMER MEDIUM

Manipulate installation media

```

Usage:
  hammer medium [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  add-operatingsystem  Associate an operating system
  create              Create a medium
  delete              Delete a medium
  info                Show a medium
  list                List all installation media
  remove-operatingsystem  Disassociate an operating system
  update              Update a medium

Options:
  -h, --help          Print help

```

10.40.1. hammer medium add-operatingsystem

Associate an operating system

```

Usage:
  hammer medium add-operatingsystem [OPTIONS]

Options:
  --id ID                ID
  --name NAME            Medium name
  --operatingsystem OPERATINGSYSTEM_TITLE Operating system title
  --operatingsystem-id OPERATINGSYSTEM_ID
  -h, --help            Print help

```

10.40.2. hammer medium create

Create a medium

Usage:

hammer medium create [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--name NAME Name of media

--operatingsystem-ids OPERATINGSYSTEM_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--os-family OS_FAMILY Operating system family, available values: AIX, Altlinux, Archlinux, Coreos, Debian, Freebsd, Gentoo, Junos, NXOS, Rancheros, Redhat, Solaris, Suse, Windows, Xenserver

--path PATH The path to the medium, can be a URL or a valid NFS server (exclusive of The architecture).

For example mirror.centos.org/centos/\$version/os/\$arch
Where \$arch will be substituted for the host's actual OS architecture
And \$version, \$major and \$minor will be substituted for the version of the Operating system.

Solaris and Debian media may also use \$release.

-h, --help Print help

10.40.3. hammer medium delete

Delete a medium

Usage:

```
hammer medium delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Medium name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help
```

10.40.4. hammer medium info

Show a medium

Usage:

```
hammer medium info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Medium name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help
```

10.40.5. hammer medium list

List all installation media

Usage:

```
hammer medium list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                     Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                 Filter results
-h, --help                     Print help
```

10.40.6. hammer medium remove-operatingsystem

Disassociate an operating system

Usage:

```
hammer medium remove-operatingsystem [OPTIONS]
```

Options:

```
--id ID
--name NAME                Medium name
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
-h, --help                Print help
```

10.40.7. hammer medium update

Update a medium

Usage:

```
hammer medium update [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS   REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
                                should be quoted or escaped with backslash
--locations LOCATION_NAMES    Comma separated list of values. Values containing comma
                                should be quoted or escaped with backslash
--name NAME                    Medium name
--new-name NEW_NAME            Name of media
--operatingsystem-ids OPERATINGSYSTEM_IDS Comma separated list of values. Values
                                containing comma should be quoted or escaped with backslash
--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values
                                containing comma should be quoted or escaped with backslash
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
                                comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
                                comma should be quoted or escaped with backslash
--os-family OS_FAMILY          Operating system family, available values: AIX, Altlinux,
                                Archlinux,
                                Coreos, Debian, Freebsd, Gentoo, Junos, NXOS, Rancheros, Redhat,
                                Solaris,
                                Suse, Windows, Xenserver
--path PATH                    The path to the medium, can be a URL or a valid NFS server
```

(exclusive of

The architecture).

For example `mirror.centos.org/centos/$version/os/$arch`

Where `$arch` will be substituted for the host's actual OS architecture

And `$version`, `$major` and `$minor` will be substituted for the version of the Operating system.

Solaris and Debian media may also use `$release`.

`-h, --help`

Print help

10.41. HAMMER MODEL

Manipulate hardware models

Usage:

`hammer model [OPTIONS] SUBCOMMAND [ARG] ...`

Parameters:

<code>SUBCOMMAND</code>	Subcommand
<code>[ARG] ...</code>	Subcommand arguments

Subcommands:

<code>create</code>	Create a hardware model
<code>delete</code>	Delete a hardware model
<code>info</code>	Show a hardware model
<code>list</code>	List all hardware models
<code>update</code>	Update a hardware model

Options:

<code>-h, --help</code>	Print help
-------------------------	------------

10.41.1. hammer model create

Create a hardware model

Usage:

`hammer model create [OPTIONS]`

Options:

<code>--hardware-model</code>	<code>HARDWARE_MODEL</code>	
<code>--info</code>	<code>INFO</code>	
<code>--location</code>	<code>LOCATION_NAME</code>	Location name
<code>--location-id</code>	<code>LOCATION_ID</code>	
<code>--location-title</code>	<code>LOCATION_TITLE</code>	Location title
<code>--name</code>	<code>NAME</code>	
<code>--organization</code>	<code>ORGANIZATION_NAME</code>	Organization name
<code>--organization-id</code>	<code>ORGANIZATION_ID</code>	Organization ID
<code>--organization-title</code>	<code>ORGANIZATION_TITLE</code>	Organization title
<code>--vendor-class</code>	<code>VENDOR_CLASS</code>	
<code>-h, --help</code>		Print help

10.41.2. hammer model delete

Delete a hardware model

Usage:

hammer model delete [OPTIONS]

Options:

--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Model name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.41.3. hammer model info

Show a hardware model

Usage:

hammer model info [OPTIONS]

Options:

--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Model name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.41.4. hammer model list

List all hardware models

Usage:

hammer model list [OPTIONS]

Options:

--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE Paginate results
--per-page PER_PAGE Number of entries per request
--search SEARCH Filter results
-h, --help Print help

10.41.5. hammer model update

Update a hardware model

Usage:

```
hammer model update [OPTIONS]
```

Options:

```
--hardware-model HARDWARE_MODEL
--id ID
--info INFO
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Model name
--new-name NEW_NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--vendor-class VENDOR_CLASS
-h, --help                    Print help
```

10.42. HAMMER MODULE-STREAM

View Module Streams

Usage:

```
hammer module-stream [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND                Subcommand
[ARG] ...                  Subcommand arguments
```

Subcommands:

```
info                      Show a module stream
list                      List module streams
```

Options:

```
-h, --help                Print help
```

10.42.1. hammer module-stream info

Show a module stream

Usage:

```
hammer module-stream info [OPTIONS]
```

Options:

```
--id ID                    A module stream identifier
--name NAME                Module stream name to search by
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--product PRODUCT_NAME     Product name to search by
```

```
--product-id PRODUCT_ID      Product numeric identifier
--repository REPOSITORY_NAME  Repository name to search by
--repository-id REPOSITORY_ID  Repository ID
-h, --help                    Print help
```

10.42.2. hammer module-stream list

List module streams

Usage:

```
hammer module-stream list [OPTIONS]
```

Options:

```
--content-view-filter CONTENT_VIEW_FILTER_NAME  Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID  Filter identifier
--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier
--environment ENVIRONMENT_NAME                  Environment name
--environment-id ENVIRONMENT_ID
--full-result FULL_RESULT                       Whether or not to show all results
                                                One of true/false, yes/no, 1/0.
--host-ids HOST_IDS                             List of host id to list available module streams for
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--hosts HOST_NAMES                             Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--ids IDS                                       Ids to filter content by
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--name-stream-only NAME_STREAM_ONLY            Return name and stream information only)
                                                One of true/false, yes/no, 1/0.
--order ORDER                                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME              Organization name to search by
--organization-id ORGANIZATION_ID              Organization ID
--organization-label ORGANIZATION_LABEL        Organization label to search by
--page PAGE                                    Page number, starting at 1
--per-page PER_PAGE                            Number of results per page to return
--product PRODUCT_NAME                         Product name to search by
--product-id PRODUCT_ID                       Product numeric identifier
--repository REPOSITORY_NAME                   Repository name to search by
--repository-id REPOSITORY_ID                  Repository ID
--search SEARCH                                Search string
-h, --help                                     Print help
```

10.43. HAMMER ORGANIZATION

Manipulate organizations

Usage:

```
hammer organization [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...            Subcommand arguments
```


Subcommands:

add-compute-resource	Associate a compute resource
add-config-template	Associate a configuration template
add-domain	Associate a domain
add-environment	Associate an environment
add-hostgroup	Associate a hostgroup
add-location	Associate a location
add-medium	Associate a medium
add-smart-proxy	Associate a smart proxy
add-subnet	Associate a subnet
add-user	Associate an user
create	Create organization
delete	Delete an organization
delete-parameter	Delete parameter for an organization
info	Show organization
list	List all organizations
remove-compute-resource	Disassociate a compute resource
remove-config-template	Disassociate a configuration template
remove-domain	Disassociate a domain
remove-environment	Disassociate an environment
remove-hostgroup	Disassociate a hostgroup
remove-location	Disassociate a location
remove-medium	Disassociate a medium
remove-smart-proxy	Disassociate a smart proxy
remove-subnet	Disassociate a subnet
remove-user	Disassociate an user
set-parameter	Create or update parameter for an organization
update	Update organization

Options:

-h, --help	Print help
------------	------------

10.43.1. hammer organization add-compute-resource

Associate a compute resource

Usage:

hammer organization add-compute-resource [OPTIONS]

Options:

--compute-resource COMPUTE_RESOURCE_NAME	Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID	
--id ID	Organization ID
--name NAME	Organization name
--title TITLE	Organization title
-h, --help	Print help

10.43.2. hammer organization add-config-template

Associate a configuration template

Usage:

hammer organization add-config-template [OPTIONS]

Options:

```
--config-template CONFIG_TEMPLATE_NAME  Name to search by
--config-template-id CONFIG_TEMPLATE_ID
--id ID                                  Organization ID
--name NAME                              Organization name
--title TITLE                            Organization title
-h, --help                               Print help
```

10.43.3. hammer organization add-domain

Associate a domain

Usage:

```
hammer organization add-domain [OPTIONS]
```

Options:

```
--domain DOMAIN_NAME      Domain name
--domain-id DOMAIN_ID     Numerical ID or domain name
--id ID                    Organization ID
--name NAME                Organization name
--title TITLE              Organization title
-h, --help                 Print help
```

10.43.4. hammer organization add-environment

Associate an environment

Usage:

```
hammer organization add-environment [OPTIONS]
```

Options:

```
--environment ENVIRONMENT_NAME  Environment name
--environment-id ENVIRONMENT_ID
--id ID                          Organization ID
--name NAME                      Organization name
--title TITLE                    Organization title
-h, --help                       Print help
```

10.43.5. hammer organization add-hostgroup

Associate a hostgroup

Usage:

```
hammer organization add-hostgroup [OPTIONS]
```

Options:

```
--hostgroup HOSTGROUP_NAME  Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--id ID                      Organization ID
```

```
--name NAME           Organization name
--title TITLE         Organization title
-h, --help            Print help
```

10.43.6. hammer organization add-location

Associate a location

```
Usage:
  hammer organization add-location [OPTIONS]
```

```
Options:
  --id ID                Organization ID
  --location LOCATION_NAME  Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME            Organization name
  --title TITLE          Organization title
  -h, --help            Print help
```

10.43.7. hammer organization add-medium

Associate a medium

```
Usage:
  hammer organization add-medium [OPTIONS]
```

```
Options:
  --id ID                Organization ID
  --medium MEDIUM_NAME  Medium name
  --medium-id MEDIUM_ID
  --name NAME            Organization name
  --title TITLE          Organization title
  -h, --help            Print help
```

10.43.8. hammer organization add-smart-proxy

Associate a smart proxy

```
Usage:
  hammer organization add-smart-proxy [OPTIONS]
```

```
Options:
  --id ID                Organization ID
  --name NAME            Organization name
  --smart-proxy SMART_PROXY_NAME Name to search by
  --smart-proxy-id SMART_PROXY_ID
  --title TITLE          Organization title
  -h, --help            Print help
```

10.43.9. hammer organization add-subnet

Associate a subnet

```
Usage:
  hammer organization add-subnet [OPTIONS]
```

```
Options:
  --id ID                Organization ID
  --name NAME            Organization name
  --subnet SUBNET_NAME   Subnet name
  --subnet-id SUBNET_ID
  --title TITLE          Organization title
  -h, --help            Print help
```

10.43.10. hammer organization add-user

Associate an user

```
Usage:
  hammer organization add-user [OPTIONS]

Options:
  --id ID                Organization ID
  --name NAME            Organization name
  --title TITLE          Organization title
  --user USER_LOGIN     User's login to search by
  --user-id USER_ID
  -h, --help            Print help
```

10.43.11. hammer organization create

Create organization

```
Usage:
  hammer organization create [OPTIONS]

Options:
  --compute-resource-ids COMPUTE_RESOURCE_IDS      Compute resource IDs
                                                    Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
  --compute-resources COMPUTE_RESOURCE_NAMES      Comma separated list of values.
Values containing comma should be quoted or escaped with backslash
  --config-template-ids CONFIG_TEMPLATE_IDS        Provisioning template IDs
                                                    Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
  --config-templates CONFIG_TEMPLATE_NAMES         Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
  --description DESCRIPTION                        Description
  --domain-ids DOMAIN_IDS                          Domain IDs
                                                    Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
  --domains DOMAIN_NAMES                          Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
  --environment-ids ENVIRONMENT_IDS                Environment IDs
                                                    Comma separated list of values. Values containing comma should
```

be quoted or escaped with backslash
 --environments ENVIRONMENT_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroup-ids HOSTGROUP_IDS Host group IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --label LABEL Unique label
 --location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-title LOCATION_TITLE Location title
 --media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --medium-ids MEDIUM_IDS Medium IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --name NAME Name
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --provisioning-template-ids PROVISIONING_TEMPLATE_IDS Provisioning template IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --ptable-ids PTABLE_IDS Partition template IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --ptables PTABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --realm-ids REALM_IDS Realm IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --realms REALM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --smart-proxies SMART_PROXY_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --smart-proxy-ids SMART_PROXY_IDS Capsule IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --subnet-ids SUBNET_IDS Subnet IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --subnets SUBNET_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --user-ids USER_IDS User IDs
 Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 --users USER_LOGINS Comma separated list of values. Values containing comma should be quoted or escaped with backslash
 -h, --help Print help

10.43.12. hammer organization delete

Delete an organization

Usage:

hammer organization delete [OPTIONS]

Options:

--async	Do not wait for the task
--id ID	
--label LABEL	Organization label to search by
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Organization name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--organization-title ORGANIZATION_TITLE	Organization title
--title TITLE	Organization title
-h, --help	Print help

10.43.13. hammer organization delete-parameter

Delete parameter for an organization

Usage:

hammer organization delete-parameter [OPTIONS]

Options:

--name NAME	Parameter name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.43.14. hammer organization info

Show organization

Usage:

hammer organization info [OPTIONS]

Options:

--id ID	
--label LABEL	Organization label to search by
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Organization name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by

```
--organization-title ORGANIZATION_TITLE Organization title
--title TITLE                      Organization title
-h, --help                        Print help
```

10.43.15. hammer organization list

List all organizations

Usage:

```
hammer organization list [OPTIONS]
```

Options:

```
--full-result FULL_RESULT          Whether or not to show all results
                                   One of true/false, yes/no, 1/0.
--location LOCATION_NAME           Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE     Location title
--order ORDER                      Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID   Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                        Page number, starting at 1
--per-page PER_PAGE                Number of results per page to return
--search SEARCH                    Search string
--sort-by SORT_BY                  Field to sort the results on
--sort-order SORT_ORDER            How to order the sorted results (e.g. ASC for ascending)
-h, --help                        Print help
```

10.43.16. hammer organization remove-compute-resource

Disassociate a compute resource

Usage:

```
hammer organization remove-compute-resource [OPTIONS]
```

Options:

```
--compute-resource COMPUTE_RESOURCE_NAME Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--id ID                            Organization ID
--name NAME                        Organization name
--title TITLE                      Organization title
-h, --help                        Print help
```

10.43.17. hammer organization remove-config-template

Disassociate a configuration template

Usage:

```
hammer organization remove-config-template [OPTIONS]
```

Options:

```
--config-template CONFIG_TEMPLATE_NAME Name to search by
```

```
--config-template-id CONFIG_TEMPLATE_ID
--id ID                               Organization ID
--name NAME                           Organization name
--title TITLE                         Organization title
-h, --help                           Print help
```

10.43.18. hammer organization remove-domain

Disassociate a domain

```
Usage:
  hammer organization remove-domain [OPTIONS]
```

```
Options:
--domain DOMAIN_NAME      Domain name
--domain-id DOMAIN_ID     Numerical ID or domain name
--id ID                   Organization ID
--name NAME               Organization name
--title TITLE             Organization title
-h, --help                Print help
```

10.43.19. hammer organization remove-environment

Disassociate an environment

```
Usage:
  hammer organization remove-environment [OPTIONS]
```

```
Options:
--environment ENVIRONMENT_NAME Environment name
--environment-id ENVIRONMENT_ID
--id ID           Organization ID
--name NAME       Organization name
--title TITLE     Organization title
-h, --help       Print help
```

10.43.20. hammer organization remove-hostgroup

Disassociate a hostgroup

```
Usage:
  hammer organization remove-hostgroup [OPTIONS]
```

```
Options:
--hostgroup HOSTGROUP_NAME      Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--id ID                         Organization ID
--name NAME                     Organization name
--title TITLE                   Organization title
-h, --help                      Print help
```


10.43.21. hammer organization remove-location

Disassociate a location

Usage:
hammer organization remove-location [OPTIONS]

Options:

--id ID	Organization ID
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Organization name
--title TITLE	Organization title
-h, --help	Print help

10.43.22. hammer organization remove-medium

Disassociate a medium

Usage:
hammer organization remove-medium [OPTIONS]

Options:

--id ID	Organization ID
--medium MEDIUM_NAME	Medium name
--medium-id MEDIUM_ID	
--name NAME	Organization name
--title TITLE	Organization title
-h, --help	Print help

10.43.23. hammer organization remove-smart-proxy

Disassociate a smart proxy

Usage:
hammer organization remove-smart-proxy [OPTIONS]

Options:

--id ID	Organization ID
--name NAME	Organization name
--smart-proxy SMART_PROXY_NAME	Name to search by
--smart-proxy-id SMART_PROXY_ID	
--title TITLE	Organization title
-h, --help	Print help

10.43.24. hammer organization remove-subnet

Disassociate a subnet

Usage:
hammer organization remove-subnet [OPTIONS]

```
Options:
--id ID                Organization ID
--name NAME            Organization name
--subnet SUBNET_NAME   Subnet name
--subnet-id SUBNET_ID
--title TITLE          Organization title
-h, --help             Print help
```

10.43.25. hammer organization remove-user

Disassociate an user

```
Usage:
  hammer organization remove-user [OPTIONS]

Options:
--id ID                Organization ID
--name NAME            Organization name
--title TITLE          Organization title
--user USER_LOGIN      User's login to search by
--user-id USER_ID
-h, --help             Print help
```

10.43.26. hammer organization set-parameter

Create or update parameter for an organization

```
Usage:
  hammer organization set-parameter [OPTIONS]

Options:
--hidden-value HIDDEN_VALUE      Should the value be hidden
                                  One of true/false, yes/no, 1/0.
--name NAME                      Parameter name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--value VALUE                    Parameter value
-h, --help                      Print help
```

10.43.27. hammer organization update

Update organization

```
Usage:
  hammer organization update [OPTIONS]

Options:
--compute-resource-ids COMPUTE_RESOURCE_IDS      Compute resource IDs
                                                    Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--compute-resources COMPUTE_RESOURCE_NAMES      Comma separated list of values.
Values containing comma should be quoted or escaped with backslash
```

```

--config-template-ids CONFIG_TEMPLATE_IDS      Provisioning template IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--config-templates CONFIG_TEMPLATE_NAMES      Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--description DESCRIPTION
--domain-ids DOMAIN_IDS                        Domain IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--domains DOMAIN_NAMES                        Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--environment-ids ENVIRONMENT_IDS             Environment IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--environments ENVIRONMENT_NAMES             Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--hostgroup-ids HOSTGROUP_IDS                 Host group IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--hostgroup-titles HOSTGROUP_TITLES           Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--hostgroups HOSTGROUP_NAMES                 Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--id ID
--ignore-types IGNORE_TYPES                   List of resources types that will be automatically
associated
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--label LABEL                                Organization label to search by
--location LOCATION_NAME                     Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE               Location title
--media MEDIUM_NAMES                         Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--medium-ids MEDIUM_IDS                      Medium IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--name NAME                                  Organization name
--new-name NEW_NAME
--organization ORGANIZATION_NAME              Organization name
--organization-id ORGANIZATION_ID             Organization ID
--organization-label ORGANIZATION_LABEL        Organization label to search by
--organization-title ORGANIZATION_TITLE        Organization title
--parent-id PARENT_ID                        Parent ID
--partition-table-ids PARTITION_TABLE_IDS      Partition template IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--partition-tables PARTITION_TABLE_NAMES      Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--provisioning-template-ids PROVISIONING_TEMPLATE_IDS Provisioning template IDs
                                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values.
Values containing comma should be quoted or escaped with backslash
--ptable-ids PTABLE_IDS                      Partition template IDs
                                                Comma separated list of values. Values containing comma should

```

```

be quoted or escaped with backslash
--ptables PTABLE_NAMES          Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--realm-ids REALM_IDS           Realm IDs
                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--realms REALM_NAMES           Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--redhat-repository-url REDHAT_REPOSITORY_URL  Red Hat CDN URL
--smart-proxies SMART_PROXY_NAMES  Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--smart-proxy-ids SMART_PROXY_IDS  Capsule IDs
                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--subnet-ids SUBNET_IDS        Subnet IDs
                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--subnets SUBNET_NAMES        Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--title TITLE                  Organization title
--user-ids USER_IDS           User IDs
                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--users USER_LOGINS           Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
-h, --help                    Print help

```

10.44. HAMMER OS

Manipulate operating system

```

Usage:
  hammer os [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  add-architecture    Associate an architecture
  add-config-template Associate a configuration template
  add-ptable          Associate a partition table
  create              Create an operating system
  delete              Delete an operating system
  delete-default-template
  delete-parameter    Delete parameter for an operating system
  info                Show an operating system
  list                List all operating systems
  remove-architecture Disassociate an architecture
  remove-config-template Disassociate a configuration template
  remove-ptable       Disassociate a partition table
  set-default-template
  set-parameter        Create or update parameter for an operating system
  update              Update an operating system

```

Options:
 -h, --help Print help

10.44.1. hammer os add-architecture

Associate an architecture

Usage:
 hammer os add-architecture [OPTIONS]

Options:
 --architecture ARCHITECTURE_NAME Architecture name
 --architecture-id ARCHITECTURE_ID
 --id ID
 --title TITLE Operating system title
 -h, --help Print help

10.44.2. hammer os add-config-template

Associate a configuration template

Usage:
 hammer os add-config-template [OPTIONS]

Options:
 --config-template CONFIG_TEMPLATE_NAME Name to search by
 --config-template-id CONFIG_TEMPLATE_ID
 --id ID
 --title TITLE Operating system title
 -h, --help Print help

10.44.3. hammer os add-ptable

Associate a partition table

Usage:
 hammer os add-ptable [OPTIONS]

Options:
 --id ID
 --partition-table PARTITION_TABLE_NAME Partition table name
 --partition-table-id PARTITION_TABLE_ID
 --title TITLE Operating system title
 -h, --help Print help

10.44.4. hammer os create

Create an operating system

Usage:
 hammer os create [OPTIONS]

Options:

--architecture-ids ARCHITECTURE_IDS IDs of associated architectures
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --architectures ARCHITECTURE_NAMES Comma separated list of values. Values
 containing comma should be quoted or escaped with backslash
 --config-template-ids CONFIG_TEMPLATE_IDS IDs of associated provisioning templates
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values
 containing comma should be quoted or escaped with backslash
 --description DESCRIPTION
 --family FAMILY
 --location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-title LOCATION_TITLE Location title
 --major MAJOR
 --media MEDIUM_NAMES Comma separated list of values. Values containing
 comma should be quoted or escaped with backslash
 --medium-ids MEDIUM_IDS IDs of associated media
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --minor MINOR
 --name NAME
 --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION_TITLE Organization title
 --os-parameters-attributes OS_PARAMETERS_ATTRIBUTES Array of parameters
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --partition-table-ids PARTITION_TABLE_IDS IDs of associated partition tables
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values
 containing comma should be quoted or escaped with backslash
 --password-hash PASSWORD_HASH Root password hash function to use, one of
 MD5, SHA256, SHA512, Base64
 --provisioning-template-ids PROVISIONING_TEMPLATE_IDS IDs of associated provisioning
 templates
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values.
 Values containing comma should be quoted or escaped with backslash
 --release-name RELEASE_NAME
 -h, --help Print help

10.44.5. hammer os delete

Delete an operating system

Usage:

hammer os delete [OPTIONS]

Options:

```

--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--title TITLE                  Operating system title
-h, --help                     Print help

```

10.44.6. hammer os delete-default-template

Usage:
hammer os delete-default-template [OPTIONS]

Options:

```

--id OS ID          Operatingsystem id
--type TPL TYPE      Type of the config template
-h, --help          Print help

```

10.44.7. hammer os delete-parameter

Delete parameter for an operating system

Usage:
hammer os delete-parameter [OPTIONS]

Options:

```

--name NAME          Parameter name
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
-h, --help          Print help

```

10.44.8. hammer os info

Show an operating system

Usage:
hammer os info [OPTIONS]

Options:

```

--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values
                                         One of true/false, yes/no, 1/0.
--title TITLE                  Operating system title
-h, --help                     Print help

```

10.44.9. hammer os list

List all operating systems

Usage:

hammer os list [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME	Architecture name
--architecture-id ARCHITECTURE_ID	
--config-template CONFIG_TEMPLATE_NAME	Name to search by
--config-template-id CONFIG_TEMPLATE_ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--medium MEDIUM_NAME	Medium name
--medium-id MEDIUM_ID	
--order ORDER	Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--os-parameters-attributes OS_PARAMETERS_ATTRIBUTES	Array of parameters
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--page PAGE	Paginate results
--partition-table PARTITION_TABLE_NAME	Partition table name
--partition-table-id PARTITION_TABLE_ID	
--per-page PER_PAGE	Number of entries per request
--provisioning-template PROVISIONING_TEMPLATE_NAME	Name to search by
--provisioning-template-id PROVISIONING_TEMPLATE_ID	
--search SEARCH	Filter results
-h, --help	Print help

10.44.10. hammer os remove-architecture

Disassociate an architecture

Usage:

hammer os remove-architecture [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME	Architecture name
--architecture-id ARCHITECTURE_ID	
--id ID	
--title TITLE	Operating system title
-h, --help	Print help

10.44.11. hammer os remove-config-template

Disassociate a configuration template

Usage:

hammer os remove-config-template [OPTIONS]

Options:

```
--config-template CONFIG_TEMPLATE_NAME Name to search by
--config-template-id CONFIG_TEMPLATE_ID
--id ID
--title TITLE           Operating system title
-h, --help             Print help
```

10.44.12. hammer os remove-ptable

Disassociate a partition table

Usage:

```
hammer os remove-ptable [OPTIONS]
```

Options:

```
--id ID
--partition-table PARTITION_TABLE_NAME Partition table name
--partition-table-id PARTITION_TABLE_ID
--title TITLE           Operating system title
-h, --help             Print help
```

10.44.13. hammer os set-default-template

Usage:

```
hammer os set-default-template [OPTIONS]
```

Options:

```
--config-template-id TPL ID Config template id to be set
--id OS ID           Operatingsystem id
-h, --help           Print help
```

10.44.14. hammer os set-parameter

Create or update parameter for an operating system

Usage:

```
hammer os set-parameter [OPTIONS]
```

Options:

```
--hidden-value HIDDEN_VALUE      Should the value be hidden
                                   One of true/false, yes/no, 1/0.
--name NAME                       Parameter name
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--value VALUE                     Parameter value
-h, --help                       Print help
```

10.44.15. hammer os update

Update an operating system

Usage:

hammer os update [OPTIONS]

Options:

--architecture-ids ARCHITECTURE_IDS IDs of associated architectures
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--architectures ARCHITECTURE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--config-template-ids CONFIG_TEMPLATE_IDS IDs of associated provisioning templates
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--description DESCRIPTION

--family FAMILY

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--major MAJOR

--media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--medium-ids MEDIUM_IDS IDs of associated media
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--minor MINOR

--name NAME

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--os-parameters-attributes OS_PARAMETERS_ATTRIBUTES Array of parameters
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--partition-table-ids PARTITION_TABLE_IDS IDs of associated partition tables
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--password-hash PASSWORD_HASH Root password hash function to use, one of MD5, SHA256, SHA512, Base64

--provisioning-template-ids PROVISIONING_TEMPLATE_IDS IDs of associated provisioning templates
Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--release-name RELEASE_NAME

--title TITLE Operating system title

-h, --help Print help

10.45. HAMMER OSTREE-BRANCH

Manipulate ostree branches

Usage:

```
hammer ostree-branch [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments
```

Subcommands:

```
info                Show an ostree branch
list                List ostree_branches
```

Options:

```
-h, --help          Print help
```

10.45.1. hammer ostree-branch info

Show an ostree branch

Usage:

```
hammer ostree-branch info [OPTIONS]
```

Options:

```
--id ID              An ostree branch identifier
--name NAME          Name to search by
--repository REPOSITORY_NAME Repository name to search by
--repository-id REPOSITORY_ID Repository ID
-h, --help           Print help
```

10.45.2. hammer ostree-branch list

List ostree_branches

Usage:

```
hammer ostree-branch list [OPTIONS]
```

Options:

```
--content-view CONTENT_VIEW_NAME      Content view name to search by
--content-view-filter CONTENT_VIEW_FILTER_NAME  Name to search by
--content-view-filter-id CONTENT_VIEW_FILTER_ID  Filter identifier
--content-view-id CONTENT_VIEW_ID        Content view numeric identifier
--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier
--environment ENVIRONMENT_NAME          Environment name
--environment-id ENVIRONMENT_ID
--full-result FULL_RESULT                Whether or not to show all results
                                         One of true/false, yes/no, 1/0.
--ids IDS                                Ids to filter content by
                                         Comma separated list of values. Values containing comma should
                                         be quoted or escaped with backslash
--order ORDER                            Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME          Organization name to search by
--organization-id ORGANIZATION_ID          Organization ID
--organization-label ORGANIZATION_LABEL    Organization label to search by
--page PAGE                               Page number, starting at 1
--per-page PER_PAGE                       Number of results per page to return
```

```

--product PRODUCT_NAME      Product name to search by
--product-id PRODUCT_ID     Product numeric identifier
--repository REPOSITORY_NAME Repository name to search by
--repository-id REPOSITORY_ID Repository ID
--search SEARCH              Search string
-h, --help                  Print help

```

10.46. HAMMER PACKAGE

Manipulate packages

```

Usage:
  hammer package [OPTIONS] SUBCOMMAND [ARG] ...

```

```

Parameters:
  SUBCOMMAND      Subcommand
  [ARG] ...       Subcommand arguments

```

```

Subcommands:
  info      Show a package
  list      List packages

```

```

Options:
  -h, --help      Print help

```

10.46.1. hammer package info

Show a package

```

Usage:
  hammer package info [OPTIONS]

```

```

Options:
  --id ID          A package identifier
  --name NAME      Name to search by
  --repository REPOSITORY_NAME Repository name to search by
  --repository-id REPOSITORY_ID Repository ID
  -h, --help      Print help

```

10.46.2. hammer package list

List packages

```

Usage:
  hammer package list [OPTIONS]

```

```

Options:
  --available-for AVAILABLE_FOR      Return packages that can be added to the
specified object. Only the value
                                     'content_view_version' is supported.
  --content-view CONTENT_VIEW_NAME   Content view name to search by
  --content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by
  --content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier

```

```

--content-view-id CONTENT_VIEW_ID          Content view numeric identifier
--content-view-version CONTENT_VIEW_VERSION_VERSION    Content view version number
--content-view-version-id CONTENT_VIEW_VERSION_ID      Content view version identifier
--environment ENVIRONMENT_NAME              Environment name
--environment-id ENVIRONMENT_ID
--full-result FULL_RESULT                  Whether or not to show all results
                                         One of true/false, yes/no, 1/0.
--host HOST_NAME                          Host name
--host-id HOST_ID
--ids IDS                                Package identifiers to filter content by
                                         Comma separated list of values. Values containing comma
                                         should be quoted or escaped with backslash
--order ORDER                            Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME          Organization name to search by
--organization-id ORGANIZATION_ID          Organization ID
--organization-label ORGANIZATION_LABEL    Organization label to search by
--packages-restrict-applicable PACKAGES_RESTRICT_APPLICABLE Return packages that are
                                         applicable to one or more hosts (defaults to true
                                         If host_id is specified)
                                         One of true/false, yes/no, 1/0.
--packages-restrict-latest PACKAGES_RESTRICT_LATEST    Return only the latest version of
                                         each package
                                         One of true/false, yes/no, 1/0.
--packages-restrict-upgradable PACKAGES_RESTRICT_UPGRADABLE Return packages that are
                                         upgradable on one or more hosts
                                         One of true/false, yes/no, 1/0.
--page PAGE                              Page number, starting at 1
--per-page PER_PAGE                      Number of results per page to return
--product PRODUCT_NAME                   Product name to search by
--product-id PRODUCT_ID                 Product numeric identifier
--repository REPOSITORY_NAME            Repository name to search by
--repository-id REPOSITORY_ID           Repository ID
--search SEARCH                         Search string
-h, --help                             Print help

```

10.47. HAMMER PACKAGE-GROUP

Manipulate package groups

```

Usage:
  hammer package-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  info                Show a package group
  list                List package_groups

Options:
  -h, --help          Print help

```

10.47.1. hammer package-group info

Show a package group

Usage:

hammer package-group info [OPTIONS]

Options:

--id ID A package group identifier
 --name NAME Name to search by
 --repository REPOSITORY_NAME Repository name to search by
 --repository-id REPOSITORY_ID Repository ID
 -h, --help Print help

10.47.2. hammer package-group list

List package_groups

Usage:

hammer package-group list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by
 --content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by
 --content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier
 --content-view-id CONTENT_VIEW_ID Content view numeric identifier
 --content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
 --content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier
 --environment ENVIRONMENT_NAME Environment name
 --environment-id ENVIRONMENT_ID
 --full-result FULL_RESULT Whether or not to show all results
 One of true/false, yes/no, 1/0.
 --ids IDS Ids to filter content by
 Comma separated list of values. Values containing comma should
 be quoted or escaped with backslash
 --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --page PAGE Page number, starting at 1
 --per-page PER_PAGE Number of results per page to return
 --product PRODUCT_NAME Product name to search by
 --product-id PRODUCT_ID Product numeric identifier
 --repository REPOSITORY_NAME Repository name to search by
 --repository-id REPOSITORY_ID Repository ID
 --search SEARCH Search string
 -h, --help Print help

10.48. HAMMER PARTITION-TABLE

Manipulate partition tables

Usage:

hammer partition-table [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

add-operatingsystem	Associate an operating system
create	Create a partition table
delete	Delete a partition table
dump	View partition table content
info	Show a partition table
list	List all partition tables
remove-operatingsystem	Disassociate an operating system
update	Update a partition table

Options:

-h, --help	Print help
------------	------------

10.48.1. hammer partition-table add-operatingsystem

Associate an operating system

Usage:

```
hammer partition-table add-operatingsystem [OPTIONS]
```

Options:

--id ID	
--name NAME	Partition table name
--operatingsystem OPERATINGSYSTEM_TITLE	Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID	
-h, --help	Print help

10.48.2. hammer partition-table create

Create a partition table

Usage:

```
hammer partition-table create [OPTIONS]
```

Options:

--audit-comment AUDIT_COMMENT	
--file LAYOUT	Path to a file that contains the partition layout
--host-ids HOST_IDS	Array of host IDs to associate with the partition table
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--hostgroup-ids HOSTGROUP_IDS	Array of host group IDs to associate with the partition table
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--hostgroup-titles HOSTGROUP_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--hostgroups HOSTGROUP_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--hosts HOST_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--location LOCATION_NAME	Location name

```

--location-id LOCATION_ID
--location-ids LOCATION_IDS          REPLACE locations with given ids
                                     Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE      Location title
--location-titles LOCATION_TITLES    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES           Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locked LOCKED                      Whether or not the template is locked for editing
                                     One of true/false, yes/no, 1/0.

--name NAME
--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with
the partition table
                                     Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID     Organization ID
--organization-ids ORGANIZATION_IDS   REPLACE organizations with given ids.
                                     Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES    Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--os-family OS_FAMILY
--snippet SNIPPET                     One of true/false, yes/no, 1/0.
-h, --help                           Print help

```

10.48.3. hammer partition-table delete

Delete a partition table

```

Usage:
  hammer partition-table delete [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Partition table name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help

```

10.48.4. hammer partition-table dump

View partition table content

Usage:

```
hammer partition-table dump [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Partition table name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.48.5. hammer partition-table info

Show a partition table

Usage:

```
hammer partition-table info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Partition table name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.48.6. hammer partition-table list

List all partition tables

Usage:

```
hammer partition-table list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                    Print help
```

10.48.7. hammer partition-table remove-operatingsystem

Disassociate an operating system

Usage:

```
hammer partition-table remove-operatingsystem [OPTIONS]
```

Options:

```
--id ID
--name NAME                Partition table name
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
-h, --help                 Print help
```

10.48.8. hammer partition-table update

Update a partition table

Usage:

```
hammer partition-table update [OPTIONS]
```

Options:

```
--audit-comment AUDIT_COMMENT
--file LAYOUT              Path to a file that contains the partition layout
--host-ids HOST_IDS        Array of host IDs to associate with the partition table
                          Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--hostgroup-ids HOSTGROUP_IDS Array of host group IDs to associate with the partition
table
                          Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--hosts HOST_NAMES        Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--id ID
--location LOCATION_NAME  Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS REPLACE locations with given ids
                          Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locked LOCKED           Whether or not the template is locked for editing
                          One of true/false, yes/no, 1/0.
--name NAME               Partition table name
--new-name NEW_NAME
--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with
the partition table
                          Comma separated list of values. Values containing comma should be
```

```

quoted or escaped with backslash
--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-ids ORGANIZATION_IDS    REPLACE organizations with given ids.
                                       Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES     Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--os-family OS_FAMILY
--snippet SNIPPET                      One of true/false, yes/no, 1/0.
-h, --help                            Print help

```

10.49. HAMMER PING

Get the status of the server

```

Usage:
  hammer ping [OPTIONS]

Options:
  -h, --help      Print help

```

10.50. HAMMER POLICY

Manipulate policies

```

Usage:
  hammer policy [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND      Subcommand
  [ARG] ...       Subcommand arguments

Subcommands:
  create          Create a Policy
  delete          Delete a Policy
  info           Show a Policy
  list           List Policies
  update         Update a Policy

Options:
  -h, --help      Print help

```

10.50.1. hammer policy create

Create a Policy

```

Usage:

```

```
hammer policy create [OPTIONS]
```

Options:

```
--cron-line CRON_LINE           Policy schedule cron line (only if period == "custom")
--day-of-month DAY_OF_MONTH      Policy schedule day of month (only if period ==
"monthly")
--description DESCRIPTION        Policy description
--host-ids HOST_IDS              Apply policy to hosts
                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--hostgroup-ids HOSTGROUP_IDS    Apply policy to host groups
                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--hostgroups HOSTGROUP_NAMES     Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--hosts HOST_NAMES              Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--location LOCATION_NAME        Name to search by
--location-id LOCATION_ID
--location-ids LOCATION_IDS      REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--locations LOCATION_NAMES       Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--name NAME                      Policy name
--organization ORGANIZATION_NAME Name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--period PERIOD                 Policy schedule period (weekly, monthly, custom)
--scap-content SCAP_CONTENT_TITLE SCAP content title
--scap-content-id SCAP_CONTENT_ID
--scap-content-profile-id SCAP_CONTENT_PROFILE_ID Policy SCAP content profile ID
--tailoring-file TAILORING_FILE_NAME Tailoring file name
--tailoring-file-id TAILORING_FILE_ID
--tailoring-file-profile-id TAILORING_FILE_PROFILE_ID Tailoring file profile ID
--weekday WEEKDAY              Policy schedule weekday (only if period == "weekly")
-h, --help                      Print help
```

10.50.2. hammer policy delete

Delete a Policy

Usage:

```
hammer policy delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME        Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                     Name to search by
```

```
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                          Print help
```

10.50.3. hammer policy info

Show a Policy

```
Usage:
  hammer policy info [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --name NAME                           Name to search by
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                            Print help
```

10.50.4. hammer policy list

List Policies

```
Usage:
  hammer policy list [OPTIONS]

Options:
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --order ORDER                        Sort field and order, eg. 'id DESC'
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --page PAGE                           Paginate results
  --per-page PER_PAGE                   Number of entries per request
  --search SEARCH                       Filter results
  -h, --help                            Print help
```

10.50.5. hammer policy update

Update a Policy

```
Usage:
  hammer policy update [OPTIONS]

Options:
  --cron-line CRON_LINE                Policy schedule cron line (only if period == "custom")
  --day-of-month DAY_OF_MONTH          Policy schedule day of month (only if period ==
```

```

“monthly”)
--description DESCRIPTION          Policy description
--host-ids HOST_IDS                Apply policy to hosts
                                   Comma separated list of values. Values containing comma should
                                   be quoted or escaped with backslash
--hostgroup-ids HOSTGROUP_IDS      Apply policy to host groups
                                   Comma separated list of values. Values containing comma should
                                   be quoted or escaped with backslash
--hostgroups HOSTGROUP_NAMES       Comma separated list of values. Values
                                   containing comma should be quoted or escaped with backslash
--hosts HOST_NAMES                 Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--id ID
--location LOCATION_NAME           Name to search by
--location-id LOCATION_ID
--location-ids LOCATION_IDS        REPLACE locations with given ids
                                   Comma separated list of values. Values containing comma should
                                   be quoted or escaped with backslash
--locations LOCATION_NAMES         Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--name NAME                        Policy name
--new-name NEW_NAME                Policy name
--organization ORGANIZATION_NAME   Name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                   Comma separated list of values. Values containing comma should
                                   be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values
                                   containing comma should be quoted or escaped with backslash
--period PERIOD                    Policy schedule period (weekly, monthly, custom)
--scap-content SCAP_CONTENT_TITLE  SCAP content title
--scap-content-id SCAP_CONTENT_ID
--scap-content-profile-id SCAP_CONTENT_PROFILE_ID Policy SCAP content profile ID
--tailoring-file TAILORING_FILE_NAME Tailoring file name
--tailoring-file-id TAILORING_FILE_ID
--tailoring-file-profile-id TAILORING_FILE_PROFILE_ID Tailoring file profile ID
--weekday WEEKDAY                  Policy schedule weekday (only if period == “weekly”)
-h, --help                          Print help

```

10.51. HAMMER PRODUCT

Manipulate products

```

Usage:
  hammer product [OPTIONS] SUBCOMMAND [ARG] ...

```

```

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

```

```

Subcommands:
  create      Create a product
  delete      Destroy a product
  info        Show a product
  list        List products

```

remove-sync-plan	Delete assignment sync plan and product
set-sync-plan	Assign sync plan to product
synchronize	Sync all repositories for a product
update	Updates a product

Options:

-h, --help	Print help
------------	------------

10.51.1. hammer product create

Create a product

Usage:

```
hammer product create [OPTIONS]
```

Options:

--description DESCRIPTION	Product description
--gpg-key GPG_KEY_NAME	Name to search by
--gpg-key-id GPG_KEY_ID	Gpg key numeric identifier
--label LABEL	
--name NAME	Product name
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--ssl-ca-cert-id SSL_CA_CERT_ID	Identifier of the SSL CA Cert
--ssl-client-cert-id SSL_CLIENT_CERT_ID	Identifier of the SSL Client Cert
--ssl-client-key-id SSL_CLIENT_KEY_ID	Identifier of the SSL Client Key
--sync-plan SYNC_PLAN_NAME	Sync plan name to search by
--sync-plan-id SYNC_PLAN_ID	Sync plan numeric identifier
-h, --help	Print help

10.51.2. hammer product delete

Destroy a product

Usage:

```
hammer product delete [OPTIONS]
```

Options:

--id ID	Product numeric identifier
--name NAME	Product name to search by
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
-h, --help	Print help

10.51.3. hammer product info

Show a product

Usage:

```
hammer product info [OPTIONS]
```

Options:

<code>--id ID</code>	Product numeric identifier
<code>--name NAME</code>	Product name to search by
<code>--organization ORGANIZATION_NAME</code>	Organization name to search by
<code>--organization-id ORGANIZATION_ID</code>	Organization ID
<code>--organization-label ORGANIZATION_LABEL</code>	Organization label to search by
<code>-h, --help</code>	Print help

10.51.4. hammer product list

List products

Usage:

hammer product list [OPTIONS]

Options:

<code>--available-for AVAILABLE_FOR</code>	Interpret specified object to return only Products that can be associated
<code>--custom CUSTOM</code>	With specified object. Only 'sync_plan' is supported. Return custom products only
<code>--enabled ENABLED</code>	One of true/false, yes/no, 1/0. Return enabled products only
<code>--full-result FULL_RESULT</code>	One of true/false, yes/no, 1/0. Whether or not to show all results
<code>--include-available-content INCLUDE_AVAILABLE_CONTENT</code>	Whether to include available content attribute in results
<code>--name NAME</code>	One of true/false, yes/no, 1/0. Filter products by name
<code>--order ORDER</code>	Sort field and order, eg. 'id DESC'
<code>--organization ORGANIZATION_NAME</code>	Organization name to search by
<code>--organization-id ORGANIZATION_ID</code>	Organization ID
<code>--organization-label ORGANIZATION_LABEL</code>	Organization label to search by
<code>--page PAGE</code>	Page number, starting at 1
<code>--per-page PER_PAGE</code>	Number of results per page to return
<code>--redhat-only REDHAT_ONLY</code>	Return Red Hat (non-custom) products only
<code>--search SEARCH</code>	One of true/false, yes/no, 1/0. Search string
<code>--subscription SUBSCRIPTION_NAME</code>	Subscription name to search by
<code>--subscription-id SUBSCRIPTION_ID</code>	Subscription identifier
<code>--sync-plan SYNC_PLAN_NAME</code>	Sync plan name to search by
<code>--sync-plan-id SYNC_PLAN_ID</code>	Sync plan numeric identifier
<code>-h, --help</code>	Print help

10.51.5. hammer product remove-sync-plan

Delete assignment sync plan and product

Usage:

hammer product remove-sync-plan [OPTIONS]

Options:

<code>--description DESCRIPTION</code>	Product description
<code>--gpg-key GPG_KEY_NAME</code>	Name to search by


```

--gpg-key-id GPG_KEY_ID      Gpg key numeric identifier
--id ID                      Product numeric identifier
--name NAME                  Product name to search by
--new-name NEW_NAME          Product name
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--ssl-ca-cert-id SSL_CA_CERT_ID Identifier of the SSL CA Cert
--ssl-client-cert-id SSL_CLIENT_CERT_ID Identifier of the SSL Client Cert
--ssl-client-key-id SSL_CLIENT_KEY_ID Identifier of the SSL Client Key
-h, --help                  Print help

```

10.51.6. hammer product set-sync-plan

Assign sync plan to product

Usage:
hammer product set-sync-plan [OPTIONS]

Options:

```

--gpg-key GPG_KEY_NAME      Name to search by
--gpg-key-id GPG_KEY_ID      Gpg key numeric identifier
--id ID                      Product numeric identifier
--name NAME                  Product name to search by
--new-name NEW_NAME          Product name
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--ssl-ca-cert-id SSL_CA_CERT_ID Identifier of the SSL CA Cert
--ssl-client-cert-id SSL_CLIENT_CERT_ID Identifier of the SSL Client Cert
--ssl-client-key-id SSL_CLIENT_KEY_ID Identifier of the SSL Client Key
--sync-plan SYNC_PLAN_NAME   Sync plan name to search by
--sync-plan-id SYNC_PLAN_ID   Sync plan numeric identifier
-h, --help                  Print help

```

10.51.7. hammer product synchronize

Sync all repositories for a product

Usage:
hammer product synchronize [OPTIONS]

Options:

```

--async                    Do not wait for the task
--id ID                    Product ID
--name NAME                Product name to search by
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                Print help

```

10.51.8. hammer product update

Updates a product

Usage:

hammer product update [OPTIONS]

Options:

--description DESCRIPTION	Product description
--gpg-key GPG_KEY_NAME	Name to search by
--gpg-key-id GPG_KEY_ID	Gpg key numeric identifier
--id ID	Product numeric identifier
--name NAME	Product name to search by
--new-name NEW_NAME	Product name
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--ssl-ca-cert-id SSL_CA_CERT_ID	Identifier of the SSL CA Cert
--ssl-client-cert-id SSL_CLIENT_CERT_ID	Identifier of the SSL Client Cert
--ssl-client-key-id SSL_CLIENT_KEY_ID	Identifier of the SSL Client Key
--sync-plan SYNC_PLAN_NAME	Sync plan name to search by
--sync-plan-id SYNC_PLAN_ID	Sync plan numeric identifier
-h, --help	Print help

10.52. HAMMER PROXY

Manipulate smart proxies

Usage:

hammer proxy [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

content	Manage the capsule content
create	Create a capsule
delete	Delete a capsule
import-classes	Import puppet classes from puppet Capsule
info	Show a capsule
list	List all capsules
refresh-features	Refresh capsule features
update	Update a capsule

Options:

-h, --help	Print help
------------	------------

10.52.1. hammer proxy content

Manage the capsule content

Usage:

hammer proxy content [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

add-lifecycle-environment	Add lifecycle environments to the capsule
available-lifecycle-environments	List the lifecycle environments not attached to the capsule
cancel-synchronization	Cancel running capsule synchronization
info	Get current capsule synchronization status
lifecycle-environments	List the lifecycle environments attached to the capsule
remove-lifecycle-environment	Remove lifecycle environments from the capsule
synchronization-status	Get current capsule synchronization status
synchronize	Synchronize the content to the capsule

Options:

-h, --help	Print help
------------	------------

10.52.1.1. hammer proxy content add-lifecycle-environment

Add lifecycle environments to the capsule

Usage:

hammer proxy content add-lifecycle-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME	Environment name
--environment-id ENVIRONMENT_ID	
--id ID	Id of the capsule
--name NAME	Name to search by
--organization NAME	Organization name
--organization-id ID	Organization ID
-h, --help	Print help

10.52.1.2. hammer proxy content available-lifecycle-environments

List the lifecycle environments not attached to the capsule

Usage:

hammer proxy content available-lifecycle-environments [OPTIONS]

Options:

--id ID	Id of the capsule
--name NAME	Name to search by
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
-h, --help	Print help

10.52.1.3. hammer proxy content cancel-synchronization

Cancel running capsule synchronization

Usage:

hammer proxy content cancel-synchronization [OPTIONS]

```
Options:
--id ID           Id of the capsule
--name NAME       Name to search by
-h, --help       Print help
```

10.52.1.4. hammer proxy content info

Get current capsule synchronization status

```
Usage:
  hammer proxy content info [OPTIONS]

Options:
--id ID           Id of the capsule
--name NAME       Name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
-h, --help       Print help
```

10.52.1.5. hammer proxy content lifecycle-environments

List the lifecycle environments attached to the capsule

```
Usage:
  hammer proxy content lifecycle-environments [OPTIONS]

Options:
--id ID           Id of the capsule
--name NAME       Name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
-h, --help       Print help
```

10.52.1.6. hammer proxy content remove-lifecycle-environment

Remove lifecycle environments from the capsule

```
Usage:
  hammer proxy content remove-lifecycle-environment [OPTIONS]

Options:
--environment ENVIRONMENT_NAME  Environment name
--environment-id ENVIRONMENT_ID
--id ID           Id of the capsule
--name NAME       Name to search by
--organization NAME  Organization name
--organization-id ID  Organization ID
-h, --help       Print help
```

10.52.1.7. hammer proxy content synchronization-status

Get current capsule synchronization status

Usage:

hammer proxy content synchronization-status [OPTIONS]

Options:

```
--id ID                Id of the capsule
--name NAME            Name to search by
--organization ORGANIZATION_NAME  Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
-h, --help            Print help
```

10.52.1.8. hammer proxy content synchronize

Synchronize the content to the capsule

Usage:

hammer proxy content synchronize [OPTIONS]

Options:

```
--async                Do not wait for the task
--environment ENVIRONMENT_NAME      Environment name
--environment-id ENVIRONMENT_ID
--id ID                Id of the capsule
--name NAME            Name to search by
--organization NAME     Organization name
--organization-id ID    Organization ID
--skip-metadata-check SKIP_METADATA_CHECK Skip metadata check on each repository on the
capsule
                        One of true/false, yes/no, 1/0.
-h, --help            Print help
```

10.52.2. hammer proxy create

Create a capsule

Usage:

hammer proxy create [OPTIONS]

Options:

```
--download-policy DOWNLOAD_POLICY      Download Policy of the capsule, must be one of
immediate, on_demand,
                                     Background, inherit
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS             REPLACE locations with given ids
                                     Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE          Location title
--location-titles LOCATION_TITLES       Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
```

```

--name NAME
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-ids ORGANIZATION_IDS    REPLACE organizations with given ids.
                                       Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES     Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--url URL
-h, --help                             Print help

```

10.52.3. hammer proxy delete

Delete a capsule

```

Usage:
  hammer proxy delete [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help

```

10.52.4. hammer proxy import-classes

Import puppet classes from puppet Capsule

```

Usage:
  hammer proxy import-classes [OPTIONS]

Options:
--dryrun                Do not run the import
--environment ENVIRONMENT_NAME Environment name
--environment-id ENVIRONMENT_ID
--except EXCEPT       Optional comma-delimited string containing either 'new',
                        'updated', or 'obsolete' that is used to limit the imported
                        Puppet classes
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name

```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                          Print help
```

10.52.5. hammer proxy info

Show a capsule

```
Usage:
  hammer proxy info [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --name NAME                           Name to search by
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                          Print help
```

10.52.6. hammer proxy list

List all capsules

```
Usage:
  hammer proxy list [OPTIONS]

Options:
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID             Location title
  --location-title LOCATION_TITLE       Location title
  --order ORDER                        Sort field and order, eg. 'id DESC'
  --organization ORGANIZATION_NAME      Organization name
  --organization-id ORGANIZATION_ID     Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --page PAGE                          Paginate results
  --per-page PER_PAGE                  Number of entries per request
  --search SEARCH                      Filter results
  -h, --help                          Print help
```

10.52.7. hammer proxy refresh-features

Refresh capsule features

```
Usage:
  hammer proxy refresh-features [OPTIONS]

Options:
  --id ID                               Location name
  --location LOCATION_NAME              Location name
  --location-id LOCATION_ID
```

```
--location-title LOCATION_TITLE      Location title
--name NAME                          Name to search by
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID     Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                          Print help
```

10.52.8. hammer proxy update

Update a capsule

Usage:

```
hammer proxy update [OPTIONS]
```

Options:

```
--download-policy DOWNLOAD_POLICY      Download Policy of the capsule, must be one of
immediate, on_demand,
                                         Background, inherit
--id ID
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS             REPLACE locations with given ids
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE         Location title
--location-titles LOCATION_TITLES       Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES              Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--name NAME                            Name to search by
--new-name NEW_NAME
--organization ORGANIZATION_NAME        Organization name
--organization-id ORGANIZATION_ID       Organization ID
--organization-ids ORGANIZATION_IDS     REPLACE organizations with given ids.
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--url URL
-h, --help                              Print help
```

10.53. HAMMER PUPPET-CLASS

Search puppet modules

Usage:

```
hammer puppet-class [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...            Subcommand arguments
```


Subcommands:

info	Show a Puppet class
list	List all Puppet classes
sc-params	List all smart class parameters
smart-variables	List all smart variables

Options:

-h, --help	Print help
------------	------------

10.53.1. hammer puppet-class info

Show a Puppet class

Usage:

```
hammer puppet-class info [OPTIONS]
```

Options:

--environment ENVIRONMENT_NAME	Environment name
--environment-id ENVIRONMENT_ID	
--host HOST_NAME	Host name
--host-id HOST_ID	
--hostgroup HOSTGROUP_NAME	Hostgroup name
--hostgroup-id HOSTGROUP_ID	
--hostgroup-title HOSTGROUP_TITLE	Hostgroup title
--id ID	ID of Puppet class
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Puppet class name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.53.2. hammer puppet-class list

List all Puppet classes

Usage:

```
hammer puppet-class list [OPTIONS]
```

Options:

--environment ENVIRONMENT_NAME	Environment name
--environment-id ENVIRONMENT_ID	
--host HOST_NAME	Host name
--host-id HOST_ID	
--hostgroup HOSTGROUP_NAME	Hostgroup name
--hostgroup-id HOSTGROUP_ID	
--hostgroup-title HOSTGROUP_TITLE	Hostgroup title
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--order ORDER	Sort field and order, eg. 'id DESC'

```
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                  Number of entries per request
--search SEARCH                      Filter results
-h, --help                          Print help
```

10.53.3. hammer puppet-class sc-params

List all smart class parameters

Usage:

```
hammer puppet-class sc-params [OPTIONS]
```

Options:

```
--location LOCATION_NAME            Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--order ORDER                       Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                  Number of entries per request
--puppet-class PUPPET_CLASS_NAME     Puppet class name
--puppet-class-id PUPPET_CLASS_ID    ID of Puppet class
--search SEARCH                      Filter results
--show-hidden SHOW_HIDDEN            Display hidden values
                                     One of true/false, yes/no, 1/0.
-h, --help                          Print help
```

10.53.4. hammer puppet-class smart-variables

List all smart variables

Usage:

```
hammer puppet-class smart-variables [OPTIONS]
```

Options:

```
--location LOCATION_NAME            Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--order ORDER                       Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                  Number of entries per request
--puppet-class PUPPET_CLASS_NAME     Puppet class name
--puppet-class-id PUPPET_CLASS_ID    ID of Puppet class
--search SEARCH                      Filter results
```

```
--show-hidden SHOW_HIDDEN      Display hidden values
                                One of true/false, yes/no, 1/0.
-h, --help                      Print help
```

10.54. HAMMER PUPPET-MODULE

View Puppet Module details

```
Usage:
  hammer puppet-module [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  info                Show a puppet module
  list                List puppet_modules

Options:
  -h, --help          Print help
```

10.54.1. hammer puppet-module info

Show a puppet module

```
Usage:
  hammer puppet-module info [OPTIONS]

Options:
  --id ID              A puppet module identifier
  --name NAME          Name to search by
  --organization ORGANIZATION_NAME Organization name to search by
  --organization-id ORGANIZATION_ID Organization ID
  --organization-label ORGANIZATION_LABEL Organization label to search by
  --repository REPOSITORY_NAME Repository name to search by
  --repository-id REPOSITORY_ID Repository ID
  -h, --help          Print help
```

10.54.2. hammer puppet-module list

List puppet_modules

```
Usage:
  hammer puppet-module list [OPTIONS]

Options:
  --content-view CONTENT_VIEW_NAME Content view name to search by
  --content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by
  --content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier
  --content-view-id CONTENT_VIEW_ID Content view numeric identifier
  --content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number
  --content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier
```

```

--environment ENVIRONMENT_NAME          Environment name
--environment-id ENVIRONMENT_ID
--full-result FULL_RESULT                Whether or not to show all results
                                         One of true/false, yes/no, 1/0.
--ids IDS                                Ids to filter content by
                                         Comma separated list of values. Values containing comma should
                                         be quoted or escaped with backslash
--order ORDER                            Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME        Organization name to search by
--organization-id ORGANIZATION_ID        Organization ID
--organization-label ORGANIZATION_LABEL  Organization label to search by
--page PAGE                              Page number, starting at 1
--per-page PER_PAGE                      Number of results per page to return
--product PRODUCT_NAME                  Product name to search by
--product-id PRODUCT_ID                 Product numeric identifier
--repository REPOSITORY_NAME            Repository name to search by
--repository-id REPOSITORY_ID            Repository ID
--search SEARCH                          Search string
-h, --help                               Print help

```

10.55. HAMMER REALM

Manipulate realms

```

Usage:
  hammer realm [OPTIONS] SUBCOMMAND [ARG] ...

```

```

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

```

```

Subcommands:
  create          Create a realm
  delete          Delete a realm
  info            Show a realm
  list            List of realms
  update          Update a realm

```

```

Options:
  -h, --help      Print help

```

10.55.1. hammer realm create

Create a realm

```

Usage:
  hammer realm create [OPTIONS]

```

```

Options:
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-ids LOCATION_IDS   REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash

```

```

--location-title LOCATION_TITLE      Location title
--location-titles LOCATION_TITLES    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES           Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--name NAME                          The realm name, e.g. EXAMPLE.COM
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-ids ORGANIZATION_IDS    REPLACE organizations with given ids.
Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES    Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--realm-proxy-id REALM_PROXY_ID        Capsule ID to use within this realm
--realm-type REALM_TYPE                Realm type, e.g. Red Hat Identity Management or Active
Directory
-h, --help                            Print help

```

10.55.2. hammer realm delete

Delete a realm

```

Usage:
  hammer realm delete [OPTIONS]

Options:
--id ID                               Numerical ID or realm name
--location LOCATION_NAME              Location name
--location-id LOCATION_ID             Location ID
--location-title LOCATION_TITLE       Location title
--name NAME                           Name to search by
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help

```

10.55.3. hammer realm info

Show a realm

```

Usage:
  hammer realm info [OPTIONS]

Options:
--id ID                               Numerical ID or realm name
--location LOCATION_NAME              Location name
--location-id LOCATION_ID             Location ID
--location-title LOCATION_TITLE       Location title
--name NAME                           Name to search by
--organization ORGANIZATION_NAME      Organization name

```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help
```

10.55.4. hammer realm list

List of realms

```
Usage:
  hammer realm list [OPTIONS]
```

```
Options:
--location LOCATION_NAME          Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE    Location title
--order ORDER                      Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                        Paginate results
--per-page PER_PAGE                Number of entries per request
--search SEARCH                    Filter results
-h, --help                          Print help
```

10.55.5. hammer realm update

Update a realm

```
Usage:
  hammer realm update [OPTIONS]
```

```
Options:
--id ID
--location LOCATION_NAME          Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS        REPLACE locations with given ids
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--location-title LOCATION_TITLE    Location title
--location-titles LOCATION_TITLES  Comma separated list of values. Values containing comma
                                   should be quoted or escaped with backslash
--locations LOCATION_NAMES         Comma separated list of values. Values containing comma
                                   should be quoted or escaped with backslash
--name NAME                        Name to search by
--new-name NEW_NAME                The realm name, e.g. EXAMPLE.COM
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
```

```

comma should be quoted or escaped with backslash
--realm-proxy-id REALM_PROXY_ID      Capsule ID to use within this realm
--realm-type REALM_TYPE              Realm type, e.g. Red Hat Identity Management or Active
Directory
-h, --help                          Print help

```

10.56. HAMMER RECURRING-LOGIC

Recurring logic related actions

```

Usage:
  hammer recurring-logic [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  cancel              Cancel recurring logic
  info                Show recurring logic details
  list                List recurring logics

Options:
  -h, --help          Print help

```

10.56.1. hammer recurring-logic cancel

Cancel recurring logic

```

Usage:
  hammer recurring-logic cancel [OPTIONS]

Options:
  --id ID                ID of the recurring logic
  --location LOCATION_NAME Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME            Name to search by
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help            Print help

```

10.56.2. hammer recurring-logic info

Show recurring logic details

```

Usage:
  hammer recurring-logic info [OPTIONS]

Options:
  --id ID                ID of the recurring logic
  --location LOCATION_NAME Location name

```

```
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--name NAME                          Name to search by
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                          Print help
```

10.56.3. hammer recurring-logic list

List recurring logics

```
Usage:
  hammer recurring-logic list [OPTIONS]

Options:
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                   Paginate results
--per-page PER_PAGE           Number of entries per request
--search SEARCH               Filter results
-h, --help                    Print help
```

10.57. HAMMER REMOTE-EXECUTION-FEATURE

Manage remote execution features

```
Usage:
  hammer remote-execution-feature [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
SUBCOMMAND      Subcommand
[ARG] ...       Subcommand arguments

Subcommands:
info            Show remote execution feature
list           List remote execution features
update         Update a job template

Options:
-h, --help      Print help
```

10.57.1. hammer remote-execution-feature info

Show remote execution feature

```
Usage:
  hammer remote-execution-feature info [OPTIONS]
```


Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.57.2. hammer remote-execution-feature list

List remote execution features

Usage:

```
hammer remote-execution-feature list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.57.3. hammer remote-execution-feature update

Update a job template

Usage:

```
hammer remote-execution-feature update [OPTIONS]
```

Options:

```
--id ID
--job-template JOB_TEMPLATE_NAME Name to search by
--job-template-id JOB_TEMPLATE_ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--new-name NEW_NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.58. HAMMER REPORT

Browse and read reports

Usage:

hammer report [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

delete	Delete a report
info	Show a report
list	List all reports

Options:

-h, --help	Print help
------------	------------

10.58.1. hammer report delete

Delete a report

Usage:

hammer report delete [OPTIONS]

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.58.2. hammer report info

Show a report

Usage:

hammer report info [OPTIONS]

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.58.3. hammer report list

List all reports

Usage:

```
hammer report list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
-h, --help                     Print help
```

10.59. HAMMER REPORT-TEMPLATE

Manipulate report templates

Usage:

```
hammer report-template [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND      Subcommand
[ARG] ...        Subcommand arguments
```

Subcommands:

```
clone           Clone a template
create          Create a report template
delete          Delete a report template
dump            View report content
generate        Generate report
info            Show a report template
list            List all report templates
update          Update a report template
```

Options:

```
-h, --help      Print help
```

10.59.1. hammer report-template clone

Clone a template

Usage:

```
hammer report-template clone [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--new-name NEW_NAME
```

```
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                          Print help
```

10.59.2. hammer report-template create

Create a report template

Usage:

```
hammer report-template create [OPTIONS]
```

Options:

```
--audit-comment AUDIT_COMMENT
--default DEFAULT              Whether or not the template is added automatically to new
organizations and
                                Locations
                                One of true/false, yes/no, 1/0.
--file LAYOUT                  Path to a file that contains the report template content
--interactive, -i              Open empty template in an $EDITOR. Upload the result
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS    REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES     Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locked LOCKED                Whether or not the template is locked for editing
                                One of true/false, yes/no, 1/0.
--name NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--snippet SNIPPET              One of true/false, yes/no, 1/0.
-h, --help                      Print help
```

10.59.3. hammer report-template delete

Delete a report template

Usage:

```
hammer report-template delete [OPTIONS]
```

Options:

```

--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help

```

10.59.4. hammer report-template dump

View report content

```

Usage:
  hammer report-template dump [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help

```

10.59.5. hammer report-template generate

Generate report

```

Usage:
  hammer report-template generate [OPTIONS]

Options:
--id ID
--inputs INPUTS               Specify inputs
                               Comma-separated list of key=value
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--path PATH                   Path to directory where downloaded content will be saved
-h, --help                    Print help

```

10.59.6. hammer report-template info

Show a report template

Usage:

hammer report-template info [OPTIONS]

Options:

--id ID
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help Print help

10.59.7. hammer report-template list

List all report templates

Usage:

hammer report-template list [OPTIONS]

Options:

--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE Paginate results
--per-page PER_PAGE Number of entries per request
--search SEARCH Filter results
-h, --help Print help

10.59.8. hammer report-template update

Update a report template

Usage:

hammer report-template update [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT
--default DEFAULT Whether or not the template is added automatically to new organizations and
Locations
One of true/false, yes/no, 1/0.
--file REPORT Path to a file that contains the report template content
--id ID
--interactive, -i Dump existing template and open it in an \$EDITOR. Update with the result
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Name to search by

--new-name NEW_NAME

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--snippet SNIPPET One of true/false, yes/no, 1/0.

-h, --help Print help

10.60. HAMMER REPOSITORY

Manipulate repositories

Usage:

hammer repository [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

create	Create a custom repository
delete	Destroy a custom repository
export	Export content from a repository to the configured directory
info	Show a repository
list	List of enabled repositories
remove-content	Remove content from a repository
synchronize	Sync a repository
update	Update a repository
upload-content	Upload content into the repository

Options:

-h, --help	Print help
------------	------------

10.60.1. hammer repository create

Create a custom repository

Usage:

hammer repository create [OPTIONS]

Options:

<code>--checksum-type CHECKSUM_TYPE</code>	Checksum of the repository, currently 'sha1' & 'sha256'
<code>--content-type CONTENT_TYPE</code>	Are supported Type of repo (either 'yum', 'deb', 'puppet', 'docker', or 'ostree') Possible value(s): 'docker', 'file', 'ostree', 'puppet', 'yum'
<code>--deb-architectures DEB_ARCHITECTURES</code>	Comma separated list of architectures to be synched from deb-archive
<code>--deb-components DEB_COMPONENTS</code>	Comma separated list of repo components to be synched from deb-archive
<code>--deb-releases DEB_RELEASES</code>	Comma separated list of releases to be synched from deb-archive
<code>--docker-tags-whitelist DOCKER_TAGS_WHITELIST</code>	Comma separated list of tags to sync for Container Image repository
<code>--docker-upstream-name DOCKER_UPSTREAM_NAME</code>	Comma separated list of values. Values containing comma should be quoted or escaped with backslash Name of the upstream docker repository
<code>--download-policy DOWNLOAD_POLICY</code>	Download policy for yum repos (either 'immediate', 'on_demand', or 'background') Possible value(s): 'immediate', 'on_demand', 'background'
<code>--gpg-key GPG_KEY_NAME</code>	Name to search by
<code>--gpg-key-id GPG_KEY_ID</code>	Gpg key numeric identifier
<code>--ignorable-content IGNORABLE_CONTENT</code>	List of content units to ignore while syncing a yum repository. Must be Subset of rpm, drpm, srpm, distribution, erratum Comma separated list of values. Values containing comma should be quoted or escaped with backslash
<code>--ignore-global-proxy IGNORE_GLOBAL_PROXY</code>	If true, will ignore the globally configured Capsule when syncing
<code>--label LABEL</code>	One of true/false, yes/no, 1/0.
<code>--mirror-on-sync MIRROR_ON_SYNC</code>	True if this repository when synced has to be mirrored from the source and Stale rpms removed One of true/false, yes/no, 1/0.
<code>--name NAME</code>	
<code>--organization ORGANIZATION_NAME</code>	Organization name to search by
<code>--organization-id ORGANIZATION_ID</code>	Organization ID
<code>--organization-label ORGANIZATION_LABEL</code>	Organization label to search by
<code>--ostree-upstream-sync-depth OSTREE_UPSTREAM_SYNC_DEPTH</code>	If a custom sync policy is chosen for ostree repositories then a 'depth' value must be provided
<code>--ostree-upstream-sync-policy OSTREE_UPSTREAM_SYNC_POLICY</code>	Policies for syncing upstream ostree repositories Possible value(s): 'latest', 'all', 'custom'
<code>--product PRODUCT_NAME</code>	Product name to search by
<code>--product-id PRODUCT_ID</code>	Product numeric identifier
<code>--publish-via-http ENABLE</code>	Publish Via HTTP One of true/false, yes/no, 1/0.
<code>--ssl-ca-cert-id SSL_CA_CERT_ID</code>	Identifier of the SSL CA Cert
<code>--ssl-client-cert-id SSL_CLIENT_CERT_ID</code>	Identifier of the SSL Client Cert


```

--ssl-client-key-id SSL_CLIENT_KEY_ID      Identifier of the SSL Client Key
--upstream-password UPSTREAM_PASSWORD      Password of the upstream repository
user used for authentication
--upstream-username UPSTREAM_USERNAME      Username of the upstream repository
user used for authentication
--url URL                                  Repository source url
--verify-ssl-on-sync VERIFY_SSL_ON_SYNC    If true, Katello will verify the upstream url's
SSL certificates are
Signed by a trusted CA
One of true/false, yes/no, 1/0.
-h, --help                                Print help

```

10.60.2. hammer repository delete

Destroy a custom repository

```

Usage:
  hammer repository delete [OPTIONS]

Options:
--id ID                                Repository name to search by
--name NAME                            Organization name to search by
--organization ORGANIZATION_NAME      Organization ID to search by
--organization-id ORGANIZATION_ID     Organization label to search by
--organization-label ORGANIZATION_LABEL
--product PRODUCT_NAME                Product name to search by
--product-id PRODUCT_ID               Product numeric identifier
-h, --help                            Print help

```

10.60.3. hammer repository export

Export content from a repository to the configured directory

```

Usage:
  hammer repository export [OPTIONS]

Options:
--async                                Do not wait for the task
--export-to-iso EXPORT_TO_ISO          Export to ISO format
One of true/false, yes/no, 1/0.
--id ID                                Repository identifier
--iso-mb-size ISO_MB_SIZE              Maximum size of each ISO in MB
--name NAME                            Repository name to search by
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID     Organization ID to search by
--organization-label ORGANIZATION_LABEL
--product PRODUCT_NAME                Product name to search by
--product-id PRODUCT_ID               Product numeric identifier
--since SINCE                          Optional date of last export (ex: 2010-01-01T12:00:00Z)
-h, --help                            Print help

```

10.60.4. hammer repository info

Show a repository

Usage:

hammer repository info [OPTIONS]

Options:

--id ID	Repository ID
--name NAME	Repository name to search by
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--product PRODUCT_NAME	Product name to search by
--product-id PRODUCT_ID	Product numeric identifier
-h, --help	Print help

10.60.5. hammer repository list

List of enabled repositories

Usage:

hammer repository list [OPTIONS]

Options:

--available-for AVAILABLE_FOR	Interpret specified object to return only Repositories that can be
	Associated with specified object. Only 'content_view' & 'content_view_version' are supported.
--content-type CONTENT_TYPE	Limit to only repositories of this type
	Possible value(s): 'docker', 'file', 'ostree', 'puppet', 'yum'
--content-view CONTENT_VIEW_NAME	Content view name to search by
--content-view-id CONTENT_VIEW_ID	Content view numeric identifier
--content-view-version CONTENT_VIEW_VERSION_VERSION	Content view version number
--content-view-version-id CONTENT_VIEW_VERSION_ID	Content view version identifier
--deb DEB_NAME	Name to search by
--deb-id DEB_ID	A deb identifier
--description DESCRIPTION	Description of the repository
--environment ENVIRONMENT_NAME	Environment name
--environment-id ENVIRONMENT_ID	
--erratum-id ERRATUM_ID	Id of an erratum to find repositories that contain the erratum
--file-id FILE_ID	Id of a file to find repositories that contain the file
--full-result FULL_RESULT	Whether or not to show all results
	One of true/false, yes/no, 1/0.
--label LABEL	Label of the repository
--library LIBRARY	Show repositories in Library and the default content view
	One of true/false, yes/no, 1/0.
--name NAME	Name of the repository
--order ORDER	Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--ostree-branch OSTREE_BRANCH_NAME	Name to search by
--ostree-branch-id OSTREE_BRANCH_ID	An ostree branch identifier
--page PAGE	Page number, starting at 1
--per-page PER_PAGE	Number of results per page to return

```

--product PRODUCT_NAME      Product name to search by
--product-id PRODUCT_ID     Product numeric identifier
--rpm-id RPM_ID              Id of a rpm package to find repositories that contain the rpm
--search SEARCH              Search string
-h, --help                   Print help

```

10.60.6. hammer repository remove-content

Remove content from a repository

```

Usage:
  hammer repository remove-content [OPTIONS]

Options:
  --id ID                Repository ID
  --ids IDS              Array of content ids to remove
                        Comma separated list of values. Values containing comma should be
                        quoted or escaped with backslash
  --name NAME            Repository name to search by
  --organization ORGANIZATION_NAME Organization name to search by
  --organization-id ORGANIZATION_ID Organization ID to search by
  --organization-label ORGANIZATION_LABEL Organization label to search by
  --product PRODUCT_NAME Product name to search by
  --product-id PRODUCT_ID Product numeric identifier
  --sync-capsule SYNC_CAPSULE Whether or not to sync an external capsule after upload.
                        Default: true
                        One of true/false, yes/no, 1/0.
  -h, --help            Print help

```

10.60.7. hammer repository synchronize

Sync a repository

```

Usage:
  hammer repository synchronize [OPTIONS]

Options:
  --async                Do not wait for the task
  --id ID                Repository ID
  --incremental INCREMENTAL Perform an incremental import
                        One of true/false, yes/no, 1/0.
  --name NAME            Repository name to search by
  --organization ORGANIZATION_NAME Organization name to search by
  --organization-id ORGANIZATION_ID Organization ID
  --organization-label ORGANIZATION_LABEL Organization label to search by
  --product PRODUCT_NAME Product name to search by
  --product-id PRODUCT_ID Product numeric identifier
  --skip-metadata-check SKIP_METADATA_CHECK Force sync even if no upstream changes are
                        detected. Only used with yum
                        Repositories.
                        One of true/false, yes/no, 1/0.
  --source-url SOURCE_URL Temporarily override feed URL for sync
  --validate-contents VALIDATE_CONTENTS Force a sync and validate the checksums of all
                        content. Only used with yum

```

-h, --help	Repositories. One of true/false, yes/no, 1/0. Print help
------------	----------------------------------------------------------------

10.60.8. hammer repository update

Update a repository

Usage:

hammer repository update [OPTIONS]

Options:

--checksum-type CHECKSUM_TYPE	Checksum of the repository, currently 'sha1' & 'sha256'
--deb-architectures DEB_ARCHITECTURES	Are supported Comma separated list of architectures to be synched from deb-archive
--deb-components DEB_COMPONENTS	Comma separated list of repo components to be synched from deb-archive
--deb-releases DEB_RELEASES	Comma separated list of releases to be synched from deb-archive
--docker-digest DIGEST	Container Image manifest digest
--docker-tag TAG	Container Image tag
--docker-tags-whitelist DOCKER_TAGS_WHITELIST	Comma separated list of tags to sync for Container Image repository
--docker-upstream-name DOCKER_UPSTREAM_NAME	Comma separated list of values. Values containing comma should be quoted or escaped with backslash Name of the upstream docker repository
--download-policy DOWNLOAD_POLICY	Download policy for yum repos (either 'immediate', 'on_demand', or 'background') Possible value(s): 'immediate', 'on_demand', 'background'
--gpg-key GPG_KEY_NAME	Name to search by
--gpg-key-id GPG_KEY_ID	Gpg key numeric identifier
--id ID	Repository ID
--ignorable-content IGNORABLE_CONTENT	List of content units to ignore while syncing a yum repository. Must be Subset of rpm,drpm,srpm,distribution,erratum Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--ignore-global-proxy IGNORE_GLOBAL_PROXY	If true, will ignore the globally configured Capsule when syncing
--mirror-on-sync MIRROR_ON_SYNC	One of true/false, yes/no, 1/0. True if this repository when synced has to be mirrored from the source and Stale rpms removed
--name NAME	One of true/false, yes/no, 1/0. Repository name to search by
--new-name NEW_NAME	
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID to search by
--organization-label ORGANIZATION_LABEL	Organization label to search by
--ostree-upstream-sync-depth OSTREE_UPSTREAM_SYNC_DEPTH	If a custom sync policy is chosen for ostree repositories then a

```

                                'depth' value must be provided
--ostree-upstream-sync-policy OSTREE_UPSTREAM_SYNC_POLICY Policies for syncing upstream
ostree repositories
                                Possible value(s): 'latest', 'all', 'custom'
--product PRODUCT_NAME          Product name to search by
--product-id PRODUCT_ID         Product numeric identifier
--publish-via-http ENABLE       Publish Via HTTP
                                One of true/false, yes/no, 1/0.
--ssl-ca-cert-id SSL_CA_CERT_ID Identifier of the SSL CA Cert
--ssl-client-cert-id SSL_CLIENT_CERT_ID Identifier of the SSL Client Cert
--ssl-client-key-id SSL_CLIENT_KEY_ID Identifier of the SSL Client Key
--upstream-password UPSTREAM_PASSWORD Password of the upstream repository
user used for authentication
--upstream-username UPSTREAM_USERNAME Username of the upstream repository
user used for authentication
--url URL                      Repository source url
--verify-ssl-on-sync VERIFY_SSL_ON_SYNC If true, Katello will verify the upstream url's
SSL certificates are
                                Signed by a trusted CA
                                One of true/false, yes/no, 1/0.
-h, --help                    Print help

```

10.60.9. hammer repository upload-content

Upload content into the repository

```

Usage:
  hammer repository upload-content [OPTIONS]

Options:
  --id ID                Repository ID
  --name NAME            Repository name to search by
  --organization ORGANIZATION_NAME Organization name to search by
  --organization-id ORGANIZATION_ID Organization ID
  --organization-label ORGANIZATION_LABEL Organization label to search by
  --path PATH            Upload file, directory of files, or glob of files as content for a
repository.
                        Globs must be escaped by single or double quotes
  --product PRODUCT_NAME Product name to search by
  --product-id PRODUCT_ID Product numeric identifier
-h, --help              Print help

```

10.61. HAMMER REPOSITORY-SET

Manipulate repository sets on the server

```

Usage:
  hammer repository-set [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:

```

available-repositories	Get list of available repositories for the repository set
disable	Disable a repository from the set
enable	Enable a repository from the set
info	Get info about a repository set
list	List repository sets.

Options:

-h, --help	Print help
------------	------------

10.61.1. hammer repository-set available-repositories

Get list of available repositories for the repository set

Usage:

hammer repository-set available-repositories [OPTIONS]

Options:

--id ID	ID of the repository set
--name NAME	Repository set name to search by
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--product PRODUCT_NAME	Product name to search by
--product-id PRODUCT_ID	Product numeric identifier
-h, --help	Print help

10.61.2. hammer repository-set disable

Disable a repository from the set

Usage:

hammer repository-set disable [OPTIONS]

Options:

--basearch BASEARCH	Basearch to disable
--id ID	ID of the repository set to disable
--name NAME	Repository set name to search by
--organization ORGANIZATION_NAME	Organization name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-label ORGANIZATION_LABEL	Organization label to search by
--product PRODUCT_NAME	Product name to search by
--product-id PRODUCT_ID	Product numeric identifier
--releasever RELEASEVER	Releasever to disable
-h, --help	Print help

10.61.3. hammer repository-set enable

Enable a repository from the set

Usage:

hammer repository-set enable [OPTIONS]

Options:

```

--basearch BASEARCH          Basearch to enable
--id ID                      ID of the repository set to enable
--name NAME                  Repository set name to search by
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--product PRODUCT_NAME       Product name to search by
--product-id PRODUCT_ID       Product numeric identifier
--releasever RELEASEVER       Releasever to enable
-h, --help                   Print help

```

10.61.4. hammer repository-set info

Get info about a repository set

Usage:
hammer repository-set info [OPTIONS]

Options:

```

--id ID                      ID of the repository set
--name NAME                  Repository set name to search by
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--product PRODUCT_NAME       Product name to search by
--product-id PRODUCT_ID       Product numeric identifier
-h, --help                   Print help

```

10.61.5. hammer repository-set list

List repository sets.

Usage:
hammer repository-set list [OPTIONS]

Options:

```

--enabled ENABLED           If true, only return repository sets that have been enabled.

```

Defaults to

```

False
One of true/false, yes/no, 1/0.
--full-result FULL_RESULT   Whether or not to show all results
                             One of true/false, yes/no, 1/0.
--name NAME                 Repository set name to search on
--order ORDER               Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--page PAGE                 Page number, starting at 1
--per-page PER_PAGE         Number of results per page to return
--product PRODUCT_NAME       Product name to search by
--product-id PRODUCT_ID       Product numeric identifier
--search SEARCH              Search string
--with-active-subscription WITH_ACTIVE_SUBSCRIPTION If true, only return repository sets that are
associated with an active

```

-h, --help

Subscriptions
 One of true/false, yes/no, 1/0.
 Print help

10.62. HAMMER ROLE

Manage user roles

Usage:

hammer role [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

clone	Clone a role
create	Create a role
delete	Delete a role
filters	List all filters
info	Show a role
list	List all roles
update	Update a role

Options:

-h, --help	Print help
-------------------	------------

10.62.1. hammer role clone

Clone a role

Usage:

hammer role clone [OPTIONS]

Options:

--description DESCRIPTION	Role description
--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-ids LOCATION_IDS	REPLACE locations with given ids Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--location-title LOCATION_TITLE	Location title
--location-titles LOCATION_TITLES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--locations LOCATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--name NAME	User role name
--new-name NEW_NAME	
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-ids ORGANIZATION_IDS	REPLACE organizations with given ids. Comma separated list of values. Values containing comma should be quoted or escaped with backslash


```
--organization-title ORGANIZATION_TITLE  Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES      Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
-h, --help                               Print help
```

10.62.2. hammer role create

Create a role

Usage:

```
hammer role create [OPTIONS]
```

Options:

```
--description DESCRIPTION      Role description
--location LOCATION_NAME       Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS    REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES     Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--name NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
-h, --help                     Print help
```

10.62.3. hammer role delete

Delete a role

Usage:

```
hammer role delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   User role name
--organization ORGANIZATION_NAME Organization name
```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                            Print help
```

10.62.4. hammer role filters

List all filters

```
Usage:
  hammer role filters [OPTIONS]

Options:
  --id ID                User role id
  --location LOCATION_NAME    Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE    Location title
  --name NAME              User role name
  --order ORDER            Sort field and order, eg. 'id DESC'
  --organization ORGANIZATION_NAME    Organization name
  --organization-id ORGANIZATION_ID    Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --page PAGE              Paginate results
  --per-page PER_PAGE      Number of entries per request
  -h, --help                Print help
```

10.62.5. hammer role info

Show a role

```
Usage:
  hammer role info [OPTIONS]

Options:
  --description DESCRIPTION
  --id ID
  --location LOCATION_NAME    Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE    Location title
  --name NAME                User role name
  --organization ORGANIZATION_NAME    Organization name
  --organization-id ORGANIZATION_ID    Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                Print help
```

10.62.6. hammer role list

List all roles

```
Usage:
  hammer role list [OPTIONS]

Options:
  --location LOCATION_NAME    Location name
```

```
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                  Number of entries per request
--search SEARCH                      Filter results
-h, --help                          Print help
```

10.62.7. hammer role update

Update a role

Usage:

```
hammer role update [OPTIONS]
```

Options:

```
--description DESCRIPTION      Role description
--id ID
--location LOCATION_NAME       Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS    REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
                                should be quoted or escaped with backslash
--locations LOCATION_NAMES     Comma separated list of values. Values containing comma
                                should be quoted or escaped with backslash
--name NAME                    User role name
--new-name NEW_NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
                                comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
                                comma should be quoted or escaped with backslash
-h, --help                    Print help
```

10.63. HAMMER SC-PARAM

Manipulate smart class parameters

Usage:

```
hammer sc-param [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
```

```
[ARG] ...          Subcommand arguments

Subcommands:
add-matcher        Create an override value for a specific smart variable
info              Show a smart class parameter
list              List all smart class parameters
remove-matcher     Delete an override value for a specific smart variable
update            Update a smart class parameter

Options:
-h, --help        Print help
```

10.63.1. hammer sc-param add-matcher

Create an override value for a specific smart variable

```
Usage:
  hammer sc-param add-matcher [OPTIONS]

Options:
--location LOCATION_NAME          Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE   Location title
--match MATCH                     Override match
--omit OMIT                       Satellite will not send this parameter in classification output,
replaces
                                Use_puppet_default
                                One of true/false, yes/no, 1/0.
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
--puppet-class PUPPET_CLASS_NAME   Puppet class name
--puppet-class-id PUPPET_CLASS_ID   ID of Puppet class
--smart-class-parameter SMART_CLASS_PARAMETER_NAME Smart class parameter name
--smart-class-parameter-id SMART_CLASS_PARAMETER_ID
--use-puppet-default USE_PUPPET_DEFAULT  Deprecated, please use omit
                                One of true/false, yes/no, 1/0.
--value VALUE                     Override value, required if omit is false
-h, --help                       Print help
```

10.63.2. hammer sc-param info

Show a smart class parameter

```
Usage:
  hammer sc-param info [OPTIONS]

Options:
--id ID
--location LOCATION_NAME          Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE   Location title
--name NAME                      Smart class parameter name
--organization ORGANIZATION_NAME  Organization name
```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--puppet-class PUPPET_CLASS_NAME      Puppet class name
--puppet-class-id PUPPET_CLASS_ID      ID of Puppet class
--show-hidden SHOW_HIDDEN              Display hidden values
                                      One of true/false, yes/no, 1/0.
-h, --help                            Print help
```

10.63.3. hammer sc-param list

List all smart class parameters

Usage:

```
hammer sc-param list [OPTIONS]
```

Options:

```
--environment ENVIRONMENT_NAME      Environment name
--environment-id ENVIRONMENT_ID
--host HOST_NAME                      Host name
--host-id HOST_ID
--hostgroup HOSTGROUP_NAME           Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE    Hostgroup title
--location LOCATION_NAME             Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                  Number of entries per request
--puppet-class PUPPET_CLASS_NAME      Puppet class name
--puppet-class-id PUPPET_CLASS_ID     ID of Puppet class
--search SEARCH                      Filter results
--show-hidden SHOW_HIDDEN            Display hidden values
                                      One of true/false, yes/no, 1/0.
-h, --help                          Print help
```

10.63.4. hammer sc-param remove-matcher

Delete an override value for a specific smart variable

Usage:

```
hammer sc-param remove-matcher [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME             Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
```

```

--puppet-class PUPPET_CLASS_NAME      Puppet class name
--puppet-class-id PUPPET_CLASS_ID      ID of Puppet class
--smart-class-parameter SMART_CLASS_PARAMETER_NAME Smart class parameter name
--smart-class-parameter-id SMART_CLASS_PARAMETER_ID
-h, --help                             Print help

```

10.63.5. hammer sc-param update

Update a smart class parameter

Usage:

```
hammer sc-param update [OPTIONS]
```

Options:

```

--avoid-duplicates AVOID_DUPLICATES      Remove duplicate values (only array type)
                                         One of true/false, yes/no, 1/0.
--default-value VALUE                     Value to use when there is no match
--description DESCRIPTION                 Description of smart class
--hidden-value HIDDEN_VALUE               When enabled the parameter is hidden in the UI
                                         One of true/false, yes/no, 1/0.
--id ID
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE            Location title
--merge-default MERGE_DEFAULT             Include default value when merging all matching values
                                         One of true/false, yes/no, 1/0.
--merge-overrides MERGE_OVERRIDES         Merge all matching values (only array/hash type)
                                         One of true/false, yes/no, 1/0.
--name NAME                               Smart class parameter name
--omit OMIT                               Satellite will not send this parameter in classification output. Puppet
                                         Will use the value defined in the Puppet manifest for this parameter
                                         One of true/false, yes/no, 1/0.
--organization ORGANIZATION_NAME          Organization name
--organization-id ORGANIZATION_ID          Organization ID
--organization-title ORGANIZATION_TITLE    Organization title
--override OVERRIDE                       Override this parameter
                                         One of true/false, yes/no, 1/0.
--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved
                                         Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--parameter-type PARAMETER_TYPE           Type of the parameter
                                         Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',
'json'
--path PATH                               The order in which values are resolved
--puppet-class PUPPET_CLASS_NAME           Puppet class name
--puppet-class-id PUPPET_CLASS_ID          ID of Puppet class
--required REQUIRED                         This parameter is required
                                         One of true/false, yes/no, 1/0.
--use-puppet-default USE_PUPPET_DEFAULT    Deprecated, please use omit
                                         One of true/false, yes/no, 1/0.
--validator-rule VALIDATOR_RULE            Used to enforce certain values for the parameter values
--validator-type VALIDATOR_TYPE            Type of the validator
                                         Possible value(s): 'regex', 'list', "
-h, --help                             Print help

```

10.64. HAMMER SCAP-CONTENT

Manipulate SCAP contents

Usage:

```
hammer scap-content [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

create	Create SCAP content
delete	Deletes an SCAP content
download	Download an SCAP content as XML
info	Show an SCAP content
list	List SCAP contents
update	Update an SCAP content

Options:

-h, --help	Print help
------------	------------

10.64.1. hammer scap-content create

Create SCAP content

Usage:

```
hammer scap-content create [OPTIONS]
```

Options:

--location LOCATION_NAME	Name to search by
--location-id LOCATION_ID	
--location-ids LOCATION_IDS	REPLACE locations with given ids
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--locations LOCATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--organization ORGANIZATION_NAME	Name to search by
--organization-id ORGANIZATION_ID	Organization ID
--organization-ids ORGANIZATION_IDS	REPLACE organizations with given ids.
	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES	Comma separated list of values. Values containing comma should be quoted or escaped with backslash
--original-filename ORIGINAL_FILENAME	Original file name of the XML file
--scap-file SCAP_FILE	SCAP content file
--title TITLE	SCAP content name
-h, --help	Print help

10.64.2. hammer scap-content delete

Deletes an SCAP content

Usage:

```
hammer scap-content delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Name to search by
--location-id LOCATION_ID
--organization ORGANIZATION_NAME Name to search by
--organization-id ORGANIZATION_ID Organization ID
--title TITLE                 SCAP content title
-h, --help                   Print help
```

10.64.3. hammer scap-content download

Download an SCAP content as XML

Usage:

```
hammer scap-content download [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Name to search by
--location-id LOCATION_ID
--organization ORGANIZATION_NAME Name to search by
--organization-id ORGANIZATION_ID Organization ID
--path PATH                   Path to directory where downloaded file will be saved
--title TITLE                 SCAP content title
-h, --help                   Print help
```

10.64.4. hammer scap-content info

Show an SCAP content

Usage:

```
hammer scap-content info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Name to search by
--location-id LOCATION_ID
--organization ORGANIZATION_NAME Name to search by
--organization-id ORGANIZATION_ID Organization ID
--title TITLE                 SCAP content title
-h, --help                   Print help
```

10.64.5. hammer scap-content list

List SCAP contents

Usage:

```
hammer scap-content list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
```



```

--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--order ORDER                        Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                          Paginate results
--per-page PER_PAGE                  Number of entries per request
--search SEARCH                      Filter results
-h, --help                          Print help

```

10.64.6. hammer scap-content update

Update an SCAP content

Usage:

```
hammer scap-content update [OPTIONS]
```

Options:

```

--id ID
--location LOCATION_NAME      Name to search by
--location-id LOCATION_ID
--location-ids LOCATION_IDS   REPLACE locations with given ids
                               Comma separated list of values. Values containing comma should be quoted
                               or escaped with backslash
--locations LOCATION_NAMES    Comma separated list of values. Values containing comma
                               should be quoted or escaped with backslash
--new-title NEW_TITLE         SCAP content name
--organization ORGANIZATION_NAME Name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                               Comma separated list of values. Values containing comma should be quoted
                               or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
                               comma should be quoted or escaped with backslash
--original-filename ORIGINAL_FILENAME Original file name of the XML file
--scap-file SCAP_FILE         SCAP content file
--title TITLE                 SCAP content title
-h, --help                    Print help

```

10.65. HAMMER SETTINGS

Change server settings

Usage:

```
hammer settings [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```

SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments

```

Subcommands:

```

list                List all settings
set                 Update a setting

```

Options:
-h, --help Print help

10.65.1. hammer settings list

List all settings

Usage:
 hammer settings list [OPTIONS]

Options:

--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--order ORDER	Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--page PAGE	Paginate results
--per-page PER_PAGE	Number of entries per request
--search SEARCH	Filter results
-h, --help	Print help

10.65.2. hammer settings set

Update a setting

Usage:
 hammer settings set [OPTIONS]

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Setting name
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--value VALUE	
-h, --help	Print help

10.66. HAMMER SHELL

Interactive shell

Usage:
 hammer shell [OPTIONS]

Options:

-h, --help	Print help
------------	------------

10.67. HAMMER SMART-VARIABLE

Manipulate smart variables

Usage:

```
hammer smart-variable [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

add-matcher	Create an override value for a specific smart variable
create	Create a smart variable
delete	Delete a smart variable
info	Show a smart variable
list	List all smart variables
remove-matcher	Delete an override value for a specific smart variable
update	Update a smart variable

Options:

-h, --help	Print help
------------	------------

10.67.1. hammer smart-variable add-matcher

Create an override value for a specific smart variable

Usage:

```
hammer smart-variable add-matcher [OPTIONS]
```

Options:

--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--match MATCH	Override match
--omit OMIT	Satellite will not send this parameter in classification output, replaces Use_puppet_default
	One of true/false, yes/no, 1/0.
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--smart-variable SMART_VARIABLE_VARIABLE	Smart variable name
--smart-variable-id SMART_VARIABLE_ID	
--use-puppet-default USE_PUPPET_DEFAULT	Deprecated, please use omit
	One of true/false, yes/no, 1/0.
--value VALUE	Override value, required if omit is false
-h, --help	Print help

10.67.2. hammer smart-variable create

Create a smart variable

Usage:

```
hammer smart-variable create [OPTIONS]
```

Options:

```

--avoid-duplicates AVOID_DUPLICATES      Remove duplicate values (only array type)
                                           One of true/false, yes/no, 1/0.
--default-value VALUE                     Value to use when there is no match
--description DESCRIPTION                 Description of variable
--hidden-value HIDDEN_VALUE              When enabled the parameter is hidden in the UI
                                           One of true/false, yes/no, 1/0.
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID                 Location ID
--location-title LOCATION_TITLE           Location title
--merge-default MERGE_DEFAULT             Include default value when merging all matching values
                                           One of true/false, yes/no, 1/0.
--merge-overrides MERGE_OVERRIDES         Merge all matching values (only array/hash type)
                                           One of true/false, yes/no, 1/0.
--organization ORGANIZATION_NAME          Organization name
--organization-id ORGANIZATION_ID          Organization ID
--organization-title ORGANIZATION_TITLE    Organization title
--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved
                                           Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--puppet-class PUPPET_CLASS_NAME           Puppet class name
--puppet-class-id PUPPET_CLASS_ID           ID of Puppet class
--validator-rule VALIDATOR_RULE            Used to enforce certain values for the parameter values
--validator-type VALIDATOR_TYPE            Type of the validator
                                           Possible value(s): 'regexp', 'list', "
--variable VARIABLE                       Name of variable
--variable-type VARIABLE_TYPE              Type of the variable
                                           Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',
'json'
-h, --help                                Print help

```

10.67.3. hammer smart-variable delete

Delete a smart variable

Usage:

```
hammer smart-variable delete [OPTIONS]
```

Options:

```

--id ID
--location LOCATION_NAME                  Location name
--location-id LOCATION_ID                 Location ID
--location-title LOCATION_TITLE           Location title
--name NAME                              Smart variable name (Deprecated: Use --variable instead)
--organization ORGANIZATION_NAME          Organization name
--organization-id ORGANIZATION_ID          Organization ID
--organization-title ORGANIZATION_TITLE    Organization title
--variable VARIABLE                       Smart variable name
-h, --help                                Print help

```

10.67.4. hammer smart-variable info

Show a smart variable

-

Usage:

```
hammer smart-variable info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Smart variable name (Deprecated: Use --variable instead)
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--show-hidden SHOW_HIDDEN     Display hidden values
                                One of true/false, yes/no, 1/0.
--variable VARIABLE           Smart variable name
-h, --help                    Print help
```

10.67.5. hammer smart-variable list

List all smart variables

Usage:

```
hammer smart-variable list [OPTIONS]
```

Options:

```
--host HOST_NAME              Host name
--host-id HOST_ID
--hostgroup HOSTGROUP_NAME    Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                   Paginate results
--per-page PER_PAGE           Number of entries per request
--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET_CLASS_ID ID of Puppet class
--search SEARCH               Filter results
--show-hidden SHOW_HIDDEN     Display hidden values
                                One of true/false, yes/no, 1/0.
-h, --help                    Print help
```

10.67.6. hammer smart-variable remove-matcher

Delete an override value for a specific smart variable

Usage:

```
hammer smart-variable remove-matcher [OPTIONS]
```

Options:

```

--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--smart-variable SMART_VARIABLE_VARIABLE Smart variable name
--smart-variable-id SMART_VARIABLE_ID
-h, --help                    Print help

```

10.67.7. hammer smart-variable update

Update a smart variable

Usage:

```
hammer smart-variable update [OPTIONS]
```

Options:

```

--avoid-duplicates AVOID_DUPLICATES      Remove duplicate values (only array type)
                                          One of true/false, yes/no, 1/0.
--default-value VALUE                    Value to use when there is no match
--description DESCRIPTION                Description of variable
--hidden-value HIDDEN_VALUE              When enabled the parameter is hidden in the UI
                                          One of true/false, yes/no, 1/0.
--id ID
--location LOCATION_NAME                Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE          Location title
--merge-default MERGE_DEFAULT            Include default value when merging all matching values
                                          One of true/false, yes/no, 1/0.
--merge-overrides MERGE_OVERRIDES        Merge all matching values (only array/hash type)
                                          One of true/false, yes/no, 1/0.
--new-variable NEW_VARIABLE              Name of variable
--organization ORGANIZATION_NAME          Organization name
--organization-id ORGANIZATION_ID         Organization ID
--organization-title ORGANIZATION_TITLE   Organization title
--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved
                                          Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--puppet-class PUPPET_CLASS_NAME          Puppet class name
--puppet-class-id PUPPET_CLASS_ID          ID of Puppet class
--validator-rule VALIDATOR_RULE            Used to enforce certain values for the parameter values
--validator-type VALIDATOR_TYPE            Type of the validator
                                          Possible value(s): 'regex', 'list', "
--variable VARIABLE                      Smart variable name
--variable-type VARIABLE_TYPE              Type of the variable
                                          Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',
'json'
-h, --help                                Print help

```

10.68. HAMMER SUBNET

Manipulate subnets

Usage:

```
hammer subnet [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments
```

Subcommands:

```
create              Create a subnet
delete             Delete a subnet
delete-parameter    Delete parameter for a subnet
info               Show a subnet
list               List of subnets
set-parameter       Create or update parameter for a subnet
update             Update a subnet
```

Options:

```
-h, --help          Print help
```

10.68.1. hammer subnet create

Create a subnet

Usage:

```
hammer subnet create [OPTIONS]
```

Options:

```
--boot-mode BOOT_MODE          Default boot mode for interfaces assigned to this subnet,
valid values are
                                "Static", "DHCP"
--description DESCRIPTION      Subnet description
--dhcp DHCP_NAME                DHCP Proxy to use within this subnet
--dhcp-id DHCP_ID              DHCP Capsule ID to use within this subnet
--discovery-id DISCOVERY_ID    ID of Discovery Capsule to use within this subnet for
managing connection
                                To discovered hosts
--dns DNS_NAME                  DNS Proxy to use within this subnet
--dns-id DNS_ID                 DNS Capsule ID to use within this subnet
--dns-primary DNS_PRIMARY      Primary DNS for this subnet
--dns-secondary DNS_SECONDARY  Secondary DNS for this subnet
--domain-ids DOMAIN_IDS        Domains in which this subnet is part
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--domains DOMAIN_NAMES          Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--from FROM                     Starting IP Address for IP auto suggestion
--gateway GATEWAY               Subnet gateway
--httpboot-id HTTPBOOT_ID       HTTPBoot Capsule ID to use within this subnet
--ipam IPAM                     IP Address auto suggestion mode for this subnet, valid values are
"DHCP",
                                "Internal DB", "None"
--location LOCATION_NAME        Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS     REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
```

```

quoted or escaped with backslash
--location-title LOCATION_TITLE      Location title
--location-titles LOCATION_TITLES    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES           Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--mask MASK                          Netmask for this subnet
--mtu MTU                            MTU for this subnet
--name NAME                          Subnet name
--network NETWORK                    Subnet network
--network-type NETWORK_TYPE           Type or protocol, IPv4 or IPv6, defaults to IPv4
Possible value(s): 'IPv4', 'IPv6'
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-ids ORGANIZATION_IDS    REPLACE organizations with given ids.
Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES    Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--template-id TEMPLATE_ID             Template HTTP(S) Capsule ID to use within this subnet
--tftp TFTP_NAME                      TFTP Proxy to use within this subnet
--tftp-id TFTP_ID                     TFTP Capsule ID to use within this subnet
--to TO                              Ending IP Address for IP auto suggestion
--vlanid VLANID                      VLAN ID for this subnet
-h, --help                            Print help

```

10.68.2. hammer subnet delete

Delete a subnet

```

Usage:
  hammer subnet delete [OPTIONS]

Options:
  --id ID                Subnet numeric identifier
  --location LOCATION_NAME Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME            Subnet name
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help            Print help

```

10.68.3. hammer subnet delete-parameter

Delete parameter for a subnet

```

Usage:
  hammer subnet delete-parameter [OPTIONS]

```


Options:

```
--name NAME           Parameter name
--subnet SUBNET_NAME   Subnet name
--subnet-id SUBNET_ID
-h, --help             Print help
```

10.68.4. hammer subnet info

Show a subnet

Usage:

```
hammer subnet info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Subnet name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values
                                     One of true/false, yes/no, 1/0.
-h, --help                   Print help
```

10.68.5. hammer subnet list

List of subnets

Usage:

```
hammer subnet list [OPTIONS]
```

Options:

```
--domain DOMAIN_NAME      Domain name
--domain-id DOMAIN_ID      Numerical ID or domain name
--location LOCATION_NAME   Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER              Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                Paginate results
--per-page PER_PAGE        Number of entries per request
--search SEARCH            Filter results
-h, --help                 Print help
```

10.68.6. hammer subnet set-parameter

Create or update parameter for a subnet

Usage:

```
hammer subnet set-parameter [OPTIONS]
```

Options:

```
--hidden-value HIDDEN_VALUE  Should the value be hidden
                                One of true/false, yes/no, 1/0.
--name NAME                    Parameter name
--subnet SUBNET_NAME           Subnet name
--subnet-id SUBNET_ID
--value VALUE                  Parameter value
-h, --help                     Print help
```

10.68.7. hammer subnet update

Update a subnet

Usage:

```
hammer subnet update [OPTIONS]
```

Options:

```
--boot-mode BOOT_MODE          Default boot mode for interfaces assigned to this subnet,
valid values are
                                "Static", "DHCP"
--description DESCRIPTION       Subnet description
--dhcp DHCP_NAME                DHCP Proxy to use within this subnet
--dhcp-id DHCP_ID               DHCP Capsule ID to use within this subnet
--discovery-id DISCOVERY_ID     ID of Discovery Capsule to use within this subnet for
managing connection
                                To discovered hosts
--dns DNS_NAME                  DNS Proxy to use within this subnet
--dns-id DNS_ID                 DNS Capsule ID to use within this subnet
--dns-primary DNS_PRIMARY       Primary DNS for this subnet
--dns-secondary DNS_SECONDARY   Secondary DNS for this subnet
--domain-ids DOMAIN_IDS         Domains in which this subnet is part
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--domains DOMAIN_NAMES          Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--from FROM                     Starting IP Address for IP auto suggestion
--gateway GATEWAY               Subnet gateway
--httpboot-id HTTPBOOT_ID       HTTPBoot Capsule ID to use within this subnet
--id ID                          Subnet numeric identifier
--ipam IPAM                     IP Address auto suggestion mode for this subnet, valid values are
"DHCP",
                                "Internal DB", "None"
--location LOCATION_NAME        Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS     REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES      Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--mask MASK                     Netmask for this subnet
```

```

--mtu MTU                MTU for this subnet
--name NAME              Subnet name
--network NETWORK        Subnet network
--network-type NETWORK_TYPE  Type or protocol, IPv4 or IPv6, defaults to IPv4
                          Possible value(s): 'IPv4', 'IPv6'
--new-name NEW_NAME      Subnet name
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-ids ORGANIZATION_IDS  REPLACE organizations with given ids.
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE  Organization title
--organization-titles ORGANIZATION_TITLES  Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES  Comma separated list of values. Values containing
                                   comma should be quoted or escaped with backslash
--template-id TEMPLATE_ID  Template HTTP(S) Capsule ID to use within this subnet
--tftp TFTP_NAME           TFTP Proxy to use within this subnet
--tftp-id TFTP_ID          TFTP Capsule ID to use within this subnet
--to TO                   Ending IP Address for IP auto suggestion
--vlanid VLANID           VLAN ID for this subnet
-h, --help                Print help

```

10.69. HAMMER SUBSCRIPTION

Manipulate subscriptions

Usage:

```
hammer subscription [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```

SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments

```

Subcommands:

```

delete-manifest      Delete manifest from Red Hat provider
list                 List organization subscriptions
manifest-history      Obtain manifest history for subscriptions
refresh-manifest      Refresh previously imported manifest for Red Hat provider
upload               Upload a subscription manifest

```

Options:

```
-h, --help          Print help
```

10.69.1. hammer subscription delete-manifest

Delete manifest from Red Hat provider

Usage:

```
hammer subscription delete-manifest [OPTIONS]
```

Options:

```

--async              Do not wait for the task
--organization ORGANIZATION_NAME  Organization name to search by

```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                            Print help
```

10.69.2. hammer subscription list

List organization subscriptions

Usage:

```
hammer subscription list [OPTIONS]
```

Options:

```
--activation-key ACTIVATION_KEY_NAME  Activation key name to search by
--activation-key-id ACTIVATION_KEY_ID  ID of the activation key
--available-for AVAILABLE_FOR          Object to show subscriptions available for, either 'host' or
                                       'activation_key'
--full-result FULL_RESULT              Whether or not to show all results
                                       One of true/false, yes/no, 1/0.
--host HOST_NAME                      Host name
--host-id HOST_ID
--match-host MATCH_HOST               Ignore subscriptions that are unavailable to the specified host
                                       One of true/false, yes/no, 1/0.
--match-installed MATCH_INSTALLED      Return subscriptions that match installed products of the
specified host
                                       One of true/false, yes/no, 1/0.
--no-overlap NO_OVERLAP               Return subscriptions which do not overlap with a currently-
attached
                                       Subscription
                                       One of true/false, yes/no, 1/0.
--order ORDER                         Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID     Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--page PAGE                           Page number, starting at 1
--per-page PER_PAGE                   Number of results per page to return
--search SEARCH                       Search string
-h, --help                            Print help
```

10.69.3. hammer subscription manifest-history

obtain manifest history for subscriptions

Usage:

```
hammer subscription manifest-history [OPTIONS]
```

Options:

```
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID     Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                            Print help
```

10.69.4. hammer subscription refresh-manifest

Refresh previously imported manifest for Red Hat provider

Usage:

hammer subscription refresh-manifest [OPTIONS]

Options:

--async Do not wait for the task
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 -h, --help Print help

10.69.5. hammer subscription upload

Upload a subscription manifest

Usage:

hammer subscription upload [OPTIONS]

Options:

--async Do not wait for the task
 --file MANIFEST Subscription manifest file
 --organization ORGANIZATION_NAME Organization name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --organization-label ORGANIZATION_LABEL Organization label to search by
 --repository-url REPOSITORY_URL Repository url
 -h, --help Print help

10.70. HAMMER SYNC-PLAN

Manipulate sync plans

Usage:

hammer sync-plan [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand
 [ARG] ... Subcommand arguments

Subcommands:

create Create a sync plan
 delete Destroy a sync plan
 info Show a sync plan
 list List sync plans
 update Update a sync plan

Options:

-h, --help Print help

10.70.1. hammer sync-plan create

Create a sync plan

Usage:

```
hammer sync-plan create [OPTIONS]
```

Options:

```
--cron-expression CRON_EXPRESSION    Set this when interval is custom cron
--description DESCRIPTION              Sync plan description
--enabled ENABLED                     Enables or disables synchronization
                                      One of true/false, yes/no, 1/0.
--interval INTERVAL                  How often synchronization should run
--name NAME                           Sync plan name
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID     Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--sync-date SYNC_DATE                 Start date and time for the sync plan. Time is optional, if kept
                                      blank current system time will be considered
                                      Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format
-h, --help                            Print help
```

10.70.2. hammer sync-plan delete

Destroy a sync plan

Usage:

```
hammer sync-plan delete [OPTIONS]
```

Options:

```
--id ID                               Sync plan numeric identifier
--name NAME                           Sync plan name to search by
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID     Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                            Print help
```

10.70.3. hammer sync-plan info

Show a sync plan

Usage:

```
hammer sync-plan info [OPTIONS]
```

Options:

```
--id ID                               Sync plan numeric identifier
--name NAME                           Sync plan name to search by
--organization ORGANIZATION_NAME      Organization name to search by
--organization-id ORGANIZATION_ID     Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
-h, --help                            Print help
```

10.70.4. hammer sync-plan list

List sync plans

Usage:

```
hammer sync-plan list [OPTIONS]
```

Options:

```
--full-result FULL_RESULT      Whether or not to show all results
                                One of true/false, yes/no, 1/0.
--interval INTERVAL            Filter by interval
                                Possible value(s): 'hourly', 'daily', 'weekly', 'custom cron'
--name NAME                     Filter by name
--order ORDER                   Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--page PAGE                     Page number, starting at 1
--per-page PER_PAGE             Number of results per page to return
--search SEARCH                 Search string
--sync-date SYNC_DATE           Filter by sync date
-h, --help                      Print help
```

10.70.5. hammer sync-plan update

Update a sync plan

Usage:

```
hammer sync-plan update [OPTIONS]
```

Options:

```
--cron-expression CRON_EXPRESSION Add custom cron logic for sync plan
--description DESCRIPTION          Sync plan description
--enabled ENABLED                  Enables or disables synchronization
                                    One of true/false, yes/no, 1/0.
--id ID                            Sync plan numeric identifier
--interval INTERVAL                How often synchronization should run
--name NAME                        Sync plan name to search by
--new-name NEW_NAME                Sync plan name
--organization ORGANIZATION_NAME   Organization name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-label ORGANIZATION_LABEL Organization label to search by
--sync-date SYNC_DATE              Start date and time of the synchronization
                                    Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format
-h, --help                        Print help
```

10.71. HAMMER TAILORING-FILE

Manipulate Tailoring files

Usage:

```
hammer tailoring-file [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments
```

Subcommands:

```
create              Create a Tailoring file
```

delete	Deletes a Tailoring file
download	Download a Tailoring file as XML
info	Show a Tailoring file
list	List Tailoring files
update	Update a Tailoring file
Options:	
-h, --help	Print help

10.71.1. hammer tailoring-file create

Create a Tailoring file

```
Usage:
  hammer tailoring-file create [OPTIONS]

Options:
  --location LOCATION_NAME      Name to search by
  --location-id LOCATION_ID
  --location-ids LOCATION_IDS   REPLACE locations with given ids
                                Comma separated list of values. Values containing comma should be quoted
                                or escaped with backslash
  --locations LOCATION_NAMES    Comma separated list of values. Values containing comma
                                should be quoted or escaped with backslash
  --name NAME                   Tailoring file name
  --organization ORGANIZATION_NAME  Name to search by
  --organization-id ORGANIZATION_ID  Organization ID
  --organization-ids ORGANIZATION_IDS  REPLACE organizations with given ids.
                                Comma separated list of values. Values containing comma should be quoted
                                or escaped with backslash
  --organizations ORGANIZATION_NAMES  Comma separated list of values. Values containing
                                comma should be quoted or escaped with backslash
  --original-filename ORIGINAL_FILENAME  Original file name of the XML file
  --scap-file SCAP_FILE           Tailoring file content
  -h, --help                     Print help
```

10.71.2. hammer tailoring-file delete

Deletes a Tailoring file

```
Usage:
  hammer tailoring-file delete [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE  Location title
  --name NAME                   Name to search by
  --organization ORGANIZATION_NAME  Organization name
  --organization-id ORGANIZATION_ID  Organization ID
  --organization-title ORGANIZATION_TITLE  Organization title
  -h, --help                     Print help
```


10.71.3. hammer tailoring-file download

Download a Tailoring file as XML

Usage:

hammer tailoring-file download [OPTIONS]

Options:

--id ID
 --location LOCATION_NAME Name to search by
 --location-id LOCATION_ID
 --name NAME Tailoring file name
 --organization ORGANIZATION_NAME Name to search by
 --organization-id ORGANIZATION_ID Organization ID
 --path PATH Path to directory where downloaded file will be saved
 -h, --help Print help

10.71.4. hammer tailoring-file info

Show a Tailoring file

Usage:

hammer tailoring-file info [OPTIONS]

Options:

--id ID
 --location LOCATION_NAME Name to search by
 --location-id LOCATION_ID
 --name NAME Tailoring file name
 --organization ORGANIZATION_NAME Name to search by
 --organization-id ORGANIZATION_ID Organization ID
 -h, --help Print help

10.71.5. hammer tailoring-file list

List Tailoring files

Usage:

hammer tailoring-file list [OPTIONS]

Options:

--location LOCATION_NAME Location name
 --location-id LOCATION_ID
 --location-title LOCATION_TITLE Location title
 --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION_TITLE Organization title
 --page PAGE Paginate results
 --per-page PER_PAGE Number of entries per request
 --search SEARCH Filter results
 -h, --help Print help

10.71.6. hammer tailoring-file update

Update a Tailoring file

Usage:

```
hammer tailoring-file update [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Name to search by
--location-id LOCATION_ID
--location-ids LOCATION_IDS   REPLACE locations with given ids
                               Comma separated list of values. Values containing comma should be quoted
                               or escaped with backslash
--locations LOCATION_NAMES    Comma separated list of values. Values containing comma
                               should be quoted or escaped with backslash
--name NAME                   Tailoring file name
--new-name NEW_NAME           Tailoring file name
--organization ORGANIZATION_NAME  Name to search by
--organization-id ORGANIZATION_ID  Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                               Comma separated list of values. Values containing comma should be quoted
                               or escaped with backslash
--organizations ORGANIZATION_NAMES  Comma separated list of values. Values containing
                               comma should be quoted or escaped with backslash
--original-filename ORIGINAL_FILENAME Original file name of the XML file
--scap-file SCAP_FILE          Tailoring file content
-h, --help                    Print help
```

10.72. HAMMER TASK

Tasks related actions.

Usage:

```
hammer task [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments
```

Subcommands:

```
info                Show task details
list                List tasks
progress            Show the progress of the task
resume             Resume all tasks paused in error state
```

Options:

```
-h, --help          Print help
```

10.72.1. hammer task info

Show task details

Usage:

```
hammer task info [OPTIONS]
```

Options:

```
--id ID                UUID of the task
--location-id LOCATION_ID  Scope by locations
--organization-id ORGANIZATION_ID Scope by organizations
-h, --help            Print help
```

10.72.2. hammer task list

List tasks

Usage:

```
hammer task list [OPTIONS]
```

Options:

```
--by BY                Field to sort the results on
--location-id LOCATION_ID  Scope by locations
--order ORDER           Sort field and order, e.g. 'name DESC'
--organization-id ORGANIZATION_ID Scope by organizations
--page PAGE             Page number, starting at 1
--per-page PER_PAGE      Number of results per page to return
--search SEARCH          Search string
-h, --help            Print help
```

10.72.3. hammer task progress

Show the progress of the task

Usage:

```
hammer task progress [OPTIONS]
```

Options:

```
--id ID                UUID of the task
--location LOCATION_NAME  Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--name NAME             Name to search by
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
-h, --help            Print help
```

10.72.4. hammer task resume

Resume all tasks paused in error state

Usage:

```
hammer task resume [OPTIONS]
```

Options:

```
--location LOCATION_NAME  Location name
--location-id LOCATION_ID
```

```

--location-title LOCATION_TITLE    Location title
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--search SEARCH                    Resume tasks matching search string
--task-ids TASK_IDS                Resume specific tasks by ID
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--tasks TASK_NAMES                Comma separated list of values. Values containing comma
                                   should be quoted or escaped with backslash
-h, --help                        Print help

```

10.73. HAMMER TEMPLATE

Manipulate config templates

Usage:

```
hammer template [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```

SUBCOMMAND          Subcommand
[ARG] ...           Subcommand arguments

```

Subcommands:

```

add-operatingsystem  Associate an operating system
build-pxe-default    Update the default PXE menu on all configured TFTP servers
clone                Clone a provision template
combination          Manage template combinations
create              Create a provisioning template
delete              Delete a provisioning template
dump                View provisioning template content
info                Show provisioning template details
kinds               List available provisioning template kinds
list                List provisioning templates
remove-operatingsystem Disassociate an operating system
update              Update a provisioning template

```

Options:

```
-h, --help    Print help
```

10.73.1. hammer template add-operatingsystem

Associate an operating system

Usage:

```
hammer template add-operatingsystem [OPTIONS]
```

Options:

```

--id ID                ID
--name NAME            Name to search by
--operatingsystem OPERATINGSYSTEM_TITLE Operating system title
--operatingsystem-id OPERATINGSYSTEM_ID
-h, --help            Print help

```

10.73.2. hammer template build-pxe-default

Update the default PXE menu on all configured TFTP servers

Usage:

```
hammer template build-pxe-default [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.73.3. hammer template clone

Clone a provision template

Usage:

```
hammer template clone [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--new-name NEW_NAME           Template name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help
```

10.73.4. hammer template combination

Manage template combinations

Usage:

```
hammer template combination [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND      Subcommand
[ARG] ...        Subcommand arguments
```

Subcommands:

```
create          Add a template combination
delete          Delete a template combination
info            Show template combination
list            List template combination
update          Update template combination
```

Options:

-h, --help

Print help

10.73.4.1. hammer template combination create

Add a template combination

Usage:

hammer template combination create [OPTIONS]

Options:

--environment ENVIRONMENT_NAME	Environment name
--environment-id ENVIRONMENT_ID	
--hostgroup HOSTGROUP_NAME	Hostgroup name
--hostgroup-id HOSTGROUP_ID	
--hostgroup-title HOSTGROUP_TITLE	Hostgroup title
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--provisioning-template PROVISIONING_TEMPLATE_NAME	Name to search by
--provisioning-template-id PROVISIONING_TEMPLATE_ID	
-h, --help	Print help

10.73.4.2. hammer template combination delete

Delete a template combination

Usage:

hammer template combination delete [OPTIONS]

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
-h, --help	Print help

10.73.4.3. hammer template combination info

Show template combination

Usage:

hammer template combination info [OPTIONS]

Options:

--environment ENVIRONMENT_NAME	Environment name
--------------------------------	------------------

```

--environment-id ENVIRONMENT_ID
--hostgroup HOSTGROUP_NAME          Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE    Hostgroup title
--id ID
--location LOCATION_NAME             Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID     Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--provisioning-template PROVISIONING_TEMPLATE_NAME Name to search by
--provisioning-template-id PROVISIONING_TEMPLATE_ID
-h, --help                          Print help

```

10.73.4.4. hammer template combination list

List template combination

```

Usage:
  hammer template combination list [OPTIONS]

Options:
--location LOCATION_NAME             Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID     Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--provisioning-template PROVISIONING_TEMPLATE_NAME Name to search by
--provisioning-template-id PROVISIONING_TEMPLATE_ID
-h, --help                          Print help

```

10.73.4.5. hammer template combination update

Update template combination

```

Usage:
  hammer template combination update [OPTIONS]

Options:
--environment ENVIRONMENT_NAME       Environment name
--environment-id ENVIRONMENT_ID
--hostgroup HOSTGROUP_NAME           Hostgroup name
--hostgroup-id HOSTGROUP_ID
--hostgroup-title HOSTGROUP_TITLE    Hostgroup title
--id ID
--location LOCATION_NAME             Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID     Organization ID
--organization-title ORGANIZATION_TITLE Organization title

```

```
--provisioning-template PROVISIONING_TEMPLATE_NAME Name to search by
--provisioning-template-id PROVISIONING_TEMPLATE_ID
-h, --help Print help
```

10.73.5. hammer template create

Create a provisioning template

Usage:

```
hammer template create [OPTIONS]
```

Options:

```
--audit-comment AUDIT_COMMENT
--file TEMPLATE Path to a file that contains the template
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS REPLACE locations with given ids
                        Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locations LOCATION_NAMES Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--locked LOCKED Whether or not the template is locked for editing
                        One of true/false, yes/no, 1/0.
--name NAME Template name
--operatingsystem-ids OPERINGSYSTEM_IDS Array of operating system IDs to associate with
the template
                        Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--operatingsystems OPERINGSYSTEM_TITLES Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                        Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--type TYPE Template type. Eg. snippet, script, provision
-h, --help Print help
```

10.73.6. hammer template delete

Delete a provisioning template

Usage:

```
hammer template delete [OPTIONS]
```

Options:


```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help
```

10.73.7. hammer template dump

View provisioning template content

```
Usage:
  hammer template dump [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help
```

10.73.8. hammer template info

Show provisioning template details

```
Usage:
  hammer template info [OPTIONS]

Options:
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                     Print help
```

10.73.9. hammer template kinds

List available provisioning template kinds

```
Usage:
  hammer template kinds [OPTIONS]
```

Options:
-h, --help Print help

10.73.10. hammer template list

List provisioning templates

Usage:
 hammer template list [OPTIONS]

Options:

--location	LOCATION_NAME	Location name
--location-id	LOCATION_ID	
--location-title	LOCATION_TITLE	Location title
--operatingsystem	OPERATINGSYSTEM_TITLE	Operating system title
--operatingsystem-id	OPERATINGSYSTEM_ID	
--order	ORDER	Sort field and order, eg. 'id DESC'
--organization	ORGANIZATION_NAME	Organization name
--organization-id	ORGANIZATION_ID	Organization ID
--organization-title	ORGANIZATION_TITLE	Organization title
--page	PAGE	Paginate results
--per-page	PER_PAGE	Number of entries per request
--search	SEARCH	Filter results
-h, --help		Print help

10.73.11. hammer template remove-operatingsystem

Disassociate an operating system

Usage:
 hammer template remove-operatingsystem [OPTIONS]

Options:

--id	ID	
--name	NAME	Name to search by
--operatingsystem	OPERATINGSYSTEM_TITLE	Operating system title
--operatingsystem-id	OPERATINGSYSTEM_ID	
-h, --help		Print help

10.73.12. hammer template update

Update a provisioning template

Usage:
 hammer template update [OPTIONS]

Options:

--audit-comment	AUDIT_COMMENT	
--file	TEMPLATE	Path to a file that contains the template
--id	ID	
--location	LOCATION_NAME	Location name
--location-id	LOCATION_ID	
--location-ids	LOCATION_IDS	REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Name to search by

--new-name NEW_NAME Template name

--operatingsystem-ids OPERINGSYSTEM_IDS Array of operating system IDs to associate with the template

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--operatingsystems OPERINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash

--type TYPE Template type. Eg. snippet, script, provision

-h, --help Print help

10.74. HAMMER TEMPLATE-INPUT

Manage template inputs

Usage:
hammer template-input [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

create	Create a template input
delete	Delete a template input
info	Show template input details
list	List template inputs

Options:

-h, --help	Print help
------------	------------

10.74.1. hammer template-input create

Create a template input

Usage:

```
hammer template-input create [OPTIONS]
```

Options:

```
--advanced ADVANCED          Input is advanced
                                One of true/false, yes/no, 1/0.
--description DESCRIPTION     Input description
--fact-name FACT_NAME         Fact name, used when input type is fact
--input-type INPUT_TYPE       Input type
                                Possible value(s): 'user', 'fact', 'variable', 'puppet_parameter'
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Input name
--options OPTIONS             Selectable values for user inputs
                                Comma separated list of values. Values containing comma should be
                                quoted or escaped with backslash
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--puppet-class-name PUPPET_CLASS_NAME Puppet class name, used when input type is
                                puppet_parameter
--puppet-parameter-name PUPPET_PARAMETER_NAME Puppet parameter name, used when
                                input type is puppet_parameter
--required REQUIRED            Input is required
                                One of true/false, yes/no, 1/0.
--template-id TEMPLATE_ID
--variable-name VARIABLE_NAME Variable name, used when input type is variable
-h, --help                    Print help
```

10.74.2. hammer template-input delete

Delete a template input

Usage:

```
hammer template-input delete [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--template-id TEMPLATE_ID
-h, --help                    Print help
```

10.74.3. hammer template-input info

Show template input details

Usage:

```
hammer template-input info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--template-id TEMPLATE_ID
-h, --help                    Print help
```

10.74.4. hammer template-input list

List template inputs

Usage:

```
hammer template-input list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                Filter results
--template-id TEMPLATE_ID
-h, --help                    Print help
```

10.75. HAMMER USER

Manipulate users

Usage:

```
hammer user [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

```
SUBCOMMAND      Subcommand
[ARG] ...        Subcommand arguments
```

Subcommands:

```
access-token      Managing personal access tokens
add-role          Assign a user role
create            Create a user
delete            Delete a user
info              Show a user
list              List all users
remove-role       Remove a user role
```

```
ssh-keys      Managing User SSH Keys.
update        Update a user

Options:
-h, --help    Print help
```

10.75.1. hammer user access-token

Managing personal access tokens

```
Usage:
  hammer user access-token [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND      Subcommand
  [ARG] ...       Subcommand arguments

Subcommands:
  create          Create a Personal Access Token for a user
  info            Show a Personal Access Token for a user
  list            List all Personal Access Tokens for a user
  revoke          Revoke a Personal Access Token for a user

Options:
-h, --help        Print help
```

10.75.1.1. hammer user access-token create

Create a Personal Access Token for a user

```
Usage:
  hammer user access-token create [OPTIONS]

Options:
--expires-at EXPIRES_AT      Expiry Date
--location LOCATION_NAME     Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user USER_LOGIN            User's login to search by
--user-id USER_ID
-h, --help                    Print help
```

10.75.1.2. hammer user access-token info

Show a Personal Access Token for a user

```
Usage:
  hammer user access-token info [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user USER_LOGIN              User's login to search by
--user-id USER_ID
-h, --help                      Print help
```

10.75.1.3. hammer user access-token list

List all Personal Access Tokens for a user

Usage:

```
hammer user access-token list [OPTIONS]
```

Options:

```
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                  Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                    Paginate results
--per-page PER_PAGE            Number of entries per request
--search SEARCH                 Filter results
--user USER_LOGIN              User's login to search by
--user-id USER_ID
-h, --help                      Print help
```

10.75.1.4. hammer user access-token revoke

Revoke a Personal Access Token for a user

Usage:

```
hammer user access-token revoke [OPTIONS]
```

Options:

```
--id ID
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user USER_LOGIN              User's login to search by
--user-id USER_ID
-h, --help                      Print help
```

10.75.2. hammer user add-role

Assign a user role

Usage:

```
hammer user add-role [OPTIONS]
```

Options:

```
--id ID
--login LOGIN          User's login to search by
--role ROLE_NAME       User role name
--role-id ROLE_ID
-h, --help             Print help
```

10.75.3. hammer user create

Create a user

Usage:

```
hammer user create [OPTIONS]
```

Options:

```
--admin ADMIN          Is an admin account
                        One of true/false, yes/no, 1/0.
--ask-password ASK_PW  One of true/false, yes/no, 1/0.
--auth-source AUTH_SOURCE_NAME  Name to search by
--auth-source-id AUTH_SOURCE_ID
--default-location DEFAULT_LOCATION_NAME  Default location name
--default-location-id DEFAULT_LOCATION_ID
--default-organization DEFAULT_ORGANIZATION_NAME  Default organization name
--default-organization-id DEFAULT_ORGANIZATION_ID
--description DESCRIPTION
--firstname FIRSTNAME
--lastname LASTNAME
--locale LOCALE         User's preferred locale
                        Possible value(s): 'ca', 'de', 'en', 'en_GB', 'es', 'fr', 'gl', 'it', 'ja', 'ko',
'nl_NL', 'pl', 'pt_BR', 'ru', 'sv_SE', 'zh_CN', 'zh_TW'
--location LOCATION_NAME  Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS  REPLACE locations with given ids
                        Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--location-title LOCATION_TITLE  Location title
--location-titles LOCATION_TITLES  Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--locations LOCATION_NAMES  Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--login LOGIN
--mail MAIL
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-ids ORGANIZATION_IDS  REPLACE organizations with given ids.
                        Comma separated list of values. Values containing comma should be
quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE  Organization title
```



```

--organization-titles ORGANIZATION_TITLES      Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES              Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--password PASSWORD                             Required unless user is in an external authentication
source
--role-ids ROLE_IDS                             Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--roles ROLE_NAMES                             Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--timezone TIMEZONE                             User's timezone
Possible value(s): 'International Date Line West', 'American Samoa',
'Midway Island', 'Hawaii', 'Alaska', 'Pacific Time (US & Canada)', 'Tijuana', 'Arizona', 'Chihuahua',
'Mazatlan', 'Mountain Time (US & Canada)', 'Central America', 'Central Time (US & Canada)',
'Guadalajara', 'Mexico City', 'Monterrey', 'Saskatchewan', 'Bogota', 'Eastern Time (US
& Canada)', 'Indiana (East)', 'Lima', 'Quito', 'Atlantic Time (Canada)', 'Caracas', 'Georgetown', 'La
Paz', 'Puerto Rico', 'Santiago', 'Newfoundland', 'Brasilia', 'Buenos Aires', 'Greenland', 'Montevideo',
'Mid-Atlantic', 'Azores', 'Cape Verde Is.', 'Casablanca', 'Dublin', 'Edinburgh', 'Lisbon', 'London',
'Monrovia', 'UTC', 'Amsterdam', 'Belgrade', 'Berlin', 'Bern', 'Bratislava', 'Brussels', 'Budapest',
'Copenhagen', 'Ljubljana', 'Madrid', 'Paris', 'Prague', 'Rome', 'Sarajevo', 'Skopje', 'Stockholm', 'Vienna',
'Warsaw', 'West Central Africa', 'Zagreb', 'Zurich', 'Athens', 'Bucharest', 'Cairo', 'Harare', 'Helsinki',
'Jerusalem', 'Kaliningrad', 'Kyiv', 'Pretoria', 'Riga', 'Sofia', 'Tallinn', 'Vilnius', 'Baghdad', 'Istanbul',
'Kuwait', 'Minsk', 'Moscow', 'Nairobi', 'Riyadh', 'St. Petersburg', 'Tehran', 'Abu Dhabi', 'Baku', 'Muscat',
'Samara', 'Tbilisi', 'Volgograd', 'Yerevan', 'Kabul', 'Ekaterinburg', 'Islamabad', 'Karachi', 'Tashkent',
'Chennai', 'Kolkata', 'Mumbai', 'New Delhi', 'Sri Jayawardenepura', 'Kathmandu', 'Almaty', 'Astana',
'Dhaka', 'Urumqi', 'Rangoon', 'Bangkok', 'Hanoi', 'Jakarta', 'Krasnoyarsk', 'Novosibirsk', 'Beijing',
'Chongqing', 'Hong Kong', 'Irkutsk', 'Kuala Lumpur', 'Perth', 'Singapore', 'Taipei', 'Ulaanbaatar',
'Osaka', 'Sapporo', 'Seoul', 'Tokyo', 'Yakutsk', 'Adelaide', 'Darwin', 'Brisbane', 'Canberra', 'Guam',
'Hobart', 'Melbourne', 'Port Moresby', 'Sydney', 'Vladivostok', 'Magadan', 'New Caledonia', 'Solomon
Is.', 'Srednekolymysk', 'Auckland', 'Fiji', 'Kamchatka', 'Marshall Is.', 'Wellington', 'Chatham Is.',
'Nuku'alofa', 'Samoa', 'Tokelau Is.'
-h, --help                                     Print help

```

10.75.4. hammer user delete

Delete a user

```

Usage:
  hammer user delete [OPTIONS]

Options:
  --id ID                                Location name
  --location LOCATION_NAME               Location name
  --location-id LOCATION_ID              Location title
  --location-title LOCATION_TITLE        Location title
  --login LOGIN                          User's login to search by
  --organization ORGANIZATION_NAME       Organization name
  --organization-id ORGANIZATION_ID      Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                             Print help

```

10.75.5. hammer user info

Show a user

-

Usage:`hammer user info [OPTIONS]`**Options:**

`--id ID`
`--location LOCATION_NAME` Location name
`--location-id LOCATION_ID`
`--location-title LOCATION_TITLE` Location title
`--login LOGIN` User's login to search by
`--organization ORGANIZATION_NAME` Organization name
`--organization-id ORGANIZATION_ID` Organization ID
`--organization-title ORGANIZATION_TITLE` Organization title
`-h, --help` Print help

10.75.6. hammer user list

List all users

Usage:`hammer user list [OPTIONS]`**Options:**

`--auth-source-ldap AUTH_SOURCE_LDAP_NAME` Name to search by
`--auth-source-ldap-id AUTH_SOURCE_LDAP_ID`
`--location LOCATION_NAME` Location name
`--location-id LOCATION_ID`
`--location-title LOCATION_TITLE` Location title
`--order ORDER` Sort field and order, eg. 'id DESC'
`--organization ORGANIZATION_NAME` Organization name
`--organization-id ORGANIZATION_ID` Organization ID
`--organization-title ORGANIZATION_TITLE` Organization title
`--page PAGE` Paginate results
`--per-page PER_PAGE` Number of entries per request
`--role ROLE_NAME` User role name
`--role-id ROLE_ID`
`--search SEARCH` Filter results
`--user-group USER_GROUP_NAME` Name to search by
`--user-group-id USER_GROUP_ID`
`-h, --help` Print help

10.75.7. hammer user remove-role

Remove a user role

Usage:`hammer user remove-role [OPTIONS]`**Options:**

`--id ID`
`--login LOGIN` User's login to search by
`--role ROLE_NAME` User role name
`--role-id ROLE_ID`
`-h, --help` Print help

10.75.8. hammer user ssh-keys

Managing User SSH Keys.

Usage:

```
hammer user ssh-keys [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

add	Add an SSH key for a user
delete	Delete an SSH key for a user
info	Show an SSH key from a user
list	List all SSH keys for a user

Options:

-h, --help	Print help
------------	------------

10.75.8.1. hammer user ssh-keys add

Add an SSH key for a user

Usage:

```
hammer user ssh-keys add [OPTIONS]
```

Options:

--key KEY	Public SSH key
--key-file KEY_FILE	Path to a SSH public key
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	
--organization ORGANIZATION_NAME	Organization name
--organization-id ORGANIZATION_ID	Organization ID
--organization-title ORGANIZATION_TITLE	Organization title
--user USER_LOGIN	User's login to search by
--user-id USER_ID	
-h, --help	Print help

10.75.8.2. hammer user ssh-keys delete

Delete an SSH key for a user

Usage:

```
hammer user ssh-keys delete [OPTIONS]
```

Options:

--id ID	
--location LOCATION_NAME	Location name
--location-id LOCATION_ID	
--location-title LOCATION_TITLE	Location title
--name NAME	Name to search by

```
--organization ORGANIZATION_NAME    Organization name
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user USER_LOGIN                   User's login to search by
--user-id USER_ID
-h, --help                           Print help
```

10.75.8.3. hammer user ssh-keys info

Show an SSH key from a user

```
Usage:
  hammer user ssh-keys info [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME          Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE   Location title
  --name NAME                       Name to search by
  --organization ORGANIZATION_NAME  Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --user USER_LOGIN                User's login to search by
  --user-id USER_ID
  -h, --help                        Print help
```

10.75.8.4. hammer user ssh-keys list

List all SSH keys for a user

```
Usage:
  hammer user ssh-keys list [OPTIONS]

Options:
  --location LOCATION_NAME          Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE   Location title
  --order ORDER                     Sort field and order, eg. 'id DESC'
  --organization ORGANIZATION_NAME  Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --page PAGE                       Paginate results
  --per-page PER_PAGE               Number of entries per request
  --search SEARCH                   Filter results
  --user USER_LOGIN                User's login to search by
  --user-id USER_ID
  -h, --help                        Print help
```

10.75.9. hammer user update

Update a user

Usage:

```
hammer user update [OPTIONS]
```

Options:

```
--admin ADMIN                      Is an admin account
                                   One of true/false, yes/no, 1/0.
--ask-password ASK_PW              One of true/false, yes/no, 1/0.
--auth-source AUTH_SOURCE_NAME     Name to search by
--auth-source-id AUTH_SOURCE_ID
--current-password CURRENT_PASSWORD Required when user want to change own
password
--default-location DEFAULT_LOCATION_NAME Default location name
--default-location-id DEFAULT_LOCATION_ID
--default-organization DEFAULT_ORGANIZATION_NAME Default organization name
--default-organization-id DEFAULT_ORGANIZATION_ID
--description DESCRIPTION
--firstname FIRSTNAME
--id ID
--lastname LASTNAME
--locale LOCALE                    User's preferred locale
                                   Possible value(s): 'ca', 'de', 'en', 'en_GB', 'es', 'fr', 'gl', 'it', 'ja', 'ko',
                                   'nl_NL', 'pl', 'pt_BR', 'ru', 'sv_SE', 'zh_CN', 'zh_TW'
--location LOCATION_NAME           Location name
--location-id LOCATION_ID
--location-ids LOCATION_IDS        REPLACE locations with given ids
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--location-title LOCATION_TITLE    Location title
--location-titles LOCATION_TITLES Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--locations LOCATION_NAMES         Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--login LOGIN                      User's login to search by
--mail MAIL
--new-login NEW_LOGIN
--organization ORGANIZATION_NAME   Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
                                   Comma separated list of values. Values containing comma should be
                                   quoted or escaped with backslash
--organization-title ORGANIZATION_TITLE Organization title
--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--organizations ORGANIZATION_NAMES Comma separated list of values. Values
containing comma should be quoted or escaped with backslash
--password PASSWORD               Required unless user is in an external authentication
source
--role-ids ROLE_IDS               Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--roles ROLE_NAMES               Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--timezone TIMEZONE              User's timezone
                                   Possible value(s): 'International Date Line West', 'American Samoa',
                                   'Midway Island', 'Hawaii', 'Alaska', 'Pacific Time (US & Canada)', 'Tijuana', 'Arizona', 'Chihuahua',
                                   'Mazatlan', 'Mountain Time (US & Canada)', 'Central America', 'Central Time (US &
                                   Canada)', 'Guadalajara', 'Mexico City', 'Monterrey', 'Saskatchewan', 'Bogota', 'Eastern Time (US
```

```
& Canada)', 'Indiana (East)', 'Lima', 'Quito', 'Atlantic Time (Canada)', 'Caracas', 'Georgetown', 'La
Paz', 'Puerto Rico', 'Santiago', 'Newfoundland', 'Brasilia', 'Buenos Aires', 'Greenland', 'Montevideo',
'Mid-Atlantic', 'Azores', 'Cape Verde Is.', 'Casablanca', 'Dublin', 'Edinburgh', 'Lisbon', 'London',
'Monrovia', 'UTC', 'Amsterdam', 'Belgrade', 'Berlin', 'Bern', 'Bratislava', 'Brussels', 'Budapest',
'Copenhagen', 'Ljubljana', 'Madrid', 'Paris', 'Prague', 'Rome', 'Sarajevo', 'Skopje', 'Stockholm', 'Vienna',
'Warsaw', 'West Central Africa', 'Zagreb', 'Zurich', 'Athens', 'Bucharest', 'Cairo', 'Harare', 'Helsinki',
'Jerusalem', 'Kaliningrad', 'Kyiv', 'Pretoria', 'Riga', 'Sofia', 'Tallinn', 'Vilnius', 'Baghdad', 'Istanbul',
'Kuwait', 'Minsk', 'Moscow', 'Nairobi', 'Riyadh', 'St. Petersburg', 'Tehran', 'Abu Dhabi', 'Baku', 'Muscat',
'Samara', 'Tbilisi', 'Volgograd', 'Yerevan', 'Kabul', 'Ekaterinburg', 'Islamabad', 'Karachi', 'Tashkent',
'Chennai', 'Kolkata', 'Mumbai', 'New Delhi', 'Sri Jayawardenepura', 'Kathmandu', 'Almaty', 'Astana',
'Dhaka', 'Urumqi', 'Rangoon', 'Bangkok', 'Hanoi', 'Jakarta', 'Krasnoyarsk', 'Novosibirsk', 'Beijing',
'Chongqing', 'Hong Kong', 'Irkutsk', 'Kuala Lumpur', 'Perth', 'Singapore', 'Taipei', 'Ulaanbaatar',
'Osaka', 'Sapporo', 'Seoul', 'Tokyo', 'Yakutsk', 'Adelaide', 'Darwin', 'Brisbane', 'Canberra', 'Guam',
'Hobart', 'Melbourne', 'Port Moresby', 'Sydney', 'Vladivostok', 'Magadan', 'New Caledonia', 'Solomon
Is.', 'Srednekolymsk', 'Auckland', 'Fiji', 'Kamchatka', 'Marshall Is.', 'Wellington', 'Chatham Is.',
'Nuku'alofa', 'Samoa', 'Tokelau Is.'
-h, --help                Print help
```

10.76. HAMMER USER-GROUP

Manage user groups

Usage:

```
hammer user-group [OPTIONS] SUBCOMMAND [ARG] ...
```

Parameters:

SUBCOMMAND	Subcommand
[ARG] ...	Subcommand arguments

Subcommands:

add-role	Assign a user role
add-user	Associate an user
add-user-group	Associate an user group
create	Create a user group
delete	Delete a user group
external	View and manage user group's external user groups
info	Show a user group
list	List all user groups
remove-role	Remove a user role
remove-user	Disassociate an user
remove-user-group	Disassociate an user group
update	Update a user group

Options:

-h, --help	Print help
------------	------------

10.76.1. hammer user-group add-role

Assign a user role

Usage:

```
hammer user-group add-role [OPTIONS]
```

Options:

```
--id ID
--name NAME           Name to search by
--role ROLE_NAME      User role name
--role-id ROLE_ID
-h, --help           Print help
```

10.76.2. hammer user-group add-user

Associate an user

```
Usage:
  hammer user-group add-user [OPTIONS]

Options:
--id ID
--name NAME           Name to search by
--user USER_LOGIN     User's login to search by
--user-id USER_ID
-h, --help           Print help
```

10.76.3. hammer user-group add-user-group

Associate an user group

```
Usage:
  hammer user-group add-user-group [OPTIONS]

Options:
--id ID
--name NAME           Name to search by
--user-group USER_GROUP_NAME Name to search by
--user-group-id USER_GROUP_ID
-h, --help           Print help
```

10.76.4. hammer user-group create

Create a user group

```
Usage:
  hammer user-group create [OPTIONS]

Options:
--admin ADMIN          Is an admin user group
                        One of true/false, yes/no, 1/0.
--location LOCATION_NAME Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--role-ids ROLE_IDS     Comma separated list of values. Values containing comma should
                        be quoted or escaped with backslash
```

```

--roles ROLE_NAMES          Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--user-group-ids USER_GROUP_IDS  Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--user-groups USER_GROUP_NAMES  Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--user-ids USER_IDS          Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--users USER_LOGINS          Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
-h, --help                    Print help

```

10.76.5. hammer user-group delete

Delete a user group

```

Usage:
  hammer user-group delete [OPTIONS]

Options:
  --id ID                      Location name
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE  Location title
  --name NAME                   Name to search by
  --organization ORGANIZATION_NAME  Organization name
  --organization-id ORGANIZATION_ID  Organization ID
  --organization-title ORGANIZATION_TITLE  Organization title
  -h, --help                    Print help

```

10.76.6. hammer user-group external

View and manage user group's external user groups

```

Usage:
  hammer user-group external [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  create          Create an external user group linked to a user group
  delete          Delete an external user group
  info            Show an external user group for user group
  list            List all external user groups for user group
  refresh         Refresh external user group
  update          Update external user group

Options:
  -h, --help          Print help

```

10.76.6.1. hammer user-group external create

Create an external user group linked to a user group

Usage:

```
hammer user-group external create [OPTIONS]
```

Options:

```
--auth-source AUTH_SOURCE_NAME      Name to search by
--auth-source-id AUTH_SOURCE_ID
--location LOCATION_NAME             Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE      Location title
--name NAME                           External user group name
--organization ORGANIZATION_NAME     Organization name
--organization-id ORGANIZATION_ID     Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user-group USER_GROUP_NAME         Name to search by
--user-group-id USER_GROUP_ID
-h, --help                           Print help
```

10.76.6.2. hammer user-group external delete

Delete an external user group

Usage:

```
hammer user-group external delete [OPTIONS]
```

Options:

```
--id ID                               ID or name external user group
--location LOCATION_NAME              Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE       Location title
--name NAME                           Name to search by
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user-group USER_GROUP_NAME         Name to search by
--user-group-id USER_GROUP_ID
-h, --help                           Print help
```

10.76.6.3. hammer user-group external info

Show an external user group for user group

Usage:

```
hammer user-group external info [OPTIONS]
```

Options:

```
--id ID                               ID or name of external user group
--location LOCATION_NAME              Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE       Location title
--name NAME                           Name to search by
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
```

```
--organization-title ORGANIZATION_TITLE Organization title
--user-group USER_GROUP_NAME           Name to search by
--user-group-id USER_GROUP_ID
-h, --help                               Print help
```

10.76.6.4. hammer user-group external list

List all external user groups for user group

```
Usage:
  hammer user-group external list [OPTIONS]

Options:
--location LOCATION_NAME           Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE    Location title
--organization ORGANIZATION_NAME   Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user-group USER_GROUP_NAME       Name to search by
--user-group-id USER_GROUP_ID
-h, --help                           Print help
```

10.76.6.5. hammer user-group external refresh

Refresh external user group

```
Usage:
  hammer user-group external refresh [OPTIONS]

Options:
--id ID                        ID or name of external user group
--location LOCATION_NAME       Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                     Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user-group USER_GROUP_NAME   Name to search by
--user-group-id USER_GROUP_ID
-h, --help                       Print help
```

10.76.6.6. hammer user-group external update

Update external user group

```
Usage:
  hammer user-group external update [OPTIONS]

Options:
--auth-source AUTH_SOURCE_NAME      Name to search by
--auth-source-id AUTH_SOURCE_ID
```

```

--id ID                      ID or name of external user group
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--new-name NEW_NAME           External user group name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user-group USER_GROUP_NAME Name to search by
--user-group-id USER_GROUP_ID
-h, --help                    Print help

```

10.76.7. hammer user-group info

Show a user group

```

Usage:
  hammer user-group info [OPTIONS]

```

```

Options:
--id ID                      ID or name of external user group
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                   Name to search by
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                    Print help

```

10.76.8. hammer user-group list

List all user groups

```

Usage:
  hammer user-group list [OPTIONS]

Options:
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--order ORDER                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--page PAGE                   Paginate results
--per-page PER_PAGE           Number of entries per request
--search SEARCH               Filter results
-h, --help                    Print help

```

10.76.9. hammer user-group remove-role

Remove a user role

```
Usage:
  hammer user-group remove-role [OPTIONS]

Options:
  --id ID
  --name NAME          Name to search by
  --role ROLE_NAME     User role name
  --role-id ROLE_ID
  -h, --help          Print help
```

10.76.10. hammer user-group remove-user

Disassociate an user

```
Usage:
  hammer user-group remove-user [OPTIONS]

Options:
  --id ID
  --name NAME          Name to search by
  --user USER_LOGIN    User's login to search by
  --user-id USER_ID
  -h, --help          Print help
```

10.76.11. hammer user-group remove-user-group

Disassociate an user group

```
Usage:
  hammer user-group remove-user-group [OPTIONS]

Options:
  --id ID
  --name NAME          Name to search by
  --user-group USER_GROUP_NAME Name to search by
  --user-group-id USER_GROUP_ID
  -h, --help          Print help
```

10.76.12. hammer user-group update

Update a user group

```
Usage:
  hammer user-group update [OPTIONS]

Options:
  --admin ADMIN          Is an admin user group
                        One of true/false, yes/no, 1/0.
  --id ID
  --location LOCATION_NAME Location name
  --location-id LOCATION_ID
```

```

--location-title LOCATION_TITLE      Location title
--name NAME                          Name to search by
--new-name NEW_NAME
--organization ORGANIZATION_NAME      Organization name
--organization-id ORGANIZATION_ID      Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--role-ids ROLE_IDS                   Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--roles ROLE_NAMES                    Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
--user-group-ids USER_GROUP_IDS       Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--user-groups USER_GROUP_NAMES        Comma separated list of values. Values containing
comma should be quoted or escaped with backslash
--user-ids USER_IDS                   Comma separated list of values. Values containing comma should
be quoted or escaped with backslash
--users USER_LOGINS                  Comma separated list of values. Values containing comma
should be quoted or escaped with backslash
-h, --help                            Print help

```

10.77. HAMMER VIRT-WHO-CONFIG

Manage Virt Who configurations

```

Usage:
  hammer virt-who-config [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:
  SUBCOMMAND          Subcommand
  [ARG] ...           Subcommand arguments

Subcommands:
  create              Create a virt-who configuration
  delete              Delete a virt-who configuration
  deploy              Download and execute script for the specified virt-who configuration
  fetch               Renders a deploy script for the specified virt-who configuration
  info                Show a virt-who configuration
  list                List of virt-who configurations
  update              Update a virt-who configuration

Options:
  -h, --help          Print help

```

10.77.1. hammer virt-who-config create

Create a virt-who configuration

```

Usage:
  hammer virt-who-config create [OPTIONS]

Options:
  --blacklist BLACKLIST      Hypervisor blacklist, applicable only when filtering mode is set to
2.
                             Wildcards and regular expressions are supported, multiple records must

```

```

be
                                Separated by comma.
--debug DEBUG                    Enable debugging output
                                One of true/false, yes/no, 1/0.
--filtering-mode MODE            Hypervisor filtering mode
                                Possible value(s): 'none', 'whitelist', 'blacklist'
--hypervisor-id HYPERVISOR_ID    Specifies how the hypervisor will be identified.
                                Possible value(s): 'hostname', 'uuid', 'hwuuid'
--hypervisor-password HYPERVISOR_PASSWORD Hypervisor password, required for all hypervisor
types except for libvirt
--hypervisor-server HYPERVISOR_SERVER Fully qualified host name or IP address of the
hypervisor
--hypervisor-type HYPERVISOR_TYPE Hypervisor type
                                Possible value(s): 'esx', 'rhev', 'hyperv', 'xen', 'libvirt'
--hypervisor-username HYPERVISOR_USERNAME Account name by which virt-who is to connect
to the hypervisor.
--interval INTERVAL              Configuration interval in minutes
                                Possible value(s): '60', '120', '240', '480', '720'
--location LOCATION_NAME         Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--name NAME                      Configuration name
--no-proxy NO_PROXY              Ignore Proxy. A comma-separated list of hostnames or
domains or ip
                                Addresses to ignore Capsule settings for. Optionally this may be set to *
                                To bypass proxy settings for all hostnames domains or ip addresses.
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--proxy PROXY                    HTTP Proxy that should be used for communication between the
server on
                                Which virt-who is running and the hypervisors and virtualization managers.
--satellite-url SATELLITE_URL    Satellite server FQDN
--whitelist WHITELIST            Hypervisor whitelist, applicable only when filtering mode is set to
1.
                                Wildcards and regular expressions are supported, multiple records must
be
                                Separated by comma.
-h, --help                      Print help

```

10.77.2. hammer virt-who-config delete

Delete a virt-who configuration

Usage:

```
hammer virt-who-config delete [OPTIONS]
```

Options:

```

--id ID                        Configuration numeric identifier
--location LOCATION_NAME       Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--organization ORGANIZATION_NAME Organization name

```

```
--organization-id ORGANIZATION_ID    Organization ID
--organization-title ORGANIZATION_TITLE Organization title
-h, --help                          Print help
```

10.77.3. hammer virt-who-config deploy

Download and execute script for the specified virt-who configuration

```
Usage:
  hammer virt-who-config deploy [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                   Name to search by
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  -h, --help                   Print help
```

10.77.4. hammer virt-who-config fetch

Renders a deploy script for the specified virt-who configuration

```
Usage:
  hammer virt-who-config fetch [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
  --name NAME                   Name to search by
  --organization ORGANIZATION_NAME Organization name
  --organization-id ORGANIZATION_ID Organization ID
  --organization-title ORGANIZATION_TITLE Organization title
  --output, -o FILE            File where the script will be written.
  -h, --help                   Print help
```

10.77.5. hammer virt-who-config info

Show a virt-who configuration

```
Usage:
  hammer virt-who-config info [OPTIONS]

Options:
  --id ID
  --location LOCATION_NAME      Location name
  --location-id LOCATION_ID
  --location-title LOCATION_TITLE Location title
```

```

--name NAME                Name to search by
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
-h, --help                  Print help

```

10.77.6. hammer virt-who-config list

List of virt-who configurations

```

Usage:
  hammer virt-who-config list [OPTIONS]

Options:
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE  Location title
--order ORDER                 Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME  Organization name
--organization-id ORGANIZATION_ID  Organization ID
--organization-title ORGANIZATION_TITLE  Organization title
--page PAGE                   Paginate results
--per-page PER_PAGE           Number of entries per request
--search SEARCH               Filter results
-h, --help                    Print help

```

10.77.7. hammer virt-who-config update

Update a virt-who configuration

```

Usage:
  hammer virt-who-config update [OPTIONS]

Options:
--blacklist BLACKLIST          Hypervisor blacklist, applicable only when filtering mode is set to
2.                             Wildcards and regular expressions are supported, multiple records must
be                             be
Separated by comma.
--debug DEBUG                  Enable debugging output
One of true/false, yes/no, 1/0.
--filtering-mode MODE          Hypervisor filtering mode
Possible value(s): 'none', 'whitelist', 'blacklist'
--hypervisor-id HYPERVISOR_ID  Specifies how the hypervisor will be identified.
Possible value(s): 'hostname', 'uuid', 'hwuuid'
--hypervisor-password HYPERVISOR_PASSWORD Hypervisor password, required for all hypervisor
types except for libvirt
--hypervisor-server HYPERVISOR_SERVER  Fully qualified host name or IP address of the
hypervisor
--hypervisor-type HYPERVISOR_TYPE      Hypervisor type
Possible value(s): 'esx', 'rhev', 'hyperv', 'xen', 'libvirt'
--hypervisor-username HYPERVISOR_USERNAME Account name by which virt-who is to connect
to the hypervisor.
--id ID                          Configuration numeric identifier

```



```

--interval INTERVAL           Configuration interval in minutes
                               Possible value(s): '60', '120', '240', '480', '720'
--location LOCATION_NAME      Location name
--location-id LOCATION_ID
--location-title LOCATION_TITLE Location title
--name NAME                    Name to search by
--new-name NEW_NAME            Configuration name
--no-proxy NO_PROXY            Ignore Proxy. A comma-separated list of hostnames or
domains or ip
                               Addresses to ignore Capsule settings for. Optionally this may be set to *
                               To bypass proxy settings for all hostnames domains or ip addresses.
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--proxy PROXY                  HTTP Proxy that should be used for communication between the
server on
                               Which virt-who is running and the hypervisors and virtualization managers.
--satellite-url SATELLITE_URL  Satellite server FQDN
--whitelist WHITELIST          Hypervisor whitelist, applicable only when filtering mode is set to
1.
                               Wildcards and regular expressions are supported, multiple records must
be
                               Separated by comma.
-h, --help                     Print help

```