



OpenShift Container Platform 4.3

Installing on IBM Z and LinuxONE

Installing OpenShift Container Platform 4.3 IBM Z and LinuxONE clusters

OpenShift Container Platform 4.3 Installing on IBM Z and LinuxONE

Installing OpenShift Container Platform 4.3 IBM Z and LinuxONE clusters

Legal Notice

Copyright © 2020 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document provides instructions for installing OpenShift Container Platform 4.3 clusters on IBM Z and LinuxONE.

Table of Contents

CHAPTER 1. INSTALLING ON IBM Z AND LINUXONE	4
1.1. INSTALLING A CLUSTER ON IBM Z AND LINUXONE	4
1.1.1. Prerequisites	4
1.1.2. Internet and Telemetry access for OpenShift Container Platform	4
1.1.3. Machine requirements for a cluster with user-provisioned infrastructure	5
1.1.3.1. Required machines	5
1.1.3.2. Network connectivity requirements	5
1.1.3.3. IBM Z network connectivity requirements	5
1.1.3.4. Minimum resource requirements	6
1.1.3.5. Minimum IBM Z system requirements	6
Hardware requirements	6
Operating system requirements	6
Disk storage for the z/VM guest virtual machines	6
Storage / Main Memory	6
1.1.3.6. Preferred IBM Z system requirements	7
Hardware requirements	7
Operating system requirements	7
Disk storage for the z/VM guest virtual machines	7
Storage / Main Memory	7
1.1.3.7. Certificate signing requests management	7
1.1.4. Creating the user-provisioned infrastructure	8
1.1.4.1. Networking requirements for user-provisioned infrastructure	8
Network topology requirements	9
Load balancers	9
1.1.4.2. User-provisioned DNS requirements	11
1.1.5. Generating an SSH private key and adding it to the agent	13
1.1.6. Obtaining the installation program	14
1.1.7. Installing the CLI by downloading the binary	15
1.1.7.1. Installing the CLI on Linux	15
1.1.7.2. Installing the CLI on Windows	16
1.1.7.3. Installing the CLI on macOS	16
1.1.8. Manually creating the installation configuration file	17
1.1.8.1. Sample install-config.yaml file for IBM Z	17
1.1.9. Creating the Kubernetes manifest and Ignition config files	19
1.1.10. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines	20
1.1.11. Creating the cluster	22
1.1.12. Logging in to the cluster	23
1.1.13. Approving the CSRs for your machines	23
1.1.14. Initial Operator configuration	25
1.1.14.1. Image registry storage configuration	25
1.1.14.1.1. Configuring registry storage for IBM Z	26
1.1.14.1.2. Configuring storage for the image registry in non-production clusters	27
1.1.15. Completing installation on user-provisioned infrastructure	27
1.1.16. Collecting debugging information	29
1.1.17. Next steps	30
1.2. INSTALLING A CLUSTER ON IBM Z AND LINUXONE IN A RESTRICTED NETWORK	30
1.2.1. Prerequisites	30
1.2.2. About installations in restricted networks	31
1.2.2.1. Additional limits	31
1.2.3. Machine requirements for a cluster with user-provisioned infrastructure	31
1.2.3.1. Required machines	31

1.2.3.2. Network connectivity requirements	32
1.2.3.3. IBM Z network connectivity requirements	32
1.2.3.4. Minimum resource requirements	32
1.2.3.5. Minimum IBM Z system requirements	32
Hardware requirements	32
Operating system requirements	33
Disk storage for the z/VM guest virtual machines	33
Storage / Main Memory	33
1.2.3.6. Preferred IBM Z system requirements	33
Hardware requirements	33
Operating system requirements	33
Disk storage for the z/VM guest virtual machines	34
Storage / Main Memory	34
1.2.3.7. Certificate signing requests management	34
1.2.4. Creating the user-provisioned infrastructure	34
1.2.4.1. Networking requirements for user-provisioned infrastructure	35
Network topology requirements	36
Load balancers	36
1.2.4.2. User-provisioned DNS requirements	37
1.2.5. Generating an SSH private key and adding it to the agent	39
1.2.6. Manually creating the installation configuration file	40
1.2.6.1. Sample install-config.yaml file for IBM Z	41
1.2.6.2. Configuring the cluster-wide proxy during installation	43
1.2.7. Creating the Kubernetes manifest and Ignition config files	44
1.2.8. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines	46
1.2.9. Creating the cluster	47
1.2.10. Logging in to the cluster	48
1.2.11. Approving the CSRs for your machines	49
1.2.12. Initial Operator configuration	50
1.2.12.1. Image registry storage configuration	51
1.2.12.1.1. Configuring registry storage for IBM Z	51
1.2.12.1.2. Configuring storage for the image registry in non-production clusters	52
1.2.13. Completing installation on user-provisioned infrastructure	53
1.2.14. Collecting debugging information	55
1.2.15. Next steps	55

CHAPTER 1. INSTALLING ON IBM Z AND LINUXONE

1.1. INSTALLING A CLUSTER ON IBM Z AND LINUXONE

In OpenShift Container Platform version 4.3, you can install a cluster on IBM Z or LinuxONE infrastructure that you provision.



NOTE

While this document refers only to IBM Z, all information in it also applies to LinuxONE.



IMPORTANT

Additional considerations exist for non-bare metal platforms. Review the information in the [guidelines for deploying OpenShift Container Platform on non-tested platforms](#) before you install an OpenShift Container Platform cluster.

1.1.1. Prerequisites

- Provision [persistent storage using NFS](#) for your cluster. To deploy a private image registry, your storage must provide ReadWriteMany access modes.
- Review details about the [OpenShift Container Platform installation and update](#) processes.
- If you use a firewall, you must [configure it to allow the sites](#) that your cluster requires access to.



NOTE

Be sure to also review this site list if you are configuring a proxy.

1.1.2. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the [Red Hat OpenShift Cluster Manager \(OCM\)](#).

Once you confirm that your Red Hat OpenShift Cluster Manager inventory is correct, either maintained automatically by Telemetry or manually using OCM, [use subscription watch](#) to track your OpenShift Container Platform subscriptions at the account or multi-cluster level.

You must have internet access to:

- Access the [Red Hat OpenShift Cluster Manager](#) page to download the installation program and perform subscription management. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster.
- Access [Quay.io](#) to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



IMPORTANT

If your cluster cannot have direct internet access, you can perform a restricted network installation on some types of infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

1.1.3. Machine requirements for a cluster with user-provisioned infrastructure

For a cluster that contains user-provisioned infrastructure, you must deploy all of the required machines.

1.1.3.1. Required machines

The smallest OpenShift Container Platform clusters require the following hosts:

- One temporary bootstrap machine
- Three control plane, or master, machines
- At least two compute machines, which are also known as worker machines



NOTE

The cluster requires the bootstrap machine to deploy the OpenShift Container Platform cluster on the three control plane machines. You can remove the bootstrap machine after you install the cluster.



IMPORTANT

To improve high availability of your cluster, distribute the control plane machines over different z/VM instances on at least two physical machines.

The bootstrap, control plane, and compute machines must use the Red Hat Enterprise Linux CoreOS (RHCOS) as the operating system.

Note that RHCOS is based on Red Hat Enterprise Linux 8 and inherits all of its hardware certifications and requirements. See [Red Hat Enterprise Linux technology capabilities and limits](#) .

1.1.3.2. Network connectivity requirements

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config files from the Machine Config Server. The machines are configured with static IP addresses. No DHCP server is required.

1.1.3.3. IBM Z network connectivity requirements

To install on IBM Z under z/VM, you require a single z/VM virtual NIC in layer 2 mode. You also need:

- A direct-attached OSA or RoCE network adapter
- A z/VM VSWITCH set up. For a preferred setup, use OSA link aggregation.

1.1.3.4. Minimum resource requirements

Each cluster machine must meet the following minimum requirements:

Machine	Operating System	vCPU	Virtual RAM	Storage
Bootstrap	RHCOS	4	16 GB	120 GB
Control plane	RHCOS	4	16 GB	120 GB
Compute	RHCOS	2	8 GB	120 GB

1.1.3.5. Minimum IBM Z system requirements

You can install OpenShift Container Platform version 4.3 on the following IBM hardware:

- IBM Z: z13, z13s, all z14 models, all z15 models
- LinuxONE: all models

Hardware requirements

- 1 LPAR with 3 IFLs that supports SMT2
- 1 OSA or RoCE network adapter

Operating system requirements

- One instance of z/VM 7.1

On your z/VM instance, set up:

- 3 guest virtual machines for OpenShift Container Platform control plane machines
- 2 guest virtual machines for OpenShift Container Platform compute machines
- 1 guest virtual machine for the temporary OpenShift Container Platform bootstrap machine

Disk storage for the z/VM guest virtual machines

- FICON attached disk storage (DASDs). These can be z/VM minidisks, fullpack minidisks, or dedicated DASDs. To reach the minimum required DASD size for Red Hat Enterprise Linux CoreOS (RHCOS) installations, you need extended address volumes (EAV). If available, use HyperPAV to ensure optimal performance.
- FCP attached disk storage

Storage / Main Memory

- 16 GB for OpenShift Container Platform control plane machines
- 8 GB for OpenShift Container Platform compute machines
- 16 GB for the temporary OpenShift Container Platform bootstrap machine

1.1.3.6. Preferred IBM Z system requirements

Hardware requirements

- 3 LPARs with 6 IFLs each that support SMT2
- 1 or 2 OSA or RoCE network adapters, or both
- Hipersockets, which are attached to a node either directly as a device or by bridging with one z/VM VSWITCH to be transparent to the z/VM guest. To directly connect Hipersockets to a node, you must set up a gateway to the external network via a RHEL 8 guest to bridge to the Hipersockets network.

Operating system requirements

- 2 or 3 instances of z/VM 7.1 for high availability

On your z/VM instances, set up:

- 3 guest virtual machines for OpenShift Container Platform control plane machines, one per z/VM instance
- At least 6 guest virtual machines for OpenShift Container Platform compute machines, distributed across the z/VM instances
- 1 guest virtual machine for the temporary OpenShift Container Platform bootstrap machine

Disk storage for the z/VM guest virtual machines

- FICON attached disk storage (DASDs). These can be z/VM minidisks, fullpack minidisks, or dedicated DASDs. To reach the minimum required DASD size for Red Hat Enterprise Linux CoreOS (RHCOS) installations, you need extended address volumes (EAV). If available, use HyperPAV and High Performance FICON (zHPF) to ensure optimal performance.
- FCP attached disk storage

Storage / Main Memory

- 16 GB for OpenShift Container Platform control plane machines
- 8 GB for OpenShift Container Platform compute machines
- 16 GB for the temporary OpenShift Container Platform bootstrap machine

1.1.3.7. Certificate signing requests management

Because your cluster has limited access to automatic machine management when you use infrastructure that you provision, you must provide a mechanism for approving cluster certificate signing requests (CSRs) after installation. The **kube-controller-manager** only approves the kubelet client CSRs. The **machine-approver** cannot guarantee the validity of a serving certificate that is requested by using kubelet credentials because it cannot confirm that the correct machine issued the request. You must determine and implement a method of verifying the validity of the kubelet serving certificate requests and approving them.

Additional resources

- See [Bridging a HiperSockets LAN with a z/VM Virtual Switch](#) in the IBM Knowledge Center.

- See [Scaling HyperPAV alias devices on Linux guests on z/VM](#) for performance optimization.

1.1.4. Creating the user-provisioned infrastructure

Before you deploy an OpenShift Container Platform cluster that uses user-provisioned infrastructure, you must create the underlying infrastructure.

Prerequisites

- Review the [OpenShift Container Platform 4.x Tested Integrations](#) page before you create the supporting infrastructure for your cluster.

Procedure

1. Set up static IP addresses.
2. Set up an FTP server.
3. Provision the required load balancers.
4. Configure the ports for your machines.
5. Configure DNS.
6. Ensure network connectivity.

1.1.4.1. Networking requirements for user-provisioned infrastructure

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config from the Machine Config Server.

During the initial boot, the machines require an FTP server in order to establish a network connection to download their Ignition config files.

Ensure that the machines have persistent IP addresses and host names.

The Kubernetes API server, which runs on each master node after a successful cluster installation, must be able to resolve the node names of the cluster machines. If the API servers and worker nodes are in different zones, you can configure a default DNS search zone to allow the API server to resolve the node names. Another supported approach is to always refer to hosts by their fully-qualified domain names in both the node objects and all DNS requests.

You must configure the network connectivity between machines to allow cluster components to communicate. Each machine must be able to resolve the host names of all other machines in the cluster.

Table 1.1. All machines to all machines

Protocol	Port	Description
ICMP	N/A	Network reachability tests
TCP	9000-9999	Host level services, including the node exporter on ports 9100-9101 and the Cluster Version Operator on port 9099 .

Protocol	Port	Description
	10250-10259	The default ports that Kubernetes reserves
	10256	openshift-sdn
UDP	4789	VXLAN and GENEVE
	6081	VXLAN and GENEVE
	9000-9999	Host level services, including the node exporter on ports 9100-9101 .
TCP/UDP	30000-32767	Kubernetes NodePort

Table 1.2. All machines to control plane

Protocol	Port	Description
TCP	2379-2380	etcd server, peer, and metrics ports
	6443	Kubernetes API

Network topology requirements

The infrastructure that you provision for your cluster must meet the following network topology requirements.



IMPORTANT

OpenShift Container Platform requires all nodes to have internet access to pull images for platform containers and provide telemetry data to Red Hat.

Load balancers

Before you install OpenShift Container Platform, you must provision two load balancers that meet the following requirements:

1. **API load balancer.** Provides a common endpoint for users, both human and machine, to interact with and configure the platform. Configure the following conditions:
 - Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
 - A stateless load balancing algorithm. The options vary based on the load balancer implementation.



NOTE

Session persistence is not required for the API load balancer to function properly.

Configure the following ports on both the front and back of the load balancers:

Table 1.3. API load balancer

Port	Back-end machines (pool members)	Internal	External	Description
6443	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane. You must configure the /readyz endpoint for the API server health check probe.	X	X	Kubernetes API server
22623	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane.	X		Machine Config server



NOTE

The load balancer must be configured to take a maximum of 30 seconds from the time the API server turns off the **/readyz** endpoint to the removal of the API server instance from the pool. Within the time frame after **/readyz** returns an error or becomes healthy, the endpoint must have been removed or added. Probing every 5 or 10 seconds, with two successful requests to become healthy and three to become unhealthy, are well-tested values.

2. **Application Ingress load balancer:** Provides an Ingress point for application traffic flowing in from outside the cluster. Configure the following conditions:
 - Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
 - A connection-based or session-based persistence is recommended, based on the options available and types of applications that will be hosted on the platform.

Configure the following ports on both the front and back of the load balancers:

Table 1.4. Application Ingress load balancer

Port	Back-end machines (pool members)	Internal	External	Description
443	The machines that run the Ingress router pods, compute, or worker, by default.	X	X	HTTPS traffic
80	The machines that run the Ingress router pods, compute, or worker by default.	X	X	HTTP traffic

TIP

If the true IP address of the client can be seen by the load balancer, enabling source IP-based session persistence can improve performance for applications that use end-to-end TLS encryption.

**NOTE**

A working configuration for the Ingress router is required for an OpenShift Container Platform cluster. You must configure the Ingress router after the control plane initializes.

1.1.4.2. User-provisioned DNS requirements

The following DNS records are required for an OpenShift Container Platform cluster that uses user-provisioned infrastructure. In each record, **<cluster_name>** is the cluster name and **<base_domain>** is the cluster base domain that you specify in the **install-config.yaml** file. A complete DNS record takes the form: **<component>.<cluster_name>.<base_domain>.**

Table 1.5. Required DNS records

Component	Record	Description
Kubernetes API	api.<cluster_name>.<base_domain>.	This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.
	api-int.<cluster_name>.<base_domain>.	This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable from all the nodes within the cluster.

IMPORTANT

The API server must be able to resolve the worker nodes by the host names that are recorded in Kubernetes. If it cannot resolve the node names, proxied API calls can fail, and you cannot retrieve logs from Pods.

Component	Record	Description
Routes	*.apps.<cluster_name>.<base_domain>.	A wildcard DNS A/AAAA or CNAME record that points to the load balancer that targets the machines that run the Ingress router pods, which are the worker nodes by default. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.
etcd	etcd-<index>.<cluster_name>.<base_domain>.	OpenShift Container Platform requires DNS A/AAAA records for each etcd instance to point to the control plane machines that host the instances. The etcd instances are differentiated by <index> values, which start with 0 and end with n-1 , where n is the number of control plane machines in the cluster. The DNS record must resolve to an unicast IPv4 address for the control plane machine, and the records must be resolvable from all the nodes in the cluster.

Component	Record	Description
	<code>_etcd-server-ssl._tcp.<cluster_name>.<base_domain>.</code>	<p>For each control plane machine, OpenShift Container Platform also requires a SRV DNS record for etcd server on that machine with priority 0, weight 10 and port 2380. A cluster that uses three control plane machines requires the following records:</p> <pre># _service._proto.name. TTL class SRV priority weight port target. _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 0.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 1.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 2.<cluster_name>. <base_domain></pre>

1.1.5. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



NOTE

In a production environment, you require disaster recovery and debugging.



IMPORTANT

Do not skip this procedure in production environments where disaster recovery and debugging is required.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's `~/.ssh/authorized_keys` list.

Procedure

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N "" \
-f <path>/<file_name> 1
```

- 1 Specify the path and file name, such as `~/.ssh/id_rsa`, of the SSH key. Do not specify an existing SSH key, as it will be overwritten.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1
Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```

- 1 Specify the path and file name for your SSH private key, such as `~/.ssh/id_rsa`

Next steps

- When you install OpenShift Container Platform, provide the SSH public key to the installation program.

1.1.6. Obtaining the installation program

Before you install OpenShift Container Platform, download the installation file on your provisioning machine.

Prerequisites

- You must install the cluster from a machine that runs Linux, for example Red Hat Enterprise Linux 8.
- You need 500 MB of local disk space to download the installation program.

Procedure

1. Access the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.
2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.

**IMPORTANT**

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.

**IMPORTANT**

Deleting the files created by the installation program does not remove your cluster, even if the cluster failed during installation. You must complete the OpenShift Container Platform uninstallation procedures outlined for your specific cloud provider to remove your cluster entirely.

3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:

```
$ tar xvf <installation_program>.tar.gz
```

4. From the [Pull Secret](#) page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a **.txt** file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

1.1.7. Installing the CLI by downloading the binary

You can install the OpenShift CLI (**oc**) in order to interact with OpenShift Container Platform from a command-line interface. You can install **oc** on Linux, Windows, or macOS.

**IMPORTANT**

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

1.1.7.1. Installing the CLI on Linux

You can install the OpenShift CLI (**oc**) binary on Linux by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.
2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **Linux** from the drop-down menu and click **Download command-line tools**.
4. Unpack the archive:

```
$ tar xvzf <file>
```

5. Place the **oc** binary in a directory that is on your **PATH**. To check your **PATH**, execute the following command:

```
$ echo $PATH
```

After you install the CLI, it is available using the **oc** command:

```
$ oc <command>
```

1.1.7.2. Installing the CLI on Windows

You can install the OpenShift CLI (**oc**) binary on Windows by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.
2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **Windows** from the drop-down menu and click **Download command-line tools**.
4. Unzip the archive with a ZIP program.
5. Move the **oc** binary to a directory that is on your **PATH**.
To check your **PATH**, open the command prompt and execute the following command:

```
C:\> path
```

After you install the CLI, it is available using the **oc** command:

```
C:\> oc <command>
```

1.1.7.3. Installing the CLI on macOS

You can install the OpenShift CLI (**oc**) binary on macOS by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.
2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **MacOS** from the drop-down menu and click **Download command-line tools**.
4. Unpack and unzip the archive.
5. Move the **oc** binary to a directory on your PATH.
To check your **PATH**, open a terminal and execute the following command:

```
$ echo $PATH
```

After you install the CLI, it is available using the **oc** command:

```
$ oc <command>
```

1.1.8. Manually creating the installation configuration file

For installations of OpenShift Container Platform that use user-provisioned infrastructure, you must manually generate your installation configuration file.

Prerequisites

- Obtain the OpenShift Container Platform installation program and the access token for your cluster.

Procedure

1. Create an installation directory to store your required installation assets in:

```
$ mkdir <installation_directory>
```



IMPORTANT

You must create a directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

2. Customize the following **install-config.yaml** file template and save it in the **<installation_directory>**.



NOTE

You must name this configuration file **install-config.yaml**.

3. Back up the **install-config.yaml** file so that you can use it to install multiple clusters.



IMPORTANT

The **install-config.yaml** file is consumed during the next step of the installation process. You must back it up now.

1.1.8.1. Sample install-config.yaml file for IBM Z

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.

```
apiVersion: v1
baseDomain: example.com 1
compute:
- hyperthreading: Enabled 2 3
  name: worker
```

```

replicas: 0 4
controlPlane:
  hyperthreading: Enabled 5 6
  name: master 7
  replicas: 3 8
metadata:
  name: test 9
networking:
  clusterNetwork:
  - cidr: 10.128.0.0/14 10
    hostPrefix: 23 11
  networkType: OpenShiftSDN
  serviceNetwork: 12
  - 172.30.0.0/16
platform:
  none: {} 13
fips: false 14
pullSecret: '{"auths": ...}' 15
sshKey: 'ssh-ed25519 AAAA...' 16

```

- 1 The base domain of the cluster. All DNS records must be sub-domains of this base and include the cluster name.
- 2 5 The **controlPlane** section is a single mapping, but the compute section is a sequence of mappings. To meet the requirements of the different data structures, the first line of the **compute** section must begin with a hyphen, -, and the first line of the **controlPlane** section must not. Although both sections currently define a single machine pool, it is possible that future versions of OpenShift Container Platform will support defining multiple compute pools during installation. Only one control plane pool is used.
- 3 6 7 Whether to enable or disable simultaneous multithreading, or **hyperthreading**. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores. You can disable it by setting the parameter value to **Disabled**. If you disable simultaneous multithreading in some cluster machines, you must disable it in all cluster machines.



IMPORTANT

If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.

- 4 You must set the value of the **replicas** parameter to **0**. This parameter controls the number of workers that the cluster creates and manages for you, which are functions that the cluster does not perform when you use user-provisioned infrastructure. You must manually deploy worker machines for the cluster to use before you finish installing OpenShift Container Platform.
- 8 The number of control plane machines that you add to the cluster. Because the cluster uses this values as the number of etcd endpoints in the cluster, the value must match the number of control plane machines that you deploy.
- 9 The cluster name that you specified in your DNS records.
- 10 A block of IP addresses from which Pod IP addresses are allocated. This block must not overlap with existing physical networks. These IP addresses are used for the Pod network. If you need to access the Pods from an external network, you must configure load balancers and routers to

manage the traffic.

- 11 The subnet prefix length to assign to each individual node. For example, if **hostPrefix** is set to **23**, then each node is assigned a **/23** subnet out of the given **cidr**, which allows for 510 ($2^{(32 - 23)} - 2$) pod IPs addresses. If you are required to provide access to nodes from an external network, configure load balancers and routers to manage the traffic.
- 12 The IP address pool to use for service IP addresses. You can enter only one IP address pool. If you need to access the services from an external network, configure load balancers and routers to manage the traffic.
- 13 You must set the platform to **none**. You cannot provide additional platform configuration variables for IBM Z infrastructure.
- 14 Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the cryptography modules that are provided with RHCOS instead.
- 15 The pullSecret value contains the authentication information for your registry. For `<bastion_host_name>`, specify the registry domain name that you specified in the certificate for your mirror registry, and for `<credentials>`, specify the base64-encoded user name and password for your mirror registry. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.
- 16 The public portion of the default SSH key for the **core** user in Red Hat Enterprise Linux CoreOS (RHCOS).



NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

1.1.9. Creating the Kubernetes manifest and Ignition config files

Because you must modify some cluster definition files and manually start the cluster machines, you must generate the Kubernetes manifest and Ignition config files that the cluster needs to make its machines.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must complete your cluster installation and keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

Prerequisites

- Obtain the OpenShift Container Platform installation program.
- Create the **install-config.yaml** installation configuration file.

Procedure

1. Generate the Kubernetes manifests for the cluster:

```
$ ./openshift-install create manifests --dir=<installation_directory> 1
```

```
INFO Consuming Install Config from target directory
WARNING Making control-plane schedulable by setting MastersSchedulable to true for
Scheduler cluster settings
```

- 1** For **<installation_directory>**, specify the installation directory that contains the **install-config.yaml** file you created.

Because you create your own compute machines later in the installation process, you can safely ignore this warning.

2. Modify the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** Kubernetes manifest file to prevent Pods from being scheduled on the control plane machines:
 - a. Open the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** file.
 - b. Locate the **mastersSchedulable** parameter and set its value to **False**.
 - c. Save and exit the file.



NOTE

Currently, due to a [Kubernetes limitation](#), router Pods running on control plane machines will not be reachable by the ingress load balancer. This step might not be required in a future minor version of OpenShift Container Platform.

3. Obtain the Ignition config files:

```
$ ./openshift-install create ignition-configs --dir=<installation_directory> 1
```

- 1** For **<installation_directory>**, specify the same installation directory.

The following files are generated in the directory:

```
.
├── auth
│   ├── kubeadmin-password
│   └── kubeconfig
├── bootstrap.ign
├── master.ign
├── metadata.json
└── worker.ign
```

1.1.10. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines

Before you install a cluster on IBM Z infrastructure that you provision, you must install RHCOS on z/VM guest virtual machines for the cluster to use. Complete the following steps to create the machines.

Prerequisites

- An FTP server running on your provisioning machine that is accessible to the machines you create.

Procedure

1. Log in to Linux on your provisioning machine.
2. Download the Red Hat Enterprise Linux CoreOS installation files from the [RHCOS image mirror](#).



IMPORTANT

The RHCOS images might not change with every release of OpenShift Container Platform. You must download images with the highest version that is less than or equal to the OpenShift Container Platform version that you install. Use the image versions that match your OpenShift Container Platform version if they are available.

Download the following files:

- The initramfs: **rhcos-<version>-installer-initramfs.img**
 - The kernel: **rhcos-<version>-installer-kernel**
 - The operating system image for the disk on which you want to install RHCOS. This type can differ by virtual machine:
 - rhcos-<version>-s390x-dasd.s390x.raw.gz** for DASD
 - rhcos-<version>-s390x-metal.s390x.raw.gz** for FCP
3. Create parameter files. The following parameters are specific for a particular virtual machine:
 - For **coreos.inst.install_dev=**, specify **dasda** for a DASD installation, or **sda** for FCP. Note that FCP requires **zfcplib.allow_lun_scan=0**.
 - For **rd.dasd=**, specifies the DASD where RHCOS is to be installed.
 - **rd.zfcplib=<adapter>,<wwpn>,<lun>** specifies the FCP disk to install RHCOS on.
 - For **ip=**, specify the following seven entries:
 - i. The IP address for the machine.
 - ii. An empty string.
 - iii. The gateway.
 - iv. The netmask.
 - v. The machine host and domain name in the form **hostname.domainname**. Omit this value to let RHCOS decide set it.
 - vi. The network interface name. Omit this value to let RHCOS decide set it.
 - vii. If you use static IP addresses, an empty string.

- For **coreos.inst.ignition_url=**, specify the Ignition file for the machine role. Use **bootstrap.ign**, **master.ign**, or **worker.ign**.
- All other parameters can stay as they are.
Example parameter file, **bootstrap-0.parm**, for the bootstrap machine:

```
rd.neednet=1 coreos.inst=yes coreos.inst.install_dev=dasda coreos.inst.image_url=ftp://
cl1.provide.example.com:8080/assets/rhcos-43.80.20200430.0-s390x-dasd.390x.raw.gz
coreos.inst.ignition_url=ftp://cl1.provide.example.com:8080/ignition-bootstrap-0
ip=172.18.78.2::172.18.78.1:255.255.255.0::none nameserver=172.18.78.1
rd.znet=qeth,0.0.bdf0,0.0.bdf1,0.0.bdf2,layer2=1,portno=0 zfcplib.allow_lun_scan=0
cio_ignore=all,
!condev rd.dasd=0.0.3490
```

4. Transfer the initramfs, kernel, parameter files, and RHCOS images to z/VM, for example with FTP. For details about how to transfer the files with FTP and boot from the virtual reader, see [Installing under Z/VM](#).
5. Punch the files to the virtual reader of the z/VM guest virtual machine that is to become your bootstrap node.
See [PUNCH](#) in the IBM Knowledge Center.

TIP

You can use the CP PUNCH command or, if you use Linux, the **vmur** command to transfer files between two z/VM guest virtual machines.

6. Log in to CMS on the bootstrap machine.
7. IPL the bootstrap machine from the reader:

```
$ ipl c
```

See [IPL](#) in the IBM Knowledge Center.

8. Repeat this procedure for the other machines in the cluster.

1.1.11. Creating the cluster

To create the OpenShift Container Platform cluster, you wait for the bootstrap process to complete on the machines that you provisioned by using the Ignition config files that you generated with the installation program.

Prerequisites

- Create the required infrastructure for the cluster.
- You obtained the installation program and generated the Ignition config files for your cluster.
- You used the Ignition config files to create RHCOS machines for your cluster.
- Your machines have direct internet access.

Procedure

1. Monitor the bootstrap process:

```
$ ./openshift-install --dir=<installation_directory> wait-for bootstrap-complete \ 1
--log-level=info 2
INFO Waiting up to 30m0s for the Kubernetes API at https://api.test.example.com...
INFO API v1.16.2 up
INFO Waiting up to 30m0s for bootstrapping to complete...
INFO It is now safe to remove the bootstrap resources
```

- 1 For **<installation_directory>**, specify the path to the directory that you stored the installation files in.
- 2 To view different installation details, specify **warn**, **debug**, or **error** instead of **info**.

The command succeeds when the Kubernetes API server signals that it has been bootstrapped on the control plane machines.

2. After bootstrap process is complete, remove the bootstrap machine from the load balancer.



IMPORTANT

You must remove the bootstrap machine from the load balancer at this point. You can also remove or reformat the machine itself.

1.1.12. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

Prerequisites

- Deploy an OpenShift Container Platform cluster.
- Install the **oc** CLI.

Procedure

1. Export the **kubeadmin** credentials:

```
$ export KUBECONFIG=<installation_directory>/auth/kubeconfig 1
```

- 1 For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

2. Verify you can run **oc** commands successfully using the exported configuration:

```
$ oc whoami
system:admin
```

1.1.13. Approving the CSRs for your machines

When you add machines to a cluster, two pending certificates signing request (CSRs) are generated for each machine that you added. You must confirm that these CSRs are approved or, if necessary, approve them yourself.

Prerequisites

- You added machines to your cluster.

Procedure

- Confirm that the cluster recognizes the machines:

```
# oc get nodes

NAME                STATUS  ROLES  AGE  VERSION
master-01.example.com Ready  master  40d  v1.16.2
master-02.example.com Ready  master  40d  v1.16.2
master-03.example.com Ready  master  40d  v1.16.2
worker-01.example.com Ready  worker  40d  v1.16.2
worker-02.example.com Ready  worker  40d  v1.16.2
```

The output lists all of the machines that you created.

- Review the pending certificate signing requests (CSRs) and ensure that the you see a client and server request with **Pending** or **Approved** status for each machine that you added to the cluster:

```
$ oc get csr

NAME      AGE  REQUESTOR                                CONDITION
csr-mddf5 20m  system:node:master-01.example.com  Approved,Issued
csr-z5rln 16m  system:node:worker-21.example.com  Approved,Issued
```

- If the CSRs were not approved, after all of the pending CSRs for the machines you added are in **Pending** status, approve the CSRs for your cluster machines:



NOTE

Because the CSRs rotate automatically, approve your CSRs within an hour of adding the machines to the cluster. If you do not approve them within an hour, the certificates will rotate, and more than two certificates will be present for each node. You must approve all of these certificates. After you approve the initial CSRs, the subsequent node client CSRs are automatically approved by the cluster **kube-controller-manager**. You must implement a method of automatically approving the kubelet serving certificate requests.

- To approve them individually, run the following command for each valid CSR:

```
$ oc adm certificate approve <csr_name> 1
```

- 1** **<csr_name>** is the name of a CSR from the list of current CSRs.

- To approve all pending CSRs, run the following command:

```
$ oc get csr -o go-template='{{range .items}}{{if not .status}}{{.metadata.name}}{\n"}\n{{end}}\n{{end}}' | xargs oc adm certificate approve
```

1.1.14. Initial Operator configuration

After the control plane initializes, you must immediately configure some Operators so that they all become available.

Prerequisites

- Your control plane has initialized.

Procedure

1. Watch the cluster components come online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED	SINCE
authentication	4.3.0	True	False	False	40d
cloud-credential	4.3.0	True	False	False	40d
cluster-autoscaler	4.3.0	True	False	False	40d
console	4.3.0	True	False	False	6d2h
dns	4.3.0	True	False	False	22d
image-registry	4.3.0	True	False	False	6d2h
ingress	4.3.0	True	False	False	6d2h
insights	4.3.0	True	False	False	40d
kube-apiserver	4.3.0	True	False	False	40d
kube-controller-manager	4.3.0	True	False	False	40d
kube-scheduler	4.3.0	True	False	False	40d
machine-api	4.3.0	True	False	False	40d
machine-config	4.3.0	True	False	False	22d
marketplace	4.3.0	True	False	False	40d
monitoring	4.3.0	True	False	False	6d16h
network	4.3.0	True	False	False	40d
node-tuning	4.3.0	True	False	False	22d
openshift-apiserver	4.3.0	True	False	False	22d
openshift-controller-manager	4.3.0	True	False	False	6d2h
openshift-samples	4.3.0	True	False	False	40d
operator-lifecycle-manager	4.3.0	True	False	False	40d
operator-lifecycle-manager-catalog	4.3.0	True	False	False	40d
operator-lifecycle-manager-packageserver	4.3.0	True	False	False	6d2h
service-ca	4.3.0	True	False	False	40d
service-catalog-apiserver	4.3.0	True	False	False	40d
service-catalog-controller-manager	4.3.0	True	False	False	40d
storage	4.3.0	True	False	False	40d

2. Configure the Operators that are not available.

1.1.14.1. Image registry storage configuration

The **image-registry** Operator is not initially available for platforms that do not provide default storage. After installation, you must configure your registry to use storage so the Registry Operator is made available.

Instructions for both configuring a PersistentVolume, which is required for production clusters, and for configuring an empty directory as the storage location, which is available for only non-production clusters, are shown.

1.1.14.1.1. Configuring registry storage for IBM Z

As a cluster administrator, following installation you must configure your registry to use storage.

Prerequisites

- Cluster administrator permissions.
- A cluster on IBM Z.
- Provision persistent storage for your cluster, such as NFS. To deploy a private image registry, your storage must provide ReadWriteMany access mode.
- Must have "100Gi" capacity.

Procedure

1. To configure your registry to use storage, change the **spec.storage.pvc** in the **configs.imageregistry/cluster** resource.



NOTE

When using shared storage such as NFS, it is strongly recommended to use the **supplementalGroups** strategy, which dictates the allowable supplemental groups for the Security Context, rather than the **fsGroup** ID. Refer to the **NFS Group IDs** documentation for details.

2. Verify you do not have a registry Pod:

```
$ oc get pod -n openshift-image-registry
```



NOTE

- If the storage type is **emptyDIR**, the replica number cannot be greater than **1**.
- If the storage type is **NFS**, you must enable the **no_wdelay** and **root_squash** mount options. For example:

```
# cat /etc/exports
/mnt/data *(rw,sync,no_wdelay,root_squash,insecure,fsid=0)
sh-4.3# exportfs -rv
exporting */mnt/data
```

3. Check the registry configuration:

```
$ oc edit configs.imageregistry.operator.openshift.io

storage:
```

```
pvc:
  claim:
```

Leave the **claim** field blank to allow the automatic creation of an **image-registry-storage** PVC.

4. Check the **clusteroperator** status:

```
$ oc get clusteroperator image-registry
```

1.1.14.1.2. Configuring storage for the image registry in non-production clusters

You must configure storage for the image registry Operator. For non-production clusters, you can set the image registry to an empty directory. If you do so, all images are lost if you restart the registry.

Procedure

- To set the image registry storage to an empty directory:

```
$ oc patch configs.imageregistry.operator.openshift.io cluster --type merge --patch '{"spec": {"storage":{"emptyDir":{}}}'
```



WARNING

Configure this option for only non-production clusters.

If you run this command before the Image Registry Operator initializes its components, the **oc patch** command fails with the following error:

```
Error from server (NotFound): configs.imageregistry.operator.openshift.io "cluster" not found
```

Wait a few minutes and run the command again.

1.1.15. Completing installation on user-provisioned infrastructure

After you complete the Operator configuration, you can finish installing the cluster on infrastructure that you provide.

Prerequisites

- Your control plane has initialized.
- You have completed the initial Operator configuration.

Procedure

1. Confirm that all the cluster components are online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED	SINCE
authentication	4.3.0	True	False	False	10m
cloud-credential	4.3.0	True	False	False	22m
cluster-autoscaler	4.3.0	True	False	False	21m
console	4.3.0	True	False	False	10m
dns	4.3.0	True	False	False	21m
image-registry	4.3.0	True	False	False	16m
ingress	4.3.0	True	False	False	16m
kube-apiserver	4.3.0	True	False	False	19m
kube-controller-manager	4.3.0	True	False	False	18m
kube-scheduler	4.3.0	True	False	False	22m
machine-api	4.3.0	True	False	False	22m
machine-config	4.3.0	True	False	False	18m
marketplace	4.3.0	True	False	False	18m
monitoring	4.3.0	True	False	False	18m
network	4.3.0	True	False	False	16m
node-tuning	4.3.0	True	False	False	21m
openshift-apiserver	4.3.0	True	False	False	21m
openshift-controller-manager	4.3.0	True	False	False	17m
openshift-samples	4.3.0	True	False	False	14m
operator-lifecycle-manager	4.3.0	True	False	False	21m
operator-lifecycle-manager-catalog	4.3.0	True	False	False	21m
service-ca	4.3.0	True	False	False	21m
service-catalog-apiserver	4.3.0	True	False	False	16m
service-catalog-controller-manager	4.3.0	True	False	False	16m
storage	4.3.0	True	False	False	16m

When all of the cluster Operators are **AVAILABLE**, you can complete the installation.

2. Monitor for cluster completion:

```
$ ./openshift-install --dir=<installation_directory> wait-for install-complete 1
INFO Waiting up to 30m0s for the cluster to initialize...
```

- 1** For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

The command succeeds when the Cluster Version Operator finishes deploying the OpenShift Container Platform cluster from Kubernetes API server.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

3. Confirm that the Kubernetes API server is communicating with the Pods.

- a. To view a list of all Pods, use the following command:

```
$ oc get pods --all-namespaces
```

```

NAMESPACE          NAME          READY  STATUS
RESTARTS  AGE
openshift-apiserver-operator  openshift-apiserver-operator-85cb746d55-zqhs8  1/1
Running    1    9m
openshift-apiserver          apiserver-67b9g          1/1  Running  0
3m
openshift-apiserver          apiserver-ljcmx          1/1  Running  0
1m
openshift-apiserver          apiserver-z25h4          1/1  Running  0
2m
openshift-authentication-operator  authentication-operator-69d5d8bf84-vh2n8  1/1
Running    0    5m
...

```

- b. View the logs for a Pod that is listed in the output of the previous command by using the following command:

```
$ oc logs <pod_name> -n <namespace> ❶
```

- ❶ Specify the Pod name and namespace, as shown in the output of the previous command.

If the Pod logs display, the Kubernetes API server can communicate with the cluster machines.

1.1.16. Collecting debugging information

You can gather debugging information that might help you to troubleshoot and debug certain issues with an OpenShift Container Platform installation on IBM Z.

Prerequisites

- The **oc** CLI tool installed.

Procedure

1. Log in to the cluster:

```
$ oc login
```

2. On the node you want to gather hardware information about, start a debugging container:

```
$ oc debug node/<nodename>
```

3. Change to the **/host** file system and start **toolbox**:

```
$ chroot /host
$ toolbox
```

4. Collect the **dbginfo** data:

```
$ dbginfo.sh
```

-
- 5. You can then retrieve the data, for example, using **scp**.

Additional resources

- See also [How to generate SOSREPORT within OpenShift4 nodes without SSH](#) .

1.1.17. Next steps

- [Customize your cluster](#).
- If necessary, you can [opt out of remote health reporting](#) .

1.2. INSTALLING A CLUSTER ON IBM Z AND LINUXONE IN A RESTRICTED NETWORK

In OpenShift Container Platform version 4.3, you can install a cluster on IBM Z and LinuxONE infrastructure that you provision in a restricted network.



NOTE

While this document refers only to IBM Z, all information in it also applies to LinuxONE.



IMPORTANT

Additional considerations exist for non-bare metal platforms. Review the information in the [guidelines for deploying OpenShift Container Platform on non-tested platforms](#) before you install an OpenShift Container Platform cluster.

1.2.1. Prerequisites

- [Create a mirror registry on your bastion host](#) and obtain the **imageContentSources** data for your version of OpenShift Container Platform.
- Before you begin the disconnected installation process, you must move or remove the existing **/usr/local/bin/openshift-install** bastion file. This ensures that the updated **/usr/local/bin/openshift-install** file is created during the disconnected installation process.



IMPORTANT

Because the installation media is on the bastion host, use that computer to complete all installation steps.

- Provision [persistent storage](#) using NFS for your cluster. To deploy a private image registry, your storage must provide ReadWriteMany access modes.
- Review details about the [OpenShift Container Platform installation and update](#) processes.
- If you use a firewall and plan to use telemetry, you must [configure the firewall to allow the sites](#) that your cluster requires access to.

**NOTE**

Be sure to also review this site list if you are configuring a proxy.

1.2.2. About installations in restricted networks

In OpenShift Container Platform 4.3, you can perform an installation that does not require an active connection to the internet to obtain software components. You complete an installation in a restricted network on only infrastructure that you provision, not infrastructure that the installation program provisions, so your platform selection is limited.

If you choose to perform a restricted network installation on a cloud platform, you still require access to its cloud APIs. Some cloud functions, like Amazon Web Service's IAM service, require internet access, so you might still require internet access. Depending on your network, you might require less internet access for an installation on bare metal hardware or on VMware vSphere.

To complete a restricted network installation, you must create a registry that mirrors the contents of the OpenShift Container Platform registry and contains the installation media. You can create this registry on a mirror host, which can access both the internet and your closed network, or by using other methods that meet your restrictions.

**IMPORTANT**

Restricted network installations always use user-provisioned infrastructure. Because of the complexity of the configuration for user-provisioned installations, consider completing a standard user-provisioned infrastructure installation before you attempt a restricted network installation. Completing this test installation might make it easier to isolate and troubleshoot any issues that might arise during your installation in a restricted network.

1.2.2.1. Additional limits

Clusters in restricted networks have the following additional limitations and restrictions:

- The ClusterVersion status includes an **Unable to retrieve available updates** error.
- By default, you cannot use the contents of the Developer Catalog because you cannot access the required ImageStreamTags.

1.2.3. Machine requirements for a cluster with user-provisioned infrastructure

For a cluster that contains user-provisioned infrastructure, you must deploy all of the required machines.

1.2.3.1. Required machines

The smallest OpenShift Container Platform clusters require the following hosts:

- One temporary bootstrap machine
- Three control plane, or master, machines
- At least two compute machines, which are also known as worker machines

**NOTE**

The cluster requires the bootstrap machine to deploy the OpenShift Container Platform cluster on the three control plane machines. You can remove the bootstrap machine after you install the cluster.

**IMPORTANT**

To improve high availability of your cluster, distribute the control plane machines over different z/VM instances on at least two physical machines.

The bootstrap, control plane, and compute machines must use the Red Hat Enterprise Linux CoreOS (RHCOS) as the operating system.

Note that RHCOS is based on Red Hat Enterprise Linux 8 and inherits all of its hardware certifications and requirements. See [Red Hat Enterprise Linux technology capabilities and limits](#) .

1.2.3.2. Network connectivity requirements

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config files from the Machine Config Server. The machines are configured with static IP addresses. No DHCP server is required.

1.2.3.3. IBM Z network connectivity requirements

To install on IBM Z under z/VM, you require a single z/VM virtual NIC in layer 2 mode. You also need:

- A direct-attached OSA or RoCE network adapter
- A z/VM VSWITCH set up. For a preferred setup, use OSA link aggregation.

1.2.3.4. Minimum resource requirements

Each cluster machine must meet the following minimum requirements:

Machine	Operating System	vCPU	Virtual RAM	Storage
Bootstrap	RHCOS	4	16 GB	120 GB
Control plane	RHCOS	4	16 GB	120 GB
Compute	RHCOS	2	8 GB	120 GB

1.2.3.5. Minimum IBM Z system requirements

You can install OpenShift Container Platform version 4.3 on the following IBM hardware:

- IBM Z: z13, z13s, all z14 models, all z15 models
- LinuxONE: all models

Hardware requirements

- 1 LPAR with 3 IFLs that supports SMT2
- 1 OSA or RoCE network adapter

Operating system requirements

- One instance of z/VM 7.1

On your z/VM instance, set up:

- 3 guest virtual machines for OpenShift Container Platform control plane machines
- 2 guest virtual machines for OpenShift Container Platform compute machines
- 1 guest virtual machine for the temporary OpenShift Container Platform bootstrap machine

Disk storage for the z/VM guest virtual machines

- FICON attached disk storage (DASDs). These can be z/VM minidisks, fullpack minidisks, or dedicated DASDs. To reach the minimum required DASD size for Red Hat Enterprise Linux CoreOS (RHCOS) installations, you need extended address volumes (EAV). If available, use HyperPAV to ensure optimal performance.
- FCP attached disk storage

Storage / Main Memory

- 16 GB for OpenShift Container Platform control plane machines
- 8 GB for OpenShift Container Platform compute machines
- 16 GB for the temporary OpenShift Container Platform bootstrap machine

1.2.3.6. Preferred IBM Z system requirements

Hardware requirements

- 3 LPARs with 6 IFLs each that support SMT2
- 1 or 2 OSA or RoCE network adapters, or both
- Hipersockets, which are attached to a node either directly as a device or by bridging with one z/VM VSWITCH to be transparent to the z/VM guest. To directly connect Hipersockets to a node, you must set up a gateway to the external network via a RHEL 8 guest to bridge to the Hipersockets network.

Operating system requirements

- 2 or 3 instances of z/VM 7.1 for high availability

On your z/VM instances, set up:

- 3 guest virtual machines for OpenShift Container Platform control plane machines, one per z/VM instance
- At least 6 guest virtual machines for OpenShift Container Platform compute machines, distributed across the z/VM instances

- 1 guest virtual machine for the temporary OpenShift Container Platform bootstrap machine

Disk storage for the z/VM guest virtual machines

- FICON attached disk storage (DASDs). These can be z/VM minidisks, fullpack minidisks, or dedicated DASDs. To reach the minimum required DASD size for Red Hat Enterprise Linux CoreOS (RHCOS) installations, you need extended address volumes (EAV). If available, use HyperPAV and High Performance FICON (zHPF) to ensure optimal performance.
- FCP attached disk storage

Storage / Main Memory

- 16 GB for OpenShift Container Platform control plane machines
- 8 GB for OpenShift Container Platform compute machines
- 16 GB for the temporary OpenShift Container Platform bootstrap machine

1.2.3.7. Certificate signing requests management

Because your cluster has limited access to automatic machine management when you use infrastructure that you provision, you must provide a mechanism for approving cluster certificate signing requests (CSRs) after installation. The **kube-controller-manager** only approves the kubelet client CSRs. The **machine-approver** cannot guarantee the validity of a serving certificate that is requested by using kubelet credentials because it cannot confirm that the correct machine issued the request. You must determine and implement a method of verifying the validity of the kubelet serving certificate requests and approving them.

Additional resources

- See [Bridging a HiperSockets LAN with a z/VM Virtual Switch](#) in the IBM Knowledge Center.
- See [Scaling HyperPAV alias devices on Linux guests on z/VM](#) for performance optimization.

1.2.4. Creating the user-provisioned infrastructure

Before you deploy an OpenShift Container Platform cluster that uses user-provisioned infrastructure, you must create the underlying infrastructure.

Prerequisites

- Review the [OpenShift Container Platform 4.x Tested Integrations](#) page before you create the supporting infrastructure for your cluster.

Procedure

1. Configure DHCP or set static IP addresses on each node.
2. Provision the required load balancers.
3. Configure the ports for your machines.
4. Configure DNS.
5. Ensure network connectivity.

1.2.4.1. Networking requirements for user-provisioned infrastructure

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config from the Machine Config Server.

During the initial boot, the machines require either a DHCP server or that static IP addresses be set on each host in the cluster in order to establish a network connection, which allows them to download their Ignition config files.

It is recommended to use the DHCP server to manage the machines for the cluster long-term. Ensure that the DHCP server is configured to provide persistent IP addresses and host names to the cluster machines.

The Kubernetes API server, which runs on each master node after a successful cluster installation, must be able to resolve the node names of the cluster machines. If the API servers and worker nodes are in different zones, you can configure a default DNS search zone to allow the API server to resolve the node names. Another supported approach is to always refer to hosts by their fully-qualified domain names in both the node objects and all DNS requests.

You must configure the network connectivity between machines to allow cluster components to communicate. Each machine must be able to resolve the host names of all other machines in the cluster.

Table 1.6. All machines to all machines

Protocol	Port	Description
ICMP	N/A	Network reachability tests
TCP	9000-9999	Host level services, including the node exporter on ports 9100-9101 and the Cluster Version Operator on port 9099 .
	10250-10259	The default ports that Kubernetes reserves
	10256	openshift-sdn
UDP	4789	VXLAN and GENEVE
	6081	VXLAN and GENEVE
	9000-9999	Host level services, including the node exporter on ports 9100-9101 .
TCP/UDP	30000-32767	Kubernetes NodePort

Table 1.7. All machines to control plane

Protocol	Port	Description
TCP	2379-2380	etcd server, peer, and metrics ports
	6443	Kubernetes API


Network topology requirements

The infrastructure that you provision for your cluster must meet the following network topology requirements.

Load balancers

Before you install OpenShift Container Platform, you must provision two load balancers that meet the following requirements:

1. **API load balancer.** Provides a common endpoint for users, both human and machine, to interact with and configure the platform. Configure the following conditions:
 - Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
 - A stateless load balancing algorithm. The options vary based on the load balancer implementation.



NOTE

Session persistence is not required for the API load balancer to function properly.

Configure the following ports on both the front and back of the load balancers:

Table 1.8. API load balancer

Port	Back-end machines (pool members)	Internal	External	Description
6443	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane. You must configure the /readyz endpoint for the API server health check probe.	X	X	Kubernetes API server
22623	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane.	X		Machine Config server



NOTE

The load balancer must be configured to take a maximum of 30 seconds from the time the API server turns off the **/readyz** endpoint to the removal of the API server instance from the pool. Within the time frame after **/readyz** returns an error or becomes healthy, the endpoint must have been removed or added. Probing every 5 or 10 seconds, with two successful requests to become healthy and three to become unhealthy, are well-tested values.

2. **Application Ingress load balancer.** Provides an Ingress point for application traffic flowing in from outside the cluster. Configure the following conditions:

- Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
- A connection-based or session-based persistence is recommended, based on the options available and types of applications that will be hosted on the platform.

Configure the following ports on both the front and back of the load balancers:

Table 1.9. Application Ingress load balancer

Port	Back-end machines (pool members)	Internal	External	Description
443	The machines that run the Ingress router pods, compute, or worker, by default.	X	X	HTTPS traffic
80	The machines that run the Ingress router pods, compute, or worker by default.	X	X	HTTP traffic

TIP

If the true IP address of the client can be seen by the load balancer, enabling source IP-based session persistence can improve performance for applications that use end-to-end TLS encryption.



NOTE

A working configuration for the Ingress router is required for an OpenShift Container Platform cluster. You must configure the Ingress router after the control plane initializes.

1.2.4.2. User-provisioned DNS requirements

The following DNS records are required for an OpenShift Container Platform cluster that uses user-provisioned infrastructure. In each record, **<cluster_name>** is the cluster name and **<base_domain>** is the cluster base domain that you specify in the **install-config.yaml** file. A complete DNS record takes the form: **<component>.<cluster_name>.<base_domain>..**

Table 1.10. Required DNS records

Component	Record	Description
Kubernetes API	api.<cluster_name>.<base_domain>.	This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.

Component	Record	Description
	api-int.<cluster_name>.<base_domain>.	<p>This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable from all the nodes within the cluster.</p> <div data-bbox="1040 517 1147 987" style="background-color: black; width: 67px; height: 210px; margin-bottom: 10px;"></div> <p>IMPORTANT</p> <p>The API server must be able to resolve the worker nodes by the host names that are recorded in Kubernetes. If it cannot resolve the node names, proxied API calls can fail, and you cannot retrieve logs from Pods.</p>
Routes	*.apps.<cluster_name>.<base_domain>.	<p>A wildcard DNS A/AAAA or CNAME record that points to the load balancer that targets the machines that run the Ingress router pods, which are the worker nodes by default. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.</p>
etcd	etcd-<index>.<cluster_name>.<base_domain>.	<p>OpenShift Container Platform requires DNS A/AAAA records for each etcd instance to point to the control plane machines that host the instances. The etcd instances are differentiated by <index> values, which start with 0 and end with n-1, where n is the number of control plane machines in the cluster. The DNS record must resolve to an unicast IPv4 address for the control plane machine, and the records must be resolvable from all the nodes in the cluster.</p>

Component	Record	Description
	<code>_etcd-server-ssl._tcp.<cluster_name>.<base_domain>.</code>	<p>For each control plane machine, OpenShift Container Platform also requires a SRV DNS record for etcd server on that machine with priority 0, weight 10 and port 2380. A cluster that uses three control plane machines requires the following records:</p> <pre># _service._proto.name. TTL class SRV priority weight port target. _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 0.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 1.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 2.<cluster_name>. <base_domain></pre>

1.2.5. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



NOTE

In a production environment, you require disaster recovery and debugging.



IMPORTANT

Do not skip this procedure in production environments where disaster recovery and debugging is required.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's `~/.ssh/authorized_keys` list.

Procedure

Procedure

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N "" \
-f <path>/<file_name> 1
```

- 1 Specify the path and file name, such as `~/.ssh/id_rsa`, of the SSH key. Do not specify an existing SSH key, as it will be overwritten.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1
Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```

- 1 Specify the path and file name for your SSH private key, such as `~/.ssh/id_rsa`

Next steps

- When you install OpenShift Container Platform, provide the SSH public key to the installation program.

1.2.6. Manually creating the installation configuration file

For installations of OpenShift Container Platform that use user-provisioned infrastructure, you must manually generate your installation configuration file.

Prerequisites

- Obtain the OpenShift Container Platform installation program and the access token for your cluster.

Procedure

1. Create an installation directory to store your required installation assets in:

```
$ mkdir <installation_directory>
```

**IMPORTANT**

You must create a directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

2. Customize the following **install-config.yaml** file template and save it in the **<installation_directory>**.

**NOTE**

You must name this configuration file **install-config.yaml**.

3. Back up the **install-config.yaml** file so that you can use it to install multiple clusters.

**IMPORTANT**

The **install-config.yaml** file is consumed during the next step of the installation process. You must back it up now.

1.2.6.1. Sample install-config.yaml file for IBM Z

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.

```

apiVersion: v1
baseDomain: example.com 1
compute:
- hyperthreading: Enabled 2 3
  name: worker
  replicas: 0 4
controlPlane:
  hyperthreading: Enabled 5 6
  name: master 7
  replicas: 3 8
metadata:
  name: test 9
networking:
  clusterNetwork:
  - cidr: 10.128.0.0/14 10
    hostPrefix: 23 11
  networkType: OpenShiftSDN
  serviceNetwork: 12
  - 172.30.0.0/16
platform:
  none: {} 13
fips: false 14
pullSecret: '{"auths":{"<mirror_registry>":{"auth": "<credentials>","email": "you@example.com"}}}' 15
sshKey: 'ssh-ed25519 AAAA...' 16

```


- 13 You must set the platform to **none**. You cannot provide additional platform configuration variables for IBM Z infrastructure.
- 14 Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the cryptography modules that are provided with RHCOS instead.
- 15 For **<mirror_registry>**, specify the registry domain name, and optionally the port, that your mirror registry uses to serve content. For example **registry.example.com** or **registry.example.com:5000**. For **<credentials>**, specify the base64-encoded user name and password for your mirror registry.
- 16 The public portion of the default SSH key for the **core** user in Red Hat Enterprise Linux CoreOS (RHCOS).



NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- 17 Add the **additionalTrustBundle** parameter and value. The value must be the contents of the certificate file that you used for your mirror registry, which can be an existing, trusted certificate authority or the self-signed certificate that you generated for the mirror registry.
- 18 Provide the **imageContentSources** section from the output of the command to mirror the repository.

1.2.6.2. Configuring the cluster-wide proxy during installation

Production environments can deny direct access to the Internet and instead have an HTTP or HTTPS proxy available. You can configure a new OpenShift Container Platform cluster to use a proxy by configuring the proxy settings in the **install-config.yaml** file.

Prerequisites

- An existing **install-config.yaml** file.
- Review the sites that your cluster requires access to and determine whether any need to bypass the proxy. By default, all cluster egress traffic is proxied, including calls to hosting cloud provider APIs. Add sites to the Proxy object's **spec.noProxy** field to bypass the proxy if necessary.



NOTE

The Proxy object's **status.noProxy** field is populated by default with the instance metadata endpoint (**169.254.169.254**) and with the values of the **networking.machineCIDR**, **networking.clusterNetwork.cidr**, and **networking.serviceNetwork[]** fields from your installation configuration.

Procedure

1. Edit your **install-config.yaml** file and add the proxy settings. For example:

```

apiVersion: v1
baseDomain: my.domain.com
proxy:
  httpProxy: http://<username>:<pswd>@<ip>:<port> 1
  httpsProxy: http://<username>:<pswd>@<ip>:<port> 2
  noProxy: example.com 3
  additionalTrustBundle: | 4
    -----BEGIN CERTIFICATE-----
    <MY_TRUSTED_CA_CERT>
    -----END CERTIFICATE-----
...

```

- 1 A proxy URL to use for creating HTTP connections outside the cluster. The URL scheme must be **http**. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must not specify an **httpProxy** value.
- 2 A proxy URL to use for creating HTTPS connections outside the cluster. If this field is not specified, then **httpProxy** is used for both HTTP and HTTPS connections. The URL scheme must be **http**; **https** is currently not supported. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must not specify an **httpsProxy** value.
- 3 A comma-separated list of destination domain names, domains, IP addresses, or other network CIDRs to exclude proxying. Preface a domain with `.` to include all subdomains of that domain. Use `*` to bypass proxy for all destinations.
- 4 If provided, the installation program generates a ConfigMap that is named **user-ca-bundle** in the **openshift-config** namespace that contains one or more additional CA certificates that are required for proxying HTTPS connections. The Cluster Network Operator then creates a **trusted-ca-bundle** ConfigMap that merges these contents with the Red Hat Enterprise Linux CoreOS (RHCOS) trust bundle, and this ConfigMap is referenced in the Proxy object's **trustedCA** field. The **additionalTrustBundle** field is required unless the proxy's identity certificate is signed by an authority from the RHCOS trust bundle. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must provide the MITM CA certificate.



NOTE

The installation program does not support the proxy **readinessEndpoints** field.

2. Save the file and reference it when installing OpenShift Container Platform.

The installation program creates a cluster-wide proxy that is named **cluster** that uses the proxy settings in the provided **install-config.yaml** file. If no proxy settings are provided, a **cluster** Proxy object is still created, but it will have a nil **spec**.



NOTE

Only the Proxy object named **cluster** is supported, and no additional proxies can be created.

1.2.7. Creating the Kubernetes manifest and Ignition config files

Because you must modify some cluster definition files and manually start the cluster machines, you must generate the Kubernetes manifest and Ignition config files that the cluster needs to make its machines.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must complete your cluster installation and keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

Prerequisites

- Obtain the OpenShift Container Platform installation program.
- Create the **install-config.yaml** installation configuration file.

Procedure

1. Generate the Kubernetes manifests for the cluster:

```
$ ./openshift-install create manifests --dir=<installation_directory> 1
```

```
INFO Consuming Install Config from target directory
WARNING Making control-plane schedulable by setting MastersSchedulable to true for
Scheduler cluster settings
```

- 1** For **<installation_directory>**, specify the installation directory that contains the **install-config.yaml** file you created.

Because you create your own compute machines later in the installation process, you can safely ignore this warning.

2. Modify the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** Kubernetes manifest file to prevent Pods from being scheduled on the control plane machines:
 - a. Open the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** file.
 - b. Locate the **mastersSchedulable** parameter and set its value to **False**.
 - c. Save and exit the file.



NOTE


Currently, due to a [Kubernetes limitation](#), router Pods running on control plane machines will not be reachable by the ingress load balancer. This step might not be required in a future minor version of OpenShift Container Platform.

3. Obtain the Ignition config files:

```
$ ./openshift-install create ignition-configs --dir=<installation_directory> 1
```

- 1** For **<installation_directory>**, specify the same installation directory.

The following files are generated in the directory:



1.2.8. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines

Before you install a cluster on IBM Z infrastructure that you provision, you must install RHCOS on z/VM guest virtual machines for the cluster to use. Complete the following steps to create the machines.

Prerequisites

- An FTP server running on your provisioning machine that is accessible to the machines you create.

Procedure

1. Log in to Linux on your provisioning machine.
2. Download the Red Hat Enterprise Linux CoreOS installation files from the [RHCOS image mirror](#).



IMPORTANT

The RHCOS images might not change with every release of OpenShift Container Platform. You must download images with the highest version that is less than or equal to the OpenShift Container Platform version that you install. Use the image versions that match your OpenShift Container Platform version if they are available.

Download the following files:

- The initramfs: **rhcos-<version>-installer-initramfs.img**
 - The kernel: **rhcos-<version>-installer-kernel**
 - The operating system image for the disk on which you want to install RHCOS. This type can differ by virtual machine:
 - rhcos-<version>-s390x-dasd.s390x.raw.gz** for DASD
 - rhcos-<version>-s390x-metal.s390x.raw.gz** for FCP
3. Create parameter files. The following parameters are specific for a particular virtual machine:
 - For **coreos.inst.install_dev=**, specify **dasda** for a DASD installation, or **sda** for FCP. Note that FCP requires **zfcplib.allow_lun_scan=0**.
 - For **rd.dasd=**, specifies the DASD where RHCOS is to be installed.
 - **rd.zfcp=<adapter>,<wwpn>,<lun>** specifies the FCP disk to install RHCOS on.

- For **ip=**, specify the following seven entries:
 - i. The IP address for the machine.
 - ii. An empty string.
 - iii. The gateway.
 - iv. The netmask.
 - v. The machine host and domain name in the form **hostname.domainname**. Omit this value to let RHCOS decide set it.
 - vi. The network interface name. Omit this value to let RHCOS decide set it.
 - vii. If you use static IP addresses, an empty string.
- For **coreos.inst.ignition_url=**, specify the Ignition file for the machine role. Use **bootstrap.ign**, **master.ign**, or **worker.ign**.
- All other parameters can stay as they are.
Example parameter file, **bootstrap-0.parm**, for the bootstrap machine:

```
rd.neednet=1 coreos.inst=yes coreos.inst.install_dev=dasda coreos.inst.image_url=ftp://
cl1.provide.example.com:8080/assets/rhcos-43.80.20200430.0-s390x-dasd.390x.raw.gz
coreos.inst.ignition_url=ftp://cl1.provide.example.com:8080/ignition-bootstrap-0
ip=172.18.78.2::172.18.78.1:255.255.255.0::none nameserver=172.18.78.1
rd.znet=qeth,0.0.bdf0,0.0.bdf1,0.0.bdf2,layer2=1,portno=0 zfcpl.allow_lun_scan=0
cio_ignore=all,
lcondev rd.dasd=0.0.3490
```

4. Transfer the initramfs, kernel, parameter files, and RHCOS images to z/VM, for example with FTP. For details about how to transfer the files with FTP and boot from the virtual reader, see [Installing under Z/VM](#).
5. Punch the files to the virtual reader of the z/VM guest virtual machine that is to become your bootstrap node.
See [PUNCH](#) in the IBM Knowledge Center.

TIP

You can use the CP PUNCH command or, if you use Linux, the **vmur** command to transfer files between two z/VM guest virtual machines.

6. Log in to CMS on the bootstrap machine.
7. IPL the bootstrap machine from the reader:

```
$ ipl c
```

See [IPL](#) in the IBM Knowledge Center.

8. Repeat this procedure for the other machines in the cluster.

1.2.9. Creating the cluster

To create the OpenShift Container Platform cluster, you wait for the bootstrap process to complete on the machines that you provisioned by using the Ignition config files that you generated with the installation program.

Prerequisites

- Create the required infrastructure for the cluster.
- You obtained the installation program and generated the Ignition config files for your cluster.
- You used the Ignition config files to create RHCOS machines for your cluster.

Procedure

1. Monitor the bootstrap process:

```
$ ./openshift-install --dir=<installation_directory> wait-for bootstrap-complete \ 1  
--log-level=info 2  
INFO Waiting up to 30m0s for the Kubernetes API at https://api.test.example.com...  
INFO API v1.16.2 up  
INFO Waiting up to 30m0s for bootstrapping to complete...  
INFO It is now safe to remove the bootstrap resources
```

- 1 For **<installation_directory>**, specify the path to the directory that you stored the installation files in.
- 2 To view different installation details, specify **warn**, **debug**, or **error** instead of **info**.

The command succeeds when the Kubernetes API server signals that it has been bootstrapped on the control plane machines.

2. After bootstrap process is complete, remove the bootstrap machine from the load balancer.



IMPORTANT

You must remove the bootstrap machine from the load balancer at this point. You can also remove or reformat the machine itself.

1.2.10. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

Prerequisites

- Deploy an OpenShift Container Platform cluster.
- Install the **oc** CLI.

Procedure

1. Export the **kubeadmin** credentials:

```
$ export KUBECONFIG=<installation_directory>/auth/kubeconfig 1
```

- 1** For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

2. Verify you can run **oc** commands successfully using the exported configuration:

```
$ oc whoami
system:admin
```

1.2.11. Approving the CSRs for your machines

When you add machines to a cluster, two pending certificates signing request (CSRs) are generated for each machine that you added. You must confirm that these CSRs are approved or, if necessary, approve them yourself.

Prerequisites

- You added machines to your cluster.

Procedure

1. Confirm that the cluster recognizes the machines:

```
$ oc get nodes

NAME      STATUS    ROLES    AGE   VERSION
master-0  Ready     master   63m   v1.16.2
master-1  Ready     master   63m   v1.16.2
master-2  Ready     master   64m   v1.16.2
worker-0  NotReady  worker   76s   v1.16.2
worker-1  NotReady  worker   70s   v1.16.2
```

The output lists all of the machines that you created.

2. Review the pending certificate signing requests (CSRs) and ensure that the you see a client and server request with **Pending** or **Approved** status for each machine that you added to the cluster:

```
$ oc get csr

NAME      AGE   REQUESTOR                                     CONDITION
csr-8b2br  15m   system:serviceaccount:openshift-machine-config-operator:node-
bootstrapper  Pending 1
csr-8vnps  15m   system:serviceaccount:openshift-machine-config-operator:node-
bootstrapper  Pending
csr-bfd72  5m26s system:node:ip-10-0-50-126.us-east-2.compute.internal
Pending 2
csr-c57lv  5m26s system:node:ip-10-0-95-157.us-east-2.compute.internal
Pending
...
```

- 1 A client request CSR.
- 2 A server request CSR.

In this example, two machines are joining the cluster. You might see more approved CSRs in the list.

3. If the CSRs were not approved, after all of the pending CSRs for the machines you added are in **Pending** status, approve the CSRs for your cluster machines:



NOTE

Because the CSRs rotate automatically, approve your CSRs within an hour of adding the machines to the cluster. If you do not approve them within an hour, the certificates will rotate, and more than two certificates will be present for each node. You must approve all of these certificates. After you approve the initial CSRs, the subsequent node client CSRs are automatically approved by the cluster **kube-controller-manager**. You must implement a method of automatically approving the kubelet serving certificate requests.

- To approve them individually, run the following command for each valid CSR:

```
$ oc adm certificate approve <csr_name> 1
```

- 1 **<csr_name>** is the name of a CSR from the list of current CSRs.

- To approve all pending CSRs, run the following command:

```
$ oc get csr -o go-template='{{range .items}}{{if not .status}}{{.metadata.name}}{\n"}\n{{end}}' | xargs oc adm certificate approve
```

1.2.12. Initial Operator configuration

After the control plane initializes, you must immediately configure some Operators so that they all become available.

Prerequisites

- Your control plane has initialized.

Procedure

1. Watch the cluster components come online:

```
$ watch -n5 oc get clusteroperators
NAME                                VERSION      AVAILABLE  PROGRESSING
DEGRADED  SINCE
authentication                       4.3.0      True      False      False      40d
cloud-credential                       4.3.0      True      False      False      40d
cluster-autoscaler                    4.3.0      True      False      False      40d
console                               4.3.0      True      False      False      6d2h
dns                                    4.3.0      True      False      False      22d
```

image-registry	4.3.0	True	False	False	6d2h
ingress	4.3.0	True	False	False	6d2h
insights	4.3.0	True	False	False	40d
kube-apiserver	4.3.0	True	False	False	40d
kube-controller-manager	4.3.0	True	False	False	40d
kube-scheduler	4.3.0	True	False	False	40d
machine-api	4.3.0	True	False	False	40d
machine-config	4.3.0	True	False	False	22d
marketplace	4.3.0	True	False	False	40d
monitoring	4.3.0	True	False	False	6d16h
network	4.3.0	True	False	False	40d
node-tuning	4.3.0	True	False	False	22d
openshift-apiserver	4.3.0	True	False	False	22d
openshift-controller-manager	4.3.0	True	False	False	6d2h
openshift-samples	4.3.0	True	False	False	40d
operator-lifecycle-manager	4.3.0	True	False	False	40d
operator-lifecycle-manager-catalog	4.3.0	True	False	False	40d
operator-lifecycle-manager-packageserver	4.3.0	True	False	False	6d2h
service-ca	4.3.0	True	False	False	40d
service-catalog-apiserver	4.3.0	True	False	False	40d
service-catalog-controller-manager	4.3.0	True	False	False	40d
storage	4.3.0	True	False	False	40d

2. Configure the Operators that are not available.

1.2.12.1. Image registry storage configuration

The **image-registry** Operator is not initially available for platforms that do not provide default storage. After installation, you must configure your registry to use storage so the Registry Operator is made available.

Instructions for both configuring a PersistentVolume, which is required for production clusters, and for configuring an empty directory as the storage location, which is available for only non-production clusters, are shown.

1.2.12.1.1. Configuring registry storage for IBM Z

As a cluster administrator, following installation you must configure your registry to use storage.

Prerequisites

- Cluster administrator permissions.
- A cluster on IBM Z.
- Provision persistent storage for your cluster, such as NFS. To deploy a private image registry, your storage must provide ReadWriteMany access mode.
- Must have "100Gi" capacity.

Procedure

1. To configure your registry to use storage, change the **spec.storage.pvc** in the **configs.imageregistry/cluster** resource.

**NOTE**

When using shared storage such as NFS, it is strongly recommended to use the **supplementalGroups** strategy, which dictates the allowable supplemental groups for the Security Context, rather than the **fsGroup** ID. Refer to the **NFS Group IDs** documentation for details.

2. Verify you do not have a registry Pod:

```
$ oc get pod -n openshift-image-registry
```

**NOTE**

- If the storage type is **emptyDIR**, the replica number cannot be greater than **1**.
- If the storage type is **NFS**, you must enable the **no_wdelay** and **root_squash** mount options. For example:

```
# cat /etc/exports
/mnt/data *(rw,sync,no_wdelay,root_squash,insecure,fsid=0)
sh-4.3# exportfs -rv
exporting */mnt/data
```

3. Check the registry configuration:

```
$ oc edit configs.imageregistry.operator.openshift.io

storage:
  pvc:
    claim:
```

Leave the **claim** field blank to allow the automatic creation of an **image-registry-storage** PVC.

4. Check the **clusteroperator** status:

```
$ oc get clusteroperator image-registry
```

1.2.12.1.2. Configuring storage for the image registry in non-production clusters

You must configure storage for the image registry Operator. For non-production clusters, you can set the image registry to an empty directory. If you do so, all images are lost if you restart the registry.

Procedure

- To set the image registry storage to an empty directory:

```
$ oc patch configs.imageregistry.operator.openshift.io cluster --type merge --patch '{"spec": {"storage":{"emptyDir":{}}}'
```

**WARNING**

Configure this option for only non-production clusters.

If you run this command before the Image Registry Operator initializes its components, the **oc patch** command fails with the following error:

```
Error from server (NotFound): configs.imageregistry.operator.openshift.io "cluster" not found
```

Wait a few minutes and run the command again.

1.2.13. Completing installation on user-provisioned infrastructure

After you complete the Operator configuration, you can finish installing the cluster on infrastructure that you provide.

Prerequisites

- Your control plane has initialized.
- You have completed the initial Operator configuration.

Procedure

1. Confirm that all the cluster components are online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED	SINCE
authentication	4.3.0	True	False	False	10m
cloud-credential	4.3.0	True	False	False	22m
cluster-autoscaler	4.3.0	True	False	False	21m
console	4.3.0	True	False	False	10m
dns	4.3.0	True	False	False	21m
image-registry	4.3.0	True	False	False	16m
ingress	4.3.0	True	False	False	16m
kube-apiserver	4.3.0	True	False	False	19m
kube-controller-manager	4.3.0	True	False	False	18m
kube-scheduler	4.3.0	True	False	False	22m
machine-api	4.3.0	True	False	False	22m
machine-config	4.3.0	True	False	False	18m
marketplace	4.3.0	True	False	False	18m
monitoring	4.3.0	True	False	False	18m
network	4.3.0	True	False	False	16m
node-tuning	4.3.0	True	False	False	21m
openshift-apiserver	4.3.0	True	False	False	21m
openshift-controller-manager	4.3.0	True	False	False	17m
openshift-samples	4.3.0	True	False	False	14m
operator-lifecycle-manager	4.3.0	True	False	False	21m

operator-lifecycle-manager-catalog	4.3.0	True	False	False	21m
service-ca	4.3.0	True	False	False	21m
service-catalog-apiserver	4.3.0	True	False	False	16m
service-catalog-controller-manager	4.3.0	True	False	False	16m
storage	4.3.0	True	False	False	16m

When all of the cluster Operators are **AVAILABLE**, you can complete the installation.

2. Monitor for cluster completion:

```
$ ./openshift-install --dir=<installation_directory> wait-for install-complete 1
INFO Waiting up to 30m0s for the cluster to initialize...
```

- 1** For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

The command succeeds when the Cluster Version Operator finishes deploying the OpenShift Container Platform cluster from Kubernetes API server.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

3. Confirm that the Kubernetes API server is communicating with the Pods.
 - a. To view a list of all Pods, use the following command:

```
$ oc get pods --all-namespaces
```

NAMESPACE	NAME	READY	STATUS
RESTARTS AGE			
openshift-apiserver-operator	openshift-apiserver-operator-85cb746d55-zqhs8	1/1	Running 0
Running 1 9m			
openshift-apiserver	apiserver-67b9g	1/1	Running 0
3m			
openshift-apiserver	apiserver-ljcmx	1/1	Running 0
1m			
openshift-apiserver	apiserver-z25h4	1/1	Running 0
2m			
openshift-authentication-operator	authentication-operator-69d5d8bf84-vh2n8	1/1	Running 0
Running 0 5m			
...			

- b. View the logs for a Pod that is listed in the output of the previous command by using the following command:

```
$ oc logs <pod_name> -n <namespace> 1
```

- 1** Specify the Pod name and namespace, as shown in the output of the previous command.

If the Pod logs display, the Kubernetes API server can communicate with the cluster machines.

4. Register your cluster on the [Cluster registration](#) page.

1.2.14. Collecting debugging information

You can gather debugging information that might help you to troubleshoot and debug certain issues with an OpenShift Container Platform installation on IBM Z.

Prerequisites

- The **oc** CLI tool installed.

Procedure

1. Log in to the cluster:

```
$ oc login
```

2. On the node you want to gather hardware information about, start a debugging container:

```
$ oc debug node/<nodename>
```

3. Change to the **/host** file system and start **toolbox**:

```
$ chroot /host  
$ toolbox
```

4. Collect the **dbginfo** data:

```
$ dbginfo.sh
```

5. You can then retrieve the data, for example, using **scp**.

Additional resources

- See also [How to generate SOSREPORT within OpenShift Container Platform version 4 nodes without SSH](#).

1.2.15. Next steps

- [Customize your cluster](#).