



OpenShift Container Platform 4.4

Monitoring

Configuring and using the monitoring stack in OpenShift Container Platform

OpenShift Container Platform 4.4 Monitoring

Configuring and using the monitoring stack in OpenShift Container Platform

Legal Notice

Copyright © 2021 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document provides instructions for configuring and using the Prometheus monitoring stack in OpenShift Container Platform.

Table of Contents

CHAPTER 1. CLUSTER MONITORING	4
1.1. ABOUT CLUSTER MONITORING	4
1.1.1. Stack components and monitored targets	4
1.1.2. Next steps	6
1.2. CONFIGURING THE MONITORING STACK	6
1.2.1. Prerequisites	6
1.2.2. Maintenance and support	6
1.2.3. Creating a cluster monitoring config map	7
1.2.4. Configuring the cluster monitoring stack	7
1.2.5. Configurable monitoring components	9
1.2.6. Moving monitoring components to different nodes	9
1.2.7. Assigning tolerations to monitoring components	11
1.2.8. Configuring persistent storage	12
1.2.9. Prerequisites	12
1.2.9.1. Configuring a local persistent volume claim	12
1.2.9.2. Modifying retention time for Prometheus metrics data	14
1.2.10. Configuring Alertmanager	15
1.2.10.1. Alertmanager default configuration	15
1.2.10.2. Applying custom Alertmanager configuration	16
1.2.10.3. Alerting rules	17
1.2.10.4. Listing acting alerting rules	18
1.2.11. Next steps	18
1.3. MANAGING CLUSTER ALERTS	19
1.3.1. Contents of the Alerting UI	19
1.3.2. Getting information about alerts and alerting rules	21
1.3.3. Silencing alerts	23
1.3.4. Getting information about silences	24
1.3.5. Editing silences	24
1.3.6. Expiring silences	24
1.3.7. Next steps	25
1.4. EXAMINING CLUSTER METRICS	25
1.4.1. Contents of the Metrics UI	25
1.4.2. Running metrics queries	27
1.4.3. Exploring the visualized metrics	28
1.4.4. Non-administrator access to metrics	28
1.4.5. Next steps	29
1.5. ACCESSING PROMETHEUS, ALERTMANAGER, AND GRAFANA	29
1.5.1. Accessing Prometheus, Alerting UI, and Grafana using the web console	29
1.5.2. Accessing Prometheus, Alertmanager, and Grafana directly	29
CHAPTER 2. MONITORING YOUR OWN SERVICES	31
2.1. ENABLING MONITORING OF YOUR OWN SERVICES	31
2.2. DEPLOYING A SAMPLE SERVICE	32
2.3. CREATING A ROLE FOR SETTING UP METRICS COLLECTION	33
2.4. GRANTING THE ROLE TO A USER	34
2.5. SETTING UP METRICS COLLECTION	34
2.6. CREATING ALERTING RULES	35
2.7. GIVING VIEW ACCESS TO A USER	36
2.8. ACCESSING THE METRICS OF YOUR SERVICE	37
CHAPTER 3. EXPOSING CUSTOM APPLICATION METRICS FOR AUTOSCALING	39

CHAPTER 1. CLUSTER MONITORING

1.1. ABOUT CLUSTER MONITORING

OpenShift Container Platform includes a pre-configured, pre-installed, and self-updating monitoring stack that is based on the [Prometheus](#) open source project and its wider eco-system. It provides monitoring of cluster components and includes a set of alerts to immediately notify the cluster administrator about any occurring problems and a set of [Grafana](#) dashboards. The cluster monitoring stack is only supported for monitoring OpenShift Container Platform clusters.



IMPORTANT

To ensure compatibility with future OpenShift Container Platform updates, configuring only the specified monitoring stack options is supported.

1.1.1. Stack components and monitored targets

The monitoring stack includes these components:

Table 1.1. Monitoring stack components

Component	Description
Cluster Monitoring Operator	The OpenShift Container Platform Cluster Monitoring Operator (CMO) is the central component of the stack. It controls the deployed monitoring components and resources and ensures that they are always up to date.
Prometheus Operator	The Prometheus Operator (PO) creates, configures, and manages Prometheus and Alertmanager instances. It also automatically generates monitoring target configurations based on familiar Kubernetes label queries.
Prometheus	The Prometheus is the systems and service monitoring system, around which the monitoring stack is based.
Prometheus Adapter	The Prometheus Adapter exposes cluster resource metrics API for horizontal pod autoscaling. Resource metrics are CPU and memory utilization.
Alertmanager	The Alertmanager service handles alerts sent by Prometheus.
kube-state-metrics	The kube-state-metrics exporter agent converts Kubernetes objects to metrics that Prometheus can use.

Component	Description
openshift-state-metrics	The openshift-state-metrics exporter expands upon kube-state-metrics by adding metrics for OpenShift Container Platform-specific resources.
node-exporter	node-exporter is an agent deployed on every node to collect metrics about it.
Thanos Querier	The Thanos Querier enables aggregating and, optionally, deduplicating cluster and user workload metrics under a single, multi-tenant interface.
Grafana	The Grafana analytics platform provides dashboards for analyzing and visualizing the metrics. The Grafana instance that is provided with the monitoring stack, along with its dashboards, is read-only.

All the components of the monitoring stack are monitored by the stack and are automatically updated when OpenShift Container Platform is updated.

In addition to the components of the stack itself, the monitoring stack monitors:

- CoreDNS
- Elasticsearch (if Logging is installed)
- etcd
- Fluentd (if Logging is installed)
- HAProxy
- Image registry
- Kubelets
- Kubernetes apiserver
- Kubernetes controller manager
- Kubernetes scheduler
- Metering (if Metering is installed)
- OpenShift apiserver
- OpenShift controller manager
- Operator Lifecycle Manager (OLM)

- Telemeter client



NOTE

Each OpenShift Container Platform component is responsible for its monitoring configuration. For problems with a component's monitoring, open a bug in Bugzilla against that component, not against the general monitoring component.

Other OpenShift Container Platform framework components might be exposing metrics as well. For details, see their respective documentation.

1.1.2. Next steps

[Configure the monitoring stack.](#)

1.2. CONFIGURING THE MONITORING STACK

Prior to OpenShift Container Platform 4, the Prometheus Cluster Monitoring stack was configured through the Ansible inventory file. For that purpose, the stack exposed a subset of its available configuration options as Ansible variables. You configured the stack before you installed OpenShift Container Platform.

In OpenShift Container Platform 4, Ansible is not the primary technology to install OpenShift Container Platform anymore. The installation program provides only a very low number of configuration options before installation. Configuring most OpenShift framework components, including the Prometheus Cluster Monitoring stack, happens post-installation.

This section explains what configuration is supported, shows how to configure the monitoring stack, and demonstrates several common configuration scenarios.

1.2.1. Prerequisites

- The monitoring stack imposes additional resource requirements. Consult the computing resources recommendations in [Scaling the Cluster Monitoring Operator](#) and verify that you have sufficient resources.

1.2.2. Maintenance and support

The supported way of configuring OpenShift Container Platform Monitoring is by configuring it using the options described in this document. **Do not use other configurations, as they are unsupported.** Configuration paradigms might change across Prometheus releases, and such cases can only be handled gracefully if all configuration possibilities are controlled. If you use configurations other than those described in this section, your changes will disappear because the cluster-monitoring-operator reconciles any differences. The operator reverses everything to the defined state by default and by design.

Explicitly unsupported cases include:

- **Creating additional ServiceMonitor objects in the openshift-* namespaces.** This extends the targets the cluster monitoring Prometheus instance scrapes, which can cause collisions and load differences that cannot be accounted for. These factors might make the Prometheus setup unstable.

- **Creating unexpected ConfigMap objects or PrometheusRule objects.** This causes the cluster monitoring Prometheus instance to include additional alerting and recording rules.
- **Modifying resources of the stack.** The Prometheus Monitoring Stack ensures its resources are always in the state it expects them to be. If they are modified, the stack will reset them.
- **Using resources of the stack for your purposes.** The resources created by the Prometheus Cluster Monitoring stack are not meant to be used by any other resources, as there are no guarantees about their backward compatibility.
- **Stopping the Cluster Monitoring Operator from reconciling the monitoring stack.**
- **Adding new alerting rules.**
- **Modifying the monitoring stack Grafana instance.**

1.2.3. Creating a cluster monitoring config map

To configure the OpenShift Container Platform monitoring stack, you must create the cluster monitoring **ConfigMap** object.

Prerequisites

- You have access to the cluster as a user with the cluster-admin role.
- You have installed the OpenShift CLI (**oc**).

Procedure

1. Check whether the **cluster-monitoring-config ConfigMap** object exists:

```
$ oc -n openshift-monitoring get configmap cluster-monitoring-config
```

2. If the **ConfigMap** object does not exist:
 - a. Create the following YAML manifest. In this example the file is called **cluster-monitoring-config.yaml**:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
```

- b. Apply the configuration to create the **ConfigMap** object:

```
$ oc apply -f cluster-monitoring-config.yaml
```

1.2.4. Configuring the cluster monitoring stack

You can configure the Prometheus Cluster Monitoring stack using config maps. Config maps configure the Cluster Monitoring Operator, which in turn configures components of the stack.

Prerequisites

- You have access to the cluster as a user with the **cluster-admin** role.
- You have installed the OpenShift CLI (oc).
- You have created the **cluster-monitoring-config ConfigMap** object.

Procedure

1. Start editing the **cluster-monitoring-config ConfigMap** object:

```
$ oc -n openshift-monitoring edit configmap cluster-monitoring-config
```

2. Put your configuration under **data/config.yaml** as key-value pair **<component_name>: <component_configuration>**:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    <component>:
      <configuration_for_the_component>
```

Substitute **<component>** and **<configuration_for_the_component>** accordingly.

For example, create this **ConfigMap** object to configure a Persistent Volume Claim (PVC) for Prometheus:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    prometheusK8s:
      volumeClaimTemplate: spec: storageClassName: fast volumeMode: Filesystem
      resources: requests: storage: 40Gi
```

Here, **prometheusK8s** defines the Prometheus component and the following lines define its configuration.

3. Save the file to apply the changes. The pods affected by the new configuration are restarted automatically.

Additional resources

- See [Creating a cluster monitoring config map](#) to learn how to create the **cluster-monitoring-config ConfigMap** object.

1.2.5. Configurable monitoring components

This table shows the monitoring components you can configure and the keys used to specify the components in the config map:

Table 1.2. Configurable monitoring components

Component	Key
Prometheus Operator	prometheusOperator
Prometheus	prometheusK8s
Alertmanager	alertmanagerMain
kube-state-metrics	kubeStateMetrics
openshift-state-metrics	openshiftStateMetrics
Grafana	grafana
Telemeter Client	telemeterClient
Prometheus Adapter	k8sPrometheusAdapter

From this list, only Prometheus and Alertmanager have extensive configuration options. All other components usually provide only the **nodeSelector** field for being deployed on a specified node.

1.2.6. Moving monitoring components to different nodes

You can move any of the monitoring stack components to specific nodes.

Prerequisites

- You have access to the cluster as a user with the **cluster-admin** role.
- You have installed the OpenShift CLI (`oc`).
- You have created the **cluster-monitoring-config ConfigMap** object.

Procedure

1. Start editing the **cluster-monitoring-config ConfigMap** object:

```
$ oc -n openshift-monitoring edit configmap cluster-monitoring-config
```

2. Specify the **nodeSelector** constraint for the component under **data/config.yaml**:

```
apiVersion: v1
kind: ConfigMap
metadata:
```

```

name: cluster-monitoring-config
namespace: openshift-monitoring
data:
  config.yaml: |
    <component>:
      nodeSelector:
        <node_key>: <node_value>
        <node_key>: <node_value>
        <...>

```

Substitute **<component>** accordingly and substitute **<node_key>: <node_value>** with the map of key-value pairs that specifies the destination node. Often, only a single key-value pair is used.

The component can only run on a node that has each of the specified key-value pairs as labels. The node can have additional labels as well.

For example, to move components to the node that is labeled **foo: bar**, use:

```

apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    prometheusOperator:
      nodeSelector:
        foo: bar
    prometheusK8s:
      nodeSelector:
        foo: bar
    alertmanagerMain:
      nodeSelector:
        foo: bar
    kubeStateMetrics:
      nodeSelector:
        foo: bar
    grafana:
      nodeSelector:
        foo: bar
    telemeterClient:
      nodeSelector:
        foo: bar
    k8sPrometheusAdapter:
      nodeSelector:
        foo: bar
    openshiftStateMetrics:
      nodeSelector:
        foo: bar

```

3. Save the file to apply the changes. The components affected by the new configuration are moved to new nodes automatically.

Additional resources

- See [Creating a cluster monitoring config map](#) to learn how to create the **cluster-monitoring-config ConfigMap** object.
- See [Placing pods on specific nodes using node selectors](#) for more information about using node selectors.
- See the [Kubernetes documentation](#) for details on the **nodeSelector** constraint.

1.2.7. Assigning tolerations to monitoring components

You can assign tolerations to any of the monitoring stack components to enable moving them to tainted nodes.

Prerequisites

- You have access to the cluster as a user with the **cluster-admin** role.
- You have installed the OpenShift CLI (oc).
- You have created the **cluster-monitoring-config ConfigMap** object.

Procedure

1. Start editing the **cluster-monitoring-config ConfigMap** object:

```
$ oc -n openshift-monitoring edit configmap cluster-monitoring-config
```

2. Specify **tolerations** for the component:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    <component>:
      tolerations:
        <toleration_specification>
```

Substitute **<component>** and **<toleration_specification>** accordingly.

For example, a **oc adm taint nodes node1 key1=value1:NoSchedule** taint prevents the scheduler from placing pods in the **foo: bar** node. To make the **alertmanagerMain** component ignore that taint and to place **alertmanagerMain** in **foo: bar** normally, use this toleration:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    alertmanagerMain:
```

```
nodeSelector:
  foo: bar
tolerations: - key: "key1" operator: "Equal" value: "value1" effect: "NoSchedule"
```


3. Save the file to apply the changes. The new component placement configuration is applied automatically.

Additional resources

- See [Creating a cluster monitoring config map](#) to learn how to create the **cluster-monitoring-config ConfigMap** object.
- See the [OpenShift Container Platform documentation](#) on taints and tolerations.
- See the [Kubernetes documentation](#) on taints and tolerations.

1.2.8. Configuring persistent storage

Running cluster monitoring with persistent storage means that your metrics are stored to a persistent volume (PV) and can survive a pod being restarted or recreated. This is ideal if you require your metrics or alerting data to be guarded from data loss. For production environments, it is highly recommended to configure persistent storage. Because of the high IO demands, it is advantageous to use local storage.



IMPORTANT

See [Recommended configurable storage technology](#).

1.2.9. Prerequisites

- Dedicate sufficient local persistent storage to ensure that the disk does not become full. How much storage you need depends on the number of pods. For information on system requirements for persistent storage, see [Prometheus database storage requirements](#).
- Make sure you have a persistent volume (PV) ready to be claimed by the persistent volume claim (PVC), one PV for each replica. Because Prometheus has two replicas and Alertmanager has three replicas, you need five PVs to support the entire monitoring stack. The PVs should be available from the Local Storage Operator. This does not apply if you enable dynamically provisioned storage.
- Use the block type of storage.
- [Configure local persistent storage](#).

1.2.9.1. Configuring a local persistent volume claim

For the Prometheus or Alertmanager to use a persistent volume (PV), you first must configure a persistent volume claim (PVC).

Prerequisites

- You have access to the cluster as a user with the **cluster-admin** role.
- You have installed the OpenShift CLI (oc).
- You have created the **cluster-monitoring-config ConfigMap** object.

Procedure

1. Edit the **cluster-monitoring-config ConfigMap** object:

```
$ oc -n openshift-monitoring edit configmap cluster-monitoring-config
```

2. Put your PVC configuration for the component under **data/config.yaml**:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    <component>:
      volumeClaimTemplate:
        metadata:
          name: <PVC_name_prefix>
        spec:
          storageClassName: <storage_class>
          resources:
            requests:
              storage: <amount_of_storage>
```

See the [Kubernetes documentation on PersistentVolumeClaims](#) for information on how to specify **volumeClaimTemplate**.

For example, to configure a PVC that claims local persistent storage for Prometheus, use:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    prometheusK8s:
      volumeClaimTemplate:
        metadata:
          name: localpvc
        spec:
          storageClassName: local-storage
          resources:
            requests:
              storage: 40Gi
```

In the above example, the storage class created by the Local Storage Operator is called **local-storage**.

To configure a PVC that claims local persistent storage for Alertmanager, use:

```
apiVersion: v1
kind: ConfigMap
metadata:
```

```

name: cluster-monitoring-config
namespace: openshift-monitoring
data:
  config.yaml: |
    alertmanagerMain:
      volumeClaimTemplate:
        metadata:
          name: localpvc
        spec:
          storageClassName: local-storage
          resources:
            requests:
              storage: 40Gi

```

3. Save the file to apply the changes. The pods affected by the new configuration are restarted automatically and the new storage configuration is applied.

1.2.9.2. Modifying retention time for Prometheus metrics data

By default, the Prometheus Cluster Monitoring stack configures the retention time for Prometheus data to be 15 days. You can modify the retention time to change how soon the data is deleted.

Prerequisites

- You have access to the cluster as a user with the **cluster-admin** role.
- You have installed the OpenShift CLI (`oc`).
- You have created the **cluster-monitoring-config ConfigMap** object.

Procedure

1. Start editing the **cluster-monitoring-config ConfigMap** object:

```
$ oc -n openshift-monitoring edit configmap cluster-monitoring-config
```

2. Put your retention time configuration under **data/config.yaml**:

```

apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    prometheusK8s:
      retention: <time_specification>

```

Substitute **<time_specification>** with a number directly followed by **ms** (milliseconds), **s** (seconds), **m** (minutes), **h** (hours), **d** (days), **w** (weeks), or **y** (years).

For example, to configure retention time to be 24 hours, use:

```
apiVersion: v1
```

```

kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
  config.yaml: |
    prometheusK8s:
      retention: 24h

```

3. Save the file to apply the changes. The pods affected by the new configuration are restarted automatically.

Additional resources

- See [Creating a cluster monitoring config map](#) to learn how to create the **cluster-monitoring-config ConfigMap** object.
- [Understanding persistent storage](#)
- [Optimizing storage](#)

1.2.10. Configuring Alertmanager

The Prometheus Alertmanager is a component that manages incoming alerts, including:

- Alert silencing
- Alert inhibition
- Alert aggregation
- Reliable deduplication of alerts
- Grouping alerts
- Sending grouped alerts as notifications through receivers such as email, PagerDuty, and HipChat

1.2.10.1. Alertmanager default configuration

The default configuration of the OpenShift Container Platform Monitoring Alertmanager cluster is this:

```

global:
  resolve_timeout: 5m
route:
  group_wait: 30s
  group_interval: 5m
  repeat_interval: 12h
  receiver: default
routes:
- match:
  alertname: Watchdog
  repeat_interval: 5m
  receiver: watchdog

```

```
receivers:
- name: default
- name: watchdog
```

OpenShift Container Platform monitoring ships with the Watchdog alert, which fires continuously. Alertmanager repeatedly sends notifications for the Watchdog alert to the notification provider, for example, to PagerDuty. The provider is usually configured to notify the administrator when it stops receiving the Watchdog alert. This mechanism helps ensure continuous operation of Prometheus as well as continuous communication between Alertmanager and the notification provider.

1.2.10.2. Applying custom Alertmanager configuration

You can overwrite the default Alertmanager configuration by editing the **alertmanager-main** secret inside the **openshift-monitoring** namespace.

Prerequisites

- An installed **jq** tool for processing JSON data

Procedure

1. Print the currently active Alertmanager configuration into file **alertmanager.yaml**:

```
$ oc -n openshift-monitoring get secret alertmanager-main --template='{{ index .data "alertmanager.yaml" }}' |base64 -d > alertmanager.yaml
```

2. Change the configuration in file **alertmanager.yaml** to your new configuration:

```
global:
  resolve_timeout: 5m
route:
  group_wait: 30s
  group_interval: 5m
  repeat_interval: 12h
  receiver: default
  routes:
  - match:
    alertname: Watchdog
    repeat_interval: 5m
    receiver: watchdog
  - match:
    service: <your_service> 1
    routes:
    - match:
      <your_matching_rules> 2
      receiver: <receiver> 3
receivers:
- name: default
- name: watchdog
- name: <receiver>
  <receiver_configuration>
```

1 **service** specifies the service that fires the alerts.

- 2 `<your_matching_rules>` specify the target alerts.
- 3 `receiver` specifies the receiver to use for the alert.

For example, this listing configures PagerDuty for notifications:

```
global:
  resolve_timeout: 5m
route:
  group_wait: 30s
  group_interval: 5m
  repeat_interval: 12h
  receiver: default
routes:
- match:
  alertname: Watchdog
  repeat_interval: 5m
  receiver: watchdog
- match: service: example-app routes: - match: severity: critical receiver: team-frontend-page
receivers:
- name: default
- name: watchdog
- name: team-frontend-page pagerduty_configs: - service_key: "your-key"
```

With this configuration, alerts of **critical** severity fired by the **example-app** service are sent using the **team-frontend-page** receiver, which means that these alerts are paged to a chosen person.

3. Apply the new configuration in the file:

```
$ oc -n openshift-monitoring create secret generic alertmanager-main --from-file=alertmanager.yaml --dry-run -o=yaml | oc -n openshift-monitoring replace secret --filename=-
```

Additional resources

- See [the PagerDuty official site](#) for more information on PagerDuty.
- See [the PagerDuty Prometheus Integration Guide](#) to learn how to retrieve the **service_key**.
- See [Alertmanager configuration](#) for configuring alerting through different alert receivers.

1.2.10.3. Alerting rules

OpenShift Container Platform Cluster Monitoring by default ships with a set of pre-defined alerting rules.

Note that:

- The default alerting rules are used specifically for the OpenShift Container Platform cluster and nothing else. For example, you get alerts for a persistent volume in the cluster, but you do not get them for persistent volume in your custom namespace.

- Currently you cannot add custom alerting rules.
- Some alerting rules have identical names. This is intentional. They are sending alerts about the same event with different thresholds, with different severity, or both.
- With the inhibition rules, the lower severity is inhibited when the higher severity is firing.

1.2.10.4. Listing acting alerting rules

You can list the alerting rules that currently apply to the cluster.

Procedure

1. Configure the necessary port forwarding:

```
$ oc -n openshift-monitoring port-forward svc/prometheus-operated 9090
```

2. Fetch the JSON object containing acting alerting rules and their properties:

```
$ curl -s http://localhost:9090/api/v1/rules | jq '[.data.groups[].rules[] |
select(.type=="alerting")]
```

Example output

```
[
  {
    "name": "ClusterOperatorDown",
    "query": "cluster_operator_up{job=\"cluster-version-operator\"} == 0",
    "duration": 600,
    "labels": {
      "severity": "critical"
    },
    "annotations": {
      "message": "Cluster operator {{ $labels.name }} has not been available for 10 mins.
Operator may be down or disabled, cluster will not be kept up to date and upgrades will not be
possible."
    },
    "alerts": [],
    "health": "ok",
    "type": "alerting"
  },
  {
    "name": "ClusterOperatorDegraded",
    ...
  }
]
```

Additional resources

- See also [the Alertmanager documentation](#).

1.2.11. Next steps

- [Manage cluster alerts](#).
- Learn about [remote health reporting](#) and, if necessary, opt out of it.

1.3. MANAGING CLUSTER ALERTS

OpenShift Container Platform 4.4 provides a web interface to the Alertmanager, which enables you to manage alerts. This section demonstrates how to use the Alerting UI.

1.3.1. Contents of the Alerting UI

This section shows and explains the contents of the Alerting UI, a web interface to the Alertmanager.

The main three pages of the Alerting UI are the **Alerts**, the **Silences**, and the **YAML** pages.

The **Alerts** page is accessible by clicking **Monitoring** → **Alerting** → **Alerts** in the OpenShift Container Platform web console.

The screenshot shows the OpenShift Alerting UI. On the left is a sidebar with navigation options: OperatorHub, Operator Management, Workloads, Networking, Storage, Builds, Monitoring (expanded), Alerts, Silences, Metrics, Dashboards, and Compute. The main content area is titled 'Alerts' and includes a search bar (1) and a filter bar (2) showing 3 Firing, 0 Silenced, 4 Pending, and 59 Not Firing alerts. Below the filter bar is a table of alerts with columns for NAME, STATE, and SEVERITY. Three alerts are listed:

NAME	STATE	SEVERITY
3 KubeClientCertificateExpiration A client certificate used to authenticate to the apiserver is expiring in less than 7 days.	5 Firing Since Mar 15, 2:01 pm	6 Warning
4 KubeClientCertificateExpiration A client certificate used to authenticate to the apiserver is expiring in less than 24 hours.	Firing Since Mar 15, 2:01 pm	Critical
7 Watchdog This is an alert meant to ensure that the entire alerting pipeline is functional. This alert is always firing, therefore it should always be firing in Alertmanager and always fire against a receiver.	Firing Since Mar 15, 1:59 pm	None

1. Filtering alerts by their names.
2. Filtering the alerts by their states. To fire, some alerts need a certain condition to be true for the duration of a timeout. If a condition of an alert is currently true, but the timeout has not been reached, such an alert is in the **Pending** state.
3. Alert name.
4. Description of an alert.
5. Current state of the alert and when the alert went into this state.
6. Value of the Severity label of the alert.
7. Actions you can do with the alert.

The **Silences** page is accessible by clicking **Monitoring** → **Alerting** → **Silences** in the OpenShift Container Platform web console.

The screenshot shows the 'Silences' page in the OpenShift Monitoring console. The left sidebar contains navigation options: OperatorHub, Operator Management, Workloads, Networking, Storage, Builds, Monitoring (selected), Alerts, Silences, Metrics, and Dashboards. The main content area is titled 'Silences' and includes a 'Create Silence' button (1), a search filter 'Filter Silences by name...' (2), and state filters for 'Active' (1), 'Pending' (0), and 'Expired' (0) (3). A table lists silences with columns 'NAME', 'STATE', and 'FIRING ALERTS'. One silence is listed: 'watchdog' (4) with state 'Active' (5) and '0' firing alerts (6). The state 'Active' includes a sub-status 'Ends 40 minutes from now'. A menu icon (7) is visible next to the row.

1. Creating a silence for an alert.
2. Filtering silences by their name.
3. Filtering silences by their states. If a silence is pending, it is currently not active because it is scheduled to start at a later time. If a silence expired, it is no longer active because it has reached its end time.
4. Description of a silence. It includes the specification of alerts that it matches.
5. Current state of the silence. For active silences, it shows when it ends, and for pending silences, it shows when it starts.
6. Number of alerts that are being silenced by the silence.
7. Actions you can do with a silence.

The **YAML** page is accessible by clicking **Monitoring** → **Alerting** → **YAML** in the OpenShift Container Platform web console.

Alerting [Alertmanager UI](#)

Alerts Silences **YAML**

Update this YAML to configure Routes, Receivers, Groupings and other Alert Manager settings

1

2 Drag and drop file with your value here or browse to upload it.

```

"global":
  "resolve_timeout": "5m"
"receivers":
- "name": "null"
"route":
  "group_by":
  - "job"
  "group_interval": "5m"
  "group_wait": "30s"
  "receiver": "null"
  "repeat_interval": "12h"
"routes":
- "match":
  "alertname": "Watchdog"

```

3

1. Upload a file with Alertmanager configuration.
2. Examine and edit the current Alertmanager configuration.
3. Save the updated Alertmanager configuration.

Also, next to the title of each of these pages is a link to the old Alertmanager interface.

Additional resources

- See [Configuring Alertmanager](#) for more information on changing Alertmanager configuration.

1.3.2. Getting information about alerts and alerting rules


You can find an alert and see information about it or its governing alerting rule.

Procedure

1. Open the OpenShift Container Platform web console and navigate to the **Monitoring** → **Alerting** → **Alerts** page.
2. Optional: Filter the alerts by name using the **Filter Alerts by name** field.

- Optional: Filter the alerts by state using one or more of the state buttons **Firing**, **Silenced**, **Pending**, **Not firing**
- Optional: Sort the alerts by clicking one or more of the **Name**, **State**, and **Severity** column headers.
- After you see the alert, you can see either details of the alert or details of its governing alerting rule.

To see alert details, click on the name of the alert. This is the page with alert details:



The page has the graph with timeseries of the alert. It also has information about the alert, including:

- A link to its governing alerting rule
- Description of the alert

To see alerting rule details, click the button in the last column and select **View Alerting Rule**. This is the page with alerting rule details:

Alerting Rule Overview

NAME: Watchdog

FOR: Os

SEVERITY: None

EXPRESSION: `vector(1)`

MESSAGE: This is an alert meant to ensure that the entire alerting pipeline is functional. This alert is always firing, therefore it should always be firing in Alertmanager and always fire against a receiver. There are integrations with various notification mechanisms that send a notification when this alert is not firing. For example the "DeadMansSnitch" integration in PagerDuty.

Active Alerts

30m | Reset Zoom | View in Prometheus UI

DESCRIPTION	ACTIVE SINCE	STATE	VALUE
This is an alert meant to ensure that the entire alerting pipeline is functional. This alert is always firing, therefore it should always be firing in Alertmanager and always fire against a receiver. There are integrations with various notification mechanisms that send a notification when this alert is not firing. For example the "DeadMansSnitch" integration in PagerDuty.	Mar 15, 1:59 pm	Firing	1

The page has information about the alerting rule, including:

- Alerting rule name, severity, and description
- The expression that defines the condition for firing the alert
- The time for which the condition should be true for an alert to fire
- Graph for each alert governed by the alerting rule, showing the value with which the alert is firing
- Table of all alerts governed by the alerting rule

1.3.3. Silencing alerts

You can either silence a specific alert or silence alerts that match a specification that you define.

Procedure

To silence a set of alerts by creating an alert specification:

1. Navigate to the **Monitoring** → **Alerting** → **Silences** page of the OpenShift Container Platform web console.
2. Click **Create Silence**.
3. Populate the **Create Silence** form.
4. To create the silence, click **Create**.

To silence a specific alert:

1. Navigate to the **Monitoring** → **Alerting** → **Alerts** page of the OpenShift Container Platform web console.

2. For the alert that you want to silence, click the button in the last column and click **Silence Alert**. The **Create Silence** form will appear with prepopulated specification of the chosen alert.
3. Optional: Modify the silence.
4. To create the silence, click **Create**.

1.3.4. Getting information about silences

You can find a silence and view its details.

Procedure

1. Open the OpenShift Container Platform web console and navigate to the **Monitoring → Alerting → Silences** page.
2. Optional: Filter the silences by name using the **Filter Silences by name** field.
3. Optional: Filter the silences by state using one or more of the state buttons **Active**, **Pending**, **Expired**.
4. Optional: Sort the silences by clicking one or more of the **Name**, **State**, and **Firing alerts** column headers.
5. After you see the silence, you can click its name to see the details, including:
 - Alert specification
 - State
 - Start time
 - End time
 - Number and list of firing alerts

1.3.5. Editing silences

You can edit a silence, which will expire the existing silence and create a new silence with the changed configuration.

Procedure

1. Navigate to the **Monitoring → Alerting → Silences** page.
2. For the silence you want to modify, click the button in the last column and click **Edit silence**. Alternatively, you can click **Actions → Edit Silence** in the **Silence Overview** screen for a particular silence.
3. In the **Edit Silence** screen, enter your changes and click the **Save** button. This will expire the existing silence and create one with the chosen configuration.

1.3.6. Expiring silences

You can expire a silence. Expiring a silence deactivates it forever.

Procedure

1. Navigate to the **Monitoring** → **Alerting** → **Silences** page.
2. For the silence you want to expire, click the button in the last column and click **Expire Silence**. Alternatively, you can click the **Actions** → **Expire Silence** button in the **Silence Overview** page for a particular silence.
3. Confirm by clicking **Expire Silence**. This expires the silence.

1.3.7. Next steps

[Examine cluster metrics.](#)

1.4. EXAMINING CLUSTER METRICS

OpenShift Container Platform 4.4 provides a web interface to Prometheus, which enables you to run Prometheus Query Language (PromQL) queries and examine the metrics visualized on a plot. This functionality provides an extensive overview of the cluster state and enables you to troubleshoot problems.

1.4.1. Contents of the Metrics UI

This section shows and explains the contents of the Metrics UI, a web interface to Prometheus.

The **Metrics** page is accessible by clicking **Monitoring** → **Metrics** in the OpenShift Container Platform web console.

Metrics [Prometheus UI](#)

1 Actions

2 Hide Graph

3 30m Reset Zoom

4 Insert Metric at Cursor

5 Add Query

6 Run Queries

7

8

9

10

11

12

13 alertname ↑	Value ↓
14 ClusterOperatorDegraded	6
ClusterOperatorDown	12
KubePodCrashLooping	32
Watchdog	71

7

7

Expression (press Shift+Enter for newlines)

Expression (press Shift+Enter for newlines)

1. Actions.
 - Add query.
 - Expand or collapse all query tables.
 - Delete all queries.
2. Hide the plot.
3. The interactive plot.
4. The catalog of available metrics.
5. Add query.
6. Run queries.
7. Query forms.
8. Expand or collapse the form.


9. The query.
10. Clear query.
11. Enable or disable query.
12. Actions for a specific query.
 - Enable or disable query.
 - Show or hide all series of the query from the plot.
 - Delete query.
13. The metrics table for a query.
14. Color assigned to the graph of the metric. Clicking the square shows or hides the metric's graph.

Additionally, there is a link to the old Prometheus interface next to the title of the page.

1.4.2. Running metrics queries

You begin working with metrics by entering one or several Prometheus Query Language (PromQL) queries.

Procedure

1. Open the OpenShift Container Platform web console and navigate to the **Monitoring** → **Metrics** page.
2. In the query field, enter your PromQL query.
 - To show all available metrics and PromQL functions, click **Insert Metric at Cursor**.
3. For multiple queries, click **Add Query**.
4. For deleting queries, click  for the query, then select **Delete query**.
5. For keeping but not running a query, click the **Disable query** button.
6. Once you finish creating queries, click the **Run Queries** button. The metrics from the queries are visualized on the plot. If a query is invalid, the UI shows an error message.



NOTE

Queries that operate on large amounts of data might timeout or overload the browser when drawing timeseries graphs. To avoid this, hide the graph and calibrate your query using only the metrics table. Then, after finding a feasible query, enable the plot to draw the graphs.

7. Optional: The page URL now contains the queries you ran. To use this set of queries again in the future, save this URL.

Additional resources


See the [Prometheus Query Language documentation](#).

1.4.3. Exploring the visualized metrics

After running the queries, the metrics are displayed on the interactive plot. The X axis of the plot represents time. The Y axis represents the metrics values. Each metric is shown as a colored graph. You can manipulate the plot and explore the metrics.

Procedure

1. Initially, all metrics from all enabled queries are shown on the plot. You can select which metrics are shown.

- To hide all metrics from a query, click  for the query and click **Hide all series**.
- To hide a specific metric, go to the query table and click the colored square near the metric name.

2. To zoom into the plot and change the shown time range, do one of the following:


- Visually select the time range by clicking and dragging on the plot horizontally.
- Use the menu in the left upper corner to select the time range.

To reset the time range, click **Reset Zoom**.

3. To display outputs of all queries at a specific point in time, hold the mouse cursor on the plot at that point. The query outputs will appear in a pop-up box.
4. For more detailed information about metrics of a specific query, expand the table of that query using the drop-down button. Every metric is shown with its current value.
5. To hide the plot, click **Hide Graph**.

1.4.4. Non-administrator access to metrics

As a developer, one can enable user workload monitoring for an application or service in a project. As an administrator, you use the same feature to enable monitoring for infrastructure workloads. In that case, a developer or administrator of that project can examine the exposed metrics using the Developer Perspective in the Web console.



IMPORTANT

Examining metrics using the Developer Perspective is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see <https://access.redhat.com/support/offerings/techpreview/>.

Additional resources

See the [documentation on monitoring your own services](#). It includes details on accessing non-cluster metrics as a developer or a privileged user.

1.4.5. Next steps

[Access the Prometheus, Alertmanager, and Grafana.](#)

1.5. ACCESSING PROMETHEUS, ALERTMANAGER, AND GRAFANA

To work with data gathered by the monitoring stack, you might want to use the Prometheus, Alertmanager, and Grafana interfaces. They are available by default.

1.5.1. Accessing Prometheus, Alerting UI, and Grafana using the web console

You can access Prometheus, Alerting, and Grafana web UIs using a web browser through the OpenShift Container Platform web console.



NOTE

The Alerting UI accessed in this procedure is the new interface for Alertmanager.

Prerequisites

- Authentication is performed against the OpenShift Container Platform identity and uses the same credentials or means of authentication as is used elsewhere in OpenShift Container Platform. You must use a role that has read access to all namespaces, such as the **cluster-monitoring-view** cluster role.


Procedure

1. Navigate to the OpenShift Container Platform web console and authenticate.
2. To access Prometheus, navigate to the "Monitoring" → "Metrics" page.
To access the Alerting UI, navigate to the "Monitoring" → "Alerting" page.

To access Grafana, navigate to the "Monitoring" → "Dashboards" page.

1.5.2. Accessing Prometheus, Alertmanager, and Grafana directly

You can access Prometheus, Alertmanager, and Grafana web UIs using the **oc** tool and a web browser.



NOTE

The Alertmanager UI accessed in this procedure is the old interface for Alertmanager.

Prerequisites

- Authentication is performed against the OpenShift Container Platform identity and uses the same credentials or means of authentication as is used elsewhere in OpenShift Container Platform. You must use a role that has read access to all namespaces, such as the **cluster-monitoring-view** cluster role.

Procedure

1. Run:

```
$ oc -n openshift-monitoring get routes
```

Example output

```
NAME          HOST/PORT          ...
alertmanager-main alertmanager-main-openshift-monitoring.apps._url_.openshift.com ...
grafana       grafana-openshift-monitoring.apps._url_.openshift.com      ...
prometheus-k8s prometheus-k8s-openshift-monitoring.apps._url_.openshift.com ...
```


2. Prepend **https://** to the address, you cannot access web UIs using unencrypted connection. For example, this is the resulting URL for Alertmanager:

```
https://alertmanager-main-openshift-monitoring.apps._url_.openshift.com
```

3. Navigate to the address using a web browser and authenticate.

Additional resources

- For documentation on the new interface for Alertmanager, see [Managing cluster alerts](#).



IMPORTANT

The monitoring routes are managed by the Cluster Monitoring Operator and cannot be modified by the user.


CHAPTER 2. MONITORING YOUR OWN SERVICES

You can use OpenShift Monitoring for your own services in addition to monitoring the cluster. This way, you do not need to use an additional monitoring solution. This helps keeping monitoring centralized. Additionally, you can extend the access to the metrics of your services beyond cluster administrators. This enables developers and arbitrary users to access these metrics.



NOTE

Custom Prometheus instances and the Prometheus Operator installed through Operator Lifecycle Manager (OLM) can cause issues with user-defined workload monitoring if it is enabled. Custom Prometheus instances are not supported in OpenShift Container Platform.



IMPORTANT

Monitoring your own services is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see <https://access.redhat.com/support/offerings/techpreview/>.

2.1. ENABLING MONITORING OF YOUR OWN SERVICES

You can enable monitoring your own services by setting the **techPreviewUserWorkload/enabled** flag in the cluster monitoring config map.

Prerequisites

- You have access to the cluster as a user with the **cluster-admin** role.
- You have installed the OpenShift CLI (oc).
- You have created the **cluster-monitoring-config ConfigMap** object.

Procedure

1. Start editing the **cluster-monitoring-config ConfigMap** object:

```
$ oc -n openshift-monitoring edit configmap cluster-monitoring-config
```

2. Set the **techPreviewUserWorkload** setting to **true** under **data/config.yaml**:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: cluster-monitoring-config
  namespace: openshift-monitoring
data:
```

```
config.yaml: |
  techPreviewUserWorkload:
    enabled: true
```

3. Save the file to apply the changes. Monitoring your own services is enabled automatically.
4. Optional: You can check that the **prometheus-user-workload** pods were created:

```
$ oc -n openshift-user-workload-monitoring get pod
```

Example output

```
NAME                                READY STATUS RESTARTS AGE
prometheus-operator-85bbb7b64d-7jwjd 1/1   Running 0       3m24s
prometheus-user-workload-0           5/5   Running 1       3m13s
prometheus-user-workload-1           5/5   Running 1       3m13s
```

Additional resources

- See [Creating a cluster monitoring config map](#) to learn how to create the **cluster-monitoring-config ConfigMap** object.

2.2. DEPLOYING A SAMPLE SERVICE

To test monitoring your own services, you can deploy a sample service.

Procedure

1. Create a YAML file for the service configuration. In this example, it is called **prometheus-example-app.yaml**.
2. Fill the file with the configuration for deploying the service:

```
apiVersion: v1
kind: Namespace
metadata:
  name: ns1
---
apiVersion: apps/v1
kind: Deployment
metadata:
  labels:
    app: prometheus-example-app
  name: prometheus-example-app
  namespace: ns1
spec:
  replicas: 1
  selector:
    matchLabels:
      app: prometheus-example-app
  template:
    metadata:
      labels:
        app: prometheus-example-app
```

```

spec:
  containers:
  - image: quay.io/brancz/prometheus-example-app:v0.2.0
    imagePullPolicy: IfNotPresent
    name: prometheus-example-app
---
apiVersion: v1
kind: Service
metadata:
  labels:
    app: prometheus-example-app
    name: prometheus-example-app
  namespace: ns1
spec:
  ports:
  - port: 8080
    protocol: TCP
    targetPort: 8080
    name: web
  selector:
    app: prometheus-example-app
  type: ClusterIP

```

This configuration deploys a service named **prometheus-example-app** in the **ns1** project. This service exposes the custom **version** metric.

3. Apply the configuration file to the cluster:

```
$ oc apply -f prometheus-example-app.yaml
```

It will take some time to deploy the service.

4. You can check that the service is running:

```
$ oc -n ns1 get pod
```

Example output

```

NAME                                READY  STATUS  RESTARTS  AGE
prometheus-example-app-7857545cb7-sbgwq  1/1    Running  0         81m

```

2.3. CREATING A ROLE FOR SETTING UP METRICS COLLECTION

This procedure shows how to create a role that allows a user to set up metrics collection for a service as described in "Setting up metrics collection".

Procedure

1. Create a YAML file for the new role. In this example, it is called **custom-metrics-role.yaml**.
2. Fill the file with the configuration for the **monitor-crd-edit** role:

```

kind: ClusterRole
apiVersion: rbac.authorization.k8s.io/v1

```

```
metadata:
  name: monitor-crd-edit
rules:
- apiGroups: ["monitoring.coreos.com"]
  resources: ["prometheusrules", "servicemonitors", "podmonitors"]
  verbs: ["get", "list", "watch", "create", "update", "patch", "delete"]
```

This role enables a user to set up metrics collection for services.

3. Apply the configuration file to the cluster:

```
$ oc apply -f custom-metrics-role.yaml
```

Now the role is created.

2.4. GRANTING THE ROLE TO A USER

This procedure shows how to assign the **monitor-crd-edit** role to a user.

Prerequisites

- You need to have a user created.
- You need to have the **monitor-crd-edit** role described in "Creating a role for setting up metrics collection" created.

Procedure

1. In the Web console, navigate to **User Management** → **Role Bindings** → **Create Binding**.
2. In **Binding Type**, select the "Namespace Role Binding" type.
3. In **Name**, enter a name for the binding.
4. In **Namespace**, select the namespace where you want to grant the access.
5. In **Role Name**, enter **monitor-crd-edit**.
6. In **Subject**, select **User**.
7. In **Subject Name**, enter name of the user, for example **johnsmith**.
8. Confirm the role binding. Now the user has been assigned the **monitor-crd-edit** role, which allows him to set up metrics collection for a service in the namespace.

2.5. SETTING UP METRICS COLLECTION

To use the metrics exposed by your service, you need to configure OpenShift Monitoring to scrape metrics from the **/metrics** endpoint. You can do this using a **ServiceMonitor** custom resource definition (CRD) that specifies how a service should be monitored, or a **PodMonitor** CRD that specifies how a pod should be monitored. The former requires a **Service** object, while the latter does not, allowing Prometheus to directly scrape metrics from the metrics endpoint exposed by a Pod.

This procedure shows how to create a **ServiceMonitor** resource for the service.

Prerequisites

- Log in as a cluster administrator or a user with the **monitor-crd-edit** role.

Procedure

1. Create a YAML file for the **ServiceMonitor** resource configuration. In this example, the file is called **example-app-service-monitor.yaml**.
2. Fill the file with the configuration for creating the **ServiceMonitor** resource:

```
apiVersion: monitoring.coreos.com/v1
kind: ServiceMonitor
metadata:
  labels:
    k8s-app: prometheus-example-monitor
  name: prometheus-example-monitor
  namespace: ns1
spec:
  endpoints:
    - interval: 30s
      port: web
      scheme: http
  selector:
    matchLabels:
      app: prometheus-example-app
```

This configuration makes OpenShift Monitoring scrape the metrics exposed by the sample service deployed in "Deploying a sample service", which includes the single **version** metric.

3. Apply the configuration file to the cluster:

```
$ oc apply -f example-app-service-monitor.yaml
```

It will take some time to deploy the **ServiceMonitor** resource.

4. You can check that the **ServiceMonitor** resource is running:

```
$ oc -n ns1 get servicemonitor
```

Example output

```
NAME                               AGE
prometheus-example-monitor 81m
```

Additional resources

See the [Prometheus Operator API documentation](#) for more information on **ServiceMonitor** and **PodMonitor** resources.

2.6. CREATING ALERTING RULES


You can create alerting rules, which will fire alerts based on values of chosen metrics of the service.

**NOTE**

In the current version of the Technology Preview, only administrators can access alerting rules using the Prometheus UI and the Web Console.

Procedure

1. Create a YAML file for alerting rules. In this example, it is called **example-app-alerting-rule.yaml**.
2. Fill the file with the configuration for the alerting rules:

**NOTE**

The expression can only reference metrics exposed by your own services. Currently it is not possible to correlate existing cluster metrics.

```
apiVersion: monitoring.coreos.com/v1
kind: PrometheusRule
metadata:
  name: example-alert
  namespace: ns1
spec:
  groups:
  - name: example
    rules:
    - alert: VersionAlert
      expr: version{job="prometheus-example-app"} == 0
```

This configuration creates an alerting rule named **example-alert**, which fires an alert when the **version** metric exposed by the sample service becomes **0**.

3. Apply the configuration file to the cluster:

```
$ oc apply -f example-app-alerting-rule.yaml
```

It will take some time to create the alerting rules.

2.7. GIVING VIEW ACCESS TO A USER

By default, only cluster administrator users and developers have access to metrics from your services. This procedure shows how to grant metrics access to a particular project to an arbitrary user.

Prerequisites

- You need to have a user created.
- You need to log in as a cluster administrator.

Procedure

- Run this command to give a user access to all metrics of your services in a defined namespace:

```
$ oc policy add-role-to-user view <user> -n <namespace>
```


■

For example, to give view access to the **ns1** namespace to user **bobwilliams**, run:

```
$ oc policy add-role-to-user view bobwilliams -n ns1
```

- Alternatively, in the Web console, switch to the Developer Perspective, and click **Advanced** → **Project Access**. From there, you can select the correct namespace and assign the **view** role to a user.

2.8. ACCESSING THE METRICS OF YOUR SERVICE

Once you have enabled monitoring your own services, deployed a service, and set up metrics collection for it, you can access the metrics of the service as a cluster administrator, as a developer, or as a user with view permissions for the project.



NOTE

The Grafana instance shipped within OpenShift Container Platform Monitoring is read-only and displays only infrastructure-related dashboards.

Prerequisites

- You need to deploy the service that you want to monitor.
- You need to enable monitoring of your own services.
- You need to have metrics scraping set up for the service.
- You need to log in as a cluster administrator, a developer, or as a user with view permissions for the project.

Procedure

1. Access the Prometheus web interface:

- To access the metrics as a cluster administrator, go to the OpenShift Container Platform web console, switch to the Administrator Perspective, and click **Monitoring** → **Metrics**.



NOTE


Cluster administrators, when using the Administrator Perspective, have access to all cluster metrics and to custom service metrics from all projects.



NOTE

Only cluster administrators have access to the Alertmanager and Prometheus UIs.

- To access the metrics as a developer or a user with permissions, go to the OpenShift Container Platform web console, switch to the Developer Perspective, then click **Advanced** → **Metrics**. Select the project you want to see the metrics for.



NOTE

Developers can only use the Developer Perspective. They can only query metrics from a single project.

2. Use the PromQL interface to run queries for your services.

Additional resources

- See the [section on using the PromQL interface](#).

CHAPTER 3. EXPOSING CUSTOM APPLICATION METRICS FOR AUTOSCALING

You can export custom application metrics for the horizontal pod autoscaler.



IMPORTANT

Prometheus Adapter is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see <https://access.redhat.com/support/offerings/techpreview/>.

3.1. EXPOSING CUSTOM APPLICATION METRICS FOR HORIZONTAL POD AUTOSCALING

You can use the **prometheus-adapter** resource to expose custom application metrics for the horizontal pod autoscaler.

Prerequisites

- Make sure you have a custom Prometheus instance installed. In this example, it is presumed that Prometheus was installed in the **default** namespace.
- Make sure you configured monitoring for your application. In this example, it is presumed that the application and the service monitor for it were installed in the **default** namespace.

Procedure

1. Create a YAML file for your configuration. In this example, it is called **deploy.yaml**.
2. Add configuration for creating the service account, necessary roles, and role bindings for **prometheus-adapter**:

```
kind: ServiceAccount
apiVersion: v1
metadata:
  name: custom-metrics-apiserver
  namespace: default
---
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRole
metadata:
  name: custom-metrics-server-resources
rules:
- apiGroups:
  - custom.metrics.k8s.io
  resources: ["*"]
  verbs: ["*"]
---
apiVersion: rbac.authorization.k8s.io/v1
```

```
kind: ClusterRole
metadata:
  name: custom-metrics-resource-reader
rules:
- apiGroups:
  - ""
  resources:
  - namespaces
  - pods
  - services
  verbs:
  - get
  - list
---
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
  name: custom-metrics:system:auth-delegator
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
  name: system:auth-delegator
subjects:
- kind: ServiceAccount
  name: custom-metrics-apiserver
  namespace: default
---
apiVersion: rbac.authorization.k8s.io/v1
kind: RoleBinding
metadata:
  name: custom-metrics-auth-reader
  namespace: kube-system
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: Role
  name: extension-apiserver-authentication-reader
subjects:
- kind: ServiceAccount
  name: custom-metrics-apiserver
  namespace: default
---
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
  name: custom-metrics-resource-reader
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
  name: custom-metrics-resource-reader
subjects:
- kind: ServiceAccount
  name: custom-metrics-apiserver
  namespace: default
---
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
```

```

metadata:
  name: hpa-controller-custom-metrics
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
  name: custom-metrics-server-resources
subjects:
- kind: ServiceAccount
  name: horizontal-pod-autoscaler
  namespace: kube-system
---
```

3. Add configuration for the custom metrics for **prometheus-adapter**:

```

apiVersion: v1
kind: ConfigMap
metadata:
  name: adapter-config
  namespace: default
data:
  config.yaml: |
    rules:
    - seriesQuery: 'http_requests_total{namespace!="",pod!=""}' ❶
      resources:
        overrides:
          namespace: {resource: "namespace"}
          pod: {resource: "pod"}
          service: {resource: "service"}
      name:
        matches: "^(.*)_total"
        as: "${1}_per_second" ❷
      metricsQuery: 'sum(rate(<<.Series>>{<<.LabelMatchers>>}[2m])) by (<<.GroupBy>>)'
---
```

❶ Specifies the chosen metric to be the number of HTTP requests.

❷ Specifies the frequency for the metric.

4. Add configuration for registering **prometheus-adapter** as an API service:

```

apiVersion: v1
kind: Service
metadata:
  annotations:
    service.alpha.openshift.io/serving-cert-secret-name: prometheus-adapter-tls
  labels:
    name: prometheus-adapter
    name: prometheus-adapter
  namespace: default
spec:
  ports:
  - name: https
    port: 443
    targetPort: 6443
```

```

selector:
  app: prometheus-adapter
  type: ClusterIP
---
apiVersion: apiregistration.k8s.io/v1beta1
kind: APIService
metadata:
  name: v1beta1.custom.metrics.k8s.io
spec:
  service:
    name: prometheus-adapter
    namespace: default
  group: custom.metrics.k8s.io
  version: v1beta1
  insecureSkipTLSVerify: true
  groupPriorityMinimum: 100
  versionPriority: 100
---

```

5. Show the Prometheus Adapter image to use:

```

$ kubectl get -n openshift-monitoring deploy/prometheus-adapter -o jsonpath="{..image}"
quay.io/openshift-release-dev/ocp-v4.3-art-dev@sha256:76db3c86554ad7f581ba33844d6a6ebc891236f7db64f2d290c3135ba81c264c

```

6. Add configuration for deploying **prometheus-adapter**:

```

apiVersion: apps/v1
kind: Deployment
metadata:
  labels:
    app: prometheus-adapter
  name: prometheus-adapter
  namespace: default
spec:
  replicas: 1
  selector:
    matchLabels:
      app: prometheus-adapter
  template:
    metadata:
      labels:
        app: prometheus-adapter
        name: prometheus-adapter
    spec:
      serviceAccountName: custom-metrics-apiserver
      containers:
        - name: prometheus-adapter
          image: openshift-release-dev/ocp-v4.3-art-dev 1
          args:
            - --secure-port=6443
            - --tls-cert-file=/var/run/serving-cert/tls.crt
            - --tls-private-key-file=/var/run/serving-cert/tls.key
            - --logtostderr=true
            - --prometheus-url=http://prometheus-operated.default.svc:9090/

```

```

- --metrics-relist-interval=1m
- --v=4
- --config=/etc/adapter/config.yaml
ports:
- containerPort: 6443
volumeMounts:
- mountPath: /var/run/serving-cert
  name: volume-serving-cert
  readOnly: true
- mountPath: /etc/adapter/
  name: config
  readOnly: true
- mountPath: /tmp
  name: tmp-vol
volumes:
- name: volume-serving-cert
  secret:
    secretName: prometheus-adapter-tls
- name: config
  configMap:
    name: adapter-config
- name: tmp-vol
  emptyDir: {}

```

1 **image: openshift-release-dev/ocp-v4.3-art-dev** specifies the Prometheus Adapter image found in the previous step.

7. Apply the configuration file to the cluster:

```
$ oc apply -f deploy.yaml
```

8. Now the application's metrics are exposed and can be used to configure horizontal pod autoscaling.

Additional resources

- See the [horizontal pod autoscaling documentation](#).
- See the [Kubernetes documentation on horizontal pod autoscaler](#).