



OpenShift Container Platform 3.7

Installation and Configuration

OpenShift Container Platform 3.7 Installation and Configuration

OpenShift Container Platform 3.7 Installation and Configuration

OpenShift Container Platform 3.7 Installation and Configuration

Legal Notice

Copyright © 2018 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

OpenShift Installation and Configuration topics cover the basics of installing and configuring OpenShift in your environment. Use these topics for the one-time tasks required to get OpenShift up and running.

Table of Contents

CHAPTER 1. OVERVIEW	20
CHAPTER 2. INSTALLING A CLUSTER	21
2.1. PLANNING	21
2.1.1. Initial Planning	21
2.1.2. Installation Methods	21
2.1.3. Sizing Considerations	21
2.1.4. Environment Scenarios	22
2.1.4.1. Single Master and Node on One System	22
2.1.4.2. Single Master and Multiple Nodes	22
2.1.4.3. Single Master, Multiple etcd, and Multiple Nodes	22
2.1.4.4. Multiple Masters Using Native HA	23
2.1.4.5. Stand-alone Registry	23
2.1.5. RPM Versus Containerized	24
2.2. PREREQUISITES	24
2.2.1. System Requirements	24
2.2.1.1. Red Hat Subscriptions	24
2.2.1.2. Minimum Hardware Requirements	24
2.2.1.3. Production Level Hardware Requirements	25
2.2.1.4. Configuring Core Usage	26
2.2.1.5. SELinux	27
Using OverlayFS	27
2.2.1.6. Security Warning	27
2.2.2. Environment Requirements	27
2.2.2.1. DNS	28
2.2.2.1.1. Configuring Hosts to Use DNS	29
2.2.2.1.2. Configuring a DNS Wildcard	29
2.2.2.2. Network Access	30
2.2.2.2.1. NetworkManager	30
2.2.2.2.2. Configuring firewalld as the firewall	30
2.2.2.2.3. Required Ports	31
2.2.2.3. Persistent Storage	33
2.2.2.4. Cloud Provider Considerations	33
2.2.2.4.1. Overriding Detected IP Addresses and Host Names	33
2.2.2.4.2. Post-Installation Configuration for Cloud Providers	35
2.2.2.5. Containerized GlusterFS Considerations	35
2.2.2.5.1. Storage Nodes	35
2.2.2.5.2. Required Software Components	35
2.3. HOST PREPARATION	35
2.3.1. Setting PATH	35
2.3.2. Operating System Requirements	36
2.3.3. Host Registration	36
2.3.4. Installing Base Packages	37
2.3.5. Installing Docker	38
2.3.6. Configuring Docker Storage	38
2.3.6.1. Configuring OverlayFS	39
2.3.6.2. Configuring Thin Pool Storage	39
2.3.6.3. Reconfiguring Docker Storage	42
2.3.6.4. Enabling Image Signature Support	42
2.3.6.5. Managing Container Logs	43
2.3.6.6. Viewing Available Container Logs	44

2.3.6.7. Blocking Local Volume Usage	44
2.3.7. Ensuring Host Access	45
2.3.8. Setting Proxy Overrides	46
2.3.9. What's Next?	46
2.4. INSTALLING ON CONTAINERIZED HOSTS	47
2.4.1. RPM Versus Containerized Installation	47
2.4.2. Install Methods for Containerized Hosts	47
2.4.3. Required Images	47
2.4.4. Starting and Stopping Containers	48
2.4.5. File Paths	48
2.4.6. Storage Requirements	48
2.4.7. Open vSwitch SDN Initialization	49
2.5. QUICK INSTALLATION	49
2.5.1. Overview	49
2.5.2. Before You Begin	50
2.5.3. Running an Interactive Installation	50
2.5.4. Defining an Installation Configuration File	51
2.5.5. Running an Unattended Installation	52
2.5.6. Verifying the Installation	53
2.5.7. Uninstalling OpenShift Container Platform	53
2.5.8. What's Next?	54
2.6. ADVANCED INSTALLATION	54
2.6.1. Overview	54
2.6.2. Before You Begin	54
2.6.3. Configuring Ansible Inventory Files	55
Image Version Policy	55
2.6.3.1. Configuring Cluster Variables	55
2.6.3.2. Configuring Deployment Type	61
2.6.3.3. Configuring Host Variables	62
2.6.3.4. Configuring Master API and Console Ports	63
2.6.3.5. Configuring Cluster Pre-install Checks	64
2.6.3.6. Configuring System Containers	65
2.6.3.6.1. Running Docker as a System Container	66
2.6.3.6.2. Running etcd as a System Container	67
2.6.3.7. Configuring a Registry Location	68
2.6.3.8. Configuring a Registry Route	68
2.6.3.9. Configuring the Registry Console	69
2.6.3.9.1. Configuring Registry Storage	70
Option A: NFS Host Group	70
Option B: External NFS Host	70
Option C: OpenStack Platform	70
Option D: AWS or Another S3 Storage Solution	71
Option E: Google Cloud Storage (GCS) bucket on Google Compute Engine (GCE)	71
2.6.3.10. Configuring Router Sharding	71
2.6.3.11. Configuring GlusterFS Persistent Storage	72
2.6.3.11.1. Configuring Containerized GlusterFS Persistent Storage	72
2.6.3.12. Configuring the OpenShift Container Registry	74
2.6.3.12.1. Configuring a Containerized GlusterFS-Backed Registry	74
2.6.3.13. Configuring Global Proxy Options	75
2.6.3.14. Configuring the Firewall	77
2.6.3.15. Configuring Schedulability on Masters	78
2.6.3.16. Configuring Node Host Labels	79
2.6.3.16.1. Configuring Dedicated Infrastructure Nodes	79

2.6.3.17. Configuring Session Options	80
2.6.3.18. Configuring Custom Certificates	80
2.6.3.19. Configuring Certificate Validity	81
2.6.3.20. Configuring Cluster Metrics	82
2.6.3.20.1. Configuring Metrics Storage	82
Option A: Dynamic	82
Option B: NFS Host Group	82
Option C: External NFS Host	83
2.6.3.21. Configuring Cluster Logging	83
2.6.3.21.1. Configuring Logging Storage	83
Option A: Dynamic	83
Option B: NFS Host Group	84
Option C: External NFS Host	84
2.6.3.22. Customizing Service Catalog Options	84
2.6.3.22.1. Configuring the OpenShift Ansible Broker	85
2.6.3.22.1.1. Configuring Persistent Storage for the OpenShift Ansible Broker	85
2.6.3.22.1.2. Configuring the OpenShift Ansible Broker for Local APB Development	86
2.6.3.22.2. Configuring the Template Service Broker	87
2.6.3.23. Configuring Web Console Customization	87
2.6.4. Example Inventory Files	88
2.6.4.1. Single Master Examples	88
Single Master, Single etcd, and Multiple Nodes	88
Single Master, Multiple etcd, and Multiple Nodes	90
2.6.4.2. Multiple Masters Examples	91
Multiple Masters with Multiple etcd	92
Multiple Masters with Master and etcd on the Same Host	94
2.6.5. Running the Advanced Installation	96
2.6.5.1. Running the RPM-based Installer	96
2.6.5.2. Running the Containerized Installer	97
2.6.5.2.1. Running the Installer as a System Container	97
2.6.5.2.2. Running Other Playbooks	98
2.6.5.2.3. Running the Installer as a Docker Container	98
2.6.5.3. Running Individual Component Playbooks	100
2.6.6. Verifying the Installation	101
Verifying Multiple etcd Hosts	101
Verifying Multiple Masters Using HAProxy	102
2.6.7. Optionally Securing Builds	102
2.6.8. Uninstalling OpenShift Container Platform	102
2.6.8.1. Uninstalling Nodes	103
2.6.9. Known Issues	104
2.6.10. What's Next?	104
2.7. DISCONNECTED INSTALLATION	104
2.7.1. Overview	104
2.7.2. Prerequisites	105
2.7.3. Required Software and Components	105
2.7.3.1. Syncing Repositories	105
2.7.3.2. Syncing Images	106
2.7.3.3. Preparing Images for Export	109
2.7.4. Repository Server	111
2.7.4.1. Placing the Software	111
2.7.5. OpenShift Container Platform Systems	111
2.7.5.1. Building Your Hosts	111
2.7.5.2. Connecting the Repositories	112

2.7.5.3. Host Preparation	112
2.7.6. Installing OpenShift Container Platform	112
2.7.6.1. Importing OpenShift Container Platform Component Images	112
2.7.6.2. Running the OpenShift Container Platform Installer	113
2.7.6.3. Creating the Internal Docker Registry	113
2.7.7. Post-Installation Changes	113
2.7.7.1. Re-tagging S2I Builder Images	113
2.7.7.2. Configuring a Registry Location	114
2.7.7.3. Creating an Administrative User	115
2.7.7.4. Modifying the Security Policies	115
2.7.7.5. Editing the Image Stream Definitions	116
2.7.7.6. Loading the Container Images	116
2.7.8. Installing a Router	117
2.8. INSTALLING A STAND-ALONE DEPLOYMENT OF OPENSIFT CONTAINER REGISTRY	117
2.8.1. About OpenShift Container Registry	117
2.8.2. Minimum Hardware Requirements	118
2.8.3. Supported System Topologies	119
2.8.4. Host Preparation	119
2.8.5. Installation Methods	119
2.8.5.1. Quick Installation for Stand-alone OpenShift Container Registry	119
2.8.5.2. Advanced Installation for Stand-alone OpenShift Container Registry	120
CHAPTER 3. SETTING UP THE REGISTRY	124
3.1. REGISTRY OVERVIEW	124
3.1.1. About the Registry	124
3.1.2. Integrated or Stand-alone Registries	124
3.2. DEPLOYING A REGISTRY ON EXISTING CLUSTERS	124
3.2.1. Overview	124
3.2.2. Deploying the Registry	124
3.2.3. Deploying the Registry as a DaemonSet	125
3.2.4. Registry Compute Resources	125
3.2.5. Storage for the Registry	125
3.2.5.1. Production Use	126
3.2.5.1.1. Use Amazon S3 as a Storage Back-end	126
3.2.5.2. Non-Production Use	127
3.2.6. Enabling the Registry Console	128
3.2.6.1. Deploying the Registry Console	128
3.2.6.2. Securing the Registry Console	129
3.2.6.3. Troubleshooting the Registry Console	130
3.2.6.3.1. Debug Mode	130
3.2.6.3.2. Display SSL Certificate Path	130
3.3. ACCESSING THE REGISTRY	131
3.3.1. Viewing Logs	131
3.3.2. File Storage	131
3.3.3. Accessing the Registry Directly	133
3.3.3.1. User Prerequisites	133
3.3.3.2. Logging in to the Registry	134
3.3.3.3. Pushing and Pulling Images	134
3.3.4. Accessing Registry Metrics	135
3.4. SECURING AND EXPOSING THE REGISTRY	136
3.4.1. Overview	136
3.4.2. Manually Securing the Registry	136
3.4.3. Manually Exposing a Secure Registry	139

3.4.4. Manually Exposing a Non-Secure Registry	141
3.5. EXTENDED REGISTRY CONFIGURATION	143
3.5.1. Maintaining the Registry IP Address	143
3.5.2. Whitelisting Docker Registries	144
3.5.3. Setting the Registry Hostname	144
3.5.4. Overriding the Registry Configuration	145
3.5.5. Registry Configuration Reference	147
3.5.5.1. Log	147
3.5.5.2. Hooks	147
3.5.5.3. Storage	147
3.5.5.4. Auth	148
3.5.5.5. Middleware	148
3.5.5.5.1. CloudFront Middleware	149
3.5.5.5.2. Overriding Middleware Configuration Options	150
3.5.5.5.3. Image Pullthrough	151
3.5.5.5.4. Manifest Schema v2 Support	152
3.5.5.6. OpenShift	153
3.5.5.7. Reporting	154
3.5.5.8. HTTP	154
3.5.5.9. Notifications	154
3.5.5.10. Redis	154
3.5.5.11. Health	154
3.5.5.12. Proxy	154
3.6. KNOWN ISSUES	155
3.6.1. Overview	155
3.6.2. Image Push Errors with Scaled Registry Using Shared NFS Volume	155
3.6.3. Pull of Internally Managed Image Fails with "not found" Error	155
3.6.4. Image Push Fails with "500 Internal Server Error" on S3 Storage	156
3.6.5. Image Pruning Fails	156
CHAPTER 4. SETTING UP A ROUTER	158
4.1. ROUTER OVERVIEW	158
4.1.1. About Routers	158
4.1.2. Router Service Account	158
4.1.2.1. Permission to Access Labels	158
4.2. USING THE DEFAULT HAProxy ROUTER	159
4.2.1. Overview	159
4.2.2. Creating a Router	160
4.2.3. Other Basic Router Commands	160
4.2.4. Filtering Routes to Specific Routers	161
4.2.5. HAProxy Strict SN1	162
4.2.6. TLS Cipher Suites	162
4.2.7. Highly-Available Routers	162
4.2.8. Customizing the Router Service Ports	162
4.2.9. Working With Multiple Routers	163
4.2.10. Adding a Node Selector to a Deployment Configuration	163
4.2.11. Using Router Shards	164
4.2.11.1. Creating Router Shards	166
4.2.11.2. Modifying Router Shards	168
4.2.12. Finding the Host Name of the Router	169
4.2.13. Customizing the Default Routing Subdomain	170
4.2.14. Forcing Route Host Names to a Custom Routing Subdomain	170
4.2.15. Using Wildcard Certificates	171

4.2.16. Manually Redeploy Certificates	171
4.2.17. Using Secured Routes	172
4.2.18. Using Wildcard Routes (for a Subdomain)	174
4.2.19. Using the Container Network Stack	179
4.2.20. Exposing Router Metrics	180
4.2.21. Preventing Connection Failures During Restarts	182
4.2.22. ARP Cache Tuning for Large-scale Clusters	182
4.2.23. Protecting Against DDoS Attacks	183
4.3. DEPLOYING A CUSTOMIZED HAPROXY ROUTER	184
4.3.1. Overview	184
4.3.2. Obtaining the Router Configuration Template	185
4.3.3. Modifying the Router Configuration Template	185
4.3.3.1. Background	185
4.3.3.2. Go Template Actions	185
4.3.3.3. Router Provided Information	186
4.3.3.4. Annotations	191
4.3.3.5. Environment Variables	191
4.3.3.6. Example Usage	192
4.3.4. Using a ConfigMap to Replace the Router Configuration Template	194
4.3.5. Using Stick Tables	195
4.3.6. Rebuilding Your Router	196
4.4. CONFIGURING THE HAPROXY ROUTER TO USE THE PROXY PROTOCOL	197
4.4.1. Overview	197
4.4.2. Why Use the PROXY Protocol?	197
4.4.3. Using the PROXY Protocol	198
4.5. USING THE F5 ROUTER PLUG-IN	201
4.5.1. Overview	201
4.5.2. Prerequisites and Supportability	202
4.5.2.1. Configuring the Virtual Servers	203
4.5.3. Deploying the F5 Router	204
4.5.4. F5 Router Partition Paths	205
4.5.5. Setting Up F5 Native Integration	205
CHAPTER 5. MASTER AND NODE CONFIGURATION	208
5.1. OVERVIEW	208
5.2. MASTER CONFIGURATION FILES	208
5.2.1. Admission Control Configuration	208
5.2.2. Asset Configuration	209
5.2.3. Authentication and Authorization Configuration	210
5.2.4. Controller Configuration	210
5.2.5. etcd Configuration	211
5.2.6. Grant Configuration	211
5.2.7. Image Configuration	212
5.2.8. Image Policy Configuration	212
5.2.9. Kubernetes Master Configuration	213
5.2.10. Network Configuration	214
5.2.11. OAuth Authentication Configuration	215
5.2.12. Project Configuration	215
5.2.13. Scheduler Configuration	216
5.2.14. Security Allocator Configuration	216
5.2.15. Service Account Configuration	216
5.2.16. Serving Information Configuration	217
5.2.17. Volume Configuration	218

5.2.18. Audit Configuration	218
5.2.19. Advanced Audit	220
5.2.20. Specifying TLS ciphers for etcd	223
5.3. NODE CONFIGURATION FILES	225
5.3.1. Pod and Node Configuration	226
5.3.2. Docker Configuration	226
5.3.3. Parallel Image Pulls with Docker 1.9+	227
5.4. PASSWORDS AND OTHER SENSITIVE DATA	227
5.5. CREATING NEW CONFIGURATION FILES	228
5.6. LAUNCHING SERVERS USING CONFIGURATION FILES	229
5.7. CONFIGURING LOGGING LEVELS	229
5.8. RESTARTING OPENSIFT CONTAINER PLATFORM SERVICES	233
CHAPTER 6. OPENSIFT ANSIBLE BROKER CONFIGURATION	235
6.1. OVERVIEW	235
6.2. MODIFYING THE OPENSIFT ANSIBLE BROKER CONFIGURATION	236
6.3. REGISTRY CONFIGURATION	236
6.3.1. Production or Development	237
6.3.2. Storing Registry Credentials	238
6.3.3. Mock Registry	240
6.3.4. Dockerhub Registry	240
6.3.5. APB Filtering	240
6.3.6. Local OpenShift Container Registry	241
6.3.7. Red Hat Container Catalog Registry	242
6.3.8. ISV Registry	242
6.3.9. Multiple Registries	242
6.4. DAO CONFIGURATION	243
6.5. LOG CONFIGURATION	243
6.6. OPENSIFT CONFIGURATION	243
6.7. BROKER CONFIGURATION	244
6.8. SECRETS CONFIGURATION	245
CHAPTER 7. ADDING HOSTS TO AN EXISTING CLUSTER	246
7.1. OVERVIEW	246
7.2. ADDING HOSTS USING THE QUICK INSTALLER TOOL	246
7.3. ADDING HOSTS	247
Procedure	247
7.4. ADDING ETCD HOSTS TO EXISTING CLUSTER	249
7.5. REPLACING EXISTING MASTERS WITH ETCD COLOCATED	250
7.6. MIGRATING THE NODES	252
CHAPTER 8. LOADING THE DEFAULT IMAGE STREAMS AND TEMPLATES	253
8.1. OVERVIEW	253
8.2. OFFERINGS BY SUBSCRIPTION TYPE	253
8.2.1. OpenShift Container Platform Subscription	253
8.2.2. xPaaS Middleware Add-on Subscriptions	254
8.3. BEFORE YOU BEGIN	254
8.4. PREREQUISITES	254
8.5. CREATING IMAGE STREAMS FOR OPENSIFT CONTAINER PLATFORM IMAGES	255
8.6. CREATING IMAGE STREAMS FOR XPAAS MIDDLEWARE IMAGES	255
8.7. CREATING DATABASE SERVICE TEMPLATES	255
8.8. CREATING INSTANT APP AND QUICKSTART TEMPLATES	256
8.9. WHAT'S NEXT?	257

CHAPTER 9. CONFIGURING CUSTOM CERTIFICATES	258
9.1. OVERVIEW	258
9.2. CONFIGURING CUSTOM CERTIFICATES DURING INSTALLATION	258
9.3. CONFIGURING CUSTOM CERTIFICATES FOR THE WEB CONSOLE OR CLI	258
9.4. CONFIGURING A CUSTOM MASTER HOST CERTIFICATE	260
9.5. CONFIGURING A CUSTOM WILDCARD CERTIFICATE FOR THE DEFAULT ROUTER	261
9.6. CONFIGURING A CUSTOM CERTIFICATE FOR THE IMAGE REGISTRY	262
9.7. CONFIGURING A CUSTOM CERTIFICATE FOR A LOAD BALANCER	263
9.8. RETROFIT CUSTOM CERTIFICATES INTO A CLUSTER	264
9.8.1. Retrofit Custom Master Certificates into a Cluster	264
9.8.2. Retrofit Custom Router Certificates into a Cluster	264
9.9. USING CUSTOM CERTIFICATES WITH OTHER COMPONENTS	265
CHAPTER 10. REDEPLOYING CERTIFICATES	266
10.1. OVERVIEW	266
10.2. CHECKING CERTIFICATE EXPIRATIONS	266
10.2.1. Role Variables	266
10.2.2. Running Certificate Expiration Playbooks	267
Other Example Playbooks	268
10.2.3. Output Formats	268
HTML Report	268
JSON Report	269
10.3. REDEPLOYING CERTIFICATES	269
10.3.1. Redeploying All Certificates Using the Current OpenShift Container Platform and etcd CA	270
10.3.2. Redeploying a New or Custom OpenShift Container Platform CA	270
10.3.3. Redeploying a New etcd CA	271
10.3.4. Redeploying Master Certificates Only	272
10.3.5. Redeploying etcd Certificates Only	272
10.3.6. Redeploying Node Certificates Only	272
10.3.7. Redeploying Registry or Router Certificates Only	273
10.3.7.1. Redeploying Registry Certificates Only	273
10.3.7.2. Redeploying Router Certificates Only	273
10.3.8. Redeploying Custom Registry or Router Certificates	273
10.3.8.1. Redeploying Registry Certificates Manually	273
10.3.8.2. Redeploying Router Certificates Manually	275
CHAPTER 11. CONFIGURING AUTHENTICATION AND USER AGENT	278
11.1. OVERVIEW	278
11.2. IDENTITY PROVIDER PARAMETERS	278
11.3. CONFIGURING IDENTITY PROVIDERS	279
11.3.1. Configuring identity providers with Ansible	280
11.3.2. Configuring identity providers in the master configuration file	280
11.3.3. Configuring an identity provider or method	281
11.3.3.1. Manually provisioning a user when using the lookup mapping method	281
11.3.4. Allow all	282
11.3.5. Deny all	282
11.3.6. HTTPasswd	283
11.3.7. Keystone	284
11.3.8. LDAP authentication	285
11.3.9. Basic authentication (remote)	288
11.3.10. Request header	290
11.3.11. GitHub	297
11.3.12. GitLab	299

11.3.13. Google	300
11.3.14. OpenID connect	301
11.4. TOKEN OPTIONS	304
11.5. GRANT OPTIONS	304
11.6. SESSION OPTIONS	305
11.7. PREVENTING CLI VERSION MISMATCH WITH USER AGENT	306
CHAPTER 12. SYNCING GROUPS WITH LDAP	308
12.1. OVERVIEW	308
12.2. CONFIGURING LDAP SYNC	308
12.2.1. LDAP Client Configuration	308
12.2.2. LDAP Query Definition	309
12.2.3. User-Defined Name Mapping	310
12.3. RUNNING LDAP SYNC	310
12.4. RUNNING A GROUP PRUNING JOB	311
12.5. SYNC EXAMPLES	311
12.5.1. RFC 2307	312
12.5.1.1. RFC2307 with User-Defined Name Mappings	314
12.5.2. RFC 2307 with User-Defined Error Tolerances	316
12.5.3. Active Directory	318
12.5.4. Augmented Active Directory	320
12.6. NESTED MEMBERSHIP SYNC EXAMPLE	323
12.7. LDAP SYNC CONFIGURATION SPECIFICATION	326
12.7.1. v1.LDAPSyncConfig	326
12.7.2. v1.StringSource	328
12.7.3. v1.LDAPQuery	329
12.7.4. v1.RFC2307Config	330
12.7.5. v1.ActiveDirectoryConfig	331
12.7.6. v1.AugmentedActiveDirectoryConfig	332
CHAPTER 13. CONFIGURING LDAP FAILOVER	334
13.1. PREREQUISITES FOR CONFIGURING BASIC REMOTE AUTHENTICATION	334
13.2. GENERATING AND SHARING CERTIFICATES WITH THE REMOTE BASIC AUTHENTICATION SERVER	334
13.3. CONFIGURING SSSD FOR LDAP FAILOVER	335
13.4. CONFIGURING APACHE TO USE SSSD	337
13.5. CONFIGURING OPENSIFT CONTAINER PLATFORM TO USE SSSD AS THE BASIC REMOTE AUTHENTICATION SERVER	340
CHAPTER 14. CONFIGURING THE SDN	342
14.1. OVERVIEW	342
14.2. AVAILABLE SDN PROVIDERS	342
Installing VMware NSX-T (™) on OpenShift Container Platform	342
14.3. CONFIGURING THE POD NETWORK WITH ANSIBLE	342
14.4. CONFIGURING THE POD NETWORK ON MASTERS	343
14.5. CONFIGURING THE POD NETWORK ON NODES	345
14.6. MIGRATING BETWEEN SDN PLUG-INS	345
14.6.1. Migrating from ovs-multitenant to ovs-networkpolicy	346
14.7. EXTERNAL ACCESS TO THE CLUSTER NETWORK	346
14.8. USING FLANNEL	347
CHAPTER 15. CONFIGURING NUAGE SDN	350
15.1. NUAGE SDN AND OPENSIFT CONTAINER PLATFORM	350
15.2. DEVELOPER WORKFLOW	350

15.3. OPERATIONS WORKFLOW	350
15.4. INSTALLATION	350
CHAPTER 16. CONFIGURING FOR AMAZON WEB SERVICES (AWS)	353
16.1. OVERVIEW	353
16.2. PERMISSIONS	353
16.3. CONFIGURING A SECURITY GROUP	354
16.3.1. Overriding Detected IP Addresses and Host Names	355
16.4. CONFIGURING AWS VARIABLES	355
16.5. CONFIGURING OPENSIFT CONTAINER PLATFORM FOR AWS	356
16.5.1. Configuring OpenShift Container Platform for AWS with Ansible	356
16.5.2. Manually Configuring OpenShift Container Platform Masters for AWS	357
16.5.3. Manually Configuring OpenShift Container Platform Nodes for AWS	357
16.5.4. Manually Setting Key-Value Access Pairs	358
16.6. APPLYING CONFIGURATION CHANGES	358
16.7. LABELING CLUSTERS FOR AWS	358
16.7.1. Resources That Need Tags	359
16.7.2. Tagging an Existing Cluster	359
CHAPTER 17. CONFIGURING FOR OPENSTACK	361
17.1. OVERVIEW	361
17.2. PERMISSIONS	361
17.3. CONFIGURING A SECURITY GROUP	361
17.4. CONFIGURING OPENSTACK VARIABLES	362
17.5. CONFIGURING OPENSIFT CONTAINER PLATFORM MASTERS FOR OPENSTACK	362
17.5.1. Configuring OpenShift Container Platform for OpenStack with Ansible	362
17.5.2. Manually Configuring OpenShift Container Platform Masters for OpenStack	363
17.5.3. Manually Configuring OpenShift Container Platform Nodes for OpenStack	364
17.6. APPLYING CONFIGURATION CHANGES	364
CHAPTER 18. CONFIGURING FOR GCE	366
18.1. OVERVIEW	366
18.2. PERMISSIONS	366
18.3. CONFIGURING MASTERS	366
18.3.1. Configuring OpenShift Container Platform Masters for GCE with Ansible	366
18.3.2. Manually Configuring OpenShift Container Platform Masters for GCE	366
18.4. CONFIGURING NODES	367
18.5. CONFIGURING MULTIZONE SUPPORT IN A GCE DEPLOYMENT	368
18.6. APPLYING CONFIGURATION CHANGES	368
CHAPTER 19. CONFIGURING FOR AZURE	370
19.1. OVERVIEW	370
19.2. PERMISSIONS	370
19.3. PREREQUISITES	370
19.4. THE AZURE CONFIGURATION FILE	370
19.5. CONFIGURING MASTERS	371
19.6. CONFIGURING NODES	371
19.7. APPLYING CONFIGURATION CHANGES	372
CHAPTER 20. CONFIGURING FOR VMWARE VSPHERE	373
20.1. OVERVIEW	373
20.2. ENABLING VMWARE VSPHERE CLOUD PROVIDER	373
20.3. THE VMWARE VSPHERE CONFIGURATION FILE	375
20.4. CONFIGURING MASTERS	376

20.5. CONFIGURING NODES	377
20.6. APPLYING CONFIGURATION CHANGES	377
20.7. BACKUP OF PERSISTENT VOLUMES	377
CHAPTER 21. CONFIGURING FOR LOCAL VOLUME	379
21.1. OVERVIEW	379
21.2. ENABLING LOCAL VOLUMES	379
21.3. MOUNTING LOCAL VOLUMES	380
21.4. CONFIGURING THE LOCAL PROVISIONER	380
21.5. DEPLOYING THE LOCAL PROVISIONER	381
21.6. ADDING NEW DEVICES	382
CHAPTER 22. CONFIGURING PERSISTENT STORAGE	383
22.1. OVERVIEW	383
22.2. PERSISTENT STORAGE USING NFS	383
22.2.1. Overview	383
22.2.2. Provisioning	384
22.2.3. Enforcing Disk Quotas	385
22.2.4. NFS Volume Security	385
22.2.4.1. Group IDs	386
22.2.4.2. User IDs	387
22.2.4.3. SELinux	388
22.2.4.4. Export Settings	388
22.2.5. Reclaiming Resources	389
22.2.6. Automation	390
22.2.7. Additional Configuration and Troubleshooting	390
22.3. PERSISTENT STORAGE USING GLUSTERFS	390
22.3.1. Overview	391
22.3.1.1. Containerized Red Hat Gluster Storage	391
22.3.1.2. Container Native Storage Recommendations	391
22.3.1.2.1. Creation Time of Volumes with Container Native Storage	392
22.3.1.2.2. Deletion Time of Volumes with Container Native Storage	392
22.3.1.2.3. Recommended Memory Requirements for Container Native Storage	392
22.3.1.3. Dedicated Storage Cluster	392
22.3.2. Support Requirements	393
22.3.2.1. Supported Operating Systems	393
22.3.2.2. Environment Requirements	394
22.3.3. Provisioning	394
22.3.3.1. Creating Gluster Endpoints	395
22.3.3.2. Creating the Persistent Volume	396
22.3.3.3. Creating the Persistent Volume Claim	397
22.3.4. Gluster Volume Security	398
22.3.4.1. Group IDs	398
22.3.4.2. User IDs	399
22.3.4.3. SELinux	400
22.4. PERSISTENT STORAGE USING OPENSTACK CINDER	400
22.4.1. Overview	400
22.4.2. Provisioning Cinder PVs	401
22.4.2.1. Creating the Persistent Volume	401
22.4.2.2. Cinder PV format	402
22.4.2.3. Cinder volume security	402
22.5. PERSISTENT STORAGE USING CEPH RADOS BLOCK DEVICE (RBD)	403
22.5.1. Overview	403

22.5.2. Provisioning	404
22.5.2.1. Creating the Ceph Secret	404
22.5.2.2. Creating the Persistent Volume	405
22.5.3. Ceph Volume Security	406
22.6. PERSISTENT STORAGE USING AWS ELASTIC BLOCK STORE	407
22.6.1. Overview	407
22.6.2. Provisioning	408
22.6.2.1. Creating the Persistent Volume	408
22.6.2.2. Volume Format	409
22.6.2.3. Maximum Number of EBS Volumes on a Node	409
22.7. PERSISTENT STORAGE USING GCE PERSISTENT DISK	409
22.7.1. Overview	409
22.7.2. Provisioning	410
22.7.2.1. Creating the Persistent Volume	410
22.7.2.2. Volume Format	411
22.8. PERSISTENT STORAGE USING ISCSI	411
22.8.1. Overview	411
22.8.2. Provisioning	412
22.8.2.1. Enforcing Disk Quotas	412
22.8.2.2. iSCSI Volume Security	412
22.8.2.3. iSCSI Multipathing	413
22.9. PERSISTENT STORAGE USING FIBRE CHANNEL	413
22.9.1. Overview	413
22.9.2. Provisioning	413
22.9.2.1. Enforcing Disk Quotas	414
22.9.2.2. Fibre Channel Volume Security	414
22.10. PERSISTENT STORAGE USING AZURE DISK	414
22.10.1. Overview	414
22.10.2. Prerequisites	415
22.10.3. Provisioning	415
22.10.4. Configuring Azure Disk for regional cloud	415
22.10.4.1. Creating the Persistent Volume	415
22.10.4.2. Volume Format	417
22.11. PERSISTENT STORAGE USING AZURE FILE	417
22.11.1. Overview	417
22.11.2. Before you begin	417
22.11.3. Configuring Azure File for regional cloud	418
22.11.4. Creating the PV	418
22.11.5. Creating the Azure Storage Account secret	418
22.12. PERSISTENT STORAGE USING FLEXVOLUME PLUG-INS	419
22.12.1. Overview	419
22.12.2. Installing FlexVolume Drivers	420
22.12.3. Consuming Storage using FlexVolume	420
22.12.4. FlexVolume Drivers	421
22.12.4.1. FlexVolume Drivers with Master-initiated Attach/Detach	422
22.12.4.2. FlexVolume Drivers Without Master-initiated Attach/Detach	424
22.13. USING VMWARE VSPHERE VOLUMES FOR PERSISTENT STORAGE	425
22.13.1. Overview	425
Prerequisites	425
22.13.2. Provisioning VMware vSphere volumes	426
22.13.2.1. Creating persistent volumes	426
22.13.2.2. Formatting VMware vSphere volumes	427
22.14. PERSISTENT STORAGE USING LOCAL VOLUME	427

22.14.1. Overview	427
22.14.2. Provisioning	428
22.14.3. Creating Local Persistent Volume Claim	428
22.14.4. Feature Status	428
22.15. DYNAMIC PROVISIONING AND CREATING STORAGE CLASSES	429
22.15.1. Overview	429
22.15.2. Available dynamically provisioned plug-ins	430
22.15.3. Defining a StorageClass	431
22.15.3.1. Basic StorageClass object definition	431
22.15.3.2. StorageClass annotations	432
22.15.3.3. OpenStack Cinder object definition	432
22.15.3.4. AWS ElasticBlockStore (EBS) object definition	433
22.15.3.5. GCE PersistentDisk (gcePD) object definition	433
22.15.3.6. GlusterFS object definition	434
22.15.3.7. Ceph RBD object definition	435
22.15.3.8. Trident object definition	436
22.15.3.9. VMware vSphere object definition	436
22.15.3.10. Azure Disk object definition	437
22.15.4. Changing the default StorageClass	438
22.15.5. Additional information and examples	438
22.16. VOLUME SECURITY	439
22.16.1. Overview	439
22.16.2. SCCs, Defaults, and Allowed Ranges	439
22.16.3. Supplemental Groups	443
22.16.4. fsGroup	446
22.16.5. User IDs	448
22.16.6. SELinux Options	450
22.17. SELECTOR-LABEL VOLUME BINDING	451
22.17.1. Overview	451
22.17.2. Motivation	451
22.17.3. Deployment	452
22.17.3.1. Prerequisites	452
22.17.3.2. Define the Persistent Volume and Claim	452
22.17.3.3. Deploy the Persistent Volume and Claim	453
22.18. ENABLING CONTROLLER-MANAGED ATTACHMENT AND DETACHMENT	453
22.18.1. Overview	453
22.18.2. Determining What Is Managing Attachment and Detachment	454
22.18.3. Configuring Nodes to Enable Controller-managed Attachment and Detachment	454
CHAPTER 23. PERSISTENT STORAGE EXAMPLES	455
23.1. OVERVIEW	455
23.2. SHARING AN NFS MOUNT ACROSS TWO PERSISTENT VOLUME CLAIMS	455
23.2.1. Overview	455
23.2.2. Creating the Persistent Volume	455
23.2.3. Creating the Persistent Volume Claim	456
23.2.4. Ensuring NFS Volume Access	457
23.2.5. Creating the Pod	458
23.2.6. Creating an Additional Pod to Reference the Same PVC	462
23.3. COMPLETE EXAMPLE USING CEPH RBD	464
23.3.1. Overview	464
23.3.2. Installing the ceph-common Package	464
23.3.3. Creating the Ceph Secret	464
23.3.4. Creating the Persistent Volume	465

23.3.5. Creating the Persistent Volume Claim	466
23.3.6. Creating the Pod	467
23.3.7. Defining Group and Owner IDs (Optional)	468
23.3.8. Setting ceph-user-secret as Default for Projects	468
23.4. USING CEPH RBD FOR DYNAMIC PROVISIONING	469
23.4.1. Overview	469
23.4.2. Creating a pool for dynamic volumes	469
23.4.3. Using an existing Ceph cluster for dynamic persistent storage	470
23.4.4. Setting ceph-user-secret as the default for projects	473
23.5. COMPLETE EXAMPLE USING GLUSTERFS	474
23.5.1. Overview	474
23.5.2. Installing the glusterfs-fuse Package	474
23.5.3. Creating the Gluster Endpoints and Gluster Service for Persistence	474
23.5.4. Creating the Persistent Volume	476
23.5.5. Creating the Persistent Volume Claim	477
23.5.6. Defining GlusterFS Volume Access	478
23.5.7. Creating the Pod using NGINX Web Server image	478
23.6. COMPLETE EXAMPLE OF DYNAMIC PROVISIONING USING CONTAINERIZED GLUSTERFS	483
23.6.1. Overview	483
23.6.2. Verify the Environment and Gather Needed Information	483
23.6.3. Create a Storage Class for Your GlusterFS Dynamic Provisioner	484
23.6.4. Create a PVC to Request Storage for Your Application	485
23.6.5. Create a NGINX Pod That Uses the PVC	486
23.7. COMPLETE EXAMPLE OF DYNAMIC PROVISIONING USING DEDICATED GLUSTERFS	488
23.7.1. Overview	488
23.7.2. Environment and Prerequisites	488
23.7.3. Installing and Configuring Heketi	489
23.7.4. Loading Topology	490
23.7.5. Dynamically Provision a Volume	492
23.7.6. Creating a NGINX Pod That Uses the PVC	493
23.8. EXAMPLE: CONTAINERIZED HEKETI FOR MANAGING DEDICATED GLUSTERFS STORAGE	494
23.8.1. Overview	495
23.8.2. Environment and Prerequisites	495
23.8.3. Installing and Configuring Heketi	495
23.8.4. Loading Topology	496
23.8.5. Dynamically Provision a Volume	498
23.8.6. Creating a NGINX Pod That Uses the PVC	500
23.9. MOUNTING VOLUMES ON PRIVILEGED PODS	501
23.9.1. Overview	501
23.9.2. Prerequisites	501
23.9.3. Creating the Persistent Volume	501
23.9.4. Creating a Regular User	502
23.9.5. Creating the Persistent Volume Claim	502
23.9.6. Verifying the Setup	503
23.9.6.1. Checking the Pod SCC	503
23.9.6.2. Verifying the Mount	503
23.10. BACKING DOCKER REGISTRY WITH GLUSTERFS STORAGE	504
23.10.1. Overview	504
23.10.2. Prerequisites	504
23.10.3. Create the Gluster Persistent Volume	504
23.10.4. Attach the PVC to the Docker Registry	505
23.10.5. Known Issues	505
23.10.5.1. Pod Cannot Resolve the Volume Host	505

23.11. BINDING PERSISTENT VOLUMES BY LABELS	506
23.11.1. Overview	506
23.11.1.1. Assumptions	507
23.11.2. Defining Specifications	507
23.11.2.1. Persistent Volume with Labels	507
23.11.2.2. Persistent Volume Claim with Selectors	508
23.11.2.3. Volume Endpoints	508
23.11.2.4. Deploy the PV, PVC, and Endpoints	509
23.12. USING STORAGE CLASSES FOR DYNAMIC PROVISIONING	509
23.12.1. Overview	509
23.12.2. Scenario 1: Basic Dynamic Provisioning with Two Types of StorageClasses	509
23.12.3. Scenario 2: How to enable Default StorageClass behavior for a Cluster	512
23.13. USING STORAGE CLASSES FOR EXISTING LEGACY STORAGE	516
23.13.1. Overview	516
23.13.1.1. Scenario 1: Link StorageClass to existing Persistent Volume with Legacy Data	516
23.14. CONFIGURING AZURE BLOB STORAGE FOR INTEGRATED DOCKER REGISTRY	519
23.14.1. Overview	519
23.14.2. Before You Begin	519
23.14.3. Overriding Registry Configuration	519
CHAPTER 24. WORKING WITH HTTP PROXIES	521
24.1. OVERVIEW	521
24.2. CONFIGURING NO_PROXY	521
24.3. CONFIGURING HOSTS FOR PROXIES	522
24.4. CONFIGURING HOSTS FOR PROXIES USING ANSIBLE	523
24.5. PROXYING DOCKER PULL	523
24.6. USING MAVEN BEHIND A PROXY	524
24.7. CONFIGURING S2I BUILDS FOR PROXIES	524
24.8. CONFIGURING DEFAULT TEMPLATES FOR PROXIES	524
24.9. SETTING PROXY ENVIRONMENT VARIABLES IN PODS	525
24.10. GIT REPOSITORY ACCESS	525
CHAPTER 25. CONFIGURING GLOBAL BUILD DEFAULTS AND OVERRIDES	527
25.1. OVERVIEW	527
25.2. SETTING GLOBAL BUILD DEFAULTS	527
25.2.1. Configuring Global Build Defaults with Ansible	528
25.2.2. Manually Setting Global Build Defaults	529
25.3. SETTING GLOBAL BUILD OVERRIDES	530
25.3.1. Configuring Global Build Overrides with Ansible	530
25.3.2. Manually Setting Global Build Overrides	531
CHAPTER 26. CONFIGURING PIPELINE EXECUTION	533
26.1. OVERVIEW	533
26.2. OPENSIFT JENKINS CLIENT PLUGIN	534
26.3. OPENSIFT JENKINS SYNC PLUGIN	534
CHAPTER 27. CONFIGURING ROUTE TIMEOUTS	536
CHAPTER 28. CONFIGURING NATIVE CONTAINER ROUTING	537
28.1. NETWORK OVERVIEW	537
28.2. CONFIGURE NATIVE CONTAINER ROUTING	537
28.3. SETTING UP A NODE FOR CONTAINER NETWORKING	538
28.4. SETTING UP A ROUTER FOR CONTAINER NETWORKING	538
CHAPTER 29. ROUTING FROM EDGE LOAD BALANCERS	539

29.1. OVERVIEW	539
29.2. INCLUDING THE LOAD BALANCER IN THE SDN	539
29.3. ESTABLISHING A TUNNEL USING A RAMP NODE	539
29.3.1. Configuring a Highly-Available Ramp Node	542
CHAPTER 30. AGGREGATING CONTAINER LOGS	543
30.1. OVERVIEW	543
30.2. PRE-DEPLOYMENT CONFIGURATION	543
30.3. SPECIFYING LOGGING ANSIBLE VARIABLES	544
30.4. DEPLOYING THE EFK STACK	553
30.5. UNDERSTANDING AND ADJUSTING THE DEPLOYMENT	554
30.5.1. Ops Cluster	554
30.5.2. Elasticsearch	554
30.5.3. Fluentd	558
30.5.4. Kibana	563
30.5.5. Curator	564
30.5.5.1. Creating the Curator Configuration	566
30.6. CLEANUP	566
30.7. TROUBLESHOOTING KIBANA	566
30.8. SENDING LOGS TO AN EXTERNAL ELASTICSEARCH INSTANCE	568
30.9. SENDING LOGS TO AN EXTERNAL SYSLOG SERVER	569
30.10. PERFORMING ADMINISTRATIVE ELASTICSEARCH OPERATIONS	572
30.11. CHANGING THE AGGREGATED LOGGING DRIVER	573
30.12. UPDATING FLUENTD'S LOG SOURCE AFTER A DOCKER LOG DRIVER UPDATE	573
30.13. MANUAL ELASTICSEARCH ROLLOUTS	574
30.13.1. Performing an Elasticsearch Rolling Cluster Restart	574
30.13.2. Performing an Elasticsearch Full Cluster Restart	575
CHAPTER 31. AGGREGATE LOGGING SIZING GUIDELINES	577
31.1. OVERVIEW	577
31.2. INSTALLATION	577
31.2.1. Large Clusters	579
31.3. SYSTEMD-JOURNALD AND RSYSLOG	579
31.4. SCALING UP EFK LOGGING	580
31.5. STORAGE CONSIDERATIONS	581
CHAPTER 32. ENABLING CLUSTER METRICS	583
32.1. OVERVIEW	583
32.2. BEFORE YOU BEGIN	583
32.3. METRICS PROJECT	583
32.4. METRICS DATA STORAGE	583
32.4.1. Persistent Storage	584
32.4.2. Capacity Planning for Cluster Metrics	584
Recommendations for OpenShift Container Platform Version 3.7	586
Known Issues and Limitations	586
32.4.3. Non-Persistent Storage	587
32.5. METRICS ANSIBLE ROLE	587
32.5.1. Specifying Metrics Ansible Variables	587
32.5.2. Using Secrets	591
32.5.2.1. Providing Your Own Certificates	591
32.6. DEPLOYING THE METRIC COMPONENTS	591
32.6.1. Metrics Diagnostics	592
32.7. SETTING THE METRICS PUBLIC URL	593
32.8. ACCESSING HAWKULAR METRICS DIRECTLY	593

32.8.1. OpenShift Container Platform Projects and Hawkular Tenants	594
32.8.2. Authorization	594
32.9. SCALING OPENSIFT CONTAINER PLATFORM CLUSTER METRICS PODS	594
32.10. INTEGRATION WITH AGGREGATED LOGGING	594
32.11. CLEANUP	594
32.12. PROMETHEUS ON OPENSIFT CONTAINER PLATFORM	595
32.12.1. Setting Prometheus Role Variables	595
32.12.2. Deploying Prometheus Using Ansible Installer	596
32.12.2.1. Additional Methods for Deploying Prometheus	597
32.12.2.2. Accessing the Prometheus Web UI	597
32.12.2.3. Configuring Prometheus for OpenShift Container Platform	597
32.12.3. OpenShift Container Platform Metrics via Prometheus	598
32.12.3.1. Current Metrics	598
32.12.4. Undeploying Prometheus	601
CHAPTER 33. CUSTOMIZING THE WEB CONSOLE	602
33.1. OVERVIEW	602
33.2. LOADING EXTENSION SCRIPTS AND STYLESHEETS	602
33.2.1. Setting Extension Properties	603
33.3. EXTENSION OPTION FOR EXTERNAL LOGGING SOLUTIONS	603
33.4. CUSTOMIZING AND DISABLING THE GUIDED TOUR	604
33.5. CUSTOMIZING DOCUMENTATION LINKS	604
33.6. CUSTOMIZING THE LOGO	604
33.7. CHANGING LINKS TO DOCUMENTATION	605
33.8. ADDING OR CHANGING LINKS TO DOWNLOAD THE CLI	605
33.8.1. Customizing the About Page	606
33.9. CONFIGURING NAVIGATION MENUS	607
33.9.1. Top Navigation Dropdown Menus	607
33.9.2. Application Launcher	608
33.9.3. System Status Badge	608
33.9.4. Project Left Navigation	609
33.10. CONFIGURING FEATURED APPLICATIONS	611
33.11. CONFIGURING CATALOG CATEGORIES	612
33.12. CONFIGURING QUOTA NOTIFICATION MESSAGES	614
33.13. CONFIGURING THE CREATE FROM URL NAMESPACE WHITELIST	614
33.14. DISABLING THE COPY LOGIN COMMAND	615
33.14.1. Enabling Wildcard Routes	615
33.15. ENABLING FEATURES IN TECHNOLOGY PREVIEW	616
33.16. SERVING STATIC FILES	617
33.16.1. Enabling HTML5 Mode	617
33.17. CUSTOMIZING THE LOGIN PAGE	617
33.17.1. Example Usage	618
33.18. CUSTOMIZING THE OAUTH ERROR PAGE	618
33.19. CHANGING THE LOGOUT URL	618
33.20. CONFIGURING WEB CONSOLE CUSTOMIZATIONS WITH ANSIBLE	619
CHAPTER 34. DEPLOYING EXTERNAL PERSISTENT VOLUME PROVISIONERS	621
34.1. OVERVIEW	621
34.2. BEFORE YOU BEGIN	621
34.2.1. External Provisioners Ansible Role	621
34.2.2. External Provisioners Ansible Variables	621
34.2.3. AWS EFS Provisioner Ansible Variables	622
34.3. DEPLOYING THE PROVISIONERS	623

34.3.1. Deploying the AWS EFS Provisioner	623
34.3.1.1. AWS EFS Object Definition	623
34.4. CLEANUP	624
CHAPTER 35. REVISION HISTORY: INSTALLATION AND CONFIGURATION	625
35.1. MON MAR 12 2018	625
35.2. WED MAR 07 2018	625
35.3. MON FEB 26 2018	625
35.4. FRI FEB 23 2018	625
35.5. MON FEB 19 2018	626
35.6. FRI FEB 16 2018	626
35.7. TUE FEB 06 2018	626
35.8. THU JAN 25 2018	627
35.9. FRI DEC 22 2017	627
35.10. MON DEC 11 2017	627
35.11. WED NOV 29 2017	628

CHAPTER 1. OVERVIEW

OpenShift Container Platform Installation and Configuration topics cover the basics of installing and configuring OpenShift Container Platform in your environment. Configuration, management, and logging are also covered. Use these topics for the one-time tasks required to quickly set up your OpenShift Container Platform environment and configure it based on your organizational needs.

For day to day cluster administration tasks, see [Cluster Administration](#).

CHAPTER 2. INSTALLING A CLUSTER

2.1. PLANNING

2.1.1. Initial Planning

For production environments, several factors influence installation. Consider the following questions as you read through the documentation:

- *Which installation method do you want to use?* The [Installation Methods](#) section provides some information about the quick and advanced installation methods.
- *How many pods are required in your cluster?* The [Sizing Considerations](#) section provides limits for nodes and pods so you can calculate how large your environment needs to be.
- *How many hosts do you require in the cluster?* The [Environment Scenarios](#) section provides multiple examples of Single Master and Multiple Master configurations.
- *Is [high availability](#) required?* High availability is recommended for fault tolerance. In this situation, you might aim to use the [Multiple Masters Using Native HA](#) example as a basis for your environment.
- *Which installation type do you want to use: [RPM](#) or [containerized](#)?* Both installations provide a working OpenShift Container Platform environment, but you might have a preference for a particular method of installing, managing, and updating your services.
- *Which identity provider do you use for [authentication](#)?* If you already use a supported identity provider, it is a best practice to configure OpenShift Container Platform to use that identity provider during [advanced installation](#).
- *Is my installation supported if integrating with other technologies?* See the [OpenShift Container Platform Tested Integrations](#) for a list of tested integrations.

2.1.2. Installation Methods

Both the quick and advanced installation methods are supported for development and production environments. If you want to quickly get OpenShift Container Platform up and running to try out for the first time, use the quick installer and let the interactive CLI guide you through the configuration options relevant to your environment.

For the most control over your cluster's configuration, you can use the advanced installation method. This method is particularly suited if you are already familiar with Ansible. However, following along with the OpenShift Container Platform documentation should equip you with enough information to reliably deploy your cluster and continue to manage its configuration post-deployment using the provided Ansible playbooks directly.

If you install initially using the quick installer, you can always further tweak your cluster's configuration and adjust the number of hosts in the cluster using the same installer tool. If you wanted to later switch to using the advanced method, you can create an inventory file for your configuration and carry on that way.

2.1.3. Sizing Considerations

Determine how many nodes and pods you require for your OpenShift Container Platform cluster. Cluster

scalability correlates to the number of pods in a cluster environment. That number influences the other numbers in your setup. See [Cluster Limits](#) for the latest limits for objects in OpenShift Container Platform.

2.1.4. Environment Scenarios

This section outlines different examples of scenarios for your OpenShift Container Platform environment. Use these scenarios as a basis for planning your own OpenShift Container Platform cluster, based on your [sizing](#) needs.



NOTE

Moving from a single master cluster to multiple masters after installation is not supported.

For information on updating labels, see [Updating Labels on Nodes](#).

2.1.4.1. Single Master and Node on One System

OpenShift Container Platform can be installed on a single system for a [development](#) environment only. An *all-in-one environment* is not considered a production environment.

2.1.4.2. Single Master and Multiple Nodes

The following table describes an example environment for a single [master](#) (with embedded **etcd**) and two [nodes](#):

Host Name	Infrastructure Component to Install
master.example.com	Master and node
node1.example.com	Node
node2.example.com	

2.1.4.3. Single Master, Multiple etcd, and Multiple Nodes

The following table describes an example environment for a single [master](#), three [etcd](#) hosts, and two [nodes](#):

Host Name	Infrastructure Component to Install
master.example.com	Master and node
etcd1.example.com	etcd
etcd2.example.com	
etcd3.example.com	

Host Name	Infrastructure Component to Install
node1.example.com	Node
node2.example.com	

**NOTE**

When specifying multiple **etcd** hosts, external **etcd** is installed and configured. Clustering of OpenShift Container Platform's embedded **etcd** is not supported.

2.1.4.4. Multiple Masters Using Native HA

The following describes an example environment for three [masters](#), one HAProxy load balancer, three [etcd](#) hosts, and two [nodes](#) using the **native** HA method:

Host Name	Infrastructure Component to Install
master1.example.com	Master (clustered using native HA) and node
master2.example.com	
master3.example.com	
lb.example.com	HAProxy to load balance API master endpoints
etcd1.example.com	etcd
etcd2.example.com	
etcd3.example.com	
node1.example.com	Node
node2.example.com	

**NOTE**

When specifying multiple **etcd** hosts, external **etcd** is installed and configured. Clustering of OpenShift Container Platform's embedded **etcd** is not supported.

2.1.4.5. Stand-alone Registry

You can also install OpenShift Container Platform to act as a stand-alone registry using the OpenShift Container Platform's integrated registry. See [Installing a Stand-alone Registry](#) for details on this scenario.

2.1.5. RPM Versus Containerized

An RPM installation installs all services through package management and configures services to run within the same user space, while a containerized installation installs services using container images and runs separate services in individual containers.

See the [Installing on Containerized Hosts](#) topic for more details on configuring your installation to use containerized services.

2.2. PREREQUISITES

2.2.1. System Requirements

The following sections identify the hardware specifications and system-level requirements of all hosts within your OpenShift Container Platform environment.

2.2.1.1. Red Hat Subscriptions

You must have an active OpenShift Container Platform subscription on your Red Hat account to proceed. If you do not, contact your sales representative for more information.



IMPORTANT

OpenShift Container Platform 3.7 requires Docker 1.12.

2.2.1.2. Minimum Hardware Requirements


The system requirements vary per host type:

Masters	<ul style="list-style-type: none"> Physical or virtual system, or an instance running on a public or private IaaS. Base OS: RHEL 7.3, 7.4, or 7.5 with the "Minimal" installation option and the latest packages from the Extras channel, or RHEL Atomic Host 7.4.2 or later. Minimum 4 vCPU (additional are strongly recommended). Minimum 16 GB RAM (additional memory is strongly recommended, especially if etcd is co-located on masters). Minimum 40 GB hard disk space for the file system containing <code>/var/</code>. 1 Minimum 1 GB hard disk space for the file system containing <code>/usr/local/bin/</code>. Minimum 1 GB hard disk space for the file system containing the system's temporary directory. 2 Masters with a co-located etcd require a minimum of 4 cores. 2 core systems will not work.
---------	---

Nodes	<ul style="list-style-type: none"> • Physical or virtual system, or an instance running on a public or private IaaS. • Base OS: RHEL 7.3, 7.4, or 7.5 with "Minimal" installation option, or RHEL Atomic Host 7.4.2 or later. • NetworkManager 1.0 or later. • 1 vCPU. • Minimum 8 GB RAM. • Minimum 15 GB hard disk space for the file system containing <code>/var/</code>. 1 • Minimum 1 GB hard disk space for the file system containing <code>/usr/local/bin/</code>. • Minimum 1 GB hard disk space for the file system containing the system's temporary directory. 2 • An additional minimum 15 GB unallocated space to be used for Docker's storage back end; see Configuring Docker Storage.
External etcd Nodes	<ul style="list-style-type: none"> • Minimum 20 GB hard disk space for etcd data. • Consult Hardware Recommendations to properly size your etcd nodes. • Currently, OpenShift Container Platform stores image, build, and deployment metadata in etcd. You must periodically prune old resources. If you are planning to leverage a large number of these resources, place etcd on machines with large amounts of memory and fast SSD drives.

1 Meeting the `/var/` file system sizing requirements in RHEL Atomic Host requires making changes to the default configuration. See [Managing Storage with Docker-formatted Containers](#) for instructions on configuring this during or after installation.

2 The system's temporary directory is determined according to the rules defined in the `tempfile` module in Python's standard library.



IMPORTANT

OpenShift Container Platform only supports servers with the x86_64 architecture.

2.2.1.3. Production Level Hardware Requirements

Test or sample environments function with the minimum requirements. For production environments, the following recommendations apply:

Master Hosts

In a highly available OpenShift Container Platform cluster with external etcd, a master host should have, in addition to the minimum requirements in the table above, 1 CPU core and 1.5 GB of memory for each 1000 pods. Therefore, the recommended size of a master host in an OpenShift Container

Platform cluster of 2000 pods would be the minimum requirements of 2 CPU cores and 16 GB of RAM, plus 2 CPU cores and 3 GB of RAM, totaling 4 CPU cores and 19 GB of RAM.

A minimum of three etcd hosts and a load-balancer between the master hosts are required.

The OpenShift Container Platform master caches deserialized versions of resources aggressively to ease CPU load. However, in smaller clusters of less than 1000 pods, this cache can waste a lot of memory for negligible CPU load reduction. The default cache size is 50,000 entries, which, depending on the size of your resources, can grow to occupy 1 to 2 GB of memory. This cache size can be reduced using the following setting in `/etc/origin/master/master-config.yaml`:

```
kubernetesMasterConfig:
  apiServerArguments:
    deserialization-cache-size:
      - "1000"
```

Node Hosts

The size of a node host depends on the expected size of its workload. As an OpenShift Container Platform cluster administrator, you will need to calculate the expected workload, then add about 10 percent for overhead. For production environments, allocate enough resources so that a node host failure does not affect your maximum capacity.

Use the above with the following table to plan the maximum loads for nodes and pods:

Host	Sizing Recommendation
Maximum nodes per cluster	2000
Maximum pods per cluster	120000
Maximum pods per nodes	250
Maximum pods per core	10



IMPORTANT

Oversubscribing the physical resources on a node affects resource guarantees the Kubernetes scheduler makes during pod placement. Learn what measures you can take to [avoid memory swapping](#).

2.2.1.4. Configuring Core Usage

By default, OpenShift Container Platform masters and nodes use all available cores in the system they run on. You can choose the number of cores you want OpenShift Container Platform to use by setting the `GOMAXPROCS` environment variable.

For example, run the following before starting the server to make OpenShift Container Platform only run on one core:

```
# export GOMAXPROCS=1
```

2.2.1.5. SELinux

Security-Enhanced Linux (SELinux) must be enabled on all of the servers before installing OpenShift Container Platform or the installer will fail. Also, configure **SELINUXTYPE=targeted** in the */etc/selinux/config* file:

```
# This file controls the state of SELinux on the system.
# SELINUX= can take one of these three values:
#     enforcing - SELinux security policy is enforced.
#     permissive - SELinux prints warnings instead of enforcing.
#     disabled - No SELinux policy is loaded.
SELINUX=enforcing
# SELINUXTYPE= can take one of these three values:
#     targeted - Targeted processes are protected,
#     minimum - Modification of targeted policy. Only selected processes
# are protected.
#     mls - Multi Level Security protection.
SELINUXTYPE=targeted
```

Using OverlayFS

OverlayFS is a union file system that allows you to overlay one file system on top of another.

As of Red Hat Enterprise Linux 7.4, you have the option to configure your OpenShift Container Platform environment to use OverlayFS. The **overlay2** graph driver is fully supported in addition to the older **overlay** driver. However, Red Hat recommends using **overlay2** instead of **overlay**, because of its speed and simple implementation.

See the [Overlay Graph Driver](#) section of the Atomic Host documentation for instructions on how to enable the **overlay2** graph driver for the Docker service.

2.2.1.6. Security Warning

OpenShift Container Platform runs containers on hosts in the cluster, and in some cases, such as build operations and the registry service, it does so using privileged containers. Furthermore, those containers access the hosts' Docker daemon and perform **docker build** and **docker push** operations. As such, cluster administrators should be aware of the inherent security risks associated with performing **docker run** operations on arbitrary images as they effectively have root access. This is particularly relevant for **docker build** operations.

Exposure to harmful containers can be limited by assigning specific builds to nodes so that any exposure is limited to those nodes. To do this, see the [Assigning Builds to Specific Nodes](#) section of the Developer Guide. For cluster administrators, see the [Configuring Global Build Defaults and Overrides](#) section of the Installation and Configuration Guide.

You can also use [security context constraints](#) to control the actions that a pod can perform and what it has the ability to access. For instructions on how to enable images to run with **USER** in the Dockerfile, see [Managing Security Context Constraints](#) (requires a user with **cluster-admin** privileges).

For more information, see these articles:

- <http://opensource.com/business/14/7/docker-security-selinux>
- <https://docs.docker.com/engine/security/security/>

2.2.2. Environment Requirements

The following section defines the requirements of the environment containing your OpenShift Container Platform configuration. This includes networking considerations and access to external services, such as Git repository access, storage, and cloud infrastructure providers.

2.2.2.1. DNS

OpenShift Container Platform requires a fully functional DNS server in the environment. This is ideally a separate host running DNS software and can provide name resolution to hosts and containers running on the platform.



IMPORTANT

Adding entries into the `/etc/hosts` file on each host is not enough. This file is not copied into containers running on the platform.

Key components of OpenShift Container Platform run themselves inside of containers and use the following process for name resolution:

1. By default, containers receive their DNS configuration file (`/etc/resolv.conf`) from their host.
2. OpenShift Container Platform then inserts one DNS value into the pods (above the node's nameserver values). That value is defined in the `/etc/origin/node/node-config.yaml` file by the `dnsIP` parameter, which by default is set to the address of the host node because the host is using `dnsmasq`.
3. If the `dnsIP` parameter is omitted from the `node-config.yaml` file, then the value defaults to the kubernetes service IP, which is the first nameserver in the pod's `/etc/resolv.conf` file.

As of OpenShift Container Platform 3.2, `dnsmasq` is automatically configured on all masters and nodes. The pods use the nodes as their DNS, and the nodes forward the requests. By default, `dnsmasq` is configured on the nodes to listen on port 53, therefore the nodes cannot run any other type of DNS application.



NOTE

NetworkManager is required on the nodes in order to populate `dnsmasq` with the DNS IP addresses. DNS does not work properly when the network interface for OpenShift Container Platform has `NM_CONTROLLED=no`.

The following is an example set of DNS records:

```
master1    A    10.64.33.100
master2    A    10.64.33.103
node1      A    10.64.33.101
node2      A    10.64.33.102
```

If you do not have a properly functioning DNS environment, you could experience failure with:

- Product installation via the reference Ansible-based scripts
- Deployment of the infrastructure containers (registry, routers)
- Access to the OpenShift Container Platform web console, because it is not accessible via IP address alone

2.2.2.1.1. Configuring Hosts to Use DNS

Make sure each host in your environment is configured to resolve hostnames from your DNS server. The configuration for hosts' DNS resolution depends on whether DHCP is enabled. If DHCP is:

- Disabled, then configure your network interface to be static, and add DNS nameservers to NetworkManager.
- Enabled, then the NetworkManager dispatch script automatically configures DNS based on the DHCP configuration. Optionally, you can add a value to **dnsIP** in the **node-config.yaml** file to prepend the pod's **resolv.conf** file. The second nameserver is then defined by the host's first nameserver. By default, this will be the IP address of the node host.



NOTE

For most configurations, do not set the **openshift_dns_ip** option during the advanced installation of OpenShift Container Platform (using Ansible), because this option overrides the default IP address set by **dnsIP**.

Instead, allow the installer to configure each node to use **dnsmasq** and forward requests to SkyDNS or the external DNS provider. If you do set the **openshift_dns_ip** option, then it should be set either with a DNS IP that queries SkyDNS first, or to the SkyDNS service or endpoint IP (the Kubernetes service IP).

To verify that hosts can be resolved by your DNS server:

1. Check the contents of **/etc/resolv.conf**:

```
$ cat /etc/resolv.conf
# Generated by NetworkManager
search example.com
nameserver 10.64.33.1
# nameserver updated by /etc/NetworkManager/dispatcher.d/99-origin-
dns.sh
```

In this example, 10.64.33.1 is the address of our DNS server.

2. Test that the DNS servers listed in **/etc/resolv.conf** are able to resolve host names to the IP addresses of all masters and nodes in your OpenShift Container Platform environment:

```
$ dig <node_hostname> @<IP_address> +short
```

For example:

```
$ dig master.example.com @10.64.33.1 +short
10.64.33.100
$ dig node1.example.com @10.64.33.1 +short
10.64.33.101
```

2.2.2.1.2. Configuring a DNS Wildcard

Optionally, configure a wildcard for the router to use, so that you do not need to update your DNS configuration when new routes are added.

A wildcard for a DNS zone must ultimately resolve to the IP address of the OpenShift Container Platform [router](#).

For example, create a wildcard DNS entry for **cloudapps** that has a low time-to-live value (TTL) and points to the public IP address of the host where the router will be deployed:

```
*.cloudapps.example.com. 300 IN A 192.168.133.2
```

In almost all cases, when referencing VMs you must use host names, and the host names that you use must match the output of the **hostname -f** command on each node.



WARNING

In your **/etc/resolv.conf** file on each node host, ensure that the DNS server that has the wildcard entry is not listed as a nameserver or that the wildcard domain is not listed in the search list. Otherwise, containers managed by OpenShift Container Platform may fail to resolve host names properly.

2.2.2.2. Network Access

A shared network must exist between the master and node hosts. If you plan to configure [multiple masters for high-availability](#) using the [advanced installation method](#), you must also select an IP to be configured as your [virtual IP](#) (VIP) during the installation process. The IP that you select must be routable between all of your nodes, and if you configure using a FQDN it should resolve on all nodes.

2.2.2.2.1. NetworkManager

NetworkManager, a program for providing detection and configuration for systems to automatically connect to the network, is required. DNS does not work properly when the network interface for OpenShift Container Platform has **NM_CONTROLLED=no**.

2.2.2.2.2. Configuring firewalld as the firewall

While iptables is the default firewall, firewalld is recommended for new installations. You can enable firewalld by setting **os_firewall_use_firewalld=true** in [the Ansible inventory file](#).

```
[OSEv3:vars]
os_firewall_use_firewalld=True
```

Setting this variable to **true** opens the required ports and adds rules to the default zone, which ensure that firewalld is configured correctly.



NOTE

Using the firewalld default configuration comes with limited configuration options, and cannot be overridden. For example, while you can set up a storage network with interfaces in multiple zones, the interface that nodes communicate on must be in the default zone.

2.2.2.2.3. Required Ports

The OpenShift Container Platform installation automatically creates a set of internal firewall rules on each host using [iptables](#). However, if your network configuration uses an external firewall, such as a hardware-based firewall, you must ensure infrastructure components can communicate with each other through specific ports that act as communication endpoints for certain processes or services.

Ensure the following ports required by OpenShift Container Platform are open on your network and configured to allow access between hosts. Some ports are optional depending on your configuration and usage.

Table 2.1. Node to Node

4789	UDP	Required for SDN communication between pods on separate hosts.
-------------	-----	--

Table 2.2. Nodes to Master

53 or 8053	TCP/ UDP	Required for DNS resolution of cluster services (SkyDNS). Installations prior to 3.2 or environments upgraded to 3.2 use port 53. New installations will use 8053 by default so that dnsmasq may be configured.
4789	UDP	Required for SDN communication between pods on separate hosts.
443 or 8443	TCP	Required for node hosts to communicate to the master API, for the node hosts to post back status, to receive tasks, and so on.

Table 2.3. Master to Node

4789	UDP	Required for SDN communication between pods on separate hosts.
10250	TCP	The master proxies to node hosts via the Kubelet for oc commands.

Table 2.4. Master to Master

53 or 8053	TCP/ UDP	Required for DNS resolution of cluster services (SkyDNS). Installations prior to 3.2 or environments upgraded to 3.2 use port 53. New installations will use 8053 by default so that dnsmasq may be configured.
2049	TCP/ UDP	Required when provisioning an NFS host as part of the installer.
2379	TCP	Used for standalone etcd (clustered) to accept changes in state.
2380	TCP	etcd requires this port be open between masters for leader election and peering connections when using standalone etcd (clustered).
4001	TCP	Used for embedded etcd (non-clustered) to accept changes in state.
4789	UDP	Required for SDN communication between pods on separate hosts.

Table 2.5. External to Load Balancer

9000	TCP	If you choose the native HA method, optional to allow access to the HAProxy statistics page.
-------------	-----	---

Table 2.6. External to Master

443 or 8443	TCP	Required for node hosts to communicate to the master API, for node hosts to post back status, to receive tasks, and so on.
8444	TCP	Port that the atomic-openshift-master-controllers service listens on. Required to be open for the /metrics and /healthz endpoints.

Table 2.7. IaaS Deployments

22	TCP	Required for SSH by the installer or system administrator.
53 or 8053	TCP/ UDP	Required for DNS resolution of cluster services (SkyDNS). Installations prior to 3.2 or environments upgraded to 3.2 use port 53. New installations will use 8053 by default so that dnsmasq may be configured. Only required to be internally open on master hosts.
80 or 443	TCP	For HTTP/HTTPS use for the router. Required to be externally open on node hosts, especially on nodes running the router.
1936	TCP	(Optional) Required to be open when running the template router to access statistics. Can be open externally or internally to connections depending on if you want the statistics to be expressed publicly. Can require extra configuration to open. See the Notes section below for more information.
4001	TCP	For embedded etcd (non-clustered) use. Only required to be internally open on the master host. 4001 is for server-client connections.
2379 and 2380	TCP	For standalone etcd use. Only required to be internally open on the master host. 2379 is for server-client connections. 2380 is for server-server connections, and is only required if you have clustered etcd.
4789	UDP	For VxLAN use (OpenShift SDN). Required only internally on node hosts.
8443	TCP	For use by the OpenShift Container Platform web console, shared with the API server.
10250	TCP	For use by the Kubelet. Required to be externally open on nodes.

Notes

- In the above examples, port **4789** is used for User Datagram Protocol (UDP).
- When deployments are using the SDN, the pod network is accessed via a service proxy, unless it is accessing the registry from the same node the registry is deployed on.

- OpenShift Container Platform internal DNS cannot be received over SDN. Depending on the detected values of **openshift_facts**, or if the **openshift_ip** and **openshift_public_ip** values are overridden, it will be the computed value of **openshift_ip**. For non-cloud deployments, this will default to the IP address associated with the default route on the master host. For cloud deployments, it will default to the IP address associated with the first internal interface as defined by the cloud metadata.
- The master host uses port **10250** to reach the nodes and does not go over SDN. It depends on the target host of the deployment and uses the computed values of **openshift_hostname** and **openshift_public_hostname**.
- Port **1936** can still be inaccessible due to your iptables rules. Use the following to configure iptables to open port **1936**:

```
# iptables -A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m tcp \
--dport 1936 -j ACCEPT
```

Table 2.8. Aggregated Logging

9200	TCP	For Elasticsearch API use. Required to be internally open on any infrastructure nodes so Kibana is able to retrieve logs for display. It can be externally opened for direct access to Elasticsearch by means of a route. The route can be created using oc expose .
9300	TCP	For Elasticsearch inter-cluster use. Required to be internally open on any infrastructure node so the members of the Elasticsearch cluster may communicate with each other.

2.2.2.3. Persistent Storage

The Kubernetes [persistent volume](#) framework allows you to provision an OpenShift Container Platform cluster with persistent storage using networked storage available in your environment. This can be done after completing the initial OpenShift Container Platform installation depending on your application needs, giving users a way to request those resources without having any knowledge of the underlying infrastructure.

The [Installation and Configuration Guide](#) provides instructions for cluster administrators on provisioning an OpenShift Container Platform cluster with persistent storage using [NFS](#), [GlusterFS](#), [Ceph RBD](#), [OpenStack Cinder](#), [AWS Elastic Block Store \(EBS\)](#), [GCE Persistent Disks](#), and [iSCSI](#).

2.2.2.4. Cloud Provider Considerations

There are certain aspects to take into consideration if installing OpenShift Container Platform on a cloud provider.

- For Amazon Web Services, see the [Permissions](#) and the [Configuring a Security Group](#) sections.
- For OpenStack, see the [Permissions](#) and the [Configuring a Security Group](#) sections.

2.2.2.4.1. Overriding Detected IP Addresses and Host Names

Some deployments require that the user override the detected host names and IP addresses for the hosts. To see the default values, run the **openshift_facts** playbook:

■

```
# ansible-playbook [-i /path/to/inventory] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift_facts.yml
```



IMPORTANT

For Amazon Web Services, see the [Overriding Detected IP Addresses and Host Names](#) section.

Now, verify the detected common settings. If they are not what you expect them to be, you can override them.

The [Advanced Installation](#) topic discusses the available Ansible variables in greater detail.

Variable	Usage
hostname	<ul style="list-style-type: none"> Should resolve to the internal IP from the instances themselves. openshift_hostname overrides.
ip	<ul style="list-style-type: none"> Should be the internal IP of the instance. openshift_ip will overrides.
public_hostname	<ul style="list-style-type: none"> Should resolve to the external IP from hosts outside of the cloud. Provider openshift_public_hostname overrides.
public_ip	<ul style="list-style-type: none"> Should be the externally accessible IP associated with the instance. openshift_public_ip overrides.
use_openshift_sdn	<ul style="list-style-type: none"> Should be true unless the cloud is GCE. openshift_use_openshift_sdn overrides.



WARNING

If **openshift_hostname** is set to a value other than the metadata-provided **private-dns-name** value, the native cloud integration for those providers will no longer work.

2.2.2.4.2. Post-Installation Configuration for Cloud Providers

Following the installation process, you can configure OpenShift Container Platform for [AWS](#), [OpenStack](#), or [GCE](#).

2.2.2.5. Containerized GlusterFS Considerations

If you choose to configure [containerized GlusterFS persistent storage](#) for your cluster, or if you choose to configure a [containerized GlusterFS-backed OpenShift Container Registry](#), you must consider the following prerequisites.

2.2.2.5.1. Storage Nodes

To use containerized GlusterFS persistent storage:

- A minimum of 3 storage nodes is required.
- Each storage node must have at least 1 raw block device with least 100 GB available.

To run a containerized GlusterFS-backed OpenShift Container Registry:

- A minimum of 3 storage nodes is required.
- Each storage node must have at least 1 raw block device with at least 10 GB of free storage.



IMPORTANT

While containerized GlusterFS persistent storage can be configured and deployed on the same OpenShift Container Platform cluster as a containerized GlusterFS-backed registry, their storage should be kept separate from each other and also requires additional storage nodes. For example, if both are configured, a total of 6 storage nodes would be needed: 3 for the registry and 3 for persistent storage. This limitation is imposed to avoid potential impacts on performance in I/O and volume creation.

2.2.2.5.2. Required Software Components

For any RHEL (non-Atomic) storage nodes, the following RPM repository must be enabled:

```
# subscription-manager repos --enable=rh-gluster-3-client-for-rhel-7-
server-rpms
```

The **mount.glusterfs** command must be available on all nodes that will host pods that will use GlusterFS volumes. For RPM-based systems, the **glusterfs-fuse** package must be installed:

```
# yum install glusterfs-fuse
```

If GlusterFS is already installed on the nodes, ensure the latest version is installed:

```
# yum update glusterfs-fuse
```

2.3. HOST PREPARATION

2.3.1. Setting PATH

The **PATH** for the root user on each host must contain the following directories:

- ***/bin***
- ***/sbin***
- ***/usr/bin***
- ***/usr/sbin***

These should all be included by default in a fresh RHEL 7.x installation.

2.3.2. Operating System Requirements

A base installation of RHEL 7.3 or 7.4 (with the latest packages from the Extras channel) or RHEL Atomic Host 7.4.2 or later is required for master and node hosts. See the following documentation for the respective installation instructions, if required:

- [Red Hat Enterprise Linux 7 Installation Guide](#)
- [Red Hat Enterprise Linux Atomic Host 7 Installation and Configuration Guide](#)

2.3.3. Host Registration

Each host must be registered using Red Hat Subscription Manager (RHSM) and have an active OpenShift Container Platform subscription attached to access the required packages.

1. On each host, register with RHSM:

```
# subscription-manager register --username=<user_name> --password=
<password>
```

2. Pull the latest subscription data from RHSM:

```
# subscription-manager refresh
```

3. List the available subscriptions:

```
# subscription-manager list --available --matches '*OpenShift*'
```

4. In the output for the previous command, find the pool ID for an OpenShift Container Platform subscription and attach it:

```
# subscription-manager attach --pool=<pool_id>
```

5. Disable all yum repositories:

- a. Disable all the enabled RHSM repositories:

```
# subscription-manager repos --disable="*"
```

- b. List the remaining yum repositories and note their names under **repo id**, if any:

```
# yum repolist
```


- c. Use **yum-config-manager** to disable the remaining yum repositories:

```
# yum-config-manager --disable <repo_id>
```

Alternatively, disable all repositories:

```
yum-config-manager --disable \*
```

Note that this could take a few minutes if you have a large number of available repositories

6. Enable only the repositories required by OpenShift Container Platform 3.7:

```
# subscription-manager repos \
  --enable="rhel-7-server-rpms" \
  --enable="rhel-7-server-extras-rpms" \
  --enable="rhel-7-server-ose-3.7-rpms" \
  --enable="rhel-7-fast-datapath-rpms"
```

2.3.4. Installing Base Packages

For RHEL 7 systems:

1. Install the following base packages:

```
# yum install wget git net-tools bind-utils yum-utils iptables-
services bridge-utils bash-completion kexec-tools sos psacct
```

2. Update the system to the latest packages:

```
# yum update
# systemctl reboot
```

3. If you plan to use the [RPM-based installer](#) to run an advanced installation, you can skip this step. However, if you plan to use the [containerized installer](#) (currently a Technology Preview feature):

- a. Install the **atomic** package:

```
# yum install atomic
```

- b. Skip to [Installing Docker](#).

4. Install the following package, which provides RPM-based OpenShift Container Platform installer utilities and pulls in other tools required by the [quick](#) and [advanced installation](#) methods, such as Ansible and related configuration files:

```
# yum install atomic-openshift-utils
```

For RHEL Atomic Host 7 systems:

1. Ensure the host is up to date by upgrading to the latest Atomic tree if one is available:

```
# atomic host upgrade
```

2. After the upgrade is completed and prepared for the next boot, reboot the host:

```
# systemctl reboot
```

2.3.5. Installing Docker

At this point, you should install Docker on all master and node hosts. This allows you to configure your [Docker storage options](#) before installing OpenShift Container Platform.

For RHEL 7 systems, install Docker 1.12:



NOTE

On RHEL Atomic Host 7 systems, Docker should already be installed, configured, and running by default.

```
# yum install docker-1.12.6
```

After the package installation is complete, verify that version 1.12 was installed:

```
# rpm -V docker-1.12.6
# docker version
```



NOTE

The [Advanced Installation](#) method automatically changes */etc/sysconfig/docker*.

2.3.6. Configuring Docker Storage

Containers and the images they are created from are stored in Docker's storage back end. This storage is ephemeral and separate from any [persistent storage](#) allocated to meet the needs of your applications.

For RHEL Atomic Host

The default storage back end for Docker on RHEL Atomic Host is a thin pool logical volume, which is supported for production environments. You must ensure that enough space is allocated for this volume per the Docker storage requirements mentioned in [System Requirements](#).

If you do not have enough allocated, see [Managing Storage with Docker Formatted Containers](#) for details on using **docker-storage-setup** and basic instructions on storage management in RHEL Atomic Host.

For RHEL

The default storage back end for Docker on RHEL 7 is a thin pool on loopback devices, which is not supported for production use and only appropriate for proof of concept environments. For production environments, you must create a thin pool logical volume and re-configure Docker to use that volume.

Docker stores images and containers in a graph driver, which is a pluggable storage technology, such as **DeviceMapper**, **OverlayFS**, and **Btrfs**. Each has advantages and disadvantages. For example, OverlayFS is faster than DeviceMapper at starting and stopping containers, but is not Portable Operating System Interface for Unix (POSIX) compliant because of the architectural limitations of a union file system and is not supported prior to Red Hat Enterprise Linux 7.2. See the [Red Hat Enterprise Linux](#) release notes for information on using OverlayFS with your version of RHEL.

For more information on the benefits and limitations of DeviceMapper and OverlayFS, see [Choosing a Graph Driver](#).

2.3.6.1. Configuring OverlayFS

OverlayFS is a type of union file system. It allows you to overlay one file system on top of another. Changes are recorded in the upper file system, while the lower file system remains unmodified.

[Comparing the Overlay Versus Overlay2 Graph Drivers](#) has more information about the **overlay** and **overlay2** drivers.

For information on enabling the OverlayFS storage driver for the Docker service, see the [Red Hat Enterprise Linux Atomic Host documentation](#).

2.3.6.2. Configuring Thin Pool Storage

You can use the **docker-storage-setup** script included with Docker to create a thin pool device and configure Docker's storage driver. This can be done after installing Docker and should be done before creating images or containers. The script reads configuration options from the **/etc/sysconfig/docker-storage-setup** file and supports three options for creating the logical volume:

- **Option A)** Use an additional block device.
- **Option B)** Use an existing, specified volume group.
- **Option C)** Use the remaining free space from the volume group where your root file system is located.

Option A is the most robust option, however it requires adding an additional block device to your host before configuring Docker storage. Options B and C both require leaving free space available when provisioning your host. Option C is known to cause issues with some applications, for example Red Hat Mobile Application Platform (RHMAP).

1. Create the **docker-pool** volume using one of the following three options:

- **Option A)** Use an additional block device.

In **/etc/sysconfig/docker-storage-setup**, set **DEVS** to the path of the block device you wish to use. Set **VG** to the volume group name you wish to create; **docker-vg** is a reasonable choice. For example:

```
# cat <<EOF > /etc/sysconfig/docker-storage-setup
DEVS=/dev/vdc
VG=docker-vg
EOF
```

Then run **docker-storage-setup** and review the output to ensure the **docker-pool** volume was created:

```
# docker-storage-setup
[5/1868]
0
Checking that no-one is using this disk right now ...
OK

Disk /dev/vdc: 31207 cylinders, 16 heads, 63 sectors/track
sfdisk: /dev/vdc: unrecognized partition table type
```

Old situation:

sfdisk: No partitions found

New situation:

Units: sectors of 512 bytes, counting from 0

Device	Boot	Start	End	#sectors	Id	System
/dev/vdc1		2048	31457279	31455232	8e	Linux LVM
/dev/vdc2		0	-	0	0	Empty
/dev/vdc3		0	-	0	0	Empty
/dev/vdc4		0	-	0	0	Empty

Warning: partition 1 does not start at a cylinder boundary

Warning: partition 1 does not end at a cylinder boundary

Warning: no primary partition is marked bootable (active)

This does not matter for LILO, but the DOS MBR will not boot this disk.

Successfully wrote the new partition table

Re-reading the partition table ...

If you created or changed a DOS partition, /dev/foo7, say, then use dd(1)

to zero the first 512 bytes: dd if=/dev/zero of=/dev/foo7 bs=512 count=1

(See fdisk(8).)

Physical volume "/dev/vdc1" successfully created

Volume group "docker-vg" successfully created

Rounding up size to full physical extent 16.00 MiB

Logical volume "docker-poolmeta" created.

Logical volume "docker-pool" created.

WARNING: Converting logical volume docker-vg/docker-pool and docker-vg/docker-poolmeta to pool's data and metadata volumes.

THIS WILL DESTROY CONTENT OF LOGICAL VOLUME (filesystem etc.)

Converted docker-vg/docker-pool to thin pool.

Logical volume "docker-pool" changed.

- **Option B)** Use an existing, specified volume group.

In **/etc/sysconfig/docker-storage-setup**, set **VG** to the desired volume group. For example:

```
# cat <<EOF > /etc/sysconfig/docker-storage-setup
VG=docker-vg
EOF
```

Then run **docker-storage-setup** and review the output to ensure the **docker-pool** volume was created:

```
# docker-storage-setup
Rounding up size to full physical extent 16.00 MiB
Logical volume "docker-poolmeta" created.
Logical volume "docker-pool" created.
WARNING: Converting logical volume docker-vg/docker-pool and
docker-vg/docker-poolmeta to pool's data and metadata volumes.
```

```
THIS WILL DESTROY CONTENT OF LOGICAL VOLUME (filesystem etc.)
Converted docker-vg/docker-pool to thin pool.
Logical volume "docker-pool" changed.
```

- **Option C)** Use the remaining free space from the volume group where your root file system is located.


Verify that the volume group where your root file system resides has the desired free space, then run **docker-storage-setup** and review the output to ensure the **docker-pool** volume was created:

```
# docker-storage-setup
Rounding up size to full physical extent 32.00 MiB
Logical volume "docker-poolmeta" created.
Logical volume "docker-pool" created.
WARNING: Converting logical volume rhel/docker-pool and
rhel/docker-poolmeta to pool's data and metadata volumes.
THIS WILL DESTROY CONTENT OF LOGICAL VOLUME (filesystem etc.)
Converted rhel/docker-pool to thin pool.
Logical volume "docker-pool" changed.
```

2. Verify your configuration. You should have a **dm.thinpooldev** value in the **/etc/sysconfig/docker-storage** file and a **docker-pool** logical volume:

```
# cat /etc/sysconfig/docker-storage
DOCKER_STORAGE_OPTIONS=--storage-opt dm.fs=xfs --storage-opt
dm.thinpooldev=/dev/mapper/docker--vg-docker--pool

# lvs
  LV          VG   Attr              LSize   Pool Origin Data%  Meta%  Move
Log Cpy%Sync Convert
  docker-pool rhel twi-a-t--- 9.29g                0.00   0.12
```



IMPORTANT

Before using Docker or OpenShift Container Platform, verify that the **docker-pool** logical volume is large enough to meet your needs. The **docker-pool** volume should be 60% of the available volume group and will grow to fill the volume group via LVM monitoring.

3. Check if Docker is running:

```
# systemctl is-active docker
```

4. If Docker has not yet been started on the host, enable and start the service:

```
# systemctl enable docker
# systemctl start docker
```

If Docker is already running, re-initialize Docker:

**WARNING**

This will destroy any containers or images currently on the host.

```
# systemctl stop docker
# rm -rf /var/lib/docker/*
# systemctl restart docker
```

If there is any content in **/var/lib/docker/**, it must be deleted. Files will be present if Docker has been used prior to the installation of OpenShift Container Platform.

2.3.6.3. Reconfiguring Docker Storage

Should you need to reconfigure Docker storage after having created the **docker-pool**, you should first remove the **docker-pool** logical volume. If you are using a dedicated volume group, you should also remove the volume group and any associated physical volumes before reconfiguring **docker-storage-setup** according to the instructions above.

See [Logical Volume Manager Administration](#) for more detailed information on LVM management.

2.3.6.4. Enabling Image Signature Support

OpenShift Container Platform is capable of cryptographically verifying images are from trusted sources. The [Container Security Guide](#) provides a high-level description of how image signing works.

You can configure image signature verification using the **atomic** command line interface (CLI), version 1.12.5 or greater. The **atomic** CLI is pre-installed on RHEL Atomic Host systems.

**NOTE**

For more on the **atomic** CLI, see the [Atomic CLI documentation](#).

Install the **atomic** package if it is not installed on the host system:

```
$ yum install atomic
```

The **atomic trust** sub-command manages trust configuration. The default configuration is to whitelist all registries. This means no signature verification is configured.

```
$ atomic trust show
* (default)                                accept
```

A reasonable configuration might be to whitelist a particular registry or namespace, blacklist (reject) untrusted registries, and require signature verification on a vendor registry. The following set of commands performs this example configuration:

Example Atomic Trust Configuration

```
$ atomic trust add --type insecureAcceptAnything 172.30.1.1:5000

$ atomic trust add --sigstoretype atomic \
  --pubkeys pub@example.com \
  172.30.1.1:5000/production

$ atomic trust add --sigstoretype atomic \
  --pubkeys /etc/pki/example.com.pub \
  172.30.1.1:5000/production

$ atomic trust add --sigstoretype web \
  --sigstore https://access.redhat.com/webassets/docker/content/sigstore \
  --pubkeys /etc/pki/rpm-gpg/RPM-GPG-KEY-redhat-release \
  registry.access.redhat.com

# atomic trust show
* (default)                                accept
172.30.1.1:5000                             accept
172.30.1.1:5000/production                  signed security@example.com
registry.access.redhat.com                  signed
security@redhat.com, security@redhat.com
```

When all the signed sources are verified, nodes may be further hardened with a global **reject** default:

```
$ atomic trust default reject

$ atomic trust show
* (default)                                reject
172.30.1.1:5000                             accept
172.30.1.1:5000/production                  signed security@example.com
registry.access.redhat.com                  signed
security@redhat.com, security@redhat.com
```

Use the **atomic** man page **man atomic-trust** for additional examples.

The following files and directories comprise the trust configuration of a host:

- ***/etc/containers/registries.d/****
- ***/etc/containers/policy.json***

The trust configuration may be managed directly on each node or the generated files managed on a separate host and distributed to the appropriate nodes using Ansible, for example. See this [Red Hat Knowledgebase Article](#) for an example of automating file distribution with Ansible.

2.3.6.5. Managing Container Logs

Sometimes a container's log file (the ***/var/lib/docker/containers/<hash>/<hash>-json.log*** file on the node where the container is running) can increase to a problematic size. You can manage this by configuring Docker's **json-file** logging driver to restrict the size and number of log files.

Option	Purpose
<code>--log-opt max-size</code>	Sets the size at which a new log file is created.
<code>--log-opt max-file</code>	Sets the file on each host to configure the options.

For example, to set the maximum file size to 1MB and always keep the last three log files, edit the `/etc/sysconfig/docker` file to configure `max-size=1M` and `max-file=3`:

```
OPTIONS='--insecure-registry=172.30.0.0/16 --selinux-enabled --log-opt
max-size=1M --log-opt max-file=3'
```

Next, restart the Docker service:

```
# systemctl restart docker
```

2.3.6.6. Viewing Available Container Logs

Container logs are stored in the `/var/lib/docker/containers/<hash>/` directory on the node where the container is running. For example:

```
# ls -lh
/var/lib/docker/containers/f088349cceac173305d3e2c2e4790051799efe363842fda
b5732f51f5b001fd8/
total 2.6M
-rw-r--r--. 1 root root 5.6K Nov 24 00:12 config.json
-rw-r--r--. 1 root root 649K Nov 24 00:15
f088349cceac173305d3e2c2e4790051799efe363842fdab5732f51f5b001fd8-
json.log
-rw-r--r--. 1 root root 977K Nov 24 00:15
f088349cceac173305d3e2c2e4790051799efe363842fdab5732f51f5b001fd8-
json.log.1
-rw-r--r--. 1 root root 977K Nov 24 00:15
f088349cceac173305d3e2c2e4790051799efe363842fdab5732f51f5b001fd8-
json.log.2
-rw-r--r--. 1 root root 1.3K Nov 24 00:12 hostconfig.json
drwx-----. 2 root root    6 Nov 24 00:12 secrets
```

See Docker's documentation for additional information on how to [configure logging drivers](#).

2.3.6.7. Blocking Local Volume Usage

When a volume is provisioned using the **VOLUME** instruction in a *Dockerfile* or using the `docker run -v <volumename>` command, a host's storage space is used. Using this storage can lead to an unexpected out of space issue and could bring down the host.

In OpenShift Container Platform, users trying to run their own images risk filling the entire storage space on a node host. One solution to this issue is to prevent users from running images with volumes. This way, the only storage a user has access to can be limited, and the cluster administrator can assign storage quota.

Using **docker-novolume-plugin** solves this issue by disallowing starting a container with local volumes defined. In particular, the plug-in blocks `docker run` commands that contain:

- The **--volumes-from** option
- Images that have **VOLUME(s)** defined
- References to existing volumes that were provisioned with the **docker volume** command

The plug-in does not block references to bind mounts.

To enable **docker-novolume-plugin**, perform the following steps on each node host:

1. Install the **docker-novolume-plugin** package:

```
$ yum install docker-novolume-plugin
```

2. Enable and start the **docker-novolume-plugin** service:

```
$ systemctl enable docker-novolume-plugin
$ systemctl start docker-novolume-plugin
```

3. Edit the **/etc/sysconfig/docker** file and append the following to the **OPTIONS** list:

```
--authorization-plugin=docker-novolume-plugin
```

4. Restart the **docker** service:

```
$ systemctl restart docker
```

After you enable this plug-in, containers with local volumes defined fail to start and show the following error message:

```
runContainer: API error (500): authorization denied by plugin
docker-novolume-plugin: volumes are not allowed
```

2.3.7. Ensuring Host Access

The [quick](#) and [advanced installation](#) methods require a user that has access to all hosts. If you want to run the installer as a non-root user, passwordless **sudo** rights must be configured on each destination host.

For example, you can generate an SSH key on the host where you will invoke the installation process:

```
# ssh-keygen
```

Do **not** use a password.

An easy way to distribute your SSH keys is by using a **bash** loop:

```
# for host in master.example.com \
  node1.example.com \
  node2.example.com; \
do ssh-copy-id -i ~/.ssh/id_rsa.pub $host; \
done
```

Modify the host names in the above command according to your configuration.

2.3.8. Setting Proxy Overrides

If the `/etc/environment` file on your nodes contains either an `http_proxy` or `https_proxy` value, you must also set a `no_proxy` value in that file to allow open communication between OpenShift Container Platform components.




NOTE

The `no_proxy` parameter in `/etc/environment` file is not the same value as the global proxy values that you set in your inventory file. The global proxy values configure specific OpenShift Container Platform services with your proxy settings. See [Configuring Global Proxy Options](#) for details.

If the `/etc/environment` file contains proxy values, define the following values in the `no_proxy` parameter of that file on each node:

- Master and node host names or their domain suffix.
- Other internal host names or their domain suffix.
- Etcd IP addresses. You must provide IP addresses and not host names because `etcd` access is controlled by IP address.
- Kubernetes IP address, by default `172.30.0.1`. Must be the value set in the `openshift_portal_net` parameter in your inventory file.
- Kubernetes internal domain suffix, `cluster.local`.
- Kubernetes internal domain suffix, `.svc`.



NOTE

Because `no_proxy` does not support CIDR, you can use domain suffixes.

If you use either an `http_proxy` or `https_proxy` value, your `no_proxy` parameter value resembles the following example:

```
no_proxy=.internal.example.com,10.0.0.1,10.0.0.2,10.0.0.3,.cluster.local,.svc,localhost,127.0.0.1,172.30.0.1
```

2.3.9. What's Next?

If you are interested in installing OpenShift Container Platform using the containerized method (optional for RHEL but required for RHEL Atomic Host), see [Installing on Containerized Hosts](#) to prepare your hosts.

When you are ready to proceed, you can install OpenShift Container Platform using the [quick installation](#) or [advanced installation](#) method.

If you are installing a stand-alone registry, continue with [Installing a Stand-alone Registry](#).

2.4. INSTALLING ON CONTAINERIZED HOSTS

2.4.1. RPM Versus Containerized Installation

You can opt to install OpenShift Container Platform using the RPM or containerized package method. Either installation method results in a working environment, but the choice comes from the operating system and how you choose to update your hosts.



IMPORTANT

The default method for installing OpenShift Container Platform on Red Hat Enterprise Linux (RHEL) uses RPMs. When targeting a Red Hat Atomic Host system, the containerized method is the only available option, and is automatically selected for you based on the detection of the `/run/ostree-booted` file.

When using RPMs, all services are installed and updated via package management from an outside source. These modify a host's existing configuration within the same user space. Alternatively, containerized installs instead are a complete, all-in-one resource using container images and its own operating system within the container. Any updated, newer containers replace any existing ones on your host. Choosing one method over the other depends on how you choose to update OpenShift Container Platform in the future.

The following table outlines further differences between the RPM and Containerized methods:

	RPM	Containerized
Installation Method	Packages via yum	Container images via docker
Service Management	systemd	docker and systemd units
Operating System	Red Hat Enterprise Linux	Red Hat Enterprise Linux or Red Hat Atomic Host

2.4.2. Install Methods for Containerized Hosts

As with the RPM installation, you can choose between the [quick](#) and [advanced](#) install methods for the containerized install.

For the quick installation method, you can choose between the RPM or containerized method on a per host basis during the interactive installation, or set the values manually in an [installation configuration file](#).

For the advanced installation method, you can set the Ansible variable `containerized=true` in an [inventory file](#) on a cluster-wide or per host basis.

For the [disconnected installation method](#), to install the etcd container, you can set the Ansible variable `osm_etcd_image` to be the fully qualified name of the etcd image on your local registry, for example, `registry.example.com/rhel7/etcd`.

2.4.3. Required Images

Containerized installations make use of the following images:

- **openshift3/ose**
- **openshift3/node**
- **openshift3/openswitch**
- **registry.access.redhat.com/rhel7/etcd**

By default, all of the above images are pulled from the Red Hat Registry at registry.access.redhat.com.

If you need to use a private registry to pull these images during the installation, you can specify the registry information ahead of time. For the advanced installation method, you can set the following Ansible variables in your inventory file, as required:

```
openshift_docker_additional_registries=<registry_hostname>
openshift_docker_insecure_registries=<registry_hostname>
openshift_docker_blocked_registries=<registry_hostname>
```

For the quick installation method, you can export the following environment variables on each target host:

```
# export OO_INSTALL_ADDITIONAL_REGISTRIES=<registry_hostname>
# export OO_INSTALL_INSECURE_REGISTRIES=<registry_hostname>
```

Blocked Docker registries cannot currently be specified using the quick installation method.

The configuration of additional, insecure, and blocked Docker registries occurs at the beginning of the installation process to ensure that these settings are applied before attempting to pull any of the required images.

2.4.4. Starting and Stopping Containers

The installation process creates relevant **systemd** units which can be used to start, stop, and poll services using normal **systemctl** commands. For containerized installations, these unit names match those of an RPM installation, with the exception of the **etcd** service which is named **etcd_container**.

This change is necessary as currently RHEL Atomic Host ships with the **etcd** package installed as part of the operating system, so a containerized version is used for the OpenShift Container Platform installation instead. The installation process disables the default **etcd** service. The **etcd** package is slated to be removed from RHEL Atomic Host in the future.

2.4.5. File Paths

All OpenShift Container Platform configuration files are placed in the same locations during containerized installation as RPM based installations and will survive **os-tree** upgrades.

However, [the default image stream and template files](#) are installed at **/etc/origin/examples/** for containerized installations rather than the standard **/usr/share/openshift/examples/**, because that directory is read-only on RHEL Atomic Host.

2.4.6. Storage Requirements

RHEL Atomic Host installations normally have a very small root file system. However, the etcd, master, and node containers persist data in the **/var/lib/** directory. Ensure that you have enough space on the root file system before installing OpenShift Container Platform. See the [System Requirements](#) section

for details.

2.4.7. Open vSwitch SDN Initialization

OpenShift SDN initialization requires that the Docker bridge be reconfigured and that Docker is restarted. This complicates the situation when the node is running within a container. When using the Open vSwitch (OVS) SDN, you will see the node start, reconfigure Docker, restart Docker (which restarts all containers), and finally start successfully.

In this case, the node service may fail to start and be restarted a few times, because the master services are also restarted along with Docker. The current implementation uses a workaround which relies on setting the **Restart=always** parameter in the Docker based **systemd** units.

2.5. QUICK INSTALLATION

2.5.1. Overview

The *quick installation* method allows you to use an interactive CLI utility, the **atomic-openshift-installer** command, to install OpenShift Container Platform across a set of hosts. This installer can deploy OpenShift Container Platform components on targeted hosts by either installing RPMs or running containerized services.



IMPORTANT

While RHEL Atomic Host is supported for running containerized OpenShift Container Platform services, the installer is [provided by an RPM](#) and not available by default in RHEL Atomic Host. Therefore, it must be run from a Red Hat Enterprise Linux 7 system. The host initiating the installation does not need to be intended for inclusion in the OpenShift Container Platform cluster, but it can be.

This installation method is provided to make the installation experience easier by [interactively gathering the data](#) needed to run on each host. The installer is a self-contained wrapper intended for usage on a Red Hat Enterprise Linux (RHEL) 7 system.

In addition to running [interactive installations](#) from scratch, the **atomic-openshift-installer** command can also be run or re-run using a predefined installation configuration file. This file can be used with the installer to:

- run an [unattended installation](#),
- [add nodes](#) to an existing cluster,
- [upgrade your cluster](#), or
- [reinstall](#) the OpenShift Container Platform cluster completely.

Alternatively, you can use the [advanced installation](#) method for more complex environments.



NOTE

To install OpenShift Container Platform as a stand-alone registry, see [Installing a Stand-alone Registry](#).

2.5.2. Before You Begin

The installer allows you to install OpenShift Container Platform [master](#) and [node](#) components on a defined set of hosts.



NOTE

By default, any hosts you designate as masters during the installation process are automatically also configured as nodes so that the masters are configured as part of the [OpenShift Container Platform SDN](#). The node component on the masters, however, are marked unschedulable, which blocks pods from being scheduled on it. After the installation, you can [mark them schedulable](#) if you want.

Before installing OpenShift Container Platform, you must first [satisfy the prerequisites](#) on your hosts, which includes verifying system and environment requirements and properly installing and configuring Docker. You must also be prepared to provide or validate the following information for each of your targeted hosts during the course of the installation:

- User name on the target host that should run the Ansible-based installation (can be root or non-root)
- Host name
- Whether to install components for master, node, or both
- Whether to use the RPM or containerized method
- Internal and external IP addresses




IMPORTANT

If you are installing OpenShift Container Platform using the containerized method (optional for RHEL but required for RHEL Atomic Host), see the [Installing on Containerized Hosts](#) topic to ensure that you understand the differences between these methods, then return to this topic to continue.

After following the instructions in the [Prerequisites](#) topic and deciding between the RPM and containerized methods, you can continue to running an [interactive](#) or [unattended](#) installation.

2.5.3. Running an Interactive Installation



NOTE

Ensure you have read through [Before You Begin](#).

You can start the interactive installation by running:

```
$ atomic-openshift-installer install
```

Then follow the on-screen instructions to install a new OpenShift Container Platform cluster.

After it has finished, ensure that you back up the `~/.config/openshift/installer.cfg.yml` [installation configuration file](#) that is created, as it is required if you later want to re-run the installation, add hosts to the cluster, or [upgrade your cluster](#). Then, [verify the installation](#).

2.5.4. Defining an Installation Configuration File


The installer can use a predefined installation configuration file, which contains information about your installation, individual hosts, and cluster. When running an [interactive installation](#), an installation configuration file based on your answers is created for you in `~/.config/openshift/installer.cfg.yml`. The file is created if you are instructed to exit the installation to manually modify the configuration or when the installation completes. You can also create the configuration file manually from scratch to perform an [unattended installation](#).

Installation Configuration File Specification

```
version: v2 ❶
variant: openshift-enterprise ❷
variant_version: 3.7 ❸
ansible_log_path: /tmp/ansible.log ❹
deployment:
  ansible_ssh_user: root ❺
  hosts: ❻
    - ip: 10.0.0.1 ❼
      hostname: master-private.example.com ❸
      public_ip: 24.222.0.1 ❾
      public_hostname: master.example.com ❿
      roles: 11
        - master
        - node
      containerized: true 12
      connect_to: 24.222.0.1 13
    - ip: 10.0.0.2
      hostname: node1-private.example.com
      public_ip: 24.222.0.2
      public_hostname: node1.example.com
      node_labels: {'region': 'infra'} 14
      roles:
        - node
      connect_to: 10.0.0.2
    - ip: 10.0.0.3
      hostname: node2-private.example.com
      public_ip: 24.222.0.3
      public_hostname: node2.example.com
      roles:
        - node
      connect_to: 10.0.0.3
  roles: 15
    master:
      <variable_name1>: "<value1>" 16
      <variable_name2>: "<value2>"
    node:
      <variable_name1>: "<value1>" 17
```

- 1 The version of this installation configuration file. As of OpenShift Container Platform 3.3, the only valid version here is **v2**.
- 2 The OpenShift Container Platform variant to install. For OpenShift Container Platform, set this to **openshift-enterprise**.
- 3 A valid version of your selected variant: **3.7**, **3.6**, **3.5**, **3.4**, **3.3**, **3.2**, or **3.1**. If not specified, this defaults to the latest version for the specified variant.
- 4 Defines where the Ansible logs are stored. By default, this is the **/tmp/ansible.log** file.
- 5 Defines which user Ansible uses to SSH in to remote systems for gathering facts and for the installation. By default, this is the root user, but you can set it to any user that has **sudo** privileges.
- 6 Defines a list of the hosts onto which you want to install the OpenShift Container Platform master and node components.
- 7 8 Required. Allows the installer to connect to the system and gather facts before proceeding with the install.
- 9 10 Required for unattended installations. If these details are not specified, then this information is pulled from the facts gathered by the installer, and you are asked to confirm the details. If undefined for an unattended installation, the installation fails.
- 11 Determines the type of services that are installed. Specified as a list.
- 12 If set to **true**, containerized OpenShift Container Platform services are run on target master and node hosts instead of installed using RPM packages. If set to **false** or unset, the default RPM method is used. RHEL Atomic Host requires the containerized method, and is automatically selected for you based on the detection of the **/run/ostree-booted** file. See [Installing on Containerized Hosts](#) for more details.
- 13 The IP address that Ansible attempts to connect to when installing, upgrading, or uninstalling the systems. If the configuration file was auto-generated, then this is the value you first enter for the host during that interactive install process.
- 14 Node labels can optionally be set per-host.
- 15 Defines a dictionary of roles across the deployment.
- 16 17 Any ansible variables that should only be applied to hosts assigned a role can be defined. For examples, see [Configuring Ansible](#).

2.5.5. Running an Unattended Installation



NOTE

Ensure you have read through the [Before You Begin](#).

Unattended installations allow you to define your hosts and cluster configuration in an [installation configuration file](#) before running the installer so that you do not have to go through all of the [interactive installation](#) questions and answers. It also allows you to resume an interactive installation you may have left unfinished, and quickly get back to where you left off.

To run an unattended installation, first define an [installation configuration file](#) at `~/.config/openshift/installer.cfg.yml`. Then, run the installer with the `-u` flag:

```
$ atomic-openshift-installer -u install
```

By default in interactive or unattended mode, the installer uses the configuration file located at `~/.config/openshift/installer.cfg.yml` if the file exists. If it does not exist, attempting to start an unattended installation fails.

Alternatively, you can specify a different location for the configuration file using the `-c` option, but doing so will require you to specify the file location every time you run the installation:

```
$ atomic-openshift-installer -u -c </path/to/file> install
```

After the unattended installation finishes, ensure that you back up the `~/.config/openshift/installer.cfg.yml` file that was used, as it is required if you later want to re-run the installation, add hosts to the cluster, or [upgrade your cluster](#). Then, [verify the installation](#).

2.5.6. Verifying the Installation

1. Verify that the master is started and nodes are registered and reporting in **Ready** status. *On the master host*, run the following as root:

```
# oc get nodes
```

NAME	STATUS	AGE
master.example.com	Ready,SchedulingDisabled	165d
node1.example.com	Ready	165d
node2.example.com	Ready	165d

2. To verify that the web console is installed correctly, use the master host name and the web console port number to access the web console with a web browser.
For example, for a master host with a host name of **master.openshift.com** and using the default port of **8443**, the web console would be found at **`https://master.openshift.com:8443/console`**.
3. Then, see [What's Next](#) for the next steps on configuring your OpenShift Container Platform cluster.

2.5.7. Uninstalling OpenShift Container Platform

You can uninstall OpenShift Container Platform from all hosts in your cluster using the installer's **uninstall** command. By default, the installer uses the installation configuration file located at `~/.config/openshift/installer.cfg.yml` if the file exists:

```
$ atomic-openshift-installer uninstall
```

Alternatively, you can specify a different location for the configuration file using the `-c` option:

```
$ atomic-openshift-installer -c </path/to/file> uninstall
```

See the [advanced installation method](#) for more options.

2.5.8. What's Next?

Now that you have a working OpenShift Container Platform instance, you can:

- [Configure authentication](#); by default, authentication is set to [Deny All](#).
- Configure the automatically-deployed [integrated Docker registry](#).
- Configure the automatically-deployed [router](#).

2.6. ADVANCED INSTALLATION

2.6.1. Overview

A reference configuration implemented using [Ansible](#) playbooks is available as the *advanced installation* method for installing a OpenShift Container Platform cluster. Familiarity with Ansible is assumed, however you can use this configuration as a reference to create your own implementation using the configuration management tool of your choosing.



IMPORTANT

While RHEL Atomic Host is supported for running containerized OpenShift Container Platform services, the advanced installation method utilizes Ansible, which is not available in RHEL Atomic Host, and must therefore be run from a RHEL 7 system. The host initiating the installation does not need to be intended for inclusion in the OpenShift Container Platform cluster, but it can be.

Alternatively, a [containerized version of the installer](#) is available as a system container, which is currently a Technology Preview feature.

Alternatively, you can use the [quick installation](#) method if you prefer an interactive installation experience.



NOTE

To install OpenShift Container Platform as a stand-alone registry, see [Installing a Stand-alone Registry](#).

2.6.2. Before You Begin

Before installing OpenShift Container Platform, you must first see the [Prerequisites](#) and [Host Preparation](#) topics to prepare your hosts. This includes verifying system and environment requirements per component type and properly installing and configuring Docker. It also includes installing Ansible version 2.3 or later, as the advanced installation method is based on Ansible playbooks and as such requires directly invoking Ansible.

If you are interested in installing OpenShift Container Platform using the containerized method (optional for RHEL but required for RHEL Atomic Host), see [Installing on Containerized Hosts](#) to ensure that you understand the differences between these methods, then return to this topic to continue.

For large-scale installs, including suggestions for optimizing install time, see the [Scaling and Performance Guide](#).

After following the instructions in the [Prerequisites](#) topic and deciding between the RPM and containerized methods, you can continue in this topic to [Configuring Ansible Inventory Files](#).

2.6.3. Configuring Ansible Inventory Files

The `/etc/ansible/hosts` file is Ansible's inventory file for the playbook used to install OpenShift Container Platform. The inventory file describes the configuration for your OpenShift Container Platform cluster. You must replace the default contents of the file with your desired configuration.

The following sections describe commonly-used variables to set in your inventory file during an advanced installation, followed by [example inventory files](#) you can use as a starting point for your installation.

Many of the Ansible variables described are optional. Accepting the default values should suffice for development environments, but for production environments, it is recommended you read through and become familiar with the various options available.

The example inventories describe various environment topographies, including [using multiple masters for high availability](#). You can choose an example that matches your requirements, modify it to match your own environment, and use it as your inventory file when [running the advanced installation](#).

Image Version Policy

Images require a version number policy in order to maintain updates. See the [Image Version Tag Policy](#) section in the Architecture Guide for more information.

2.6.3.1. Configuring Cluster Variables

To assign environment variables during the Ansible install that apply more globally to your OpenShift Container Platform cluster overall, indicate the desired variables in the `/etc/ansible/hosts` file on separate, single lines within the `[OSEv3:vars]` section. For example:

```
[OSEv3:vars]

openshift_master_identity_providers=[{'name': 'htpasswd_auth',
'login': 'true', 'challenge': 'true',
'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

openshift_master_default_subdomain=apps.test.example.com
```

IMPORTANT

If a parameter value in the Ansible inventory file contains special characters, such as `#`, `{` or `}`, you must double-escape the value (that is enclose the value in both single and double quotation marks). For example, to use `mypasswordwith###hashsigns` as a value for the variable `openshift_cloudprovider_openstack_password`, declare it as `openshift_cloudprovider_openstack_password="mypasswordwith###hashsigns"` in the Ansible host inventory file.

The following table describe variables for use with the Ansible installer that can be assigned cluster-wide:

Table 2.9. General Cluster Variables

Variable	Purpose
ansible_ssh_user	This variable sets the SSH user for the installer to use and defaults to root . This user should allow SSH-based authentication without requiring a password . If using SSH key-based authentication, then the key should be managed by an SSH agent.
ansible_become	If ansible_ssh_user is not root , this variable must be set to true and the user must be configured for passwordless sudo .
debug_level	<p>This variable sets which INFO messages are logged to the systemd-journald.service. Set one of the following:</p> <ul style="list-style-type: none"> • 0 to log errors and warnings only • 2 to log normal information (This is the default level.) • 4 to log debugging-level information • 6 to log API-level debugging information (request / response) • 8 to log body-level API debugging information <p>For more information on debug log levels, see Configuring Logging Levels.</p>
containerized	If set to true , containerized OpenShift Container Platform services are run on all target master and node hosts in the cluster instead of installed using RPM packages. If set to false or unset, the default RPM method is used. RHEL Atomic Host requires the containerized method, and is automatically selected for you based on the detection of the /run/ostree-booted file. See Installing on Containerized Hosts for more details. Containerized installations are supported starting in OpenShift Container Platform 3.1.1.
openshift_clock_enabled	<p>Whether to enable Network Time Protocol (NTP) on cluster nodes. true by default.</p> <div>  <div> <p>IMPORTANT</p> <p>To prevent masters and nodes in the cluster from going out of sync, do not change the default value of this parameter.</p> </div> </div>

Variable	Purpose
openshift_master_admission_plugin_config	<p>This variable sets the parameter and arbitrary JSON values as per the requirement in your inventory hosts file. For example:</p> <pre>openshift_master_admission_plugin_config={ "ClusterResourceOverride": { "configuration": { "apiVersion": "v1", "kind": "ClusterResourceOverrideConfig", "memoryRequestToLimitPercent": "25", "cpuRequestToLimitPercent": "25", "limitCPUToMemoryPercent": "200" } } }</pre>
openshift_master_audit_config	<p>This variable enables API service auditing. See Audit Configuration for more information.</p>
openshift_master_cluster_hostname	<p>This variable overrides the host name for the cluster, which defaults to the host name of the master.</p>
openshift_master_cluster_public_host_name	<p>This variable overrides the public host name for the cluster, which defaults to the host name of the master. If you use an external load balancer, specify the address of the external load balancer.</p> <p>For example:</p> <pre>openshift_master_cluster_public_hostname=openshift-ansible.public.example.com</pre>
openshift_master_cluster_method	<p>Optional. This variable defines the HA method when deploying multiple masters. Supports the native method. See Multiple Masters for more information.</p>
openshift_rolling_restart_mode	<p>This variable enables rolling restarts of HA masters (i.e., masters are taken down one at a time) when running the upgrade playbook directly. It defaults to services, which allows rolling restarts of services on the masters. It can instead be set to system, which enables rolling, full system restarts and also works for single master clusters.</p>

Variable	Purpose
<code>os_sdn_network_plugin_name</code>	This variable configures which OpenShift SDN plug-in to use for the pod network, which defaults to redhat/openshift-ovs-subnet for the standard SDN plug-in. Set the variable to redhat/openshift-ovs-multitenant to use the multitenant plug-in.
<code>openshift_master_identity_providers</code>	This variable sets the identity provider . The default value is Deny All . If you use a supported identity provider, configure OpenShift Container Platform to use it.
<code>openshift_master_named_certificates</code>	These variables are used to configure custom certificates which are deployed as part of the installation. See Configuring Custom Certificates for more information.
<code>openshift_master_overwrite_named_certificates</code>	
<code>openshift_hosted_router_certificate</code>	Provide the location of the custom certificates for the hosted router.
<code>openshift_hosted_registry_cert_expire_days</code>	Validity of the auto-generated registry certificate in days. Defaults to 730 (2 years).
<code>openshift_ca_cert_expire_days</code>	Validity of the auto-generated CA certificate in days. Defaults to 1825 (5 years).
<code>openshift_node_cert_expire_days</code>	Validity of the auto-generated node certificate in days. Defaults to 730 (2 years).
<code>openshift_master_cert_expire_days</code>	Validity of the auto-generated master certificate in days. Defaults to 730 (2 years).
<code>etcd_ca_default_days</code>	Validity of the auto-generated external etcd certificates in days. Controls validity for etcd CA, peer, server and client certificates. Defaults to 1825 (5 years).
<code>os_firewall_use_firewalld</code>	Set to true to use firewalld instead of the default iptables. Not available on RHEL Atomic Host. See the Configuring the Firewall section for more information.
<code>openshift_master_session_name</code>	These variables override defaults for session options in the OAuth configuration. See Configuring Session Options for more information.
<code>openshift_master_session_max_seconds</code>	

Variable	Purpose
<code>openshift_master_session_auth_secrets</code>	
<code>openshift_master_session_encryption_secrets</code>	
<code>openshift_set_node_ip</code>	This variable configures nodeIP in the node configuration. This variable is needed in cases where it is desired for node traffic to go over an interface other than the default network interface. The host variable openshift_ip can also be configured on each node to set a specific IP that might not be the IP of the default route.
<code>openshift_portal_net</code>	This variable configures the subnet in which services will be created within the OpenShift Container Platform SDN . This network block should be private and must not conflict with any existing network blocks in your infrastructure to which pods, nodes, or the master may require access to, or the installation will fail. Defaults to 172.30.0.0/16 , and cannot be re-configured after deployment. If changing from the default, avoid 172.17.0.0/16 , which the docker0 network bridge uses by default, or modify the docker0 network.
<code>openshift_master_default_subdomain</code>	This variable overrides the default subdomain to use for exposed routes .
<code>openshift_node_proxy_mode</code>	This variable specifies the service proxy mode to use: either iptables for the default, pure- iptables implementation, or userspace for the user space proxy.
<code>openshift_router_selector</code>	Default node selector for automatically deploying router pods. See Configuring Node Host Labels for details.
<code>openshift_registry_selector</code>	Default node selector for automatically deploying registry pods. See Configuring Node Host Labels for details.
<code>openshift_template_service_broker_namespaces</code>	This variable enables the template service broker by specifying one or more namespaces whose templates will be served by the broker.

Variable	Purpose
template_service_broker_selector	Default node selector for automatically deploying template service broker pods, defaults {"region": "infra"} . See Configuring Node Host Labels for details.
osm_default_node_selector	This variable overrides the node selector that projects will use by default when placing pods.
osm_cluster_network_cidr	This variable overrides the SDN cluster network CIDR block. This is the network from which pod IPs are assigned. This network block should be a private block and must not conflict with existing network blocks in your infrastructure to which pods, nodes, or the master may require access. Defaults to 10.128.0.0/14 and cannot be arbitrarily re-configured after deployment, although certain changes to it can be made in the SDN master configuration .
osm_host_subnet_length	This variable specifies the size of the per host subnet allocated for pod IPs by OpenShift Container Platform SDN . Defaults to 9 which means that a subnet of size /23 is allocated to each host; for example, given the default 10.128.0.0/14 cluster network, this will allocate 10.128.0.0/23, 10.128.2.0/23, 10.128.4.0/23, and so on. This cannot be re-configured after deployment.
openshift_use_flannel	This variable enables flannel as an alternative networking layer instead of the default SDN. If enabling flannel , disable the default SDN with the openshift_use_openshift_sdn variable. For more information, see Using Flannel .
openshift_docker_additional_registries	OpenShift Container Platform adds the specified additional registry or registries to the docker configuration. These are the registries to search.
openshift_docker_insecure_registries	OpenShift Container Platform adds the specified additional insecure registry or registries to the docker configuration. For any of these registries, secure sockets layer (SSL) is not verified. Also, add these registries to openshift_docker_additional_registries .

Variable	Purpose
openshift_docker_blocked_registries	OpenShift Container Platform adds the specified blocked registry or registries to the docker configuration. Block the listed registries. Setting this to all blocks everything not in the other variables.
openshift_metrics_hawkular_hostname	This variable sets the host name for integration with the metrics console by overriding metricsPublicURL in the master configuration for cluster metrics. If you alter this variable, ensure the host name is accessible via your router.
openshift_clusterid	This variable is a cluster identifier unique to the AWS Availability Zone. Using this avoids potential issues in Amazon Web Service (AWS) with multiple zones or multiple clusters. See Labeling Clusters for AWS for details.
openshift_image_tag	Use this variable to specify a container image tag to install or configure.
openshift_pkg_version	Use this variable to specify an RPM version to install or configure.



WARNING

If you modify the **openshift_image_tag** or the **openshift_pkg_version** variables after the cluster is set up, then an upgrade can be triggered, resulting in downtime.

- If **openshift_image_tag** is set, its value is used for all hosts in containerized environments, even those that have another version installed. If
- **openshift_pkg_version** is set, its value is used for all hosts in RPM-based environments, even those that have another version installed.

2.6.3.2. Configuring Deployment Type

Various defaults used throughout the playbooks and roles used by the installer are based on the deployment type configuration (usually defined in an Ansible inventory file).

Ensure the **openshift_deployment_type** parameter in your inventory file's **[OSEv3:vars]** section is set to **openshift-enterprise** to install the OpenShift Container Platform variant:

```
[OSEv3:vars]
openshift_deployment_type=openshift-enterprise
```

2.6.3.3. Configuring Host Variables

To assign environment variables to hosts during the Ansible installation, indicate the desired variables in the `/etc/ansible/hosts` file after the host entry in the **[masters]** or **[nodes]** sections. For example:

```
[masters]
ec2-52-6-179-239.compute-1.amazonaws.com openshift_public_hostname=ose3-
master.public.example.com
```

The following table describes variables for use with the Ansible installer that can be assigned to individual host entries:

Table 2.10. Host Variables

Variable	Purpose
openshift_hostname	This variable overrides the internal cluster host name for the system. Use this when the system's default IP address does not resolve to the system host name.
openshift_public_hostname	This variable overrides the system's public host name. Use this for cloud installations, or for hosts on networks using a network address translation (NAT).
openshift_ip	This variable overrides the cluster internal IP address for the system. Use this when using an interface that is not configured with the default route. openshift_ip can be used for <code>etcd</code> .
openshift_public_ip	This variable overrides the system's public IP address. Use this for cloud installations, or for hosts on networks using a network address translation (NAT).
containerized	If set to true , containerized OpenShift Container Platform services are run on the target master and node hosts instead of installed using RPM packages. If set to false or unset, the default RPM method is used. RHEL Atomic Host requires the containerized method, and is automatically selected for you based on the detection of the <code>/run/ostree-booted</code> file. See Installing on Containerized Hosts for more details. Containerized installations are supported starting in OpenShift Container Platform 3.1.1.
openshift_node_labels	This variable adds labels to nodes during installation. See Configuring Node Host Labels for more details.

Variable	Purpose
openshift_node_kubelet_args	<p>This variable is used to configure kubeletArguments on nodes, such as arguments used in container and image garbage collection, and to specify resources per node. kubeletArguments are key value pairs that are passed directly to the Kubelet that match the Kubelet's command line arguments. kubeletArguments are not migrated or validated and may become invalid if used. These values override other settings in node configuration which may cause invalid configurations. Example usage: <code>{'image-gc-high-threshold': ['90'],'image-gc-low-threshold': ['80']}</code>.</p>
openshift_docker_options	<p>This variable configures additional docker options within <code>/etc/sysconfig/docker</code>, such as options used in Managing Container Logs. Use json-file or journald. The default is journald. Example usage:</p> <pre>--log-driver json-file --log-opt max-size=1M --log-opt max-file=3" --log-driver journald"</pre> <p>Do not use when running docker as a system container.</p>
openshift_schedulable	<p>This variable configures whether the host is marked as a schedulable node, meaning that it is available for placement of new pods. See Configuring Schedulability on Masters.</p>

2.6.3.4. Configuring Master API and Console Ports

To configure the default ports used by the master API and web console, configure the following variables in the `/etc/ansible/hosts` file:

Table 2.11. Master API and Console Ports

Variable	Purpose
openshift_master_api_port	This variable sets the port number to access the OpenShift Container Platform API.
openshift_master_console_port	This variable sets the console port number to access the OpenShift Container Platform console with a web browser.

For example:

```
openshift_master_api_port=3443
openshift_master_console_port=8756
```

2.6.3.5. Configuring Cluster Pre-install Checks

Pre-install checks are a set of diagnostic tasks that run as part of the **openshift_health_checker** Ansible role. They run prior to an Ansible installation of OpenShift Container Platform, ensure that required inventory values are set, and identify potential issues on a host that can prevent or interfere with a successful installation.

The following table describes available pre-install checks that will run before every Ansible installation of OpenShift Container Platform:

Table 2.12. Pre-install Checks

Check Name	Purpose
memory_availability	This check ensures that a host has the recommended amount of memory for the specific deployment of OpenShift Container Platform. Default values have been derived from the latest installation documentation . A user-defined value for minimum memory requirements may be set by setting the openshift_check_min_host_memory_gb cluster variable in your inventory file.
disk_availability	This check only runs on etcd, master, and node hosts. It ensures that the mount path for an OpenShift Container Platform installation has sufficient disk space remaining. Recommended disk values are taken from the latest installation documentation . A user-defined value for minimum disk space requirements may be set by setting openshift_check_min_host_disk_gb cluster variable in your inventory file.
docker_storage	Only runs on hosts that depend on the docker daemon (nodes and containerized installations). Checks that docker 's total usage does not exceed a user-defined limit. If no user-defined limit is set, docker 's maximum usage threshold defaults to 90% of the total size available. The threshold limit for total percent usage can be set with a variable in your inventory file: max_thinpool_data_usage_percent=90 . A user-defined limit for maximum thinpool usage may be set by setting the max_thinpool_data_usage_percent cluster variable in your inventory file.

Check Name	Purpose
docker_storage_driver	Ensures that the docker daemon is using a storage driver supported by OpenShift Container Platform. If the devicemapper storage driver is being used, the check additionally ensures that a loopback device is not being used.
docker_image_availability	Attempts to ensure that images required by an OpenShift Container Platform installation are available either locally or in at least one of the configured container image registries on the host machine.
package_version	Runs on yum -based systems determining if multiple releases of a required OpenShift Container Platform package are available. Having multiple releases of a package available during an enterprise installation of OpenShift suggests that there are multiple yum repositories enabled for different releases, which may lead to installation problems. This check is skipped if the openshift_release variable is not defined in the inventory file.
package_availability	Runs prior to non-containerized installations of OpenShift Container Platform. Ensures that RPM packages required for the current installation are available.
package_update	Checks whether a yum update or package installation will succeed, without actually performing it or running yum on the host.

To disable specific pre-install checks, include the variable **openshift_disable_check** with a comma-delimited list of check names in your inventory file. For example:

```
openshift_disable_check=memory_availability,disk_availability
```



NOTE

A similar set of health checks meant to run for diagnostics on existing clusters can be found in [Ansible-based Health Checks](#). Another set of checks for checking certificate expiration can be found in [Redeploying Certificates](#).

2.6.3.6. Configuring System Containers



IMPORTANT

All system container components are [Technology Preview](#) features in OpenShift Container Platform 3.7. They must not be used in production and they are not supported for upgrades to OpenShift Container Platform 3.7. During this phase, they are only meant for use with new cluster installations in non-production environments.

System containers provide a way to containerize services that need to run before the **docker** daemon is running. They are Docker-formatted containers that use:

- [OSTree](#) for storage,
- [runC](#) for the runtime,
- [systemd](#) for service management, and
- [skopeo](#) for searching.

System containers are therefore stored and run outside of the traditional **docker** service. For more details on system container technology, see [Running System Containers](#) in the *Red Hat Enterprise Linux Atomic Host: Managing Containers* documentation.

You can configure your OpenShift Container Platform installation to run certain components as system containers instead of their RPM or standard containerized methods. Currently, the **docker** and **etcd** components can be run as system containers in OpenShift Container Platform.



WARNING

System containers are currently OS-specific because they require specific versions of **atomic** and **systemd**. For example, different system containers are created for RHEL, Fedora, or CentOS. Ensure that the system containers you are using match the OS of the host they will run on. OpenShift Container Platform only supports RHEL and RHEL Atomic as the host OS, so by default system containers built for RHEL are used.

2.6.3.6.1. Running Docker as a System Container



IMPORTANT

All system container components are [Technology Preview](#) features in OpenShift Container Platform 3.7. They must not be used in production and they are not supported for upgrades to OpenShift Container Platform 3.7. During this phase, they are only meant for use with new cluster installations in non-production environments.

The traditional method for using **docker** in an OpenShift Container Platform cluster is an [RPM package installation](#). For Red Hat Enterprise Linux (RHEL) systems, it must be specifically installed; for RHEL Atomic Host systems, it is provided by default.

However, you can configure your OpenShift Container Platform installation to alternatively run **docker** on node hosts as a system container. When using the system container method, the **container-**

engine container image and systemd service is used on the host instead of the **docker** package and service.

To run **docker** as a system container:

1. Because the default storage back end for Docker on RHEL 7 is a thin pool on loopback devices, for any RHEL systems you must still configure a thin pool logical volume for **docker** to use before running the OpenShift Container Platform installation. You can skip these steps for any RHEL Atomic Host systems.

For any RHEL systems, perform the steps described in the following sections:

- i. [Installing Docker](#)
- ii. [Configuring Docker Storage](#)

After completing the storage configuration steps, you can leave the RPM installed.

2. Set the following cluster variable to **True** in your inventory file in the **[OSEv3:vars]** section:

```
openshift_docker_use_system_container=True
```

When using the system container method, the following inventory variables for **docker** are ignored:

- **docker_version**
- **docker_upgrade**

Further, the following inventory variable must not be used:

- **openshift_docker_options**

You can also force **docker** in the system container to use a specific container registry and repository when pulling the **container-engine** image instead of from the default **registry.access.redhat.com/openshift3/**. To do so, set the following cluster variable in your inventory file in the **[OSEv3:vars]** section:

```
openshift_docker_systemcontainer_image_override="
<registry>/<user>/<image>:<tag>"
```

2.6.3.6.2. Running etcd as a System Container



IMPORTANT

All system container components are [Technology Preview](#) features in OpenShift Container Platform 3.7. They must not be used in production and they are not supported for upgrades to OpenShift Container Platform 3.7. During this phase, they are only meant for use with new cluster installations in non-production environments.

When using the RPM-based installation method for OpenShift Container Platform, etcd is installed using RPM packages on any RHEL systems. When using the containerized installation method, the **rhe17/etcd** image is used instead for RHEL or RHEL Atomic Hosts.

However, you can configure your OpenShift Container Platform installation to alternatively run etcd as a system container. Whereas the standard containerized method uses a systemd service named

etcd_container, the system container method uses the service name `etcd`, same as the RPM-based method. The data directory for `etcd` using this method is `/var/lib/etcd`.

To run `etcd` as a system container, set the following cluster variable in your inventory file in the `[OSEv3:vars]` section:

```
openshift_use_etcd_system_container=True
```

2.6.3.7. Configuring a Registry Location

If you are using an image registry other than the default at `registry.access.redhat.com`, specify the desired registry within the `/etc/ansible/hosts` file.

```
oreg_url=example.com/openshift3/ose-${component}:${version}
openshift_examples_modify_imagestreams=true
```

Table 2.13. Registry Variables

Variable	Purpose
oreg_url	Set to the alternate image location. Necessary if you are not using the default registry at registry.access.redhat.com .
openshift_examples_modify_imagestreams	Set to true if pointing to a registry other than the default. Modifies the image stream location to the value of oreg_url .

2.6.3.8. Configuring a Registry Route

To allow users to push and pull images to the internal Docker registry from outside of the OpenShift Container Platform cluster, configure the registry route in the `/etc/ansible/hosts` file. By default, the registry route is **docker-registry-default.router.default.svc.cluster.local**.

Table 2.14. Registry Route Variables

Variable	Purpose
openshift_hosted_registry_routehost	Set to the value of the desired registry route. The route contains either a name that resolves to an infrastructure node where a router manages communication or the subdomain that you set as the default application subdomain wildcard value. For example, if you set the openshift_master_default_subdomain parameter to apps.example.com and .apps.example.com resolves to infrastructure nodes or a load balancer, you might use registry.apps.example.com as the registry route.

Variable	Purpose
openshift_hosted_registry_routecertificates	Set the paths to the registry certificates. If you do not provide values for the certificate locations, certificates are generated. You can define locations for the following certificates: <ul style="list-style-type: none"> • certfile • keyfile • cafile
openshift_hosted_registry_routetermination	Set to one of the following values: <ul style="list-style-type: none"> • Set to reencrypt to terminate encryption at the edge router and re-encrypt it with a new certificate supplied by the destination. • Set to passthrough to terminate encryption at the destination. The destination is responsible for decrypting traffic.

For example:

```
openshift_hosted_registry_routehost=<path>
openshift_hosted_registry_routetermination=reencrypt
openshift_hosted_registry_routecertificates= '{"certfile': '<path>/org-
cert.pem', 'keyfile': '<path>/org-privkey.pem', 'cafile': '<path>/org-
chain.pem'}"
```

2.6.3.9. Configuring the Registry Console

If you are using a Cockpit registry console image other than the default or require a specific version of the console, specify the desired registry within the */etc/ansible/hosts* file.

```
openshift_cockpit_deployer_prefix=<registry-name>/<namespace>/
openshift_cockpit_deployer_version=<cockpit-image-tag>
```

Table 2.15. Registry Variables

Variable	Purpose
openshift_cockpit_deployer_prefix	Specify the URL and path to the directory where the image is located.
openshift_cockpit_deployer_version	Specify the Cockpit image version.

For example: If your image is at **registry.example.com/openshift3/registry-console** and you require version 1.4.1, enter:

```
openshift_cockpit_deployer_prefix='registry.example.com/openshift3/'
openshift_cockpit_deployer_version='1.4.1'
```

2.6.3.9.1. Configuring Registry Storage

There are several options for enabling registry storage when using the advanced install:

Option A: NFS Host Group



NOTE

The use of NFS for registry storage is not recommended in OpenShift Container Platform.

When the following variables are set, an NFS volume is created during an advanced install with the path **<nfs_directory>/<volume_name>** on the host within the **[nfs]** host group. For example, the volume path using these options would be **/exports/registry**.

```
[OSEv3:vars]

openshift_hosted_registry_storage_kind=nfs
openshift_hosted_registry_storage_access_modes=['ReadWriteMany']
openshift_hosted_registry_storage_nfs_directory=/exports
openshift_hosted_registry_storage_nfs_options='*(rw,root_squash)'
openshift_hosted_registry_storage_volume_name=registry
openshift_hosted_registry_storage_volume_size=10Gi
```

Option B: External NFS Host



NOTE

The use of NFS for registry storage is not recommended in OpenShift Container Platform.

To use an external NFS volume, one must already exist with a path of **<nfs_directory>/<volume_name>** on the storage host. The remote volume path using the following options would be **nfs.example.com:/exports/registry**.

```
[OSEv3:vars]

openshift_hosted_registry_storage_kind=nfs
openshift_hosted_registry_storage_access_modes=['ReadWriteMany']
openshift_hosted_registry_storage_host=nfs.example.com
openshift_hosted_registry_storage_nfs_directory=/exports
openshift_hosted_registry_storage_volume_name=registry
openshift_hosted_registry_storage_volume_size=10Gi
```

Option C: OpenStack Platform

An OpenStack storage configuration must already exist.

```
[OSEv3:vars]

openshift_hosted_registry_storage_kind=openstack
openshift_hosted_registry_storage_access_modes=['ReadWriteOnce']
openshift_hosted_registry_storage_openstack_filesystem=ext4
```

```
openshift_hosted_registry_storage_openstack_volumeID=3a650b4f-c8c5-4e0a-
8ca5-eaee11f16c57
openshift_hosted_registry_storage_volume_size=10Gi
```

Option D: AWS or Another S3 Storage Solution

The simple storage solution (S3) bucket must already exist.

```
[OSEv3:vars]

#openshift_hosted_registry_storage_kind=object
#openshift_hosted_registry_storage_provider=s3
#openshift_hosted_registry_storage_s3_accesskey=access_key_id
#openshift_hosted_registry_storage_s3_secretkey=secret_access_key
#openshift_hosted_registry_storage_s3_bucket=bucket_name
#openshift_hosted_registry_storage_s3_region=bucket_region
#openshift_hosted_registry_storage_s3_chunksize=26214400
#openshift_hosted_registry_storage_s3_rootdirectory=/registry
#openshift_hosted_registry_pullthrough=true
#openshift_hosted_registry_acceptschema2=true
#openshift_hosted_registry_enforcequota=true
```

If you are using a different S3 service, such as Minio or ExoScale, also add the region endpoint parameter:

```
openshift_hosted_registry_storage_s3_regionendpoint=https://myendpoint.exa
mple.com/
```

Option E: Google Cloud Storage (GCS) bucket on Google Compute Engine (GCE)

A GCS bucket must already exist.

```
[OSEv3:vars]

openshift_hosted_registry_storage_provider=gcs
openshift_hosted_registry_storage_gcs_bucket=bucket01
openshift_hosted_registry_storage_gcs_keyfile=test.key
openshift_hosted_registry_storage_gcs_rootdirectory=/registry
```

2.6.3.10. Configuring Router Sharding

[Router sharding](#) support is enabled by supplying the correct data to the inventory. The variable **openshift_hosted_routers** holds the data, which is in the form of a list. If no data is passed, then a default router is created. There are multiple combinations of router sharding. The following example supports routers on separate nodes:

```
openshift_hosted_routers=[{'name': 'router1', 'certificate': {'certfile':
'/path/to/certificate/abc.crt',
'keyfile': '/path/to/certificate/abc.key', 'cafile':
'/path/to/certificate/ca.crt'}, 'replicas': 1, 'serviceaccount': 'router',
'namespace': 'default', 'stats_port': 1936, 'edits': [], 'images':
'openshift3/ose-${component}:${version}', 'selector': 'type=router1',
'ports':
['80:80', '443:443']},
{'name': 'router2', 'certificate': {'certfile':
'/path/to/certificate/xyz.crt',
```

```
'keyfile': '/path/to/certificate/xyz.key', 'cafile':
'/path/to/certificate/ca.crt'}, 'replicas': 1, 'serviceaccount': 'router',
'namespace': 'default', 'stats_port': 1936, 'edits': [{'action': 'append',
'key': 'spec.template.spec.containers[0].env', 'value': {'name':
'ROUTE_LABELS',
'value': 'route=external'}}], 'images':
'openshift3/ose-${component}:${version}', 'selector': 'type=router2',
'ports':
['80:80', '443:443']}]
```

2.6.3.11. Configuring GlusterFS Persistent Storage

GlusterFS can be configured to provide [persistent storage](#) and [dynamic provisioning](#) for OpenShift Container Platform. It can be used both containerized within OpenShift Container Platform and non-containerized on its own nodes.

2.6.3.11.1. Configuring Containerized GlusterFS Persistent Storage

This option utilizes [Red Hat Container Native Storage \(CNS\)](#) for configuring containerized GlusterFS persistent storage in OpenShift Container Platform.



IMPORTANT

See [Containerized GlusterFS Considerations](#) for specific host preparations and prerequisites.

1. In your inventory file, add **glusterfs** in the **[OSEv3:children]** section to enable the **[glusterfs]** group:

```
[OSEv3:children]
masters
nodes
glusterfs
```

2. (Optional) Include any of the following role variables in the **[OSEv3:vars]** section you wish to change:

```
[OSEv3:vars]
openshift_storage_glusterfs_namespace=glusterfs ❶
openshift_storage_glusterfs_name=storage ❷
```

- ❶ The project (namespace) to host the storage pods. Defaults to **glusterfs**.
- ❷ A name to identify the GlusterFS cluster, which will be used in resource names. Defaults to **storage**.

3. Add a **[glusterfs]** section with entries for each storage node that will host the GlusterFS storage and include the **glusterfs_ip** and **glusterfs_devices** parameters in the form:

```
<hostname_or_ip> glusterfs_ip=<ip_address> glusterfs_devices='[ "
</path/to/device1/>', "</path/to/device2/>", ... ]'
```

For example:

```
[glusterfs]
192.168.10.11 glusterfs_ip=192.168.10.11 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
192.168.10.12 glusterfs_ip=192.168.10.12 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
192.168.10.13 glusterfs_ip=192.168.10.13 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
```

Set **glusterfs_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Set **glusterfs_ip** to the IP address that will be used by pods to communicate with the GlusterFS node.

4. Add the hosts listed under **[glusterfs]** to the **[nodes]** group as well:

```
[nodes]
192.168.10.11
192.168.10.12
192.168.10.13
```

5. After completing the cluster installation per [Running the Advanced Installation](#), run the following from a master to verify the necessary objects were successfully created:

- a. Verify that the GlusterFS **StorageClass** was created:

```
# oc get storageclass
NAME                                TYPE
glusterfs-storage                  kubernetes.io/glusterfs
```

- b. Verify that the route was created:

```
# oc get routes
NAME                                HOST/PORT
PATH                                SERVICES  PORT    TERMINATION  WILDCARD
heketi-glusterfs-route             heketi-glusterfs-
default.cloudapps.example.com      heketi-glusterfs <all>
None
```



NOTE

The name for the route will be **heketi-glusterfs-route** unless the default **glusterfs** value was overridden using the **openshift_glusterfs_storage_name** variable in the inventory file.

- c. Use **curl** to verify the route works correctly:

```
# curl http://heketi-glusterfs-
default.cloudapps.example.com/hello
Hello from Heketi.
```

After successful installation, see [Operations on a Red Hat Gluster Storage Pod in an OpenShift Environment](#) to check the status of the GlusterFS clusters.

[Dynamic provisioning](#) of GlusterFS volumes can occur by [creating a PVC to request storage](#).


2.6.3.12. Configuring the OpenShift Container Registry

Additional configuration options are available at installation time for the [OpenShift Container Registry](#).

If no registry storage options are used, the default OpenShift Container Platform registry is ephemeral and all data will be lost if the pod no longer exists. OpenShift Container Platform also supports a single node NFS-backed registry, but this option lacks redundancy and reliability compared with the GlusterFS-backed option.

2.6.3.12.1. Configuring a Containerized GlusterFS-Backed Registry

Similar to [configuring containerized GlusterFS for persistent storage](#), GlusterFS storage can be configured and deployed for an OpenShift Container Registry during the initial installation of the cluster to offer redundant and more reliable storage for the registry.



IMPORTANT

See [Containerized GlusterFS Considerations](#) for specific host preparations and prerequisites.

Configuration of storage for an OpenShift Container Registry is very similar to configuration for GlusterFS persistent storage in that it can be either containerized or non-containerized. For this containerized method, the following exceptions and additions apply:

1. In your inventory file, add **glusterfs_registry** in the **[OSEv3:children]** section to enable the **[glusterfs_registry]** group:

```
[OSEv3:children]
masters
nodes
glusterfs_registry
```

2. Add the following role variable in the **[OSEv3:vars]** section to enable the GlusterFS-backed registry, provided that the **glusterfs_registry** group name and the **[glusterfs_registry]** group exist:

```
[OSEv3:vars]
openshift_hosted_registry_storage_kind=glusterfs
```

3. It is recommended to have at least three registry pods, so set the following role variable in the **[OSEv3:vars]** section:

```
openshift_hosted_registry_replicas=3
```

4. If you want to specify the volume size for the GlusterFS-backed registry, set the following role variable in **[OSEv3:vars]** section:

```
openshift_hosted_registry_storage_volume_size=10Gi
```

If unspecified, the volume size defaults to **5Gi**.

5. The installer will deploy the OpenShift Container Registry pods and associated routers on nodes containing the **region=infra** label. Add this label on at least one node entry in the **[nodes]** section, otherwise the registry deployment will fail. For example:

```
[nodes]
192.168.10.14 openshift_schedulable=True openshift_node_labels="
{'region': 'infra'}"
```

6. Add a **[glusterfs_registry]** section with entries for each storage node that will host the GlusterFS-backed registry and include the **glusterfs_ip** and **glusterfs_devices** parameters in the form:

```
<hostname_or_ip> glusterfs_ip=<ip_address> glusterfs_devices='[ "
</path/to/device1/>', "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs_registry]
192.168.10.14 glusterfs_ip=192.168.10.14 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
192.168.10.15 glusterfs_ip=192.168.10.15 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
192.168.10.16 glusterfs_ip=192.168.10.16 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
```

Set **glusterfs_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Set **glusterfs_ip** to the IP address that will be used by pods to communicate with the GlusterFS node.

7. Add the hosts listed under **[glusterfs_registry]** to the **[nodes]** group as well:

```
[nodes]
192.168.10.14
192.168.10.15
192.168.10.16
```

After successful installation, see [Operations on a Red Hat Gluster Storage Pod in an OpenShift Environment](#) to check the status of the GlusterFS clusters.

2.6.3.13. Configuring Global Proxy Options

If your hosts require use of a HTTP or HTTPS proxy in order to connect to external hosts, there are many components that must be configured to use the proxy, including masters, Docker, and builds. Node services only connect to the master API requiring no external access and therefore do not need to be configured to use a proxy.

In order to simplify this configuration, the following Ansible variables can be specified at a cluster or host level to apply these settings uniformly across your environment.

**NOTE**


See [Configuring Global Build Defaults and Overrides](#) for more information on how the proxy environment is defined for builds.

Table 2.16. Cluster Proxy Variables

Variable	Purpose
openshift_http_proxy	This variable specifies the HTTP_PROXY environment variable for masters and the Docker daemon.
openshift_https_proxy	This variable specifies the HTTPS_PROXY environment variable for masters and the Docker daemon.
openshift_no_proxy	<p>This variable is used to set the NO_PROXY environment variable for masters and the Docker daemon. Provide a comma-separated list of host names, domain names, or wildcard host names that do not use the defined proxy. By default, this list is augmented with the list of all defined OpenShift Container Platform host names.</p> <p>The host names that do not use the defined proxy include:</p> <ul style="list-style-type: none"> • Master and node host names. You must include the domain suffix. • Other internal host names. You must include the domain suffix. • etcd IP addresses. You must provide the IP address because etcd access is managed by IP address. • The Docker registry IP address. • The Kubernetes IP address. This value is 172.30.0.1 by default and the openshift_portal_net parameter value if you provided one. • The cluster.local Kubernetes internal domain suffix. • The svc Kubernetes internal domain suffix.
openshift_generate_no_proxy_hosts	This boolean variable specifies whether or not the names of all defined OpenShift hosts and *.cluster.local should be automatically appended to the NO_PROXY list. Defaults to true ; set it to false to override this option.

Variable	Purpose
openshift_builddefaults_http_proxy	This variable defines the HTTP_PROXY environment variable inserted into builds using the BuildDefaults admission controller. If you do not define this parameter but define the openshift_http_proxy parameter, the openshift_http_proxy value is used. Set the openshift_builddefaults_http_proxy value to False to disable default http proxy for builds regardless of the openshift_http_proxy value.
openshift_builddefaults_https_proxy	This variable defines the HTTPS_PROXY environment variable inserted into builds using the BuildDefaults admission controller. If you do not define this parameter but define the openshift_http_proxy parameter, the openshift_https_proxy value is used. Set the openshift_builddefaults_https_proxy value to False to disable default https proxy for builds regardless of the openshift_https_proxy value.
openshift_builddefaults_no_proxy	This variable defines the NO_PROXY environment variable inserted into builds using the BuildDefaults admission controller. Set the openshift_builddefaults_no_proxy value to False to disable default no proxy settings for builds regardless of the openshift_no_proxy value.
openshift_builddefaults_git_http_proxy	This variable defines the HTTP proxy used by git clone operations during a build, defined using the BuildDefaults admission controller. Set the openshift_builddefaults_git_http_proxy value to False to disable default http proxy for git clone operations during a build regardless of the openshift_http_proxy value.
openshift_builddefaults_git_https_proxy	This variable defines the HTTPS proxy used by git clone operations during a build, defined using the BuildDefaults admission controller. Set the openshift_builddefaults_git_https_proxy value to False to disable default https proxy for git clone operations during a build regardless of the openshift_https_proxy value.

2.6.3.14. Configuring the Firewall

**IMPORTANT**

- If you are changing the default firewall, ensure that each host in your cluster is using the same firewall type to prevent inconsistencies.
- Do not use firewalld with the OpenShift Container Platform installed on Atomic Host. firewalld is not supported on Atomic host.

**NOTE**

While iptables is the default firewall, firewalld is recommended for new installations.

OpenShift Container Platform uses iptables as the default firewall, but you can configure your cluster to use firewalld during the install process.

Because iptables is the default firewall, OpenShift Container Platform is designed to have it configured automatically. However, iptables rules can break OpenShift Container Platform if not configured correctly. The advantages of firewalld include allowing multiple objects to safely share the firewall rules.

To use firewalld as the firewall for an OpenShift Container Platform installation, add the **os_firewall_use_firewalld** variable to the list of configuration variables in the Ansible host file at install:

```
[OSEv3:vars]
os_firewall_use_firewalld=True 1
```

- 1** Setting this variable to **true** opens the required ports and adds rules to the default zone, ensuring that firewalld is configured correctly.

**NOTE**

Using the firewalld default configuration comes with limited configuration options, and cannot be overridden. For example, while you can set up a storage network with interfaces in multiple zones, the interface that nodes communicate on must be in the default zone.

2.6.3.15. Configuring Schedulability on Masters

Any hosts you designate as masters during the installation process should also be configured as nodes so that the masters are configured as part of the [OpenShift SDN](#). You must do so by adding entries for these hosts to the **[nodes]** section:

```
[nodes]
master.example.com
```

In order to ensure that your masters are not burdened with running pods, they are automatically marked unschedulable by default by the installer, meaning that new pods cannot be placed on the hosts. This is the same as setting the **openshift_schedulable=false** host variable.

You can manually set a master host to schedulable during installation using the **openshift_schedulable=true** host variable, though this is not recommended in production environments:

■

```
[nodes]
master.example.com openshift_schedulable=true
```

If you want to change the schedulability of a host post-installation, see [Marking Nodes as Unschedulable or Schedulable](#).

2.6.3.16. Configuring Node Host Labels

You can assign [labels](#) to node hosts during the Ansible install by configuring the `/etc/ansible/hosts` file. Labels are useful for determining the placement of pods onto nodes using the [scheduler](#). Other than **region=infra** (discussed in [Configuring Dedicated Infrastructure Nodes](#)), the actual label names and values are arbitrary and can be assigned however you see fit per your cluster's requirements.

To assign labels to a node host during an Ansible install, use the **openshift_node_labels** variable with the desired labels added to the desired node host entry in the **[nodes]** section. In the following example, labels are set for a region called **primary** and a zone called **east**:

```
[nodes]
node1.example.com openshift_node_labels="{ 'region': 'primary', 'zone':
'east' }"
```


2.6.3.16.1. Configuring Dedicated Infrastructure Nodes

The **openshift_router_selector** and **openshift_registry_selector** Ansible settings determine the label selectors used when placing registry and router pods. They are set to **region=infra** by default:

```
# default selectors for router and registry services
# openshift_router_selector='region=infra'
# openshift_registry_selector='region=infra'
```

The default router and registry will be automatically deployed during installation if nodes exist in the **[nodes]** section that match the selector settings. For example:

```
[nodes]
infra-node1.example.com openshift_node_labels="{ 'region': 'infra', 'zone':
'default' }"
```



IMPORTANT

The registry and router are only able to run on node hosts with the **region=infra** label. Ensure that at least one node host in your OpenShift Container Platform environment has the **region=infra** label.

It is recommended for production environments that you maintain dedicated infrastructure nodes where the registry and router pods can run separately from pods used for user applications.

If you do not intend to use OpenShift Container Platform to manage the registry and router, configure the following Ansible settings:

```
openshift_hosted_manage_registry=false
openshift_hosted_manage_router=false
```

If you are using an image registry other than the default **registry.access.redhat.com**, you need to [specify the desired registry](#) in the **/etc/ansible/hosts** file.

As described in [Configuring Schedulability on Masters](#), master hosts are marked unschedulable by default. If you label a master host with **region=infra** and have no other dedicated infrastructure nodes, you must also explicitly mark these master hosts as schedulable. Otherwise, the registry and router pods cannot be placed anywhere:

```
[nodes]
master.example.com openshift_node_labels="{ 'region': 'infra', 'zone':
'default' }" openshift_schedulable=true
```

2.6.3.17. Configuring Session Options

[Session options](#) in the OAuth configuration are configurable in the inventory file. By default, Ansible populates a **sessionSecretsFile** with generated authentication and encryption secrets so that sessions generated by one master can be decoded by the others. The default location is **/etc/origin/master/session-secrets.yaml**, and this file will only be re-created if deleted on all masters.

You can set the session name and maximum number of seconds with **openshift_master_session_name** and **openshift_master_session_max_seconds**:

```
openshift_master_session_name=ssn
openshift_master_session_max_seconds=3600
```

If provided, **openshift_master_session_auth_secrets** and **openshift_master_encryption_secrets** must be equal length.

For **openshift_master_session_auth_secrets**, used to authenticate sessions using HMAC, it is recommended to use secrets with 32 or 64 bytes:

```
openshift_master_session_auth_secrets=[ 'DONT+USE+THIS+SECRET+b4NV+pmZNS0' ]
```

For **openshift_master_encryption_secrets**, used to encrypt sessions, secrets must be 16, 24, or 32 characters long, to select AES-128, AES-192, or AES-256:

```
openshift_master_session_encryption_secrets=
[ 'DONT+USE+THIS+SECRET+b4NV+pmZNS0' ]
```

2.6.3.18. Configuring Custom Certificates

[Custom serving certificates](#) for the public host names of the OpenShift Container Platform API and [web console](#) can be deployed during an advanced installation and are configurable in the inventory file.



NOTE

Custom certificates should only be configured for the host name associated with the **publicMasterURL** which can be set using **openshift_master_cluster_public_hostname**. Using a custom serving certificate for the host name associated with the **masterURL** (**openshift_master_cluster_hostname**) will result in TLS errors as infrastructure components will attempt to contact the master API using the internal **masterURL** host.

Certificate and key file paths can be configured using the **openshift_master_named_certificates** cluster variable:

```
openshift_master_named_certificates=[{"certfile": "/path/to/custom1.crt",
"keyfile": "/path/to/custom1.key", "cafile": "/path/to/custom-ca1.crt"}]
```

File paths must be local to the system where Ansible will be run. Certificates are copied to master hosts and are deployed within the **/etc/origin/master/named_certificates/** directory.

Ansible detects a certificate's **Common Name** and **Subject Alternative Names**. Detected names can be overridden by providing the "names" key when setting **openshift_master_named_certificates**:

```
openshift_master_named_certificates=[{"certfile": "/path/to/custom1.crt",
"keyfile": "/path/to/custom1.key", "names": ["public-master-host.com"],
"cafile": "/path/to/custom-ca1.crt"}]
```

Certificates configured using **openshift_master_named_certificates** are cached on masters, meaning that each additional Ansible run with a different set of certificates results in all previously deployed certificates remaining in place on master hosts and within the master configuration file.

If you would like **openshift_master_named_certificates** to be overwritten with the provided value (or no value), specify the **openshift_master_overwrite_named_certificates** cluster variable:

```
openshift_master_overwrite_named_certificates=true
```

For a more complete example, consider the following cluster variables in an inventory file:

```
openshift_master_cluster_method=native
openshift_master_cluster_hostname=lb-internal.openshift.com
openshift_master_cluster_public_hostname=custom.openshift.com
```

To overwrite the certificates on a subsequent Ansible run, you could set the following:

```
openshift_master_named_certificates=[{"certfile":
"/root/STAR.openshift.com.crt", "keyfile": "/root/STAR.openshift.com.key",
"names": ["custom.openshift.com"]}]]
openshift_master_overwrite_named_certificates=true
```

2.6.3.19. Configuring Certificate Validity

By default, the certificates used to govern the etcd, master, and kubelet expire after two to five years. The validity (length in days until they expire) for the auto-generated registry, CA, node, and master certificates can be configured during installation using the following variables (default values shown):

```
[OSEv3:vars]

openshift_hosted_registry_cert_expire_days=730
openshift_ca_cert_expire_days=1825
openshift_node_cert_expire_days=730
openshift_master_cert_expire_days=730
etcd_ca_default_days=1825
```


These values are also used when [redeploying certificates](#) via Ansible post-installation.

2.6.3.20. Configuring Cluster Metrics

The OpenShift Container Platform web console uses the data coming from the Hawkular Metrics service to display its graphs. The metrics public URL can be set during cluster installation using the **openshift_metrics_hawkular_hostname** Ansible variable, which defaults to:

```
https://hawkular-metrics.  
{{openshift_master_default_subdomain}}/hawkular/metrics
```

If you alter this variable, ensure the host name is accessible via your router.



IMPORTANT

In accordance with upstream Kubernetes rules, metrics can be collected only on the default interface of **eth0**.



NOTE

You must set an **openshift_master_default_subdomain** value to deploy metrics.

2.6.3.20.1. Configuring Metrics Storage

The **openshift_metrics_cassandra_storage_type** variable must be set in order to use persistent storage for metrics. If **openshift_metrics_cassandra_storage_type** is not set, then cluster metrics data is stored in an **emptyDir** volume, which will be deleted when the Cassandra pod terminates.

There are three options for enabling cluster metrics storage when using the advanced install:

Option A: Dynamic

If your OpenShift Container Platform environment supports [dynamic volume provisioning](#) for your cloud provider, use the following variable:


```
[OSEv3:vars]
```

```
openshift_metrics_cassandra_storage_type=dynamic
```

If there are multiple default dynamically provisioned volume types, such as gluster-storage and glusterfs-storage-block, you can specify the provisioned volume type by variable. For example, **openshift_metrics_cassandra_pvc_storage_class_name=glusterfs-storage-block**.

Check [Volume Configuration](#) for more information on using **DynamicProvisioningEnabled** to enable or disable dynamic provisioning.

Option B: NFS Host Group



IMPORTANT


The use of NFS for metrics storage is not recommended in OpenShift Container Platform.

When the following variables are set, an NFS volume is created during an advanced install with path **<nfs_directory>/<volume_name>** on the host within the **[nfs]** host group. For example, the volume path using these options would be **/exports/metrics**:

```
[OSEv3:vars]

openshift_metrics_storage_kind=nfs
openshift_metrics_storage_access_modes=['ReadWriteOnce']
openshift_metrics_storage_nfs_directory=/exports
openshift_metrics_storage_nfs_options='*(rw,root_squash)'
openshift_metrics_storage_volume_name=metrics
openshift_metrics_storage_volume_size=10Gi
```

Option C: External NFS Host



IMPORTANT

The use of NFS for metrics storage is not recommended in OpenShift Container Platform.

To use an external NFS volume, one must already exist with a path of **<nfs_directory>/<volume_name>** on the storage host.

```
[OSEv3:vars]

openshift_metrics_storage_kind=nfs
openshift_metrics_storage_access_modes=['ReadWriteOnce']
openshift_metrics_storage_host=nfs.example.com
openshift_metrics_storage_nfs_directory=/exports
openshift_metrics_storage_volume_name=metrics
openshift_metrics_storage_volume_size=10Gi
```

The remote volume path using the following options would be **nfs.example.com:/exports/metrics**.

2.6.3.21. Configuring Cluster Logging

Cluster logging is not set to automatically deploy by default. Set the following to enable cluster logging when using the advanced installation method:

```
[OSEv3:vars]

openshift_logging_install_logging=true
```

2.6.3.21.1. Configuring Logging Storage

The **openshift_logging_es_pvc_dynamic** variable must be set in order to use persistent storage for logging. If **openshift_logging_es_pvc_dynamic** is not set, then cluster logging data is stored in an **emptyDir** volume, which will be deleted when the Elasticsearch pod terminates.

There are three options for enabling cluster logging storage when using the advanced install:

Option A: Dynamic

If your OpenShift Container Platform environment supports [dynamic volume provisioning](#) for your cloud provider, use the following variable:


```
[OSEv3:vars]

openshift_logging_es_pvc_dynamic=true
```

If there are multiple default dynamically provisioned volume types, such as gluster-storage and glusterfs-storage-block, you can specify the provisioned volume type by variable. For example, **openshift_logging_es_pvc_storage_class_name=glusterfs-storage-block**.

Check [Volume Configuration](#) for more information on using **DynamicProvisioningEnabled** to enable or disable dynamic provisioning.

Option B: NFS Host Group



IMPORTANT


The use of NFS for logging storage is not recommended in OpenShift Container Platform.

When the following variables are set, an NFS volume is created during an advanced install with path **<nfs_directory>/<volume_name>** on the host within the **[nfs]** host group. For example, the volume path using these options would be **/exports/logging**:

```
[OSEv3:vars]

openshift_logging_storage_kind=nfs
openshift_logging_storage_access_modes=[ 'ReadWriteOnce' ]
openshift_logging_storage_nfs_directory=/exports
openshift_logging_storage_nfs_options='*(rw,root_squash)'
openshift_logging_storage_volume_name=logging
openshift_logging_storage_volume_size=10Gi
```

Option C: External NFS Host



IMPORTANT

The use of NFS for logging storage is not recommended in OpenShift Container Platform.

To use an external NFS volume, one must already exist with a path of **<nfs_directory>/<volume_name>** on the storage host.

```
[OSEv3:vars]

openshift_logging_storage_kind=nfs
openshift_logging_storage_access_modes=[ 'ReadWriteOnce' ]
openshift_logging_storage_host=nfs.example.com
openshift_logging_storage_nfs_directory=/exports
openshift_logging_storage_volume_name=logging
openshift_logging_storage_volume_size=10Gi
```

The remote volume path using the following options would be **nfs.example.com:/exports/logging**.

2.6.3.22. Customizing Service Catalog Options

Starting with OpenShift Container Platform 3.7, the [service catalog](#) is enabled by default during

installation. Enabling the service broker allows you to register service brokers with the catalog. When the service catalog is enabled, the OpenShift Ansible broker and template service broker are both installed as well; see [Configuring the OpenShift Ansible Broker](#) and [Configuring the Template Service Broker](#) for more information. If you disable the service catalog, the OpenShift Ansible broker and template service broker are not installed.

To disable automatic deployment of the service catalog, set the following cluster variable in your inventory file:

```
openshift_enable_service_catalog=false
```

When the service catalog is enabled, the web console shows the updated landing page. The OpenShift Ansible broker and template service broker are both enabled as well; see [Configuring the OpenShift Ansible Broker](#) and [Configuring the Template Service Broker](#) for more information.

2.6.3.22.1. Configuring the OpenShift Ansible Broker

Starting with OpenShift Container Platform 3.7, the [OpenShift Ansible broker](#) (OAB) is enabled by default during installation.

If you do not want to install the OAB, set the `ansible_service_broker_install` parameter value to `false` in the inventory file:

```
ansible_service_broker_install=false
```

2.6.3.22.1.1. Configuring Persistent Storage for the OpenShift Ansible Broker

The OAB deploys its own etcd instance separate from the etcd used by the rest of the OpenShift Container Platform cluster. The OAB's etcd instance requires separate storage using persistent volumes (PVs) to function. If no PV is available, etcd will wait until the PV can be satisfied. The OAB application will enter a **CrashLoop** state until its etcd instance is available.

You can use the installer with the following variables to configure persistent storage for the OAB using NFS.

Table 2.17. OpenShift Ansible Broker Storage Ansible Variables

Variable	Purpose
<code>openshift_hosted_etcd_storage_kind</code>	Storage type to use for the etcd PV. <code>nfs</code> is supported using this method.
<code>openshift_hosted_etcd_storage_volume_name</code>	Name of etcd PV.
<code>openshift_hosted_etcd_storage_access_modes</code>	Defaults to <code>ReadWriteOnce</code> .
<code>openshift_hosted_etcd_storage_volume_size</code>	Size of the etcd PV. Defaults to <code>1Gi</code> .

Variable	Purpose
openshift_hosted_etcd_storage_labels	Labels to use for the etcd PV. Defaults to {'storage': 'etcd'}
openshift_hosted_etcd_storage_nfs_options	NFS options to use. Defaults to * (rw,root_squash)
openshift_hosted_etcd_storage_nfs_directory	Directory for NFS exports. Defaults to /exports .

Some Ansible playbook bundles (APBs) may also require a PV for their own usage. Two APBs are currently provided with OpenShift Container Platform 3.7: MediaWiki and PostgreSQL. Both of these require their own PV to deploy.

To configure persistent storage for the OAB:

1. In your inventory file, add **nfs** to the **[OSEv3:children]** section to enable the **[nfs]** group:

```
[OSEv3:children]
masters
nodes
nfs
```

2. Add a **[nfs]** group section and add the host name for the system that will be the NFS host:

```
[nfs]
master1.example.com
```

3. Add the following in the **[OSEv3:vars]** section:

```
openshift_hosted_etcd_storage_kind=nfs
openshift_hosted_etcd_storage_nfs_options="*
(rw,root_squash, sync, no_wdelay)"
openshift_hosted_etcd_storage_nfs_directory=/opt/osev3-etcd 1
openshift_hosted_etcd_storage_volume_name=etcd-vol2 2
openshift_hosted_etcd_storage_access_modes=["ReadWriteOnce"]
openshift_hosted_etcd_storage_volume_size=1G
openshift_hosted_etcd_storage_labels={'storage': 'etcd'}
```

- 1 2** An NFS volume will be created with path **<nfs_directory>/<volume_name>** on the host within the **[nfs]** group. For example, the volume path using these options would be **/opt/osev3-etcd/etcd-vol2**.

These settings create a persistent volume that is attached to the OAB's etcd instance during cluster installation.

2.6.3.22.1.2. Configuring the OpenShift Ansible Broker for Local APB Development

In order to do [APB development](#) with the OpenShift Container Registry in conjunction with the OAB, a whitelist of images the OAB can access must be defined. If a whitelist is not defined, the broker will ignore APBs and users will not see any APBs available.

By default, the whitelist is empty so that a user cannot add APB images to the broker without a cluster administrator configuring the broker. To whitelist all images that end in **-apb**:

1. In your inventory file, add the following to the **[OSEv3:vars]** section:

```
ansible_service_broker_local_registry_whitelist=['.*-apb$']
```

2.6.3.22.2. Configuring the Template Service Broker

Starting with OpenShift Container Platform 3.7, the [template service broker](#) (TSB) is enabled by default.

If you do not want to install the TSB, set the **template_service_broker_install** parameter value to **false**:

```
template_service_broker_install=false
```

To configure the TSB, one or more projects must be defined as the broker's source namespace(s) for loading templates and image streams into the service catalog. Set the desired projects by modifying the following in your inventory file's **[OSEv3:vars]** section:

```
openshift_template_service_broker_namespaces=['openshift','myproject']
```

By default, the TSB will use the nodeselector **{"region": "infra"}** for deploying its pods. You can modify this by setting the desired nodeselector in your inventory file's **[OSEv3:vars]** section:

```
template_service_broker_selector={"region": "infra"}
```

2.6.3.23. Configuring Web Console Customization

The following Ansible variables set master configuration options for customizing the web console. See [Customizing the Web Console](#) for more details on these customization options.

Table 2.18. Web Console Customization Variables

Variable	Purpose
openshift_master_logout_url	Sets logoutURL in the master configuration. See Changing the Logout URL for details. Example value: http://example.com
openshift_master_extension_scripts	Sets extensionScripts in the master configuration. See Loading Extension Scripts and Stylesheets for details. Example value: ['/path/to/script1.js', '/path/to/script2.js']

Variable	Purpose
openshift_master_extension_stylesheets	Sets extensionStylesheets in the master configuration. See Loading Extension Scripts and Stylesheets for details. Example value: <code>['/path/to/stylesheet1.css', '/path/to/stylesheet2.css']</code>
openshift_master_extensions	Sets extensions in the master configuration. See Serving Static Files and Customizing the About Page for details. Example value: <code>[{'name': 'images', 'sourceDirectory': '/path/to/my_images'}]</code>
openshift_master_oauth_template	Sets the OAuth template in the master configuration. See Customizing the Login Page for details. Example value: <code>['/path/to/login-template.html']</code>
openshift_master_metrics_public_url	Sets metricsPublicURL in the master configuration. See Setting the Metrics Public URL for details. Example value: <code>https://hawkular-metrics.example.com/hawkular/metrics</code>
openshift_master_logging_public_url	Sets loggingPublicURL in the master configuration. See Kibana for details. Example value: <code>https://kibana.example.com</code>

2.6.4. Example Inventory Files

2.6.4.1. Single Master Examples

You can configure an environment with a single master and multiple nodes, and either a single or multiple number of external etcd hosts.



NOTE

Moving from a single master cluster to multiple masters after installation is not supported.

Single Master, Single etcd, and Multiple Nodes

The following table describes an example environment for a single [master](#) (with a single **etcd** on the same host), two [nodes](#) for hosting user applications, and two nodes with the **region=infra** label for hosting [dedicated infrastructure](#):

Host Name	Infrastructure Component to Install
master.example.com	Master, etcd, and node
node1.example.com	Node

Host Name	Infrastructure Component to Install
node2.example.com	
infra-node1.example.com	Node (with region=infra label)
infra-node2.example.com	

You can see these example hosts present in the **[masters]**, **[etcd]**, and **[nodes]** sections of the following example inventory file:

Single Master, Single etcd, and Multiple Nodes Inventory File

```
# Create an OSEv3 group that contains the masters, nodes, and etcd groups
[OSEv3:children]
masters
nodes
etcd

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
# SSH user, this user should allow ssh based auth without requiring a
password
ansible_ssh_user=root

# If ansible_ssh_user is not root, ansible_become must be set to true
#ansible_become=true

openshift_deployment_type=openshift-enterprise

# uncomment the following to enable httpasswd authentication; defaults to
DenyAllPasswordIdentityProvider
#openshift_master_identity_providers=[{'name': 'httpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/httpasswd'}]

# host group for masters
[masters]
master.example.com

# host group for etcd
[etcd]
master.example.com

# host group for nodes, includes region info
[nodes]
master.example.com
node1.example.com openshift_node_labels="{ 'region': 'primary', 'zone':
'east' }"
node2.example.com openshift_node_labels="{ 'region': 'primary', 'zone':
'west' }"
infra-node1.example.com openshift_node_labels="{ 'region': 'infra', 'zone':
```

```
'default'}"
infra-node2.example.com openshift_node_labels="{ 'region': 'infra', 'zone':
'default' }"
```

To use this example, modify the file to match your environment and specifications, and save it as */etc/ansible/hosts*.

Single Master, Multiple etcd, and Multiple Nodes

The following table describes an example environment for a single master, three etcd hosts, two nodes for hosting user applications, and two nodes with the **region=infra** label for hosting dedicated infrastructure:

Host Name	Infrastructure Component to Install
master.example.com	Master and node
etcd1.example.com	etcd
etcd2.example.com	
etcd3.example.com	
node1.example.com	Node
node2.example.com	
infra-node1.example.com	Node (with region=infra label)
infra-node2.example.com	

You can see these example hosts present in the **[masters]**, **[nodes]**, and **[etcd]** sections of the following example inventory file:

Single Master, Multiple etcd, and Multiple Nodes Inventory File

```
# Create an OSEv3 group that contains the masters, nodes, and etcd groups
[OSEv3:children]
masters
nodes
etcd

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise

# uncomment the following to enable httpasswd authentication; defaults to
DenyAllPasswordIdentityProvider
#openshift_master_identity_providers=[{'name': 'httpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/httpasswd'}]
```

```
# host group for masters
[masters]
master.example.com

# host group for etcd
[etcd]
etcd1.example.com
etcd2.example.com
etcd3.example.com

# host group for nodes, includes region info
[nodes]
master.example.com
node1.example.com openshift_node_labels="{ 'region': 'primary', 'zone': 'east' }"
node2.example.com openshift_node_labels="{ 'region': 'primary', 'zone': 'west' }"
infra-node1.example.com openshift_node_labels="{ 'region': 'infra', 'zone': 'default' }"
infra-node2.example.com openshift_node_labels="{ 'region': 'infra', 'zone': 'default' }"
```

To use this example, modify the file to match your environment and specifications, and save it as */etc/ansible/hosts*.

2.6.4.2. Multiple Masters Examples

You can configure an environment with multiple masters, multiple etcd hosts, and multiple nodes. Configuring [multiple masters for high availability](#) (HA) ensures that the cluster has no single point of failure.



NOTE

Moving from a single master cluster to multiple masters after installation is not supported.

When configuring multiple masters, the advanced installation supports the **native** high availability (HA) method. This method leverages the native HA master capabilities built into OpenShift Container Platform and can be combined with any load balancing solution.

If a host is defined in the **[lb]** section of the inventory file, Ansible installs and configures HAProxy automatically as the load balancing solution. If no host is defined, it is assumed you have pre-configured an external load balancing solution of your choice to balance the master API (port 8443) on all master hosts.



NOTE

This HAProxy load balancer is intended to demonstrate the API server's HA mode and is not recommended for production environments. If you are deploying to a cloud provider, Red Hat recommends deploying a cloud-native TCP-based load balancer or take other steps to provide a highly available load balancer.

For an external load balancing solution, you must have:

- A pre-created load balancer VIP configured for SSL passthrough.
- A VIP listening on the port specified by the `openshift_master_api_port` and `openshift_master_console_port` values (8443 by default) and proxying back to all master hosts on that port.
- A domain name for VIP registered in DNS.
 - The domain name will become the value of both `openshift_master_cluster_public_hostname` and `openshift_master_cluster_hostname` in the OpenShift Container Platform installer.

See [External Load Balancer Integrations](#) for more information. For more on the high availability master architecture, see [Kubernetes Infrastructure](#).



NOTE

The advanced installation method does not currently support multiple HAProxy load balancers in an active-passive setup. See the [Load Balancer Administration documentation](#) for post-installation amendments.

To configure multiple masters, refer to the following section.

Multiple Masters with Multiple etcd

The following describes an example environment for three [masters](#) using the **native** HA method:; one HAProxy load balancer, three [etcd](#) hosts, two [nodes](#) for hosting user applications, and two nodes with the `region=infra` label for hosting [dedicated infrastructure](#):

Host Name	Infrastructure Component to Install
master1.example.com	Master (clustered using native HA) and node
master2.example.com	
master3.example.com	
lb.example.com	HAProxy to load balance API master endpoints
etcd1.example.com	etcd
etcd2.example.com	
etcd3.example.com	
node1.example.com	Node
node2.example.com	
infra-node1.example.com	Node (with <code>region=infra</code> label)

Host Name	Infrastructure Component to Install
infra-node2.example.com	

You can see these example hosts present in the **[masters]**, **[etcd]**, **[lb]**, and **[nodes]** sections of the following example inventory file:

Multiple Masters Using HAProxy Inventory File

```
# Create an OSEv3 group that contains the master, nodes, etcd, and lb
groups.
# The lb group lets Ansible configure HAProxy as the load balancing
solution.
# Comment lb out if your load balancer is pre-configured.
[OSEv3:children]
masters
nodes
etcd
lb

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise

# Uncomment the following to enable htpasswd authentication; defaults to
# DenyAllPasswordIdentityProvider.
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

# Native high availability cluster method with optional load balancer.
# If no lb group is defined installer assumes that a load balancer has
# been preconfigured. For installation the value of
# openshift_master_cluster_hostname must resolve to the load balancer
# or to one or all of the masters defined in the inventory if no load
# balancer is present.
openshift_master_cluster_method=native
openshift_master_cluster_hostname=openshift-internal.example.com
openshift_master_cluster_public_hostname=openshift-cluster.example.com

# apply updated node defaults
openshift_node_kubelet_args={'pods-per-core': ['10'], 'max-pods': ['250'],
'image-gc-high-threshold': ['90'], 'image-gc-low-threshold': ['80']}

# enable ntp on masters to ensure proper failover
openshift_clock_enabled=true

# host group for masters
[masters]
master1.example.com
master2.example.com
master3.example.com
```

```
# host group for etcd
[etcd]
etcd1.example.com
etcd2.example.com
etcd3.example.com

# Specify load balancer host
[lb]
lb.example.com

# host group for nodes, includes region info
[nodes]
master[1:3].example.com
node1.example.com openshift_node_labels="{ 'region': 'primary', 'zone': 'east' }"
node2.example.com openshift_node_labels="{ 'region': 'primary', 'zone': 'west' }"
infra-node1.example.com openshift_node_labels="{ 'region': 'infra', 'zone': 'default' }"
infra-node2.example.com openshift_node_labels="{ 'region': 'infra', 'zone': 'default' }"
```

To use this example, modify the file to match your environment and specifications, and save it as ***/etc/ansible/hosts***.

Multiple Masters with Master and etcd on the Same Host

The following describes an example environment for three [masters](#) using the **native** HA method (with [etcd](#) on each host), one HAProxy load balancer, two [nodes](#) for hosting user applications, and two nodes with the **region=infra** label for hosting [dedicated infrastructure](#):

Host Name	Infrastructure Component to Install
master1.example.com	Master (clustered using native HA) and node with etcd on each host
master2.example.com	
master3.example.com	
lb.example.com	HAProxy to load balance API master endpoints
node1.example.com	Node
node2.example.com	
infra-node1.example.com	Node (with region=infra label)
infra-node2.example.com	

You can see these example hosts present in the **[masters]**, **[etcd]**, **[lb]**, and **[nodes]** sections of the following example inventory file:

```

# Create an OSEv3 group that contains the master, nodes, etcd, and lb
groups.
# The lb group lets Ansible configure HAProxy as the load balancing
solution.
# Comment lb out if your load balancer is pre-configured.
[OSEv3:children]
masters
nodes
etcd
lb

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise

# Uncomment the following to enable httpasswd authentication; defaults to
# DenyAllPasswordIdentityProvider.
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

# Native high availability cluster method with optional load balancer.
# If no lb group is defined installer assumes that a load balancer has
# been preconfigured. For installation the value of
# openshift_master_cluster_hostname must resolve to the load balancer
# or to one or all of the masters defined in the inventory if no load
# balancer is present.
openshift_master_cluster_method=native
openshift_master_cluster_hostname=openshift-internal.example.com
openshift_master_cluster_public_hostname=openshift-cluster.example.com

# host group for masters
[masters]
master1.example.com
master2.example.com
master3.example.com

# host group for etcd
[etcd]
master1.example.com
master2.example.com
master3.example.com

# Specify load balancer host
[lb]
lb.example.com

# host group for nodes, includes region info
[nodes]
master[1:3].example.com
node1.example.com openshift_node_labels="{ 'region': 'primary', 'zone':
'east' }"
node2.example.com openshift_node_labels="{ 'region': 'primary', 'zone':
'west' }"
infra-node1.example.com openshift_node_labels="{ 'region': 'infra', 'zone':

```

```
'default'}"
infra-node2.example.com openshift_node_labels="{ 'region': 'infra', 'zone':
'default' }"
```

To use this example, modify the file to match your environment and specifications, and save it as ***/etc/ansible/hosts***.

2.6.5. Running the Advanced Installation

After you have [configured Ansible](#) by defining an inventory file in ***/etc/ansible/hosts***, you run the advanced installation playbook via Ansible. OpenShift Container Platform installations are currently supported using the RPM-based installer, while the containerized installer is currently a Technology Preview feature.

The installer uses modularized playbooks allowing administrators to install specific components as needed. By breaking up the roles and playbooks, there is better targeting of ad hoc administration tasks. This results in an increased level of control during installations and results in time savings.

The playbooks and their ordering are detailed below in [Running Individual Component Playbooks](#).

NOTE

Due to a known issue, after running the installation, if NFS volumes are provisioned for any component, the following directories might be created whether their components are being deployed to NFS volumes or not:

- ***/exports/logging-es***
- ***/exports/logging-es-ops/***
- ***/exports/metrics/***
- ***/exports/prometheus***
- ***/exports/prometheus-alertbuffer/***
- ***/exports/prometheus-alertmanager/***

You can delete these directories after installation, as needed.


2.6.5.1. Running the RPM-based Installer

The RPM-based installer uses Ansible installed via RPM packages to run playbooks and configuration files available on the local host. To run the installer, use the following command, specifying ***-i*** if your inventory file located somewhere other than ***/etc/ansible/hosts***:

If you are using a proxy, you must add the IP address of the etcd endpoints to the ***openshift_no_proxy*** cluster variable in your inventory file.

NOTE

If you are not using a proxy, you can skip this step.



IMPORTANT

Do not run OpenShift Ansible playbooks under **nohup**. Using **nohup** with the playbooks causes file descriptors to be created and not closed. Therefore, the system can run out of files to open and the playbook will fail.

In OpenShift Container Platform:

```
# ansible-playbook [-i /path/to/inventory] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/config.yml
```

If for any reason the installation fails, before re-running the installer, see [Known Issues](#) to check for any specific instructions or workarounds.



WARNING

The installer caches playbook configuration values for 10 minutes, by default. If you change any system, network, or inventory configuration, and then re-run the installer within that 10 minute period, the new values are not used, and the previous values are used instead. You can delete the contents of the cache, which is defined by the **fact_caching_connection** value in the `/etc/ansible/ansible.cfg` file. An example of this file is shown in [Recommended Installation Practices](#).

2.6.5.2. Running the Containerized Installer

The **openshift3/ose-ansible** image is a containerized version of the OpenShift Container Platform installer. This installer image provides the same functionality as the RPM-based installer, but it runs in a containerized environment that provides all of its dependencies rather than being installed directly on the host. The only requirement to use it is the ability to run a container.

2.6.5.2.1. Running the Installer as a System Container



IMPORTANT

All system container components are [Technology Preview](#) features in OpenShift Container Platform 3.7. They must not be used in production and they are not supported for upgrades to OpenShift Container Platform 3.7. During this phase, they are only meant for use with new cluster installations in non-production environments.

The installer image can be used as a [system container](#). System containers are stored and run outside of the traditional **docker** service. This enables running the installer image from one of the target hosts without concern for the install restarting **docker** on the host.

1. As the **root** user, use the Atomic CLI to run the installer as a run-once system container:

```
# atomic install --system \
    --storage=ostree \
    --set INVENTORY_FILE=/path/to/inventory \
    registry.access.redhat.com/openshift3/ose-ansible:v3.7
```

■

- 1 Specify the location on the local host for your inventory file.

This command initiates the cluster installation by using the inventory file specified and the **root** user's SSH configuration. It logs the output on the terminal and also saves it in the `/var/log/ansible.log` file. The first time this command is run, the image is imported into [OSTree](#) storage (system containers use this rather than **docker** daemon storage). On subsequent runs, it reuses the stored image.

If for any reason the installation fails, before re-running the installer, see [Known Issues](#) to check for any specific instructions or workarounds.

2.6.5.2.2. Running Other Playbooks

You can use the **PLAYBOOK_FILE** environment variable to specify other playbooks you want to run by using the containerized installer. The default value of the **PLAYBOOK_FILE** is `/usr/share/ansible/openshift-ansible/playbooks/byo/config.yml`, which is the main cluster installation playbook, but you can set it to the path of another playbook inside the container.

For example, to run the [pre-install checks](#) playbook before installation, use the following command:

```
# atomic install --system \
  --storage=ostree \
  --set INVENTORY_FILE=/path/to/inventory \
  --set PLAYBOOK_FILE=/usr/share/ansible/openshift-
ansible/playbooks/byo/openshift-checks/pre-install.yml \ 1
  --set OPTS="-v" \ 2
  registry.access.redhat.com/openshift3/ose-ansible:v3.7
```

- 1 Set **PLAYBOOK_FILE** to the full path of the playbook starting at the **playbooks/** directory. Playbooks are located in the same locations as with the RPM-based installer.
- 2 Set **OPTS** to add command line options to **ansible-playbook**.

2.6.5.2.3. Running the Installer as a Docker Container

The installer image can also run as a **docker** container anywhere that **docker** can run.



WARNING

This method must not be used to run the installer on one of the hosts being configured, as the install may restart **docker** on the host, disrupting the installer container execution.



NOTE

Although this method and the system container method above use the same image, they run with different entry points and contexts, so runtime parameters are not the same.

At a minimum, when running the installer as a **docker** container you must provide:

- SSH key(s), so that Ansible can reach your hosts.
- An Ansible inventory file.
- The location of the Ansible playbook to run against that inventory.

Here is an example of how to run an install via **docker**. Note that this must be run by a non-**root** user with access to **docker**.

```
$ docker run -t -u `id -u` \ ❶
    -v $HOME/.ssh/id_rsa:/opt/app-root/src/.ssh/id_rsa:Z \ ❷
    -v $HOME/ansible/hosts:/tmp/inventory:Z \ ❸
    -e INVENTORY_FILE=/tmp/inventory \ ❹
    -e PLAYBOOK_FILE=playbooks/byo/config.yml \ ❺
    -e OPTS="-v" \ ❻
    registry.access.redhat.com/openshift3/ose-ansible:v3.7
```

❶ **-u `id -u`** makes the container run with the same UID as the current user, which allows that user to use the SSH key inside the container (SSH private keys are expected to be readable only by their owner).

❷ **-v \$HOME/.ssh/id_rsa:/opt/app-root/src/.ssh/id_rsa:Z** mounts your SSH key (**\$HOME/.ssh/id_rsa**) under the container user's **\$HOME/.ssh** (**/opt/app-root/src** is the **\$HOME** of the user in the container). If you mount the SSH key into a non-standard location you can add an environment variable with **-e ANSIBLE_PRIVATE_KEY_FILE=/the/mount/point** or set **ansible_ssh_private_key_file=/the/mount/point** as a variable in the inventory to point Ansible at it.

Note that the SSH key is mounted with the **:Z** flag. This is required so that the container can read the SSH key under its restricted SELinux context. This also means that your original SSH key file will be re-labeled to something like **system_u:object_r:container_file_t:s0:c113,c247**. For more details about **:Z**, check the **docker-run(1)** man page. Keep this in mind when providing these volume mount specifications because this might have unexpected consequences: for example, if you mount (and therefore re-label) your whole **\$HOME/.ssh** directory it will block the host's **sshd** from accessing your public keys to login. For this reason you may want to use a separate copy of the SSH key (or directory), so that the original file labels remain untouched.

❸ ❹ **-v \$HOME/ansible/hosts:/tmp/inventory:Z** and **-e INVENTORY_FILE=/tmp/inventory** mount a static Ansible inventory file into the container as **/tmp/inventory** and set the corresponding environment variable to point at it. As with the SSH key, the inventory file SELinux labels may need to be relabeled by using the **:Z** flag to allow reading in the container, depending on the existing label (for files in a user **\$HOME** directory this is likely to be needed). So again you may prefer to copy the inventory to a dedicated location before mounting it.

The inventory file can also be downloaded from a web server if you specify the **INVENTORY_URL** environment variable, or generated dynamically using **DYNAMIC_SCRIPT_URL** to specify an executable script that provides a dynamic inventory.

❺ **-e PLAYBOOK_FILE=playbooks/byo/config.yml** specifies the playbook to run (in this example, the BYO installer) as a relative path from the top level directory of **openshift-ansible** content. The full path from the RPM can also be used, as well as the path to any other playbook file in the container.

- 6** `-e OPTS="-v"` supplies arbitrary command line options (in this case, `-v` to increase verbosity) to the **ansible-playbook** command that runs inside the container.

2.6.5.3. Running Individual Component Playbooks

The main installation playbook `/usr/share/ansible/openshift-ansible/playbooks/byo/config.yml` runs a set of individual component playbooks in a specific order, and the installer reports back at the end what phases you have gone through. If the installation fails, you are notified which phase failed along with the errors from the Ansible run.

After you resolve the errors, you can continue installation:

- You can run the remaining individual installation playbooks.
- If you are installing in a new environment, you can run the **`deploy_cluster.yml`** playbook again.

If you want to run only the remaining playbooks, start by running the playbook for the phase that failed and then run each of the remaining playbooks in order:

```
# ansible-playbook [-i /path/to/inventory] <playbook_file_location>
```

The following table lists the playbooks in the order that they must run:

Table 2.19. Individual Component Playbook Run Order

Playbook Name	File Location
Health Check	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-checks/pre-install.yml</code>
etcd Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-etcd/config.yml</code>
NFS Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-nfs/config.yml</code>
Load Balancer Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-loadbalancer/config.yml</code>
Master Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-master/config.yml</code>
Master Additional Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-master/additional_config.yml</code>
Node Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-node/config.yml</code>
GlusterFS Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-glusterfs/config.yml</code>

Playbook Name	File Location
Hosted Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-cluster/openshift-hosted.yml</code>
Metrics Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-cluster/openshift-metrics.yml</code>
Logging Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-cluster/openshift-logging.yml</code>
Prometheus Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-cluster/openshift-prometheus.yml</code>
Service Catalog Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-cluster/service-catalog.yml</code>
Management Install	<code>/usr/share/ansible/openshift-ansible/playbooks/byo/openshift-management/config.yml</code>

2.6.6. Verifying the Installation

After the installation completes:

1. Verify that the master is started and nodes are registered and reporting in **Ready** status. *On the master host*, run the following as root:

```
# oc get nodes

NAME                                STATUS                    AGE
master.example.com                 Ready, SchedulingDisabled 165d
node1.example.com                  Ready                     165d
node2.example.com                  Ready                     165d
```

2. To verify that the web console is installed correctly, use the master host name and the web console port number to access the web console with a web browser.
For example, for a master host with a host name of **master.openshift.com** and using the default port of **8443**, the web console would be found at **https://master.openshift.com:8443/console**.



NOTE

The default port for the console is **8443**. If this was changed during the installation, the port can be found at **openshift_master_console_port** in the `/etc/ansible/hosts` file.

Verifying Multiple etcd Hosts

If you installed multiple etcd hosts:

1. First, verify that the **etcd** package, which provides the **etcdctl** command, is installed:

```
# yum install etcd
```

-
- 2. On a master host, verify the etcd cluster health, substituting for the FQDNs of your etcd hosts in the following:

```
# etcdctl -C \
https://etcd1.example.com:2379,https://etcd2.example.com:2379,https://etcd3.example.com:2379 \
--ca-file=/etc/origin/master/master.etcd-ca.crt \
--cert-file=/etc/origin/master/master.etcd-client.crt \
--key-file=/etc/origin/master/master.etcd-client.key cluster-
health
```

- 3. Also verify the member list is correct:

```
# etcdctl -C \
https://etcd1.example.com:2379,https://etcd2.example.com:2379,https://etcd3.example.com:2379 \
--ca-file=/etc/origin/master/master.etcd-ca.crt \
--cert-file=/etc/origin/master/master.etcd-client.crt \
--key-file=/etc/origin/master/master.etcd-client.key member list
```

Verifying Multiple Masters Using HAProxy

If you installed multiple masters using HAProxy as a load balancer, browse to the following URL according to your **[lb]** section definition and check HAProxy's status:

```
http://<lb_hostname>:9000
```

You can verify your installation by consulting the [HAProxy Configuration documentation](#).

2.6.7. Optionally Securing Builds

Running **docker build** is a privileged process, so the container has more access to the node than might be considered acceptable in some multi-tenant environments. If you do not trust your users, you can use a more secure option at the time of installation. Disable Docker builds on the cluster and require that users build images outside of the cluster. See [Securing Builds by Strategy](#) for more information on this optional process.

2.6.8. Uninstalling OpenShift Container Platform

You can uninstall OpenShift Container Platform hosts in your cluster by running the ***uninstall.yml*** playbook. This playbook deletes OpenShift Container Platform content installed by Ansible, including:

- Configuration
- Containers
- Default templates and image streams
- Images
- RPM packages

The playbook will delete content for any hosts defined in the inventory file that you specify when running the playbook. If you want to uninstall OpenShift Container Platform across all hosts in your cluster, run the playbook using the inventory file you used when installing OpenShift Container Platform initially or ran most recently:

```
# ansible-playbook [-i /path/to/file] \
    /usr/share/ansible/openshift-ansible/playbooks/adhoc/uninstall.yml
```

2.6.8.1. Uninstalling Nodes

You can also uninstall node components from specific hosts using the ***uninstall.yml*** playbook while leaving the remaining hosts and cluster alone:



WARNING

This method should only be used when attempting to uninstall specific node hosts and not for specific masters or etcd hosts, which would require further configuration changes within the cluster.

1. First follow the steps in [Deleting Nodes](#) to remove the node object from the cluster, then continue with the remaining steps in this procedure.
2. Create a different inventory file that only references those hosts. For example, to only delete content from one node:

```
[OSEv3:children]
nodes 1

[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise

[nodes]
node3.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'west' }" 2
```

- 1** Only include the sections that pertain to the hosts you are interested in uninstalling.
- 2** Only include hosts that you want to uninstall.

3. Specify that new inventory file using the **-i** option when running the ***uninstall.yml*** playbook:

```
# ansible-playbook -i /path/to/new/file \
    /usr/share/ansible/openshift-
    ansible/playbooks/adhoc/uninstall.yml
```

When the playbook completes, all OpenShift Container Platform content should be removed from any specified hosts.

2.6.9. Known Issues

- On failover in multiple master clusters, it is possible for the controller manager to overcorrect, which causes the system to run more pods than what was intended. However, this is a transient event and the system does correct itself over time. See <https://github.com/kubernetes/kubernetes/issues/10030> for details.
- If the Ansible installer fails, you can still install OpenShift Container Platform:
 - If you did not modify the SDN configuration or generate new certificates, run the **`deploy_cluster.yml`** playbook again.
 - If you modified the SDN configuration, generated new certificates, or the installer fails again, you must either start over with a clean operating system installation or [uninstall](#) and install again.
 - If you use virtual machines, start from a fresh image or [uninstall](#) and install again.
 - If you use bare metal machines, [uninstall](#) and install again.

2.6.10. What's Next?

Now that you have a working OpenShift Container Platform instance, you can:

- Deploy an [integrated Docker registry](#).
- Deploy a [router](#).

2.7. DISCONNECTED INSTALLATION

2.7.1. Overview

Frequently, portions of a datacenter may not have access to the Internet, even via proxy servers. Installing OpenShift Container Platform in these environments is considered a disconnected installation.

An OpenShift Container Platform disconnected installation differs from a regular installation in two primary ways:

- The OpenShift Container Platform software channels and repositories are not available via Red Hat's content distribution network.
- OpenShift Container Platform uses several containerized components. Normally, these images are pulled directly from Red Hat's Docker registry. In a disconnected environment, this is not possible.

A disconnected installation ensures the OpenShift Container Platform software is made available to the relevant servers, then follows the same installation process as a standard connected installation. This topic additionally details how to manually download the container images and transport them onto the relevant servers.

Once installed, in order to use OpenShift Container Platform, you will need source code in a source control repository (for example, Git). This topic assumes that an internal Git repository is available that can host source code and this repository is accessible from the OpenShift Container Platform nodes. Installing the source control repository is outside the scope of this document.

Also, when building applications in OpenShift Container Platform, your build may have some external

dependencies, such as a Maven Repository or Gem files for Ruby applications. For this reason, and because they might require certain tags, many of the Quickstart templates offered by OpenShift Container Platform may not work on a disconnected environment. However, while Red Hat container images try to reach out to external repositories by default, you can configure OpenShift Container Platform to use your own internal repositories. For the purposes of this document, we assume that such internal repositories already exist and are accessible from the OpenShift Container Platform nodes hosts. Installing such repositories is outside the scope of this document.



NOTE

You can also have a [Red Hat Satellite](#) server that provides access to Red Hat content via an intranet or LAN. For environments with Satellite, you can synchronize the OpenShift Container Platform software onto the Satellite for use with the OpenShift Container Platform servers.

[Red Hat Satellite 6.1](#) also introduces the ability to act as a Docker registry, and it can be used to host the OpenShift Container Platform containerized components. Doing so is outside of the scope of this document.

2.7.2. Prerequisites

This document assumes that you understand [OpenShift Container Platform's overall architecture](#) and that you have already planned out what the topology of your environment will look like.

2.7.3. Required Software and Components

In order to pull down the required software repositories and container images, you will need a Red Hat Enterprise Linux (RHEL) 7 server with access to the Internet and at least 100GB of additional free space. All steps in this section should be performed on the Internet-connected server as the root system user.

2.7.3.1. Syncing Repositories

Before you sync with the required repositories, you may need to import the appropriate GPG key:

```
$ rpm --import /etc/pki/rpm-gpg/RPM-GPG-KEY-redhat-release
```

If the key is not imported, the indicated package is deleted after syncing the repository.

To sync the required repositories:

1. Register the server with the Red Hat Customer Portal. You must use the login and password associated with the account that has access to the OpenShift Container Platform subscriptions:

```
$ subscription-manager register
```

2. Pull the latest subscription data from RHSM:

```
$ subscription-manager refresh
```

3. Attach to a subscription that provides OpenShift Container Platform channels. You can find the list of available subscriptions using:

```
$ subscription-manager list --available --matches '*OpenShift*'
```

Then, find the pool ID for the subscription that provides OpenShift Container Platform, and attach it:

```
$ subscription-manager attach --pool=<pool_id>
$ subscription-manager repos --disable="*"
$ subscription-manager repos \
  --enable="rhel-7-server-rpms" \
  --enable="rhel-7-server-extras-rpms" \
  --enable="rhel-7-fast-datapath-rpms" \
  --enable="rhel-7-server-ose-3.7-rpms"
```

4. The **yum-utils** command provides the **reposync** utility, which lets you mirror yum repositories, and **createrepo** can create a usable **yum** repository from a directory:

```
$ sudo yum -y install yum-utils createrepo docker git
```

You will need up to 110GB of free space in order to sync the software. Depending on how restrictive your organization's policies are, you could re-connect this server to the disconnected LAN and use it as the repository server. You could use USB-connected storage and transport the software to another server that will act as the repository server. This topic covers these options.

5. Make a path to where you want to sync the software (either locally or on your USB or other device):

```
$ mkdir -p </path/to/repos>
```

6. Sync the packages and create the repository for each of them. You will need to modify the command for the appropriate path you created above:

```
$ for repo in \
  rhel-7-server-rpms \
  rhel-7-server-extras-rpms \
  rhel-7-fast-datapath-rpms \
  rhel-7-server-ose-3.7-rpms
do
  reposync --gpgcheck -lm --repoid=${repo} --
  download_path=/path/to/repos
  createrepo -v </path/to/repos/>${repo} -o </path/to/repos/>${repo}
done
```

2.7.3.2. Syncing Images

To sync the container images:

1. Start the Docker daemon:

```
$ systemctl start docker
```

2. If you are performing a [containerized install](#), pull all of the required OpenShift Container Platform host component images. Replace **<tag>** with **v3.7.64** for the latest version.

```
# docker pull registry.access.redhat.com/rhel7/etcd
# docker pull registry.access.redhat.com/openshift3/ose:<tag>
```

```
# docker pull registry.access.redhat.com/openshift3/node:<tag>
# docker pull registry.access.redhat.com/openshift3/openswitch:
<tag>
```

3. Pull all of the required OpenShift Container Platform infrastructure component images. Replace **<tag>** with **v3.7.64** for the latest version.

```
$ docker pull registry.access.redhat.com/openshift3/ose-ansible:
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-cluster-
capacity:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-deployer:
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-docker-
builder:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-docker-
registry:<tag>
$ docker pull registry.access.redhat.com/openshift3/registry-
console:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-egress-http-
proxy:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-egress-
router:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-f5-router:
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-haproxy-
router:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-keepalived-
ipfailover:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-pod:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-sti-builder:
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose:<tag>
$ docker pull registry.access.redhat.com/openshift3/container-
engine:<tag>
$ docker pull registry.access.redhat.com/openshift3/node:<tag>
$ docker pull registry.access.redhat.com/openshift3/openswitch:
<tag>
```



NOTE

If you are using NFS, you need the **ose-recycler** image. Otherwise, the volumes will not recycle, potentially causing errors.

4. Pull all of the required OpenShift Container Platform component images for the additional centralized log aggregation and metrics aggregation components. Replace **<tag>** with **v3.7.64** for the latest version.

```
$ docker pull registry.access.redhat.com/openshift3/logging-auth-
proxy:<tag>
$ docker pull registry.access.redhat.com/openshift3/logging-curator:
<tag>
$ docker pull registry.access.redhat.com/openshift3/logging-
elasticsearch:<tag>
```

```
$ docker pull registry.access.redhat.com/openshift3/logging-fluentd:
<tag>
$ docker pull registry.access.redhat.com/openshift3/logging-kibana:
<tag>
$ docker pull registry.access.redhat.com/openshift3/metrics-
cassandra:<tag>
$ docker pull registry.access.redhat.com/openshift3/metrics-
hawkular-metrics:<tag>
$ docker pull registry.access.redhat.com/openshift3/metrics-
hawkular-openshift-agent:<tag>
$ docker pull registry.access.redhat.com/openshift3/metrics-
heapster:<tag>
$ docker pull registry.access.redhat.com/openshift3/oauth-proxy:
<tag>
```

IMPORTANT

Prometheus on OpenShift Container Platform is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offerings/techpreview/>.

5. For the service catalog, OpenShift Ansible broker, and template service broker features (as described in [Advanced Installation](#)), pull the following images.

- a. Replace **<tag>** with **v3.7.64** for the latest version.

```
$ docker pull registry.access.redhat.com/openshift3/ose-service-
catalog:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-ansible-
service-broker:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-template-
service-broker:<tag>
```

- b. Replace **<tag>** with **v3.7.64** for the latest version.

```
$ docker pull registry.access.redhat.com/openshift3/mediawiki-
apb:<tag>
$ docker pull registry.access.redhat.com/openshift3/postgresql-
apb:<tag>
```

6. Pull the Red Hat-certified [Source-to-Image \(S2I\)](#) builder images that you intend to use in your OpenShift environment. You can pull the following images:

```
$ docker pull registry.access.redhat.com/jboss-amq-6/amq63-openshift
$ docker pull registry.access.redhat.com/jboss-datagrid-
7/datagrid71-openshift
$ docker pull registry.access.redhat.com/jboss-datagrid-
7/datagrid71-client-openshift
```



```

$ docker pull registry.access.redhat.com/jboss-datavirt-
6/datavirt63-openshift
$ docker pull registry.access.redhat.com/jboss-datavirt-
6/datavirt63-driver-openshift
$ docker pull registry.access.redhat.com/jboss-decisionserver-
6/decisionserver64-openshift
$ docker pull registry.access.redhat.com/jboss-processserver-
6/processserver64-openshift
$ docker pull registry.access.redhat.com/jboss-eap-6/eap64-openshift
$ docker pull registry.access.redhat.com/jboss-eap-7/eap70-openshift
$ docker pull registry.access.redhat.com/jboss-webserver-
3/webserver31-tomcat7-openshift
$ docker pull registry.access.redhat.com/jboss-webserver-
3/webserver31-tomcat8-openshift
$ docker pull registry.access.redhat.com/openshift3/jenkins-1-rhel7
$ docker pull registry.access.redhat.com/openshift3/jenkins-2-rhel7
$ docker pull registry.access.redhat.com/openshift3/jenkins-slave-
base-rhel7
$ docker pull registry.access.redhat.com/openshift3/jenkins-slave-
maven-rhel7
$ docker pull registry.access.redhat.com/openshift3/jenkins-slave-
nodejs-rhel7
$ docker pull registry.access.redhat.com/rhsc1/mongodb-32-rhel7
$ docker pull registry.access.redhat.com/rhsc1/mysql-57-rhel7
$ docker pull registry.access.redhat.com/rhsc1/perl-524-rhel7
$ docker pull registry.access.redhat.com/rhsc1/php-56-rhel7
$ docker pull registry.access.redhat.com/rhsc1/postgresql-95-rhel7
$ docker pull registry.access.redhat.com/rhsc1/python-35-rhel7
$ docker pull registry.access.redhat.com/redhat-sso-7/sso70-
openshift
$ docker pull registry.access.redhat.com/rhsc1/ruby-24-rhel7
$ docker pull registry.access.redhat.com/redhat-openjdk-
18/openjdk18-openshift
$ docker pull registry.access.redhat.com/redhat-sso-7/sso71-
openshift
$ docker pull registry.access.redhat.com/rhsc1/nodejs-6-rhel7
$ docker pull registry.access.redhat.com/rhsc1/mariadb-101-rhel7

```

Make sure to indicate the correct tag specifying the desired version number. For example, to pull both the previous and latest version of the Tomcat image:

```

$ docker pull \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:latest
$ docker pull \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:1.1

```

2.7.3.3. Preparing Images for Export

Container images can be exported from a system by first saving them to a tarball and then transporting them:

1. Make and change into a repository home directory:

```
$ mkdir </path/to/repos/images>
$ cd </path/to/repos/images>
```

2. If you are performing a [containerized install](#), export the OpenShift Container Platform host component images:

```
# docker save -o ose3-host-images.tar \
  registry.access.redhat.com/rhel7/etcd \
  registry.access.redhat.com/openshift3/ose \
  registry.access.redhat.com/openshift3/node \
  registry.access.redhat.com/openshift3/opensvswitch
```

3. Export the OpenShift Container Platform infrastructure component images:

```
$ docker save -o ose3-images.tar \
  registry.access.redhat.com/openshift3/ose-ansible \
  registry.access.redhat.com/openshift3/ose-cluster-capacity \
  registry.access.redhat.com/openshift3/ose-deployer \
  registry.access.redhat.com/openshift3/ose-docker-builder \
  registry.access.redhat.com/openshift3/ose-docker-registry \
  registry.access.redhat.com/openshift3/registry-console \
  registry.access.redhat.com/openshift3/ose-egress-http-proxy \
  registry.access.redhat.com/openshift3/ose-egress-router \
  registry.access.redhat.com/openshift3/ose-f5-router \
  registry.access.redhat.com/openshift3/ose-haproxy-router \
  registry.access.redhat.com/openshift3/ose-keepalived-ipfailover \
  \
  registry.access.redhat.com/openshift3/ose-pod \
  registry.access.redhat.com/openshift3/ose-sti-builder \
  registry.access.redhat.com/openshift3/ose \
  registry.access.redhat.com/openshift3/container-engine \
  registry.access.redhat.com/openshift3/node \
  registry.access.redhat.com/openshift3/opensvswitch
```

4. If you synchronized the metrics and log aggregation images, export them:

```
$ docker save -o ose3-logging-metrics-images.tar \
  registry.access.redhat.com/openshift3/logging-auth-proxy \
  registry.access.redhat.com/openshift3/logging-curator \
  registry.access.redhat.com/openshift3/logging-elasticsearch \
  registry.access.redhat.com/openshift3/logging-fluentd \
  registry.access.redhat.com/openshift3/logging-kibana \
  registry.access.redhat.com/openshift3/metrics-cassandra \
  registry.access.redhat.com/openshift3/metrics-hawkular-metrics \
  registry.access.redhat.com/openshift3/metrics-hawkular-
openshift-agent \
  registry.access.redhat.com/openshift3/metrics-heapster
```

5. Export the S2I builder images that you synced in the previous section. For example, if you synced only the Jenkins and Tomcat images:

```
$ docker save -o ose3-builder-images.tar \
  registry.access.redhat.com/jboss-webserver-3/webserver30-
tomcat7-openshift:latest \
```

```
registry.access.redhat.com/jboss-webserver-3/webserver30-
tomcat7-openshift:1.1 \
registry.access.redhat.com/openshift3/jenkins-1-rhel7 \
registry.access.redhat.com/openshift3/jenkins-2-rhel7 \
registry.access.redhat.com/openshift3/jenkins-slave-base-rhel7 \
registry.access.redhat.com/openshift3/jenkins-slave-maven-rhel7
\
registry.access.redhat.com/openshift3/jenkins-slave-nodejs-rhel7
```

2.7.4. Repository Server

During the installation (and for later updates, should you so choose), you will need a webserver to host the repositories. RHEL 7 can provide the Apache webserver.

Option 1: Re-configuring as a Web server

If you can re-connect the server where you synchronized the software and images to your LAN, then you can simply install Apache on the server:

```
$ sudo yum install httpd
```

Skip to [Placing the Software](#).

Option 2: Building a Repository Server

If you need to build a separate server to act as the repository server, install a new RHEL 7 system with at least 110GB of space. On this repository server during the installation, make sure you select the **Basic Web Server** option.

2.7.4.1. Placing the Software

1. If necessary, attach the external storage, and then copy the repository files into Apache's root folder. Note that the below copy step (**cp -a**) should be substituted with move (**mv**) if you are repurposing the server you used to sync:

```
$ cp -a /path/to/repos /var/www/html/
$ chmod -R +r /var/www/html/repos
$ restorecon -vR /var/www/html
```

2. Add the firewall rules:

```
$ sudo firewall-cmd --permanent --add-service=http
$ sudo firewall-cmd --reload
```

3. Enable and start Apache for the changes to take effect:

```
$ systemctl enable httpd
$ systemctl start httpd
```

2.7.5. OpenShift Container Platform Systems

2.7.5.1. Building Your Hosts

At this point you can perform the initial creation of the hosts that will be part of the OpenShift Container Platform environment. It is recommended to use the latest version of RHEL 7 and to perform a minimal installation. You will also want to pay attention to the other [OpenShift Container Platform-specific prerequisites](#).

Once the hosts are initially built, the repositories can be set up.

2.7.5.2. Connecting the Repositories

On all of the relevant systems that will need OpenShift Container Platform software components, create the required repository definitions. Place the following text in the `/etc/yum.repos.d/ose.repo` file, replacing `<server_IP>` with the IP or host name of the Apache server hosting the software repositories:

```
[rhel-7-server-rpms]
name=rhel-7-server-rpms
baseurl=http://<server_IP>/repos/rhel-7-server-rpms
enabled=1
gpgcheck=0
[rhel-7-server-extras-rpms]
name=rhel-7-server-extras-rpms
baseurl=http://<server_IP>/repos/rhel-7-server-extras-rpms
enabled=1
gpgcheck=0
[rhel-7-fast-datapath-rpms]
name=rhel-7-fast-datapath-rpms
baseurl=http://<server_IP>/repos/rhel-7-fast-datapath-rpms
enabled=1
gpgcheck=0
[rhel-7-server-ose-3.7-rpms]
name=rhel-7-server-ose-3.7-rpms
baseurl=http://<server_IP>/repos/rhel-7-server-ose-3.7-rpms
enabled=1
gpgcheck=0
```

2.7.5.3. Host Preparation

At this point, the systems are ready to continue to be prepared [following the OpenShift Container Platform documentation](#).

Skip the section titled **Host Registration** and start with **Installing Base Packages**.

2.7.6. Installing OpenShift Container Platform

2.7.6.1. Importing OpenShift Container Platform Component Images

To import the relevant components, securely copy the images from the connected host to the individual OpenShift Container Platform hosts:

```
$ scp /var/www/html/repos/images/ose3-images.tar
root@<openshift_host_name>:
$ ssh root@<openshift_host_name> "docker load -i ose3-images.tar"
$ scp /var/www/html/images/ose3-builder-images.tar
```

```
root@<openshift_master_host_name>:
$ ssh root@<openshift_master_host_name> "docker load -i ose3-builder-
images.tar"
```

Perform the same steps for the host components if your install will be containerized. Perform the same steps for the metrics and logging images, if your cluster will use them.

If you prefer, you could use **wget** on each OpenShift Container Platform host to fetch the tar file, and then perform the Docker import command locally.

2.7.6.2. Running the OpenShift Container Platform Installer

You can now choose to follow the [quick](#) or [advanced](#) OpenShift Container Platform installation instructions in the documentation.

2.7.6.3. Creating the Internal Docker Registry

You now need to [create the internal Docker registry](#).

If you want to [install a stand-alone registry](#), you must [pull the registry-console container image](#) and set **deployment_subtype=registry** in the inventory file.

2.7.7. Post-Installation Changes

In one of the previous steps, the S2I images were imported into the Docker daemon running on one of the OpenShift Container Platform master hosts. In a connected installation, these images would be pulled from Red Hat's registry on demand. Since the Internet is not available to do this, the images must be made available in another Docker registry.

OpenShift Container Platform provides an internal registry for storing the images that are built as a result of the S2I process, but it can also be used to hold the S2I builder images. The following steps assume you did not customize the service IP subnet (172.30.0.0/16) or the Docker registry port (5000).

2.7.7.1. Re-tagging S2I Builder Images

1. On the master host where you imported the S2I builder images, obtain the service address of your Docker registry that you installed on the master:

```
$ export REGISTRY=$(oc get service -n default \
    docker-registry --output=go-template='{{.spec.clusterIP}}
    {{"\n"}}')
```

2. Next, tag all of the builder images that you synced and exported before pushing them into the OpenShift Container Platform Docker registry. For example, if you synced and exported only the Tomcat image:

```
$ docker tag \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:1.1 \
$REGISTRY:5000/openshift/webserver30-tomcat7-openshift:1.1
$ docker tag \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:latest \
$REGISTRY:5000/openshift/webserver30-tomcat7-openshift:1.2
$ docker tag \
```

```
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:latest \
$REGISTRY:5000/openshift/webserver30-tomcat7-openshift:latest
```

2.7.7.2. Configuring a Registry Location

If you are using an image registry other than the default at **registry.access.redhat.com**, specify the desired registry within the **/etc/ansible/hosts** file.

```
oreg_url=example.com/openshift3/ose-${component}:${version}
openshift_examples_modify_imagestreams=true
```

Depending on your registry, you may need to configure:

```
openshift_docker_additional_registries=example.com
openshift_docker_insecure_registries=example.com
```



NOTE

You can also set the **openshift_docker_insecure_registries** variable to the IP address of the host. **0.0.0.0/0** is not a valid setting.

Table 2.20. Registry Variables

Variable	Purpose
oreg_url	Set to the alternate image location. Necessary if you are not using the default registry at registry.access.redhat.com .
openshift_examples_modify_imagestreams	Set to true if pointing to a registry other than the default. Modifies the image stream location to the value of oreg_url .
openshift_docker_additional_registries	Set openshift_docker_additional_registries to add its value in the add_registry line in /etc/sysconfig/docker . With add_registry , you can add your own registry to be used for Docker search and Docker pull. Use the add_registry option to list a set of registries, each prepended with --add-registry flag. The first registry added will be the first registry searched. For example, add_registry=--add-registry registry.access.redhat.com --add-registry example.com .

Variable	Purpose
openshift_docker_insecure_registries	Set openshift_docker_insecure_registries to add its value in the insecure_registry line in /etc/sysconfig/docker . If you have a registry secured with HTTPS but do not have proper certificates distributed, you can tell Docker not to look for full authorization by adding the registry to the insecure_registry line and uncommenting it. For example, insecure_registry=example.com . Can be set to the host name or IP address of the host. 0.0.0.0/0 is not a valid setting for the IP address.

2.7.7.3. Creating an Administrative User

Pushing the container images into OpenShift Container Platform's Docker registry requires a user with **cluster-admin** privileges. Because the default OpenShift Container Platform system administrator does not have a standard authorization token, they cannot be used to log in to the Docker registry.

To create an administrative user:

1. Create a new user account in the authentication system you are using with OpenShift Container Platform. For example, if you are using local **htpasswd**-based authentication:

```
$ htpasswd -b /etc/openshift/openshift-passwd <admin_username>
<password>
```

2. The external authentication system now has a user account, but a user must log in to OpenShift Container Platform before an account is created in the internal database. Log in to OpenShift Container Platform for this account to be created. This assumes you are using the self-signed certificates generated by OpenShift Container Platform during the installation:

```
$ oc login --certificate-authority=/etc/origin/master/ca.crt \
-u <admin_username> https://<openshift_master_host>:8443
```

3. Get the user's authentication token:

```
$ MYTOKEN=$(oc whoami -t)
$ echo $MYTOKEN
iwo7hc4Xi1D2K0LL4V1055ExH2V1PmLD-W2-J0d6Fko
```

2.7.7.4. Modifying the Security Policies

1. Using **oc login** switches to the new user. Switch back to the OpenShift Container Platform system administrator in order to make policy changes:

```
$ oc login -u system:admin
```

2. In order to push images into the OpenShift Container Platform Docker registry, an account must have the **image-builder** security role. Add this to your OpenShift Container Platform administrative user:

```
$ oc adm policy add-role-to-user system:image-builder
<admin_username>
```

3. Next, add the administrative role to the user in the **openshift** project. This allows the administrative user to edit the **openshift** project, and, in this case, push the container images:

```
$ oc adm policy add-role-to-user admin <admin_username> -n openshift
```

2.7.7.5. Editing the Image Stream Definitions

The **openshift** project is where all of the image streams for builder images are created by the installer. They are loaded by the installer from the **/usr/share/openshift/examples** directory. Change all of the definitions by deleting the image streams which had been loaded into OpenShift Container Platform's database, then re-create them:

1. Delete the existing image streams:

```
$ oc delete is -n openshift --all
```

2. Make a backup of the files in **/usr/share/openshift/examples** if you desire. Next, edit the file **image-streams-rhel7.json** in the **/usr/share/openshift/examples/image-streams** folder. You will find an image stream section for each of the builder images. Edit the **spec** stanza to point to your internal Docker registry.

For example, change:

```
"from": {
  "kind": "DockerImage",
  "name": "registry.access.redhat.com/rhsc1/httpd-24-rhel7"
}
```

to:

```
"from": {
  "kind": "DockerImage",
  "name": "172.30.69.44:5000/openshift/httpd-24-rhel7"
}
```

In the above, the repository name was changed from **rhsc1** to **openshift**. You will need to ensure the change, regardless of whether the repository is **rhsc1**, **openshift3**, or another directory. Every definition should have the following format:

```
<registry_ip>:5000/openshift/<image_name>
```

Repeat this change for every image stream in the file. Ensure you use the correct IP address that you determined earlier. When you are finished, save and exit. Repeat the same process for the JBoss image streams in the **/usr/share/openshift/examples/xpaas-streams/jboss-image-streams.json** file.

2.7.7.6. Loading the Container Images

At this point the system is ready to load the container images.

1. Log in to the Docker registry using the token and registry service IP obtained earlier:

```
$ docker login -u adminuser -e mailto:adminuser@abc.com \
  -p $MYTOKEN $REGISTRY:5000
```

2. Push the Docker images:

```
$ docker push $REGISTRY:5000/openshift/webserver30-tomcat7-
openshift:1.1
$ docker push $REGISTRY:5000/openshift/webserver30-tomcat7-
openshift:1.2
$ docker push $REGISTRY:5000/openshift/webserver30-tomcat7-
openshift:latest
```

3. Load the updated image stream definitions:

```
$ oc create -f /usr/share/openshift/examples/image-streams/image-
streams-rhel7.json -n openshift
$ oc create -f /usr/share/openshift/examples/xpaas-streams/jboss-
image-streams.json -n openshift
```

4. Verify that all the image streams now have the tags populated:

```
$ oc get imagestreams -n openshift
NAME                                     DOCKER REPO
TAGS                                     UPDATED
jboss-webserver30-tomcat7-openshift    $REGISTRY/jboss-webserver-
3/webserver30-jboss-tomcat7-openshift  1.1,1.1-2,1.1-6 + 2 more...
2 weeks ago
...
```

2.7.8. Installing a Router

At this point, the OpenShift Container Platform environment is almost ready for use. It is likely that you will want to [install and configure a router](#).

2.8. INSTALLING A STAND-ALONE DEPLOYMENT OF OPENSIFT CONTAINER REGISTRY

2.8.1. About OpenShift Container Registry

OpenShift Container Platform is a fully-featured enterprise solution that includes an integrated container registry called [OpenShift Container Registry](#) (OCR). Alternatively, instead of deploying OpenShift Container Platform as a full PaaS environment for developers, you can install OCR as a stand-alone container registry to run on-premise or in the cloud.

When installing a stand-alone deployment of OCR, a cluster of masters and nodes is still installed, similar to a typical OpenShift Container Platform installation. Then, the container registry is deployed to run on the cluster. This stand-alone deployment option is useful for administrators that want a container registry, but do not require the full OpenShift Container Platform environment that includes the developer-focused web console and application build and deployment tools.

**NOTE**

OCR should not be confused with the upstream project [Atomic Registry](#), which is a different implementation using a non-Kubernetes deployment method that leverages **systemd** and local configuration files to manage services.

OCR provides the following capabilities:


- A user-focused [registry web console](#), Cockpit.
- [Secured traffic](#) by default, served via TLS.
- Global [identity provider authentication](#).
- A [project namespace](#) model to enable teams to collaborate through [role-based access control \(RBAC\)](#) authorization.
- A [Kubernetes-based cluster](#) to manage services.
- An image abstraction called [image streams](#) to enhance image management.

Administrators may want to deploy a stand-alone OCR to manage a registry separately that supports multiple OpenShift Container Platform clusters. A stand-alone OCR also enables administrators to separate their registry to satisfy their own security or compliance requirements.

2.8.2. Minimum Hardware Requirements

Installing a stand-alone OCR has the following hardware requirements:

- Physical or virtual system, or an instance running on a public or private IaaS.
- Base OS: RHEL 7.3 or 7.4 with the "Minimal" installation option and the latest packages from the RHEL 7 Extras channel, or RHEL Atomic Host 7.4.2 or later.
- NetworkManager 1.0 or later
- 2 vCPU.
- Minimum 16 GB RAM.
- Minimum 15 GB hard disk space for the file system containing **/var/**.
- An additional minimum 15 GB unallocated space to be used for Docker's storage back end; see [Configuring Docker Storage](#) for details.

**IMPORTANT**

OpenShift Container Platform only supports servers with x86_64 architecture.

**NOTE**

Meeting the **/var/** file system sizing requirements in RHEL Atomic Host requires making changes to the default configuration. See [Managing Storage in Red Hat Enterprise Linux Atomic Host](#) for instructions on configuring this during or after installation.

2.8.3. Supported System Topologies

The following system topologies are supported for stand-alone OCR:

All-in-one	A single host that includes the master, node, etcd, and registry components.
Multiple Masters (Highly-Available)	Three hosts with all components included on each (master, node, etcd, and registry), with the masters configured for native high-availability.

2.8.4. Host Preparation

Before installing stand-alone OCR, all of the same steps detailed in the [Host Preparation](#) topic for installing a full OpenShift Container Platform PaaS must be performed. This includes registering and subscribing the host(s) to the proper repositories, installing or updating certain packages, and setting up Docker and its storage requirements.

Follow the steps in the [Host Preparation](#) topic, then continue to [Installation Methods](#).

2.8.5. Installation Methods

To install a stand-alone registry, use either of the standard installation methods (quick or advanced) used to install any variant of OpenShift Container Platform.

2.8.5.1. Quick Installation for Stand-alone OpenShift Container Registry

The following shows the step-by-step process for running the quick install tool to install an OpenShift Container Registry, instead of the full OpenShift Container Platform install.

1. Start the interactive installation:

```
$ atomic-openshift-installer install
```

2. Follow the on-screen instructions to install a new registry. The installation questions will be largely the same as if you were installing a full OpenShift Container Platform PaaS. When you reach the following screen, choose **2** to follow the registry installation path:

```
Which variant would you like to install?
```

```
(1) OpenShift Container Platform
(2) Registry
```

3. Specify the hosts that make up your cluster:

```
Enter hostname or IP address:
Will this host be an OpenShift master? [y/N]:
Will this host be RPM or Container based (rpm/container)? [rpm]:
```

See the [Installing on Containerized Hosts](#) topic for information about RPM versus containerized hosts.

4. Change the cluster host name, if desired:

```
Enter hostname or IP address [None]:
```

5. Choose the host to act as the storage host (the master host by default):

```
Enter hostname or IP address [master.host.example.com]:
```

6. Change the default subdomain, if desired:

```
New default subdomain (ENTER for none) []:
```



NOTE

All certificates and routes are created with this subdomain. Ensure this is set to the correct desired subdomain to avoid having to change the configuration after installation.

7. Specify a HTTP or HTTPS proxy, if needed:

```
Specify your http proxy ? (ENTER for none) []:
Specify your https proxy ? (ENTER for none) []:
```

After the previous has been entered, the next page summarizes your install and starts to gather the host information.



NOTE

For further usage details on the quick installer in general, including next steps, see the full topic at [Quick Installation](#).

2.8.5.2. Advanced Installation for Stand-alone OpenShift Container Registry

When using the advanced installation method to install stand-alone OCR, use the same steps for installing a full OpenShift Container Platform PaaS using Ansible described in the full [Advanced Installation](#) topic. The main difference is that you must set **deployment_subtype=registry** in the inventory file within the **[OSEv3:vars]** section for the playbooks to follow the registry installation path.

See the following example inventory files for the different supported system topologies:

All-in-one Stand-alone OpenShift Container Registry Inventory File

```
# Create an OSEv3 group that contains the masters and nodes groups
[OSEv3:children]
masters
nodes

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
# SSH user, this user should allow ssh based auth without requiring a
password
ansible_ssh_user=root
```

```

openshift_master_default_subdomain=apps.test.example.com

# If ansible_ssh_user is not root, ansible_become must be set to true
#ansible_become=true

openshift_deployment_type=openshift-enterprise
deployment_subtype=registry ❶

# uncomment the following to enable htpasswd authentication; defaults to
DenyAllPasswordIdentityProvider
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

# host group for masters
[masters]
registry.example.com

# host group for nodes, includes region info
[nodes]
registry.example.com openshift_node_labels="{ 'region': 'infra', 'zone':
'default' }" openshift_schedulable=true ❷

```

- ❶ Set **deployment_subtype=registry** to ensure installation of stand-alone OCR and not a full OpenShift Container Platform environment.
- ❷ Set **openshift_schedulable=true** on the node entry to make the single node schedulable for pod placement.

Multiple Masters (Highly-Available) Stand-alone OpenShift Container Registry Inventory File

```

# Create an OSEv3 group that contains the master, nodes, etcd, and lb
groups.
# The lb group lets Ansible configure HAProxy as the load balancing
solution.
# Comment lb out if your load balancer is pre-configured.
[OSEv3:children]
masters
nodes
etcd
lb

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise
deployment_subtype=registry ❶

openshift_master_default_subdomain=apps.test.example.com

# Uncomment the following to enable htpasswd authentication; defaults to
# DenyAllPasswordIdentityProvider.
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':

```

```
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}}

# Native high availability cluster method with optional load balancer.
# If no lb group is defined installer assumes that a load balancer has
# been preconfigured. For installation the value of
# openshift_master_cluster_hostname must resolve to the load balancer
# or to one or all of the masters defined in the inventory if no load
# balancer is present.
openshift_master_cluster_method=native
openshift_master_cluster_hostname=openshift-internal.example.com
openshift_master_cluster_public_hostname=openshift-cluster.example.com

# apply updated node defaults
openshift_node_kubelet_args={'pods-per-core': ['10'], 'max-pods': ['250'],
'image-gc-high-threshold': ['90'], 'image-gc-low-threshold': ['80']}

# override the default controller lease ttl
#osm_controller_lease_ttl=30

# enable ntp on masters to ensure proper failover
openshift_clock_enabled=true

# host group for masters
[masters]
master1.example.com
master2.example.com
master3.example.com

# host group for etcd
[etcd]
etcd1.example.com
etcd2.example.com
etcd3.example.com

# Specify load balancer host
[lb]
lb.example.com

# host group for nodes, includes region info
[nodes]
master[1:3].example.com openshift_node_labels="{ 'region': 'infra', 'zone':
'default' }" openshift_schedulable=true
node1.example.com openshift_node_labels="{ 'region': 'primary', 'zone':
'east' }"
node2.example.com openshift_node_labels="{ 'region': 'primary', 'zone':
'west' }"
```

- 1 Set **deployment_subtype=registry** to ensure installation of stand-alone OCR and not a full OpenShift Container Platform environment.

After you have configured Ansible by defining an inventory file in **/etc/ansible/hosts**, you can run the advanced installation using the following playbook:

```
# ansible-playbook /usr/share/ansible/openshift-  
ansible/playbooks/byo/config.yml
```

**NOTE**

For more detailed usage information on the advanced installation method, including a comprehensive list of available Ansible variables, see the full topic at [Advanced Installation](#).

CHAPTER 3. SETTING UP THE REGISTRY

3.1. REGISTRY OVERVIEW

3.1.1. About the Registry

OpenShift Container Platform can build [container images](#) from your source code, deploy them, and manage their lifecycle. To enable this, OpenShift Container Platform provides an internal, [integrated Docker registry](#) that can be deployed in your OpenShift Container Platform environment to locally manage images.

3.1.2. Integrated or Stand-alone Registries

During an initial installation of a full OpenShift Container Platform cluster, it is likely that the registry was deployed automatically during the installation process. If it was not, or if you want to further customize the configuration of your registry, see [Deploying a Registry on Existing Clusters](#).

While it can be deployed to run as an integrated part of your full OpenShift Container Platform cluster, the OpenShift Container Platform registry can alternatively be installed separately as a stand-alone container image registry.

To install a stand-alone registry, follow [Installing a Stand-alone Registry](#). This installation path deploys an all-in-one cluster running a registry and specialized web console.

3.2. DEPLOYING A REGISTRY ON EXISTING CLUSTERS

3.2.1. Overview

If the integrated registry was not previously deployed automatically during the initial installation of your OpenShift Container Platform cluster, or if it is no longer running successfully and you need to redeploy it on your existing cluster, see the following sections for options on deploying a new registry.



NOTE

This topic is not required if you installed a [stand-alone registry](#).

3.2.2. Deploying the Registry

To deploy the integrated Docker registry, use the **oc adm registry** command as a user with cluster administrator privileges. For example:

```
$ oc adm registry --config=/etc/origin/master/admin.kubeconfig \ 1  
    --service-account=registry \ 2  
    --images='registry.access.redhat.com/openshift3/ose-  
    ${component}:${version}' 3
```

1 --config is the path to the [CLI configuration file](#) for the [cluster administrator](#).

2 --service-account is the service account used to run the registry's pod.

3 Required to pull the correct image for OpenShift Container Platform.

This creates a service and a deployment configuration, both called **docker-registry**. Once deployed successfully, a pod is created with a name similar to **docker-registry-1-cpty9**.

To see a full list of options that you can specify when creating the registry:

```
$ oc adm registry --help
```

The value for **--fs-group** must be [permitted by the SCC](#) used by the registry (typically, the restricted SCC).

3.2.3. Deploying the Registry as a DaemonSet

Use the **oc adm registry** command to deploy the registry as a **DaemonSet** with the **--daemonset** option.

Daemonsets ensure that when nodes are created, they contain copies of a specified pod. When the nodes are removed, the pods are garbage collected.

For more information on **DaemonSets**, see [Using Daemonsets](#).

3.2.4. Registry Compute Resources

By default, the registry is created with no settings for [compute resource requests or limits](#). For production, it is highly recommended that the deployment configuration for the registry be updated to set resource requests and limits for the registry pod. Otherwise, the registry pod will be considered a **BestEffort** pod.

See [Compute Resources](#) for more information on configuring requests and limits.

3.2.5. Storage for the Registry

The registry stores container images and metadata. If you simply deploy a pod with the registry, it uses an ephemeral volume that is destroyed if the pod exits. Any images anyone has built or pushed into the registry would disappear.

This section lists the supported [registry storage drivers](#).

The following list includes storage drivers that need to be configured in the registry's configuration file:

- [Filesystem](#). Filesystem is the default and does not need to be configured.
- [S3](#). Learn more about [CloudFront configuration](#).
- [OpenStack Swift](#)
- [Google Cloud Storage \(GCS\)](#)
- [Microsoft Azure](#)
- [Aliyun OSS](#)

General [registry storage configuration options](#) are supported.

The following storage options need to be configured through the [filesystem driver](#):

- [Backing Docker Registry with GlusterFS Storage](#)

- [Ceph Rados Block Device](#)



NOTE


For more information on supported persistent storage drivers, see [Configuring Persistent Storage](#) and [Persistent Storage Examples](#).

3.2.5.1. Production Use

For production use, attach a remote volume or [define and use the persistent storage method of your choice](#).

For example, to use an existing persistent volume claim:

```
$ oc volume deploymentconfigs/docker-registry --add --name=registry-storage -t pvc \
    --claim-name=<pvc_name> --overwrite
```



IMPORTANT

Testing shows issues with using the NFS server on RHEL as storage backend for the container registry. This includes the OpenShift Container Registry and Quay. Therefore, using NFS to back PVs used by core services is not recommended.

Other NFS implementations on the marketplace might not have these issues. Contact the individual NFS implementation vendor for more information on any testing that was possibly completed against these OpenShift core components.

3.2.5.1.1. Use Amazon S3 as a Storage Back-end

There is also an option to use Amazon Simple Storage Service storage with the internal Docker registry. It is a secure cloud storage manageable through [AWS Management Console](#). To use it, the registry's configuration file must be manually edited and mounted to the registry pod. However, before you start with the configuration, look at upstream's [recommended steps](#).

Take a [default YAML configuration file](#) as a base and replace the **filesystem** entry in the **storage** section with **s3** entry such as below. The resulting storage section may look like this:

```
storage:
  cache:
    layerinfo: inmemory
  delete:
    enabled: true
  s3:
    accesskey: awsaccesskey 1
    secretkey: awssecretkey 2
    region: us-west-1
    regionendpoint: http://myobjects.local
    bucket: bucketname
    encrypt: true
    keyid: mykeyid
    secure: true
```

```
v4auth: false
chunksize: 5242880
rootdirectory: /s3/object/name/prefix
```

- 1 Replace with your Amazon access key.
- 2 Replace with your Amazon secret key.

All of the **s3** configuration options are documented in upstream's [driver reference documentation](#).

[Overriding the registry configuration](#) will take you through the additional steps on mounting the configuration file into pod.



WARNING

When the registry runs on the S3 storage back-end, there are [reported issues](#).

3.2.5.2. Non-Production Use

For non-production use, you can use the `--mount-host=<path>` option to specify a directory for the registry to use for persistent storage. The registry volume is then created as a host-mount at the specified `<path>`.



IMPORTANT

The `--mount-host` option mounts a directory from the node on which the registry container lives. If you scale up the **docker-registry** deployment configuration, it is possible that your registry pods and containers will run on different nodes, which can result in two or more registry containers, each with its own local storage. This will lead to unpredictable behavior, as subsequent requests to pull the same image repeatedly may not always succeed, depending on which container the request ultimately goes to.

The `--mount-host` option requires that the registry container run in privileged mode. This is automatically enabled when you specify `--mount-host`. However, not all pods are allowed to run [privileged containers](#) by default. If you still want to use this option, create the registry and specify that it use the **registry** service account that was created during installation:

```
$ oc adm registry --service-account=registry \
  --config=/etc/origin/master/admin.kubeconfig \
  --images='registry.access.redhat.com/openshift3/ose-
${component}:${version}' \
  --mount-host=<path>
```

**IMPORTANT**

The Docker registry pod runs as user **1001**. This user must be able to write to the host directory. You may need to change directory ownership to user ID **1001** with this command:


```
$ sudo chown 1001:root <path>
```

3.2.6. Enabling the Registry Console

OpenShift Container Platform provides a web-based interface to the integrated registry. This registry console is an optional component for browsing and managing images. It is deployed as a stateless service running as a pod.

**NOTE**

If you installed OpenShift Container Platform as a [stand-alone registry](#), the registry console is already deployed and secured automatically during installation.

**IMPORTANT**

If Cockpit is already running, you'll need to shut it down before proceeding in order to avoid a port conflict (9090 by default) with the registry console.

3.2.6.1. Deploying the Registry Console**IMPORTANT**

You must first have [exposed the registry](#).

1. Create a passthrough route in the **default** project. You will need this when creating the registry console application in the next step.

```
$ oc create route passthrough --service registry-console \
  --port registry-console \
  -n default
```

2. Deploy the registry console application. Replace **<openshift_oauth_url>** with the URL of the OpenShift Container Platform OAuth provider, which is typically the master.

```
$ oc new-app -n default --template=registry-console \
  -p
  OPENSIFT_OAUTH_PROVIDER_URL="https://<openshift_oauth_url>:8443" \
  -p REGISTRY_HOST=$(oc get route docker-registry -n default --
  template='{{ .spec.host }}') \
  -p COCKPIT_KUBE_URL=$(oc get route registry-console -n default -
  -template='https://{{ .spec.host }}')
```

**NOTE**

If the redirection URL is wrong when you are trying to log in to the registry console, check your OAuth client with **oc get oauthclients**.

1. Finally, use a web browser to view the console using the route URI.

3.2.6.2. Securing the Registry Console

By default, the registry console generates self-signed TLS certificates if deployed manually per the steps in [Deploying the Registry Console](#). See [Troubleshooting the Registry Console](#) for more information.

Use the following steps to add your organization's signed certificates as a secret volume. This assumes your certificates are available on the **oc** client host.

1. Create a **.cert** file containing the certificate and key. Format the file with:

- One or more **BEGIN CERTIFICATE** blocks for the server certificate and the intermediate certificate authorities
 - A block containing a **BEGIN PRIVATE KEY** or similar for the key. The key must not be encrypted
- For example:

```
-----BEGIN CERTIFICATE-----
MIIDUzCCAjugAwIBAgIJAPXW+CuNYS6QMA0GCSqGSIb3DQEBCwUAMD8xKTAnBgNV
BAoMIGI00GE2NGNkNmMwNTQ1YThhZTgx0TEzZDE5YmJjMmRjMRIwEAYDVQQDDAIs
...
-----END CERTIFICATE-----
-----BEGIN CERTIFICATE-----
MIIDUzCCAjugAwIBAgIJAPXW+CuNYS6QMA0GCSqGSIb3DQEBCwUAMD8xKTAnBgNV
BAoMIGI00GE2NGNkNmMwNTQ1YThhZTgx0TEzZDE5YmJjMmRjMRIwEAYDVQQDDAIs
...
-----END CERTIFICATE-----
-----BEGIN PRIVATE KEY-----
MIIEvgIBADANBgkqhkiG9w0BAQEFAASCBAKggwggSkAgEAAoIBAQCyoJ5garOYw0sm
8TBCDSqQ/H1awGMzDYdB11xuHHsxYS2VepPMzMzryHR137I4dGFLhvdTvJUH8lUS
...
-----END PRIVATE KEY-----
```

- The secured registry should contain the following Subject Alternative Names (SAN) list:
 - Two service hostnames.

For example:

```
docker-registry.default.svc.cluster.local
docker-registry.default.svc
```

- Service IP address.
- For example:

```
172.30.124.220
```

Use the following command to get the Docker registry service IP address:

```
oc get service docker-registry --
template='{{.spec.clusterIP}}'
```

- Public hostname.

For example:

```
docker-registry-default.apps.example.com
```

Use the following command to get the Docker registry public hostname:

```
oc get route docker-registry --template '{{.spec.host}}'
```

For example, the server certificate should contain SAN details similar to the following:

```
X509v3 Subject Alternative Name:
      DNS:docker-registry-public.openshift.com,
      DNS:docker-registry.default.svc, DNS:docker-
      registry.default.svc.cluster.local, DNS:172.30.2.98, IP
      Address:172.30.2.98
```

The registry console loads a certificate from the `/etc/cockpit/ws-certs.d` directory. It uses the last file with a `.cert` extension in alphabetical order. Therefore, the `.cert` file should contain at least two PEM blocks formatted in the OpenSSL style.

If no certificate is found, a self-signed certificate is created using the `openssl` command and stored in the `0-self-signed.cert` file.

2. Create the secret:

```
$ oc secrets new console-secret \
  /path/to/console.cert
```

3. Add the secrets to the **registry-console** deployment configuration:

```
$ oc volume dc/registry-console --add --type=secret \
  --secret-name=console-secret -m /etc/cockpit/ws-certs.d
```

This triggers a new deployment of the registry console to include your signed certificates.

3.2.6.3. Troubleshooting the Registry Console

3.2.6.3.1. Debug Mode

The registry console debug mode is enabled using an environment variable. The following command redeploys the registry console in debug mode:

```
$ oc set env dc registry-console G_MESSAGES_DEBUG=cockpit-ws,cockpit-
wrapper
```

Enabling debug mode allows more verbose logging to appear in the registry console's pod logs.

3.2.6.3.2. Display SSL Certificate Path

To check which certificate the registry console is using, a command can be run from inside the console pod.

1. List the pods in the **default** project and find the registry console's pod name:

```
$ oc get pods -n default
```

NAME	READY	STATUS	RESTARTS	AGE
registry-console-1-rssrw	1/1	Running	0	1d

- Using the pod name from the previous command, get the certificate path that the **cockpit-ws** process is using. This example shows the console using the auto-generated certificate:

```
$ oc exec registry-console-1-rssrw remotectl certificate
certificate: /etc/cockpit/ws-certs.d/0-self-signed.cert
```

3.3. ACCESSING THE REGISTRY

3.3.1. Viewing Logs

To view the logs for the Docker registry, use the **oc logs** command with the deployment configuration:

```
$ oc logs dc/docker-registry
2015-05-01T19:48:36.300593110Z time="2015-05-01T19:48:36Z" level=info
msg="version=v2.0.0+unknown"
2015-05-01T19:48:36.303294724Z time="2015-05-01T19:48:36Z" level=info
msg="redis not configured" instance.id=9ed6c43d-23ee-453f-9a4b-
031fea646002
2015-05-01T19:48:36.303422845Z time="2015-05-01T19:48:36Z" level=info
msg="using inmemory layerinfo cache" instance.id=9ed6c43d-23ee-453f-9a4b-
031fea646002
2015-05-01T19:48:36.303433991Z time="2015-05-01T19:48:36Z" level=info
msg="Using OpenShift Auth handler"
2015-05-01T19:48:36.303439084Z time="2015-05-01T19:48:36Z" level=info
msg="listening on :5000" instance.id=9ed6c43d-23ee-453f-9a4b-031fea646002
```

3.3.2. File Storage

Tag and image metadata is stored in OpenShift Container Platform, but the registry stores layer and signature data in a volume that is mounted into the registry container at **/registry**. As **oc exec** does not work on privileged containers, to view a registry's contents you must manually SSH into the node housing the registry pod's container, then run **docker exec** on the container itself:

- List the current pods to find the pod name of your Docker registry:

```
# oc get pods
```

Then, use **oc describe** to find the host name for the node running the container:

```
# oc describe pod <pod_name>
```

- Log into the desired node:

```
# ssh node.example.com
```

- List the running containers from the default project on the node host and identify the container ID for the Docker registry:

-

```
# docker ps --filter=name=registry_docker-registry.*_default_
```

4. List the registry contents using the **oc rsh** command:

```
# oc rsh dc/docker-registry find /registry
/registry/docker
/registry/docker/registry
/registry/docker/registry/v2
/registry/docker/registry/v2/blobs 1
/registry/docker/registry/v2/blobs/sha256
/registry/docker/registry/v2/blobs/sha256/ed
/registry/docker/registry/v2/blobs/sha256/ed/ede17b139a271d6b1331ca3
d83c648c24f92cece5f89d95ac6c34ce751111810
/registry/docker/registry/v2/blobs/sha256/ed/ede17b139a271d6b1331ca3
d83c648c24f92cece5f89d95ac6c34ce751111810/data 2
/registry/docker/registry/v2/blobs/sha256/a3
/registry/docker/registry/v2/blobs/sha256/a3/a3ed95caeb02ffe68cdd9fd
84406680ae93d633cb16422d00e8a7c22955b46d4
/registry/docker/registry/v2/blobs/sha256/a3/a3ed95caeb02ffe68cdd9fd
84406680ae93d633cb16422d00e8a7c22955b46d4/data
/registry/docker/registry/v2/blobs/sha256/f7
/registry/docker/registry/v2/blobs/sha256/f7/f72a00a23f01987b42cb26f
259582bb33502bdb0fcf5011e03c60577c4284845
/registry/docker/registry/v2/blobs/sha256/f7/f72a00a23f01987b42cb26f
259582bb33502bdb0fcf5011e03c60577c4284845/data
/registry/docker/registry/v2/repositories 3
/registry/docker/registry/v2/repositories/p1
/registry/docker/registry/v2/repositories/p1/pause 4
/registry/docker/registry/v2/repositories/p1/pause/_manifests
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisi
ons
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisi
ons/sha256
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisi
ons/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisi
ons/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf/signatures 5
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisi
ons/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf/signatures/sha256
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisi
ons/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf/signatures/sha256/ede17b139a271d6b1331ca3d83c648c24f92cece5f
89d95ac6c34ce751111810
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisi
ons/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf/signatures/sha256/ede17b139a271d6b1331ca3d83c648c24f92cece5f
89d95ac6c34ce751111810/link 6
/registry/docker/registry/v2/repositories/p1/pause/_uploads 7
/registry/docker/registry/v2/repositories/p1/pause/_layers 8
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256/a3
```



```
ed95caeb02ffe68cdd9fd84406680ae93d633cb16422d00e8a7c22955b46d4
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256/a3
ed95caeb02ffe68cdd9fd84406680ae93d633cb16422d00e8a7c22955b46d4/link
9
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256/f7
2a00a23f01987b42cb26f259582bb33502bdb0fcf5011e03c60577c4284845
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256/f7
2a00a23f01987b42cb26f259582bb33502bdb0fcf5011e03c60577c4284845/link
```

- 1 This directory stores all layers and signatures as blobs.
- 2 This file contains the blob's contents.
- 3 This directory stores all the image repositories.
- 4 This directory is for a single image repository **p1/pause**.
- 5 This directory contains signatures for a particular image manifest revision.
- 6 This file contains a reference back to a blob (which contains the signature data).
- 7 This directory contains any layers that are currently being uploaded and staged for the given repository.
- 8 This directory contains links to all the layers this repository references.
- 9 This file contains a reference to a specific layer that has been linked into this repository via an image.

3.3.3. Accessing the Registry Directly

For advanced usage, you can access the registry directly to invoke **docker** commands. This allows you to push images to or pull them from the integrated registry directly using operations like **docker push** or **docker pull**. To do so, you must be logged in to the registry using the **docker login** command. The operations you can perform depend on your user permissions, as described in the following sections.

3.3.3.1. User Prerequisites

To access the registry directly, the user that you use must satisfy the following, depending on your intended usage:

- For any direct access, you must have a [regular user](#), if one does not already exist, for your preferred [identity provider](#). A regular user can generate an access token required for logging in to the registry. [System users](#), such as **system:admin**, cannot obtain access tokens and, therefore, cannot access the registry directly.
For example, if you are using **HTPASSWD** authentication, you can create one using the following command:

```
# htpasswd /etc/origin/openshift-htpasswd <user_name>
```

- For pulling images, for example when using the **docker pull** command, the user must have the **registry-viewer** role. To add this role:

```
$ oc policy add-role-to-user registry-viewer <user_name>
```

- For writing or pushing images, for example when using the **docker push** command, the user must have the **registry-editor** role. To add this role:

```
$ oc policy add-role-to-user registry-editor <user_name>
```

For more information on user permissions, see [Managing Role Bindings](#).

3.3.3.2. Logging in to the Registry



NOTE

Ensure your user satisfies the [prerequisites](#) for accessing the registry directly.

To log in to the registry directly:

1. Ensure you are logged in to OpenShift Container Platform as a **regular user**:

```
$ oc login
```

2. Log in to the Docker registry by using your access token:

```
docker login -u openshift -p $(oc whoami -t) <registry_ip>:<port>
```



NOTE

You can pass any value for the username, the token contains all necessary information. Passing a username that contains colons will result in a login failure.

3.3.3.3. Pushing and Pulling Images

After [logging in to the registry](#), you can perform **docker pull** and **docker push** operations against your registry.



IMPORTANT

You can pull arbitrary images, but if you have the **system:registry** role added, you can only push images to the registry in your project.

In the following examples, we use:

Component	Value
<registry_ip>	172.30.124.220
<port>	5000
<project>	openshift

<image>	busybox
<tag>	omitted (defaults to latest)

1. Pull an arbitrary image:

```
$ docker pull docker.io/busybox
```

2. Tag the new image with the form **<registry_ip>:<port>/<project>/<image>**. The project name **must** appear in this [pull specification](#) for OpenShift Container Platform to correctly place and later access the image in the registry.

```
$ docker tag docker.io/busybox 172.30.124.220:5000/openshift/busybox
```



NOTE

Your regular user must have the **system:image-builder** role for the specified project, which allows the user to write or push an image. Otherwise, the **docker push** in the next step will fail. To test, you can [create a new project](#) to push the **busybox** image.

3. Push the newly-tagged image to your registry:

```
$ docker push 172.30.124.220:5000/openshift/busybox
...
cf2616975b4a: Image successfully pushed
Digest:
sha256:3662dd821983bc4326bee12caec61367e7fb6f6a3ee547cbaff98f77403cab55
```

3.3.4. Accessing Registry Metrics

The OpenShift Container Registry provides an endpoint for [Prometheus metrics](#). Prometheus is a stand-alone, open source systems monitoring and alerting toolkit.

The metrics are exposed at the **/extensions/v2/metrics** path of the registry endpoint. However, this route must first be enabled; see [Extended Registry Configuration](#) for instructions.

The following is a simple example of a metrics query:

```
$ curl -s -u <user>:<secret> \ 1
  http://172.30.30.30:5000/extensions/v2/metrics | grep openshift | head
-n 10

# HELP openshift_build_info A metric with a constant '1' value labeled by
major, minor, git commit & git version from which OpenShift was built.
# TYPE openshift_build_info gauge
openshift_build_info{gitCommit="67275e1",gitVersion="v3.6.0-alpha.1+67275e1-803",major="3",minor="6+"} 1
# HELP openshift_registry_request_duration_seconds Request latency summary
in microseconds for each operation
```

```
# TYPE openshift_registry_request_duration_seconds summary
openshift_registry_request_duration_seconds{name="test/origin-
pod",operation="blobstore.create",quantile="0.5"} 0
openshift_registry_request_duration_seconds{name="test/origin-
pod",operation="blobstore.create",quantile="0.9"} 0
openshift_registry_request_duration_seconds{name="test/origin-
pod",operation="blobstore.create",quantile="0.99"} 0
openshift_registry_request_duration_seconds_sum{name="test/origin-
pod",operation="blobstore.create"} 0
openshift_registry_request_duration_seconds_count{name="test/origin-
pod",operation="blobstore.create"} 5
```

- 1 **<user>** can be arbitrary, but **<secret>** must match the value specified in the [registry configuration](#).

See the [upstream Prometheus documentation](#) for more advanced queries and recommended visualizers.

3.4. SECURING AND EXPOSING THE REGISTRY

3.4.1. Overview

By default, the OpenShift Container Registry is secured during cluster installation so that it serves traffic via TLS. A passthrough route is also created by default to expose the service externally.

If for any reason your registry has not been secured or exposed, see the following sections for steps on how to manually do so.

3.4.2. Manually Securing the Registry

To manually secure the registry to serve traffic via TLS:

1. [Deploy the registry](#).
2. Fetch the service IP and port of the registry:

```
$ oc get svc/docker-registry
NAME                                LABELS
SELECTOR                            IP(S)                                PORT(S)
docker-registry                    docker-registry=default              docker-
registry=default                  172.30.124.220                      5000/TCP
```

3. You can use an existing server certificate, or create a key and server certificate valid for specified IPs and host names, signed by a specified CA. To create a server certificate for the registry service IP and the **docker-registry.default.svc.cluster.local** host name, run the following command from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**:

```
$ oc adm ca create-server-cert \
  --signer-cert=/etc/origin/master/ca.crt \
  --signer-key=/etc/origin/master/ca.key \
  --signer-serial=/etc/origin/master/ca.serial.txt \
  --hostnames='docker-registry.default.svc.cluster.local,docker-
registry.default.svc,172.30.124.220' \
  --cert=/etc/secrets/registry.crt \
```

```
--key=/etc/secrets/registry.key
```

If the router will be [exposed externally](#), add the public route host name in the **--hostnames** flag:

```
--hostnames='mydocker-registry.example.com,docker-registry.default.svc.cluster.local,172.30.124.220 \
```

See [Redeploying Registry and Router Certificates](#) for additional details on updating the default certificate so that the route is externally accessible.



NOTE

The **oc adm ca create-server-cert** command generates a certificate that is valid for two years. This can be altered with the **--expire-days** option, but for security reasons, it is recommended to not make it greater than this value.

4. Create the secret for the registry certificates:

```
$ oc secrets new registry-certificates \
  /etc/secrets/registry.crt \
  /etc/secrets/registry.key
```

5. Add the secret to the registry pod's service accounts (including the **default** service account):

```
$ oc secrets link registry registry-certificates
$ oc secrets link default registry-certificates
```



NOTE

Limiting secrets to only the service accounts that reference them is disabled by default. This means that if **serviceAccountConfig.limitSecretReferences** is set to **false** (the default setting) in the master configuration file, linking secrets to a service is not required.

6. Pause the **docker-registry** service:

```
$ oc rollout pause dc/docker-registry
```

7. Add the secret volume to the registry deployment configuration:

```
$ oc volume dc/docker-registry --add --type=secret \
  --secret-name=registry-certificates -m /etc/secrets
```

8. Enable TLS by adding the following environment variables to the registry deployment configuration:

```
$ oc set env dc/docker-registry \
  REGISTRY_HTTP_TLS_CERTIFICATE=/etc/secrets/registry.crt \
  REGISTRY_HTTP_TLS_KEY=/etc/secrets/registry.key
```

See more details on [overriding registry options](#).

9. Update the scheme used for the registry's liveness probe from HTTP to HTTPS:

```
$ oc patch dc/docker-registry -p '{"spec": {"template": {"spec": {"containers": [{
  "name": "registry",
  "livenessProbe": {"httpGet": {"scheme": "HTTPS"}}
}]}}}'
```

10. If your registry was initially deployed on OpenShift Container Platform 3.2 or later, update the scheme used for the registry's readiness probe from HTTP to HTTPS:

```
$ oc patch dc/docker-registry -p '{"spec": {"template": {"spec": {"containers": [{
  "name": "registry",
  "readinessProbe": {"httpGet": {"scheme": "HTTPS"}}
}]}}}'
```

11. Resume the **docker-registry** service:

```
$ oc rollout resume dc/docker-registry
```

12. Validate the registry is running in TLS mode. Wait until the latest **docker-registry** deployment completes and verify the Docker logs for the registry container. You should find an entry for **listening on :5000, tls**.

```
$ oc logs dc/docker-registry | grep tls
time="2015-05-27T05:05:53Z" level=info msg="listening on :5000, tls"
instance.id=deeba528-c478-41f5-b751-dc48e4935fc2
```

13. Copy the CA certificate to the Docker certificates directory. This must be done on all nodes in the cluster:

```
$ dcertsdir=/etc/docker/certs.d
$ destdir_addr=$dcertsdir/172.30.124.220:5000
$ destdir_name=$dcertsdir/docker-
registry.default.svc.cluster.local:5000

$ sudo mkdir -p $destdir_addr $destdir_name
$ sudo cp ca.crt $destdir_addr
$ sudo cp ca.crt $destdir_name
```

1 The **ca.crt** file is a copy of **/etc/origin/master/ca.crt** on the master.

14. When using authentication, some versions of **docker** also require you to configure your cluster to trust the certificate at the OS level.

- a. Copy the certificate:

```
$ cp /etc/origin/master/ca.crt /etc/pki/ca-
trust/source/anchors/myregistrydomain.com.crt
```

b. Run:

```
$ update-ca-trust enable
```

15. Remove the **--insecure-registry** option only for this particular registry in the **/etc/sysconfig/docker** file. Then, reload the daemon and restart the **docker** service to reflect this configuration change:

```
$ sudo systemctl daemon-reload
$ sudo systemctl restart docker
```

16. Validate the **docker** client connection. Running **docker push** to the registry or **docker pull** from the registry should succeed. Make sure you have [logged into the registry](#).

```
$ docker tag|push <registry/image> <internal_registry/project/image>
```

For example:

```
$ docker pull busybox
$ docker tag docker.io/busybox 172.30.124.220:5000/openshift/busybox
$ docker push 172.30.124.220:5000/openshift/busybox
...
cf2616975b4a: Image successfully pushed
Digest:
sha256:3662dd821983bc4326bee12caec61367e7fb6f6a3ee547cbaff98f77403ca
b55
```

3.4.3. Manually Exposing a Secure Registry

Instead of logging in to the OpenShift Container Registry from within the OpenShift Container Platform cluster, you can gain external access to it by first securing the registry and then exposing it with a route. This allows you to log in to the registry from outside the cluster using the route address, and to tag and push images using the route host.

1. Each of the following prerequisite steps are performed by default during a typical cluster installation. If they have not been, perform them manually:
 - a. [Manually deploy the registry](#).
 - b. [Manually secure the registry](#).
 - c. [Manually deploy a router](#).
2. A [passthrough](#) route should have been created by default for the registry during the initial cluster installation:
 - a. Verify whether the route exists:

```
$ oc get route/docker-registry -o yaml
apiVersion: v1
kind: Route
metadata:
  name: docker-registry
spec:
```

```

host: <host> ❶
to:
  kind: Service
  name: docker-registry ❷
tls:
  termination: passthrough ❸

```

- ❶ The host for your route. You must be able to resolve this name externally via DNS to the router's IP address.
- ❷ The service name for your registry.
- ❸ Specifies this route as a passthrough route.

**NOTE**

Re-encrypt routes are also supported for exposing the secure registry.

- b. If it does not exist, create the route via the **oc create route passthrough** command, specifying the registry as the route's service. By default, the name of the created route is the same as the service name:

- i. Get the **docker-registry** service details:

```

$ oc get svc
NAME                                CLUSTER_IP           EXTERNAL_IP    PORT(S)
SELECTOR                           AGE
docker-registry                    172.30.69.167        <none>         5000/TCP
docker-registry=default            4h
kubernetes                         172.30.0.1           <none>
443/TCP, 53/UDP, 53/TCP            <none>               4h
router                             172.30.172.132       <none>         80/TCP
router=router                      4h

```

- ii. Create the route:

```

$ oc create route passthrough \
  --service=docker-registry \ ❶
  --hostname=<host>
route "docker-registry" created ❷

```

- ❶ Specifies the registry as the route's service.
 - ❷ The route name is identical to the service name.
- 3. Next, you must trust the certificates being used for the registry on your host system to allow the host to push and pull images. The certificates referenced were created when you secured your registry.

```

$ sudo mkdir -p /etc/docker/certs.d/<host>
$ sudo cp <ca_certificate_file> /etc/docker/certs.d/<host>
$ sudo systemctl restart docker

```


4. [Log in to the registry](#) using the information from securing the registry. However, this time point to the host name used in the route rather than your service IP. When logging in to a secured and exposed registry, make sure you specify the registry in the **docker login** command:

```
# docker login -e user@company.com \
  -u f83j5h6 \
  -p Ju1PeM47R0B92Lk3AZp-bWJSck2F7aGCiZ66aFGZrs2 \
  <host>
```

5. You can now tag and push images using the route host. For example, to tag and push a **busybox** image in a project called **test**:

```
$ oc get imagestreams -n test
NAME          DOCKER REPO          TAGS          UPDATED

$ docker pull busybox
$ docker tag busybox <host>/test/busybox
$ docker push <host>/test/busybox
The push refers to a repository [<host>/test/busybox] (len: 1)
8c2e06607696: Image already exists
6ce2e90b0bc7: Image successfully pushed
cf2616975b4a: Image successfully pushed
Digest:
sha256:6c7e676d76921031532d7d9c0394d0da7c2906f4cb4c049904c4031147d8c
a31

$ docker pull <host>/test/busybox
latest: Pulling from <host>/test/busybox
cf2616975b4a: Already exists
6ce2e90b0bc7: Already exists
8c2e06607696: Already exists
Digest:
sha256:6c7e676d76921031532d7d9c0394d0da7c2906f4cb4c049904c4031147d8c
a31
Status: Image is up to date for <host>/test/busybox:latest

$ oc get imagestreams -n test
NAME          DOCKER REPO          TAGS          UPDATED
busybox       172.30.11.215:5000/test/busybox   latest        2 seconds ago
```



NOTE

Your image streams will have the IP address and port of the registry service, not the route name and port. See **oc get imagestreams** for details.

3.4.4. Manually Exposing a Non-Secure Registry

Instead of securing the registry in order to expose the registry, you can simply expose a non-secure registry for non-production OpenShift Container Platform environments. This allows you to have an external route to the registry without using SSL certificates.

**WARNING**

Only non-production environments should expose a non-secure registry to external access.

To expose a non-secure registry:

1. Expose the registry:

```
# oc expose service docker-registry --hostname=<hostname> -n default
```

This creates the following JSON file:

```
apiVersion: v1
kind: Route
metadata:
  creationTimestamp: null
  labels:
    docker-registry: default
  name: docker-registry
spec:
  host: registry.example.com
  port:
    targetPort: "5000"
  to:
    kind: Service
    name: docker-registry
status: {}
```

2. Verify that the route has been created successfully:

```
# oc get route
```

NAME	HOST/PORT	PATH	SERVICE
docker-registry	registry.example.com		docker-registry
docker-registry=default			

3. Check the health of the registry:

```
$ curl -v http://registry.example.com/healthz
```

Expect an HTTP 200/OK message.

After exposing the registry, update your `/etc/sysconfig/docker` file by adding the port number to the **OPTIONS** entry. For example:

```
OPTIONS='--selinux-enabled --insecure-registry=172.30.0.0/16 --insecure-registry registry.example.com:80'
```



IMPORTANT

The above options should be added on the client from which you are trying to log in.

Also, ensure that Docker is running on the client.

When [logging in](#) to the non-secured and exposed registry, make sure you specify the registry in the **docker login** command. For example:

```
# docker login -e user@company.com \
  -u f83j5h6 \
  -p Ju1PeM47R0B92Lk3AZp-bWJSck2F7aGCiZ66aFGZrs2 \
  <host>
```

3.5. EXTENDED REGISTRY CONFIGURATION

3.5.1. Maintaining the Registry IP Address

OpenShift Container Platform refers to the integrated registry by its service IP address, so if you decide to delete and recreate the **docker-registry** service, you can ensure a completely transparent transition by arranging to re-use the old IP address in the new service. If a new IP address cannot be avoided, you can minimize cluster disruption by rebooting only the masters.

Re-using the Address

To re-use the IP address, you must save the IP address of the old **docker-registry** service prior to deleting it, and arrange to replace the newly assigned IP address with the saved one in the new **docker-registry** service.

1. Make a note of the **clusterIP** for the service:

```
$ oc get svc/docker-registry -o yaml | grep clusterIP:
```

2. Delete the service:

```
$ oc delete svc/docker-registry dc/docker-registry
```

3. Create the registry definition in **registry.yaml**, replacing **<options>** with, for example, those used in step 3 of the instructions in the [Non-Production Use](#) section:

```
$ oc adm registry <options> -o yaml > registry.yaml
```

4. Edit **registry.yaml**, find the **Service** there, and change its **clusterIP** to the address noted in step 1.
5. Create the registry using the modified **registry.yaml**:


```
$ oc create -f registry.yaml
```

Rebooting the Masters

If you are unable to re-use the IP address, any operation that uses a [pull specification](#) that includes the old IP address will fail. To minimize cluster disruption, you must reboot the masters:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

This ensures that the old registry URL, which includes the old IP address, is cleared from the cache.



NOTE

We recommend against rebooting the entire cluster because that incurs unnecessary downtime for pods and does not actually clear the cache.

3.5.2. Whitelisting Docker Registries

You can specify a whitelist of docker registries, allowing you to curate a set of images and templates that are available for download by OpenShift Container Platform users. This curated set can be placed in one or more docker registries, and then added to the whitelist. When using a whitelist, only the specified registries are accessible within OpenShift Container Platform, and all other registries are denied access by default.

To configure a whitelist:

1. Edit the `/etc/sysconfig/docker` file to block all registries:

```
BLOCK_REGISTRY='--block-registry=all'
```

You may need to uncomment the **BLOCK_REGISTRY** line.

2. In the same file, add registries to which you want to allow access:

```
ADD_REGISTRY='--add-registry=<registry1> --add-registry=<registry2>'
```

Allowing Access to Registries

```
ADD_REGISTRY='--add-registry=registry.access.redhat.com'
```

This example would restrict access to images available on the [Red Hat Customer Portal](#).

Once the whitelist is configured, if a user tries to pull from a docker registry that is not on the whitelist, they will receive an error message stating that this registry is not allowed.


3.5.3. Setting the Registry Hostname

You can configure the hostname and port the registry is known by for both internal and external references. By doing this, image streams will provide hostname based push and pull specifications for images, allowing consumers of the images to be isolated from changes to the registry service ip and potentially allowing image streams and their references to be portable between clusters.

To set the hostname used to reference the registry from within the cluster, set the **internalRegistryHostname** in the **imagePolicyConfig** section of the master configuration file. The external hostname is controlled by setting the **externalRegistryHostname** value in the same location.

Image Policy Configuration

```
imagePolicyConfig:
  internalRegistryHostname: docker-registry.default.svc.cluster.local:5000
  externalRegistryHostname: docker-registry.mycompany.com
```



NOTE

If you have enabled TLS for your registry the server certificate must include the hostnames by which you expect the registry to be referenced. See [securing the registry](#) for instructions on adding hostnames to the server certificate.

3.5.4. Overriding the Registry Configuration

You can override the integrated registry's default configuration, found by default at `/config.yml` in a running registry's container, with your own [custom configuration](#).



NOTE

Upstream configuration options in this file may also be overridden using environment variables. The [middleware section](#) is an exception as there are just a few options that can be overridden using environment variables. [Learn how to override specific configuration options](#).

To enable management of the registry configuration file directly and deploy an updated configuration using a **ConfigMap**:

1. [Deploy the registry](#).
2. Edit the registry configuration file locally as needed. The initial YAML file deployed on the registry is provided below. [Review supported options](#).

Registry Configuration File

```
version: 0.1
log:
  level: debug
http:
  addr: :5000
storage:
  cache:
    blobdescriptor: inmemory
  filesystem:
    rootdirectory: /registry
delete:
  enabled: true
auth:
  openshift:
    realm: openshift
middleware:
  registry:
    - name: openshift
repository:
  - name: openshift
    options:
      acceptschema2: true
```

```

    pullthrough: true
    enforcequota: false
    projectcachettl: 1m
    blobrepositorycachettl: 10m
  storage:
    - name: openshift
  openshift:
    version: 1.0
  metrics:
    enabled: false
    secret: <secret>

```

3. Create a **ConfigMap** holding the content of each file in this directory:

```

$ oc create configmap registry-config \
  --from-file=</path/to/custom/registry/config.yml>/

```

4. Add the **registry-config** ConfigMap as a volume to the registry's deployment configuration to mount the custom configuration file at **/etc/docker/registry/**:

```

$ oc volume dc/docker-registry --add --type=configmap \
  --configmap-name=registry-config -m /etc/docker/registry/

```

5. Update the registry to reference the configuration path from the previous step by adding the following environment variable to the registry's deployment configuration:

```

$ oc set env dc/docker-registry \
  REGISTRY_CONFIGURATION_PATH=/etc/docker/registry/config.yml

```

This may be performed as an iterative process to achieve the desired configuration. For example, during troubleshooting, the configuration may be temporarily updated to put it in **debug** mode.

To update an existing configuration:



WARNING

This procedure will overwrite the currently deployed registry configuration.

1. Edit the local registry configuration file, **config.yml**.
2. Delete the **registry-config** secret:

```

$ oc delete secret registry-config

```

3. Recreate the secret to reference the updated configuration file:

```

$ oc secrets new registry-config config.yml=
  </path/to/custom/registry/config.yml>

```

4. Redeploy the registry to read the updated configuration:

```
$ oc rollout latest docker-registry
```

TIP

Maintain configuration files in a source control repository.

3.5.5. Registry Configuration Reference

There are many configuration options available in the upstream [docker distribution](#) library. Not all [configuration options](#) are supported or enabled. Use this section as a reference when [overriding the registry configuration](#).



NOTE

Upstream configuration options in this file may also be overridden using environment variables. However, the [middleware section](#) may **not** be overridden using environment variables. [Learn how to override specific configuration options](#).

3.5.5.1. Log

[Upstream options](#) are supported.

Example:

```
log:
  level: debug
  formatter: text
  fields:
    service: registry
    environment: staging
```

3.5.5.2. Hooks

Mail hooks are not supported.

3.5.5.3. Storage

This section lists the supported [registry storage drivers](#).

The following list includes storage drivers that need to be configured in the registry's configuration file:

- [Filesystem](#). Filesystem is the default and does not need to be configured.
- [S3](#). Learn more about [CloudFront configuration](#).
- [OpenStack Swift](#)
- [Google Cloud Storage \(GCS\)](#)
- [Microsoft Azure](#)
- [Aliyun OSS](#)

[General registry storage configuration options](#) are supported.

The following storage options need to be configured through the [filesystem driver](#):

- [Backing Docker Registry with GlusterFS Storage](#)
- [Ceph Rados Block Device](#)



NOTE

For more information on supported persistent storage drivers, see [Configuring Persistent Storage](#) and [Persistent Storage Examples](#).

General Storage Configuration Options

```
storage:
  delete:
    enabled: true 1
  redirect:
    disable: false
  cache:
    blobdescriptor: inmemory
  maintenance:
    uploadpurging:
      enabled: true
      age: 168h
      interval: 24h
      dryrun: false
    readonly:
      enabled: false
```

1 This entry is **mandatory** for image pruning to work properly.

3.5.5.4. Auth

Auth options should not be altered. The **openshift** extension is the only supported option.

```
auth:
  openshift:
    realm: openshift
```

3.5.5.5. Middleware

The **repository** middleware extension allows to configure OpenShift Container Platform middleware responsible for interaction with OpenShift Container Platform and image proxying.

```
middleware:
  registry:
    - name: openshift 1
  repository:
    - name: openshift 2
    options:
```



```

    acceptschema2: true 3
    pullthrough: true 4
    mirrorpullthrough: true 5
    enforcequota: false 6
    projectcachettl: 1m 7
    blobrepositorycachettl: 10m 8
storage:
  - name: openshift 9

```

1 2 9 These entries are mandatory. Their presence ensures required components are loaded. These values should not be changed.

3 Allows you to store [manifest schema v2](#) during a push to the registry. See [below](#) for more details.

4 Allows the registry to act as a proxy for remote blobs. See [below](#) for more details.

5 Allows the registry cache blobs to be served from remote registries for fast access later. The mirroring starts when the blob is accessed for the first time. The option has no effect if the [pullthrough](#) is disabled.

6 Prevents blob uploads exceeding the size limit, which are defined in the targeted project.

7 An expiration timeout for limits cached in the registry. The lower the value, the less time it takes for the limit changes to propagate to the registry. However, the registry will query limits from the server more frequently and, as a consequence, pushes will be slower.

8 An expiration timeout for remembered associations between blob and repository. The higher the value, the higher probability of fast lookup and more efficient registry operation. On the other hand, memory usage will raise as well as a risk of serving image layer to user, who is no longer authorized to access it.

3.5.5.5.1. CloudFront Middleware

The [CloudFront middleware extension](#) can be added to support AWS, CloudFront CDN storage provider. CloudFront middleware speeds up distribution of image content internationally. The blobs are distributed to several edge locations around the world. The client is always directed to the edge with the lowest latency.



NOTE

The [CloudFront middleware extension](#) can be only used with [S3](#) storage. It is utilized only during blob serving. Therefore, only blob downloads can be speeded up, not uploads.

The following is an example of minimal configuration of S3 storage driver with a CloudFront middleware:

```

version: 0.1
log:
  level: debug
http:
  addr: :5000
storage:
  cache:

```

```

    blobdescriptor: inmemory
  delete:
    enabled: true
  s3: ❶
    accesskey: BJKMSZBRESWJQXRWMAEQ
    secretkey: 5ah5I91SNXbeoUXXDasFtadRq0dy62Jz1n0W1goS
    region: us-east-1
    bucket: docker.myregistry.com
  auth:
    openshift:
      realm: openshift
  middleware:
    registry:
      - name: openshift
    repository:
      - name: openshift
  storage:
    - name: cloudfront ❷
      options:
        baseurl: https://jrpbyn0k5k88bi.cloudfront.net/ ❸
        privatekey: /etc/docker/cloudfront-ABCDEFGHJKLMNOPQRST.pem ❹
        keypairid: ABCDEFGHJKLMNOPQRST ❺
    - name: openshift

```

- ❶ The S3 storage must be configured the same way regardless of CloudFront middleware.
- ❷ The CloudFront storage middleware needs to be listed before OpenShift middleware.
- ❸ The CloudFront base URL. In the AWS management console, this is listed as **Domain Name** of CloudFront distribution.
- ❹ The location of your AWS private key on the filesystem. This must be not confused with Amazon EC2 key pair. See the [AWS documentation](#) on creating CloudFront key pairs for your trusted signers. The file needs to be mounted as a `secret` into the registry pod.
- ❺ The ID of your Cloudfront key pair.

3.5.5.5.2. Overriding Middleware Configuration Options

The **middleware** section cannot be overridden using environment variables. There are a few exceptions, however. For example:

```

middleware:
  repository:
    - name: openshift
      options:
        acceptschema2: true ❶
        pullthrough: true ❷
        mirrorpullthrough: true ❸
        enforcequota: false ❹
        projectcachettl: 1m ❺
        blobrepositorycachettl: 10m ❻

```

- 1 A configuration option that can be overridden by the boolean environment variable **REGISTRY_MIDDLEWARE_REPOSITORY_OPENSIFT_ACCEPTSCHEMA2**, which allows for the ability to accept manifest schema v2 on manifest put requests. Recognized values are **true** and **false** (which applies to all the other boolean variables below).
- 2 A configuration option that can be overridden by the boolean environment variable **REGISTRY_MIDDLEWARE_REPOSITORY_OPENSIFT_PULLTHROUGH**, which enables a proxy mode for remote repositories.
- 3 A configuration option that can be overridden by the boolean environment variable **REGISTRY_MIDDLEWARE_REPOSITORY_OPENSIFT_MIRRORPULLTHROUGH**, which instructs registry to mirror blobs locally if serving remote blobs.
- 4 A configuration option that can be overridden by the boolean environment variable **REGISTRY_MIDDLEWARE_REPOSITORY_OPENSIFT_ENFORCEQUOTA**, which allows the ability to turn quota enforcement on or off. By default, quota enforcement is off.
- 5 A configuration option that can be overridden by the environment variable **REGISTRY_MIDDLEWARE_REPOSITORY_OPENSIFT_PROJECTCACHETTTL**, specifying an eviction timeout for project quota objects. It takes a valid time duration string (for example, **2m**). If empty, you get the default timeout. If zero (**0m**), caching is disabled.
- 6 A configuration option that can be overridden by the environment variable **REGISTRY_MIDDLEWARE_REPOSITORY_OPENSIFT_BLOBREPOSITORYCACHETTTL**, specifying an eviction timeout for associations between blob and containing repository. The format of the value is the same as in **projectcachettl** case.

3.5.5.5.3. Image Pullthrough

If enabled, the registry will attempt to fetch requested blob from a remote registry unless the blob exists locally. The remote candidates are calculated from **DockerImage** entries stored in status of the [image stream](#), a client pulls from. All the unique remote registry references in such entries will be tried in turn until the blob is found.

Pullthrough will only occur if an image stream tag exists for the image being pulled. For example, if the image being pulled is **docker-registry.default.svc:5000/yourproject/yourimage:prod** then the registry will look for an image stream tag named **yourimage:prod** in the project **yourproject**. If it finds one, it will attempt to pull the image using the **dockerImageReference** associated with that image stream tag.

When performing pullthrough, the registry will use pull credentials found in the project associated with the image stream tag that is being referenced. This capability also makes it possible for you to pull images that reside on a registry they do not have credentials to access, as long as you have access to the image stream tag that references the image.

You must ensure that your registry has appropriate certificates to trust any external registries you do a pullthrough against. The certificates need to be placed in the **/etc/pki/tls/certs** directory on the pod. You can mount the certificates using a [configuration map](#) or [secret](#). Note that the entire **/etc/pki/tls/certs** directory must be replaced. You must include the new certificates and replace the system certificates in your secret or configuration map that you mount.

Note that by default image stream tags use a reference policy type of **Source** which means that when the image stream reference is resolved to an image pull specification, the specification used will point to the source of the image. For images hosted on external registries, this will be the external registry and as a result the resource will reference and pull the image by the external registry. For example,

`registry.access.redhat.com/openshift3/jenkins-2-rhel7` and pullthrough will not apply. To ensure that resources referencing image streams use a pull specification that points to the internal registry, the image stream tag should use a reference policy type of **Local**. More information is available on [Reference Policy](#).

This feature is on by default. However, it can be disabled using a [configuration option](#).

By default, all the remote blobs served this way are stored locally for subsequent faster access unless **mirrorpullthrough** is disabled. The downside of this mirroring feature is an increased storage usage.



NOTE

The mirroring starts when a client tries to fetch at least a single byte of the blob. To pre-fetch a particular image into integrated registry before it is actually needed, you can run the following command:

```
$ oc get imagestreamtag/${IS}:${TAG} -o jsonpath='{
  .image.dockerImageLayers[*].name }' | \
  xargs -n1 -I {} curl -H "Range: bytes=0-1" -u user:${TOKEN} \
  http://${REGISTRY_IP}:${PORT}/v2/default/mysql/blobs/{}"
```



NOTE

This OpenShift Container Platform mirroring feature should not be confused with the upstream [registry pull through cache feature](#), which is a similar but distinct capability.

3.5.5.4. Manifest Schema v2 Support

Each image has a manifest describing its blobs, instructions for running it and additional metadata. The manifest is versioned, with each version having different structure and fields as it evolves over time. The same image can be represented by multiple manifest versions. Each version will have different digest though.

The registry currently supports [manifest v2 schema 1 \(schema1\)](#) and [manifest v2 schema 2 \(schema2\)](#). The former is being obsoleted but will be supported for an extended amount of time.

You should be wary of compatibility issues with various Docker clients:

- Docker clients of version 1.9 or older support only **schema1**. Any manifest this client pulls or pushes will be of this legacy schema.
- Docker clients of version 1.10 support both **schema1** and **schema2**. And by default, it will push the latter to the registry if it supports newer schema.

The registry, storing an image with **schema1** will always return it unchanged to the client. **Schema2** will be transferred unchanged only to newer Docker client. For the older one, it will be converted on-the-fly to **schema1**.

This has significant consequences. For example an image pushed to the registry by a newer Docker client cannot be pulled by the older Docker by its digest. That's because the stored image's manifest is of **schema2** and its digest can be used to pull only this version of manifest.

For this reason, the registry is configured by default not to store **schema2**. This ensures that any docker client will be able to pull from the registry any image pushed there regardless of client's version.

Once you're confident that all the registry clients support **schema2**, you'll be safe to enable its support in the registry. See the [middleware configuration reference](#) above for particular option.

3.5.5.6. OpenShift

This section reviews the configuration of global settings for features specific to OpenShift Container Platform. In a future release, **openshift**-related settings in the [Middleware](#) section will be obsoleted.

Currently, this section allows you to configure registry metrics collection:

```
openshift:
  version: 1.0 ❶
  server:
    addr: docker-registry.default.svc ❷
  metrics:
    enabled: false ❸
    secret: <secret> ❹
  requests:
    read:
      maxrunning: 10 ❺
      maxinqueue: 10 ❻
      maxwaitinqueue 2m ❼
    write:
      maxrunning: 10 ❽
      maxinqueue: 10 ❾
      maxwaitinqueue 2m ❿
```

- ❶ A mandatory entry specifying configuration version of this section. The only supported value is **1.0**.
- ❷ The hostname of the registry. Should be set to the same value configured on the master. It can be overridden by the environment variable **REGISTRY_OPENSIFT_SERVER_ADDR**.
- ❸ Can be set to **true** to enable metrics collection. It can be overridden by the boolean environment variable **REGISTRY_OPENSIFT_METRICS_ENABLED**.
- ❹ A secret used to authorize client requests. Metrics clients must use it as a bearer token in **Authorization** header. It can be overridden by the environment variable **REGISTRY_OPENSIFT_METRICS_SECRET**.
- ❺ Maximum number of simultaneous pull requests. It can be overridden by the environment variable **REGISTRY_OPENSIFT_REQUESTS_READ_MAXRUNNING**. Zero indicates no limit.
- ❻ Maximum number of queued pull requests. It can be overridden by the environment variable **REGISTRY_OPENSIFT_REQUESTS_READ_MAXINQUEUE**. Zero indicates no limit.
- ❼ Maximum time a pull request can wait in the queue before being rejected. It can be overridden by the environment variable **REGISTRY_OPENSIFT_REQUESTS_READ_MAXWAITINQUEUE**. Zero indicates no limit.
- ❽ Maximum number of simultaneous push requests. It can be overridden by the environment variable **REGISTRY_OPENSIFT_REQUESTS_WRITE_MAXRUNNING**. Zero indicates no limit.
- ❾ Maximum number of queued push requests. It can be overridden by the environment variable **REGISTRY_OPENSIFT_REQUESTS_WRITE_MAXINQUEUE**. Zero indicates no limit.

- 10** Maximum time a push request can wait in the queue before being rejected. It can be overridden by the environment variable **REGISTRY_OPENSHIFT_REQUESTS_WRITE_MAXWAITINQUEUE**. Zero indicates no limit.

See [Accessing Registry Metrics](#) for usage information.

3.5.5.7. Reporting

Reporting is unsupported.

3.5.5.8. HTTP

[Upstream options](#) are supported. [Learn how to alter these settings via environment variables](#). Only the **tls** section should be altered. For example:

```
http:
  addr: :5000
  tls:
    certificate: /etc/secrets/registry.crt
    key: /etc/secrets/registry.key
```

3.5.5.9. Notifications

[Upstream options](#) are supported.

Example:

```
notifications:
  endpoints:
    - name: registry
      disabled: false
      url: https://url:port/path
      headers:
        Accept:
          - text/plain
      timeout: 500
      threshold: 5
      backoff: 1000
```

3.5.5.10. Redis

Redis is not supported.

3.5.5.11. Health

[Upstream options](#) are supported. The registry deployment configuration provides an integrated health check at **/healthz**.

3.5.5.12. Proxy

Proxy configuration should not be enabled. This functionality is provided by the [OpenShift Container Platform repository middleware extension](#), **pullthrough: true**.

3.6. KNOWN ISSUES

3.6.1. Overview

The following are the known issues when deploying or using the integrated registry.

3.6.2. Image Push Errors with Scaled Registry Using Shared NFS Volume

When using a scaled registry with a shared NFS volume, you may see one of the following errors during the push of an image:

- **digest invalid: provided digest did not match uploaded content**
- **blob upload unknown**
- **blob upload invalid**

These errors are returned by an internal registry service when Docker attempts to push the image. Its cause originates in the synchronization of file attributes across nodes. Factors such as NFS client side caching, network latency, and layer size can all contribute to potential errors that might occur when pushing an image using the default round-robin load balancing configuration.

You can perform the following steps to minimize the probability of such a failure:


1. Ensure that the **sessionAffinity** of your **docker-registry** service is set to **ClientIP**:

```
$ oc get svc/docker-registry --template='{{.spec.sessionAffinity}}'
```

This should return **ClientIP**, which is the default in recent OpenShift Container Platform versions. If not, change it:

```
$ oc patch svc/docker-registry -p '{"spec":{"sessionAffinity":  
"ClientIP"}}'
```

2. Ensure that the NFS export line of your registry volume on your NFS server has the **no_wdelay** options listed. The **no_wdelay** option prevents the server from delaying writes, which greatly improves read-after-write consistency, a requirement of the registry.



IMPORTANT

Testing shows issues with using the NFS server on RHEL as storage backend for the container registry. This includes the OpenShift Container Registry and Quay. Therefore, using NFS to back PVs used by core services is not recommended.

Other NFS implementations on the marketplace might not have these issues. Contact the individual NFS implementation vendor for more information on any testing that was possibly completed against these OpenShift core components.

3.6.3. Pull of Internally Managed Image Fails with "not found" Error

This error occurs when the pulled image is pushed to an image stream different from the one it is being pulled from. This is caused by re-tagging a built image into an arbitrary image stream:

```
$ oc tag srcimagestream:latest anyproject/pullimagestream:latest
```

And subsequently pulling from it, using an image reference such as:

```
internal.registry.url:5000/anyproject/pullimagestream:latest
```

During a manual Docker pull, this will produce a similar error:

```
Error: image anyproject/pullimagestream:latest not found
```

To prevent this, avoid the tagging of internally managed images completely, or re-push the built image to the desired namespace [manually](#).

3.6.4. Image Push Fails with "500 Internal Server Error" on S3 Storage

There are problems reported happening when the registry runs on S3 storage back-end. Pushing to a Docker registry occasionally fails with the following error:

```
Received unexpected HTTP status: 500 Internal Server Error
```

To debug this, you need to [view the registry logs](#). In there, look for similar error messages occurring at the time of the failed push:

```
time="2016-03-30T15:01:21.22287816-04:00" level=error msg="unknown error
completing upload: driver.Error{DriverName:\"s3\", Enclosed>(*url.Error)
(0xc20901cea0)}" http.request.method=PUT
...
time="2016-03-30T15:01:21.493067808-04:00" level=error msg="response
completed with error" err.code=UNKNOWN err.detail="s3: Put
https://s3.amazonaws.com/oso-tsi-
docker/registry/docker/registry/v2/blobs/sha256/ab/abe5af443833d60cf672e2a
c57589410dddec060ed725d3e676f1865af63d2e2/data: EOF" err.message="unknown
error" http.request.method=PUT
...
time="2016-04-02T07:01:46.056520049-04:00" level=error msg="error putting
into main store: s3: The request signature we calculated does not match
the signature you provided. Check your key and signing method."
http.request.method=PUT
atest
```

If you see such errors, contact your Amazon S3 support. There may be a problem in your region or with your particular bucket.

3.6.5. Image Pruning Fails

If you encounter the following error when pruning images:

```
BLOB
sha256:49638d540b2b62f3b01c388e9d8134c55493b1fa659ed84e97cb59b87a6b8e6c
error deleting blob
```

And your [registry log](#) contains the following information:

-


```
error deleting blob
\"sha256:49638d540b2b62f3b01c388e9d8134c55493b1fa659ed84e97cb59b87a6b8e6c\
\": operation unsupported
```

It means that your [custom configuration file](#) lacks mandatory entries in the [storage section](#), namely **storage:delete:enabled** set to **true**. Add them, re-deploy the registry, and repeat your image pruning operation.

CHAPTER 4. SETTING UP A ROUTER

4.1. ROUTER OVERVIEW

4.1.1. About Routers

There are many ways to [get traffic into the cluster](#). The most common approach is to use the OpenShift Container Platform [router](#) as the ingress point for external traffic destined for [services](#) in your OpenShift Container Platform installation.

OpenShift Container Platform provides and supports the following router plug-ins:

- The [HAProxy template router](#) is the default plug-in. It uses the **openshift3/ose-haproxy-router** image to run an HAProxy instance alongside the template router plug-in inside a container on OpenShift Container Platform. It currently supports HTTP(S) traffic and TLS-enabled traffic via SNI. The router's container listens on the host network interface, unlike most containers that listen only on private IPs. The router proxies external requests for route names to the IPs of actual pods identified by the service associated with the route.
- The [F5 router](#) integrates with an existing **F5 BIG-IP®** system in your environment to synchronize routes. **F5 BIG-IP®** version 11.4 or newer is required in order to have the F5 iControl REST API.



NOTE

The F5 router plug-in is available starting in OpenShift Container Platform 3.0.2.

- [Deploying a Default HAProxy Router](#)
- [Deploying a Custom HAProxy Router](#)
- [Deploying a F5 BIG-IP® Router](#)
- [Configuring the HAProxy Router to Use PROXY Protocol](#)
- [Configuring Route Timeouts](#)

4.1.2. Router Service Account

Before deploying an OpenShift Container Platform cluster, you must have a service account for the router. Starting in OpenShift Container Platform 3.1, a router [service account](#) is automatically created during a quick or advanced installation (previously, this required manual creation). This service account has permissions to a [security context constraint](#) (SCC) that allows it to specify host ports.

4.1.2.1. Permission to Access Labels

When [namespace labels](#) are used, for example in creating [router shards](#), the service account for the router must have **cluster-reader** permission.

```
$ oc adm policy add-cluster-role-to-user \
    cluster-reader \
    system:serviceaccount:default:router
```

With a service account in place, you can proceed to installing [a default HAProxy Router](#), [a customized HAProxy Router](#) or [F5 Router](#).


4.2. USING THE DEFAULT HAPROXY ROUTER

4.2.1. Overview

The `oc adm router` command is provided with the administrator CLI to simplify the tasks of setting up routers in a new installation. If you followed the [quick installation](#), then a default router was automatically created for you. The `oc adm router` command creates the service and deployment configuration objects. Use the `--service-account` option to specify the service account the router will use to contact the master.

The [router service account](#) can be created in advance or created by the `oc adm router --service-account` command.


Every form of communication between OpenShift Container Platform components is secured by TLS and uses various certificates and authentication methods. The `--default-certificate` .pem format file can be supplied or one is created by the `oc adm router` command. When [routes](#) are created, the user can provide route certificates that the router will use when handling the route.



IMPORTANT


When deleting a router, ensure the deployment configuration, service, and secret are deleted as well.

Routers are deployed on specific nodes. This makes it easier for the cluster administrator and external network manager to coordinate which IP address will run a router and which traffic the router will handle. The routers are deployed on specific nodes by using [node selectors](#).



IMPORTANT

Routers use host networking by default, and they directly attach to port 80 and 443 on all interfaces on a host. Restrict routers to hosts where ports 80/443 are available and not being consumed by another service, and set this using [node selectors](#) and the [scheduler configuration](#). As an example, you can achieve this by dedicating infrastructure nodes to run services such as routers.




IMPORTANT

It is recommended to use separate distinct **openshift-router** service account with your router. This can be provided using the `--service-account` flag to the `oc adm router` command.

```
$ oc adm router --dry-run --service-account=router 1
```

1 `--service-account` is the name of a [service account](#) for the **openshift-router**.



IMPORTANT

Router pods created using **oc adm router** have default resource requests that a node must satisfy for the router pod to be deployed. In an effort to increase the reliability of infrastructure components, the default resource requests are used to increase the QoS tier of the router pods above pods without resource requests. The default values represent the observed minimum resources required for a basic router to be deployed and can be edited in the routers deployment configuration and you may want to increase them based on the load of the router.

4.2.2. Creating a Router

The [quick installation](#) process automatically creates a default router. If the router does not exist, run the following to create a router:

```
$ oc adm router <router_name> --replicas=<number> --service-account=router
```

--replicas is usually **1** unless a [high availability](#) configuration is being created.

To find the host IP address of the router:

```
$ oc get po <router-pod> --template={{.status.hostIP}}
```

You can also [use router shards](#) to ensure that the router is filtered to specific namespaces or routes, or [set any environment variables](#) after router creation. In this case create a router for each shard.

4.2.3. Other Basic Router Commands

Checking the Default Router

The default router service account, named **router**, is automatically created during quick and advanced installations. To verify that this account already exists:

```
$ oc adm router --dry-run --service-account=router
```

Viewing the Default Router

To see what the default router would look like if created:

```
$ oc adm router --dry-run -o yaml --service-account=router
```

Deploying the Router to a Labeled Node

To deploy the router to any node(s) that match a specified [node label](#):

```
$ oc adm router <router_name> --replicas=<number> --selector=<label> \
  --service-account=router
```

For example, if you want to create a router named **router** and have it placed on a node labeled with **region=infra**:

```
$ oc adm router router --replicas=1 --selector='region=infra' \
  --service-account=router
```

During [advanced installation](#), the **openshift_router_selector** and

openshift_registry_selector Ansible settings are set to **region=infra** by default. The default router and registry will only be automatically deployed if a node exists that matches the **region=infra** label.

For information on updating labels, see [Updating Labels on Nodes](#).

Multiple instances are created on different hosts according to the [scheduler policy](#).

Using a Different Router Image

To use a different router image and view the router configuration that would be used:

```
$ oc adm router <router_name> -o <format> --images=<image> \
  --service-account=router
```

For example:

```
$ oc adm router region-west -o yaml --images=myrepo/somerouter:mytag \
  --service-account=router
```

4.2.4. Filtering Routes to Specific Routers

Using the **ROUTE_LABELS** environment variable, you can filter routes so that they are used only by specific routers.

For example, if you have multiple routers, and 100 routes, you can attach labels to the routes so that a portion of them are handled by one router, whereas the rest are handled by another.

1. After [creating a router](#), use the **ROUTE_LABELS** environment variable to tag the router:

```
$ oc env dc/<router=name> ROUTE_LABELS="key=value"
```

2. Add the label to the desired routes:

```
oc label route <route=name> key=value
```

3. To verify that the label has been attached to the route, check the route configuration:

```
$ oc describe dc/<route_name>
```

Setting the Maximum Number of Concurrent Connections

The router can handle a maximum number of 20000 connections by default. You can change that limit depending on your needs. Having too few connections prevents the health check from working, which causes unnecessary restarts. You need to configure the system to support the maximum number of connections. The limits shown in **'sysctl fs.nr_open'** and **'sysctl fs.file-max'** must be large enough. Otherwise, HAproxy will not start.

When the router is created, the **--max-connections=** option sets the desired limit:

```
$ oc adm router --max-connections=10000 ....
```

Edit the **ROUTER_MAX_CONNECTIONS** environment variable in the router's deployment configuration to change the value. The router pods are restarted with the new value. If **ROUTER_MAX_CONNECTIONS** is not present, the default value of 20000, is used.



NOTE

A connection includes the frontend and internal backend. This counts as two connections. Be sure to set **ROUTER_MAX_CONNECTIONS** to double than the number of connections you intend to create.

4.2.5. HAProxy Strict SNI

The **HAProxy strict-sni** can be controlled through the **ROUTER_STRICT_SNI** environment variable in the router's deployment configuration. It can also be set when the router is created by using the **--strict-sni** command line option.

```
$ oc adm router --strict-sni
```

4.2.6. TLS Cipher Suites

Set the router **cipher suite** using the **--ciphers** option when creating a router:

```
$ oc adm router --ciphers=modern ....
```

The values are: **modern**, **intermediate**, or **old**, with **intermediate** as the default. Alternatively, a set of ":" separated ciphers can be provided. The ciphers must be from the set displayed by:

```
$ openssl ciphers
```

Alternatively, use the **ROUTER_CIPHERS** environment variable for an existing router.

4.2.7. Highly-Available Routers

You can [set up a highly-available router](#) on your OpenShift Container Platform cluster using IP failover. This setup has multiple replicas on different nodes so the failover software can switch to another replica if the current one fails.

4.2.8. Customizing the Router Service Ports

You can customize the service ports that a template router binds to by setting the environment variables **ROUTER_SERVICE_HTTP_PORT** and **ROUTER_SERVICE_HTTPS_PORT**. This can be done by creating a template router, then editing its deployment configuration.

The following example creates a router deployment with **0** replicas and customizes the router service HTTP and HTTPS ports, then scales it appropriately (to **1** replica).

```
$ oc adm router --replicas=0 --ports='10080:10080,10443:10443'
$ oc set env dc/router ROUTER_SERVICE_HTTP_PORT=10080 \
    ROUTER_SERVICE_HTTPS_PORT=10443
$ oc scale dc/router --replicas=1
```

1

- 1 Ensures exposed ports are appropriately set for routers that use the container networking mode -- **host-network=false**.



IMPORTANT

If you do customize the template router service ports, you will also need to ensure that the nodes where the router pods run have those custom ports opened in the firewall (either via Ansible or **iptables**, or any other custom method that you use via **firewall-cmd**).

The following is an example using **iptables** to open the custom router service ports.

```
$ iptables -A INPUT -p tcp --dport 10080 -j ACCEPT
$ iptables -A INPUT -p tcp --dport 10443 -j ACCEPT
```

4.2.9. Working With Multiple Routers

An administrator can create multiple routers with the same definition to serve the same set of routes. Each router will be on a different [node](#) and will have a different IP address. The network administrator will need to get the desired traffic to each node.

Multiple routers can be grouped to distribute routing load in the cluster and separate tenants to different routers or [shards](#). Each router or shard in the group admits routes based on the selectors in the router. An administrator can create shards over the whole cluster using [ROUTE_LABELS](#). A user can create shards over a namespace (project) by using [NAMESPACE_LABELS](#).

4.2.10. Adding a Node Selector to a Deployment Configuration

Making specific routers deploy on specific nodes requires two steps:

1. Add a [label](#) to the desired node:

```
$ oc label node 10.254.254.28 "router=first"
```

2. Add a node selector to the router deployment configuration:

```
$ oc edit dc <deploymentConfigName>
```

Add the **template.spec.nodeSelector** field with a key and value corresponding to the label:

```
...
template:
  metadata:
    creationTimestamp: null
    labels:
      router: router1
  spec:
    nodeSelector:
      router: "first"
...
```

1

- 1 The key and value are **router** and **first**, respectively, corresponding to the **router=first** label.

4.2.11. Using Router Shards

Router sharding uses **NAMESPACE_LABELS** and **ROUTE_LABELS**, to filter router namespaces and routes. This enables you to distribute subsets of routes over multiple router deployments. By using non-overlapping subsets, you can effectively partition the set of routes. Alternatively, you can define shards comprising overlapping subsets of routes.

By default, a router selects all routes from all [projects \(namespaces\)](#). Sharding involves adding labels to routes or namespaces and label selectors to routers. Each router shard comprises the routes that are selected by a specific set of label selectors or belong to the namespaces that are selected by a specific set of label selectors.



NOTE

The router service account must have the [**cluster reader**] permission set to allow access to labels in other namespaces.

Router Sharding and DNS

Because an external DNS server is needed to route requests to the desired shard, the administrator is responsible for making a separate DNS entry for each router in a project. A router will not forward unknown routes to another router.

Consider the following example:

- Router A lives on host 192.168.0.5 and has routes with ***.foo.com**.
- Router B lives on host 192.168.1.9 and has routes with ***.example.com**.


Separate DNS entries must resolve *.foo.com to the node hosting Router A and *.example.com to the node hosting Router B:

- ***.foo.com A IN 192.168.0.5**
- ***.example.com A IN 192.168.1.9**

Router Sharding Examples

This section describes router sharding using namespace and route labels.

Figure 4.1. Router Sharding Based on Namespace Labels



OPENSIFT_415490_0217

1. Configure a router with a namespace label selector:

```
$ oc set env dc/router NAMESPACE_LABELS="router=r1"
```

2. Because the router has a selector on the namespace, the router will handle routes only for matching namespaces. In order to make this selector match a namespace, label the namespace accordingly:

```
$ oc label namespace default "router=r1"
```

3. Now, if you create a route in the default namespace, the route is available in the default router:

```
$ oc create -f route1.yaml
```

4. Create a new project (namespace) and create a route, **route2**:

```
$ oc new-project p1
$ oc create -f route2.yaml
```

Notice the route is not available in your router.

5. Label namespace **p1** with **router=r1**

```
$ oc label namespace p1 "router=r1"
```

Adding this label makes the route available in the router.

Example

A router deployment **finops-router** is configured with the label selector **NAMESPACE_LABELS="name in (finance, ops)"**, and a router deployment **dev-router** is configured with the label selector **NAMESPACE_LABELS="name=dev"**.

If all routes are in namespaces labeled **name=finance**, **name=ops**, and **name=dev**, then this configuration effectively distributes your routes between the two router deployments.

In the above scenario, sharding becomes a special case of partitioning, with no overlapping subsets. Routes are divided between router shards.

The criteria for route selection govern how the routes are distributed. It is possible to have overlapping subsets of routes across router deployments.

Example

In addition to **finops-router** and **dev-router** in the example above, you also have **devops-router**, which is configured with a label selector **NAMESPACE_LABELS="name in (dev, ops)"**. The routes in namespaces labeled **name=dev** or **name=ops** now are serviced by two different router deployments. This becomes a case in which you have defined overlapping subsets of routes, as illustrated in the procedure in [Router Sharding Based on Namespace Labels](#).

In addition, this enables you to create more complex routing rules, allowing the diversion of higher priority traffic to the dedicated **finops-router** while sending lower priority traffic to **devops-router**.

Router Sharding Based on Route Labels

NAMESPACE_LABELS allows filtering of the projects to service and selecting all the routes from those projects, but you may want to partition routes based on other criteria associated with the routes themselves. The **ROUTE_LABELS** selector allows you to slice-and-dice the routes themselves.

Example

A router deployment **prod-router** is configured with the label selector **ROUTE_LABELS="mydeployment=prod"**, and a router deployment **devtest-router** is configured with the label selector **ROUTE_LABELS="mydeployment in (dev, test)"**. This configuration partitions routes between the two router deployments according to the routes' labels, irrespective of their namespaces.

The example assumes you have all the routes you want to be serviced tagged with a label **"mydeployment=<tag>"**.

4.2.11.1. Creating Router Shards

This section describes an advanced example of router sharding. Suppose there are 26 routes, named **a** — **z**, with various labels:

Possible labels on routes

```

sla=high      geo=east    hw=modest    dept=finance
sla=medium    geo=west    hw=strong    dept=dev
sla=low       dept=ops

```

These labels express the concepts including service level agreement, geographical location, hardware requirements, and department. The routes can have at most one label from each column. Some routes may have other labels or no labels at all.

Name(s)	SLA	Geo	HW	Dept	Other Labels
a	high	east	modest	finance	type=static
b		west	strong		type=dynamic
c, d, e	low		modest		type=static
g—k	medium		strong	dev	
l—s	high		modest	ops	
t—z		west			type=dynamic

Here is a convenience script **mkshard** that illustrates how **oc adm router**, **oc set env**, and **oc scale** can be used together to make a router shard.

```

#!/bin/bash
# Usage: mkshard ID SELECTION-EXPRESSION
id=$1
sel="$2"
router=router-shard-$id
oc adm router $router --replicas=0
dc=dc/router-shard-$id
oc set env $dc ROUTE_LABELS="$sel"
oc scale $dc --replicas=3

```

- 1 The created router has name **router-shard-*<id>***.
- 2 Specify no scaling for now.
- 3 The deployment configuration for the router.
- 4 Set the selection expression using **oc set env**. The selection expression is the value of the **ROUTE_LABELS** environment variable.
- 5 Scale it up.

Running **mkshard** several times creates several routers:

Router	Selection Expression	Routes
router-shard-1	sla=high	a, l — s
router-shard-2	geo=west	b, t — z
router-shard-3	dept=dev	g — k

4.2.11.2. Modifying Router Shards

Because a router shard is a construct [based on labels](#), you can modify either the labels (via **oc label**) or the selection expression (via **oc set env**).

This section extends the example started in the [Creating Router Shards](#) section, demonstrating how to change the selection expression.

Here is a convenience script **modshard** that modifies an existing router to use a new selection expression:

```
#!/bin/bash
# Usage: modshard ID SELECTION-EXPRESSION...
id=$1
shift
router=router-shard-$id
dc=dc/$router
oc scale $dc --replicas=0
oc set env $dc "$@"
oc scale $dc --replicas=3
```

- 1 The modified router has name **router-shard-*<id>***.
- 2 The deployment configuration where the modifications occur.
- 3 Scale it down.
- 4 Set the new selection expression using **oc set env**. Unlike **mkshard** from the [Creating Router Shards](#) section, the selection expression specified as the non-**ID** arguments to **modshard** must include the environment variable name as well as its value.
- 5 Scale it back up.



NOTE

In **modshard**, the **oc scale** commands are not necessary if the [deployment strategy](#) for **router-shard-*<id>*** is **Rolling**.

For example, to expand the department for **router-shard-3** to include **ops** as well as **dev**:

```
$ modshard 3 ROUTE_LABELS='dept in (dev, ops)'
```

The result is that **router-shard-3** now selects routes **g — s** (the combined sets of **g — k** and **l — s**).

This example takes into account that there are only three departments in this example scenario, and specifies a department to leave out of the shard, thus achieving the same result as the preceding example:

```
$ modshard 3 ROUTE_LABELS='dept != finance'
```

This example specifies three comma-separated qualities, and results in only route **b** being selected:

```
$ modshard 3 ROUTE_LABELS='hw=strong,type=dynamic,geo=west'
```

Similarly to **ROUTE_LABELS**, which involves a route's labels, you can select routes based on the labels of the route's namespace using the **NAMESPACE_LABELS** environment variable. This example modifies **router-shard-3** to serve routes whose namespace has the label **frequency=weekly**:

```
$ modshard 3 NAMESPACE_LABELS='frequency=weekly'
```

The last example combines **ROUTE_LABELS** and **NAMESPACE_LABELS** to select routes with label **sla=low** and whose namespace has the label **frequency=weekly**:

```
$ modshard 3 \
  NAMESPACE_LABELS='frequency=weekly' \
  ROUTE_LABELS='sla=low'
```

4.2.12. Finding the Host Name of the Router

When exposing a service, a user can use the same route from the DNS name that external users use to access the application. The network administrator of the external network must make sure the host name resolves to the name of a router that has admitted the route. The user can set up their DNS with a CNAME that points to this host name. However, the user may not know the host name of the router. When it is not known, the cluster administrator can provide it.

The cluster administrator can use the **--router-canonical-hostname** option with the router's canonical host name when creating the router. For example:

```
# oc adm router myrouter --router-canonical-hostname="rtr.example.com"
```

This creates the **ROUTER_CANONICAL_HOSTNAME** environment variable in the router's deployment configuration containing the host name of the router.

For routers that already exist, the cluster administrator can edit the router's deployment configuration and add the **ROUTER_CANONICAL_HOSTNAME** environment variable:

```
spec:
  template:
    spec:
      containers:
      - env:
        - name: ROUTER_CANONICAL_HOSTNAME
          value: rtr.example.com
```

The **ROUTER_CANONICAL_HOSTNAME** value is displayed in the route status for all routers that have

admitted the route. The route status is refreshed every time the router is reloaded.

When a user creates a route, all of the active routers evaluate the route and, if conditions are met, admit it. When a router that defines the **ROUTER_CANONICAL_HOSTNAME** environment variable admits the route, the router places the value in the **routerCanonicalHostname** field in the route status. The user can examine the route status to determine which, if any, routers have admitted the route, select a router from the list, and find the host name of the router to pass along to the network administrator.

```
status:
  ingress:
    conditions:
      lastTransitionTime: 2016-12-07T15:20:57Z
      status: "True"
      type: Admitted
      host: hello.in.mycloud.com
      routerCanonicalHostname: rtr.example.com
      routerName: myrouter
      wildcardPolicy: None
```

oc describe includes the host name when available:

```
$ oc describe route/hello-route3
...
Requested Host: hello.in.mycloud.com exposed on router myroute (host
rtr.example.com) 12 minutes ago
```

Using the above information, the user can ask the DNS administrator to set up a CNAME from the route's host, **hello.in.mycloud.com**, to the router's canonical hostname, **rtr.example.com**. This results in any traffic to **hello.in.mycloud.com** reaching the user's application.

4.2.13. Customizing the Default Routing Subdomain

You can customize the suffix used as the default routing subdomain for your environment by modifying the [master configuration file](#) (the **/etc/origin/master/master-config.yaml** file by default). Routes that do not specify a host name would have one generated using this default routing subdomain.

The following example shows how you can set the configured suffix to **v3.openshift.test**:

```
routingConfig:
  subdomain: v3.openshift.test
```



NOTE

This change requires a restart of the master if it is running.

With the OpenShift Container Platform master(s) running the above configuration, the [generated host name](#) for the example of a route named **no-route-hostname** without a host name added to a namespace **mynamespace** would be:

```
no-route-hostname-mynamespace.v3.openshift.test
```

4.2.14. Forcing Route Host Names to a Custom Routing Subdomain

If an administrator wants to restrict all routes to a specific routing subdomain, they can pass the **--force-subdomain** option to the **oc adm router** command. This forces the router to override any host names specified in a route and generate one based on the template provided to the **--force-subdomain** option.

The following example runs a router, which overrides the route host names using a custom subdomain template **\${name}-\${namespace}.apps.example.com**.

```
$ oc adm router --force-subdomain='${name}-${namespace}.apps.example.com'
```

4.2.15. Using Wildcard Certificates

A TLS-enabled route that does not include a certificate uses the router's default certificate instead. In most cases, this certificate should be provided by a trusted certificate authority, but for convenience you can use the OpenShift Container Platform CA to create the certificate. For example:

```
$ CA=/etc/origin/master
$ oc adm ca create-server-cert --signer-cert=$CA/ca.crt \
  --signer-key=$CA/ca.key --signer-serial=$CA/ca.serial.txt \
  --hostnames='*.cloudapps.example.com' \
  --cert=cloudapps.crt --key=cloudapps.key
```

NOTE

The **oc adm ca create-server-cert** command generates a certificate that is valid for two years. This can be altered with the **--expire-days** option, but for security reasons, it is recommended to not make it greater than this value.

Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

The router expects the certificate and key to be in PEM format in a single file:

```
$ cat cloudapps.crt cloudapps.key $CA/ca.crt > cloudapps.router.pem
```

From there you can use the **--default-cert** flag:

```
$ oc adm router --default-cert=cloudapps.router.pem --service-account=router
```

NOTE

Browsers only consider wildcards valid for subdomains one level deep. So in this example, the certificate would be valid for *a.cloudapps.example.com* but not for *a.b.cloudapps.example.com*.

4.2.16. Manually Redeploy Certificates

To manually redeploy the router certificates:

1. Check to see if a secret containing the default router certificate was added to the router:

■

```
$ oc volumes dc/router
deploymentconfigs/router
secret/router-certs as server-certificate
mounted at /etc/pki/tls/private
```

If the certificate is added, skip the following step and overwrite the secret.

2. Make sure that you have a default certificate directory set for the following variable **DEFAULT_CERTIFICATE_DIR**:

```
$ oc env dc/router --list
DEFAULT_CERTIFICATE_DIR=/etc/pki/tls/private
```

If not, create the directory using the following command:

```
$ oc env dc/router DEFAULT_CERTIFICATE_DIR=/etc/pki/tls/private
```

3. Export the certificate to PEM format:

```
$ cat custom-router.key custom-router.crt custom-ca.crt > custom-
router.crt
```

4. Overwrite or create a router certificate secret:

If the certificate secret was added to the router, overwrite the secret. If not, create a new secret.

To overwrite the secret, run the following command:

```
$ oc secrets new router-certs tls.crt=custom-router.crt
tls.key=custom-router.key -o json --type='kubernetes.io/tls' --
confirm | oc replace -f -
```

To create a new secret, run the following commands:

```
$ oc secrets new router-certs tls.crt=custom-router.crt
tls.key=custom-router.key --type='kubernetes.io/tls' --confirm

$ oc volume dc/router --add --mount-path=/etc/pki/tls/private --
secret-name='router-certs' --name router-certs
```

5. Deploy the router.

```
$ oc rollout latest dc/router
```

4.2.17. Using Secured Routes

Currently, password protected key files are not supported. HAProxy prompts for a password upon starting and does not have a way to automate this process. To remove a passphrase from a keyfile, you can run:

```
# openssl rsa -in <passwordProtectedKey.key> -out <new.key>
```


Here is an example of how to use a secure edge terminated route with TLS termination occurring on the router before traffic is proxied to the destination. The secure edge terminated route specifies the TLS certificate and key information. The TLS certificate is served by the router front end.

First, start up a router instance:

```
# oc adm router --replicas=1 --service-account=router
```

Next, create a private key, csr and certificate for our edge secured route. The instructions on how to do that would be specific to your certificate authority and provider. For a simple self-signed certificate for a domain named **www.example.test**, see the example shown below:

```
# sudo openssl genrsa -out example-test.key 2048
#
# sudo openssl req -new -key example-test.key -out example-test.csr \
  -subj "/C=US/ST=CA/L=Mountain View/O=OS3/OU=Eng/CN=www.example.test"
#
# sudo openssl x509 -req -days 366 -in example-test.csr \
  -signkey example-test.key -out example-test.crt
```

Generate a route using the above certificate and key.

```
$ oc create route edge --service=my-service \
  --hostname=www.example.test \
  --key=example-test.key --cert=example-test.crt
route "my-service" created
```

Look at its definition.

```
$ oc get route/my-service -o yaml
apiVersion: v1
kind: Route
metadata:
  name: my-service
spec:
  host: www.example.test
  to:
    kind: Service
    name: my-service
  tls:
    termination: edge
    key: |
      -----BEGIN PRIVATE KEY-----
      [...]
      -----END PRIVATE KEY-----
    certificate: |
      -----BEGIN CERTIFICATE-----
      [...]
      -----END CERTIFICATE-----
```

Make sure your DNS entry for **www.example.test** points to your router instance(s) and the route to your domain should be available. The example below uses curl along with a local resolver to simulate the DNS lookup:

```
# routerip="4.1.1.1" # replace with IP address of one of your router
instances.
# curl -k --resolve www.example.test:443:$routerip
https://www.example.test/
```

4.2.18. Using Wildcard Routes (for a Subdomain)

The HAProxy router has support for wildcard routes, which are enabled by setting the **ROUTER_ALLOW_WILDCARD_ROUTES** environment variable to **true**. Any routes with a wildcard policy of **Subdomain** that pass the router admission checks will be serviced by the HAProxy router. Then, the HAProxy router exposes the associated service (for the route) per the route's wildcard policy.



IMPORTANT

To change a route's wildcard policy, you must remove the route and recreate it with the updated wildcard policy. Editing only the route's wildcard policy in a route's **.yaml** file does not work.

```
$ oc adm router --replicas=0 ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true
$ oc scale dc/router --replicas=1
```

[Learn how to configure the web console for wildcard routes.](#)

Using a Secure Wildcard Edge Terminated Route

This example reflects TLS termination occurring on the router before traffic is proxied to the destination. Traffic sent to any hosts in the subdomain **example.org** (***.example.org**) is proxied to the exposed service.

The secure edge terminated route specifies the TLS certificate and key information. The TLS certificate is served by the router front end for all hosts that match the subdomain (***.example.org**).

1. Start up a router instance:

```
$ oc adm router --replicas=0 --service-account=router
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true
$ oc scale dc/router --replicas=1
```

2. Create a private key, certificate signing request (CSR), and certificate for the edge secured route.

The instructions on how to do this are specific to your certificate authority and provider. For a simple self-signed certificate for a domain named ***.example.test**, see this example:

```
# sudo openssl genrsa -out example-test.key 2048
#
# sudo openssl req -new -key example-test.key -out example-test.csr \
  -subj "/C=US/ST=CA/L=Mountain View/O=OS3/OU=Eng/CN=*.example.test"
#
# sudo openssl x509 -req -days 366 -in example-test.csr \
  -signkey example-test.key -out example-test.crt
```

3. Generate a wildcard route using the above certificate and key:

```
$ cat > route.yaml <<EOF
apiVersion: v1
kind: Route
metadata:
  name: my-service
spec:
  host: www.example.test
  wildcardPolicy: Subdomain
  to:
    kind: Service
    name: my-service
  tls:
    termination: edge
    key: "$(perl -pe 's/\n/\\n/' example-test.key)"
    certificate: "$(perl -pe 's/\n/\\n/' example-test.cert)"
EOF
$ oc create -f route.yaml
```

Ensure your DNS entry for ***.example.test** points to your router instance(s) and the route to your domain is available.

This example uses **curl** with a local resolver to simulate the DNS lookup:

```
# routerip="4.1.1.1" # replace with IP address of one of your
router instances.
# curl -k --resolve www.example.test:443:$routerip
https://www.example.test/
# curl -k --resolve abc.example.test:443:$routerip
https://abc.example.test/
# curl -k --resolve anyname.example.test:443:$routerip
https://anyname.example.test/
```

For routers that allow wildcard routes (**ROUTER_ALLOW_WILDCARD_ROUTES** set to **true**), there are some caveats to the ownership of a subdomain associated with a wildcard route.

Prior to wildcard routes, ownership was based on the claims made for a host name with the namespace with the oldest route winning against any other claimants. For example, route **r1** in namespace **ns1** with a claim for **one.example.test** would win over another route **r2** in namespace **ns2** for the same host name **one.example.test** if route **r1** was older than route **r2**.

In addition, routes in other namespaces were allowed to claim non-overlapping hostnames. For example, route **rone** in namespace **ns1** could claim **www.example.test** and another route **rtwo** in namespace **d2** could claim **c3po.example.test**.

This is still the case if there are *no* wildcard routes claiming that same subdomain (**example.test** in the above example).

However, a wildcard route needs to claim all of the host names within a subdomain (host names of the form ***.example.test**). A wildcard route's claim is allowed or denied based on whether or not the oldest route for that subdomain (**example.test**) is in the same namespace as the wildcard route. The oldest route can be either a regular route or a wildcard route.

For example, if there is already a route **eldest** that exists in the **ns1** namespace that claimed a host

named **owner.example.test** and, if at a later point in time, a new wildcard route **wildthing** requesting for routes in that subdomain (**example.test**) is added, the claim by the wildcard route will *only* be allowed if it is the same namespace (**ns1**) as the owning route.

The following examples illustrate various scenarios in which claims for wildcard routes will succeed or fail.

In the example below, a router that allows wildcard routes will allow non-overlapping claims for hosts in the subdomain **example.test** as long as a wildcard route has not claimed a subdomain.

```
$ oc adm router ...
$ oc set env dc/router
$ oc project ns1 ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test
$ oc expose service myservice --hostname=aname.example.test
$ oc expose service myservice --hostname=bname.example.test

$ oc project ns2
$ oc expose service anotherservice --hostname=second.example.test
$ oc expose service anotherservice --hostname=cname.example.test

$ oc project othersns
$ oc expose service thirdservice --hostname=emmy.example.test
$ oc expose service thirdservice --hostname=webby.example.test
```

In the example below, a router that allows wildcard routes will not allow the claim for **owner.example.test** or **aname.example.test** to succeed since the owning namespace is **ns1**.

```
$ oc adm router ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test
$ oc expose service myservice --hostname=aname.example.test

$ oc project ns2
$ oc expose service secondservice --hostname=bname.example.test
$ oc expose service secondservice --hostname=cname.example.test

$ # Router will not allow this claim with a different path name `/p1` as
$ # namespace `ns1` has an older route claiming host `aname.example.test`.
$ oc expose service secondservice --hostname=aname.example.test --
path="/p1"

$ # Router will not allow this claim as namespace `ns1` has an older route
$ # claiming host name `owner.example.test`.
$ oc expose service secondservice --hostname=owner.example.test

$ oc project othersns

$ # Router will not allow this claim as namespace `ns1` has an older route
$ # claiming host name `aname.example.test`.
$ oc expose service thirdservice --hostname=aname.example.test
```

In the example below, a router that allows wildcard routes will allow the claim for ``*.example.test` to succeed since the owning namespace is **ns1** and the wildcard route belongs to that same namespace.

```
$ oc adm router ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test

$ # Reusing the route.yaml from the previous example.
$ # spec:
$ #   host: www.example.test
$ #   wildcardPolicy: Subdomain

$ oc create -f route.yaml # router will allow this claim.
```

In the example below, a router that allows wildcard routes will not allow the claim for ``*.example.test` to succeed since the owning namespace is **ns1** and the wildcard route belongs to another namespace **cyclone**.

```
$ oc adm router ...
$ oc set env dc/router
$ oc project ns1 ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test

$ # Switch to a different namespace/project.
$ oc project cyclone

$ # Reusing the route.yaml from a prior example.
$ # spec:
$ #   host: www.example.test
$ #   wildcardPolicy: Subdomain

$ oc create -f route.yaml # router will deny (_NOT_ allow) this claim.
```

Similarly, once a namespace with a wildcard route claims a subdomain, only routes within that namespace can claim any hosts in that same subdomain.

In the example below, once a route in namespace **ns1** with a wildcard route claims subdomain **example.test**, only routes in the namespace **ns1** are allowed to claim any hosts in that same subdomain.

```
$ oc adm router ...
$ oc set env dc/router
$ oc project ns1 ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test

$ oc project othersns

$ # namespace `othersns` is allowed to claim for other.example.test
```

```

$ oc expose service otherservice --hostname=other.example.test

$ oc project ns1

$ # Reusing the route.yaml from the previous example.
$ # spec:
$ #   host: www.example.test
$ #   wildcardPolicy: Subdomain

$ oc create -f route.yaml # Router will allow this claim.

$ # In addition, route in namespace othersns will lose its claim to host
$ # `other.example.test` due to the wildcard route claiming the
subdomain.

$ # namespace `ns1` is allowed to claim for deux.example.test
$ oc expose service mysecondservice --hostname=deux.example.test

$ # namespace `ns1` is allowed to claim for deux.example.test with path
/p1
$ oc expose service mythirdservice --hostname=deux.example.test --
path="/p1"

$ oc project othersns

$ # namespace `othersns` is not allowed to claim for deux.example.test
$ # with a different path '/otherpath'
$ oc expose service otherservice --hostname=deux.example.test --
path="/otherpath"

$ # namespace `othersns` is not allowed to claim for owner.example.test
$ oc expose service yetanotherservice --hostname=owner.example.test

$ # namespace `othersns` is not allowed to claim for unclaimed.example.test
$ oc expose service yetanotherservice --hostname=unclaimed.example.test

```

In the example below, different scenarios are shown, in which the owner routes are deleted and ownership is passed within and across namespaces. While a route claiming host **eldest.example.test** in the namespace **ns1** exists, wildcard routes in that namespace can claim subdomain **example.test**. When the route for host **eldest.example.test** is deleted, the next oldest route **senior.example.test** would become the oldest route and would not affect any other routes. Once the route for host **senior.example.test** is deleted, the next oldest route **junior.example.test** becomes the oldest route and block the wildcard route claimant.

```

$ oc adm router ...
$ oc set env dc/router
$ oc project ns1 ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=eldest.example.test
$ oc expose service seniorservice --hostname=senior.example.test

$ oc project othersns

$ # namespace `othersns` is allowed to claim for other.example.test
$ oc expose service juniorservice --hostname=junior.example.test

```

```

$ oc project ns1

$ # Reusing the route.yaml from the previous example.
$ # spec:
$ #   host: www.example.test
$ #   wildcardPolicy: Subdomain

$ oc create -f route.yaml # Router will allow this claim.

$ # In addition, route in namespace othersns will lose its claim to host
$ # `junior.example.test` due to the wildcard route claiming the
subdomain.

$ # namespace `ns1` is allowed to claim for dos.example.test
$ oc expose service mysecondservice --hostname=dos.example.test

$ # Delete route for host `eldest.example.test`, the next oldest route is
$ # the one claiming `senior.example.test`, so route claims are
unaffected.
$ oc delete route myservice

$ # Delete route for host `senior.example.test`, the next oldest route is
$ # the one claiming `junior.example.test` in another namespace, so claims
$ # for a wildcard route would be affected. The route for the host
$ # `dos.example.test` would be unaffected as there are no other wildcard
$ # claimants blocking it.
$ oc delete route seniorservice

```

4.2.19. Using the Container Network Stack


The OpenShift Container Platform router runs inside a container and the default behavior is to use the network stack of the host (i.e., the node where the router container runs). This default behavior benefits performance because network traffic from remote clients does not need to take multiple hops through user space to reach the target service and container.

Additionally, this default behavior enables the router to get the actual source IP address of the remote connection rather than getting the node's IP address. This is useful for defining ingress rules based on the originating IP, supporting sticky sessions, and monitoring traffic, among other uses.

This host network behavior is controlled by the **--host-network** router command line option, and the default behaviour is the equivalent of using **--host-network=true**. If you wish to run the router with the container network stack, use the **--host-network=false** option when creating the router. For example:

```
$ oc adm router --service-account=router --host-network=false
```

Internally, this means the router container must publish the 80 and 443 ports in order for the external network to communicate with the router.



NOTE

Running with the container network stack means that the router sees the source IP address of a connection to be the NATed IP address of the node, rather than the actual remote IP address.

**NOTE**

On OpenShift Container Platform clusters using [multi-tenant network isolation](#), routers on a non-default namespace with the `--host-network=false` option will load all routes in the cluster, but routes across the namespaces will not be reachable due to network isolation. With the `--host-network=true` option, routes bypass the container network and it can access any pod in the cluster. If isolation is needed in this case, then do not add routes across the namespaces.

4.2.20. Exposing Router Metrics

The [HAProxy router metrics](#) are, by default, exposed or published in [Prometheus format](#) for consumption by external metrics collection and aggregation systems (e.g. Prometheus, statsd). Metrics are also available directly from the [HAProxy router](#) in its own HTML format for viewing in a browser or CSV download. These metrics include the HAProxy native metrics and some controller metrics.

When you create a router using the following command, OpenShift Container Platform makes metrics available in Prometheus format on the stats port, by default 1936.

```
$ oc adm router --service-account=router
```

- To extract the raw statistics in Prometheus format run the following command:

```
curl <user>:<password>@<router_IP>:<STATS_PORT>
```

For example:

```
$ curl admin:sLzdR6SgDJ@10.254.254.35:1936/metrics
```

You can get the information you need to access the metrics from the router service annotations:

```
$ oc edit router service <router-service-name>

apiVersion: v1
kind: Service
metadata:
  annotations:
    prometheus.io/port: "1936"
    prometheus.io/scrape: "true"
    prometheus.openshift.io/password: IImoDqON02
    prometheus.openshift.io/username: admin
```

The **prometheus.io/port** is the stats port, by default 1936. You might need to configure your firewall to permit access. Use the previous user name and password to access the metrics. The path is **/metrics**.

```
$ curl <user>:<password>@<router_IP>:<STATS_PORT>
for example:
$ curl admin:sLzdR6SgDJ@10.254.254.35:1936/metrics
...
# HELP haproxy_backend_connections_total Total number of
connections.
# TYPE haproxy_backend_connections_total gauge
haproxy_backend_connections_total{backend="http",namespace="default"
```



```
,route="hello-route"} 0
haproxy_backend_connections_total{backend="http",namespace="default"
,route="hello-route-alt"} 0
haproxy_backend_connections_total{backend="http",namespace="default"
,route="hello-route01"} 0
...
# HELP haproxy_exporter_server_threshold Number of servers tracked
and the current threshold value.
# TYPE haproxy_exporter_server_threshold gauge
haproxy_exporter_server_threshold{type="current"} 11
haproxy_exporter_server_threshold{type="limit"} 500
...
# HELP haproxy_frontend_bytes_in_total Current total of incoming
bytes.
# TYPE haproxy_frontend_bytes_in_total gauge
haproxy_frontend_bytes_in_total{frontend="fe_no_sni"} 0
haproxy_frontend_bytes_in_total{frontend="fe_sni"} 0
haproxy_frontend_bytes_in_total{frontend="public"} 119070
...
# HELP haproxy_server_bytes_in_total Current total of incoming
bytes.
# TYPE haproxy_server_bytes_in_total gauge
haproxy_server_bytes_in_total{namespace="",pod="",route="",server="f
e_no_sni",service=""} 0
haproxy_server_bytes_in_total{namespace="",pod="",route="",server="f
e_sni",service=""} 0
haproxy_server_bytes_in_total{namespace="default",pod="docker-
registry-5-nk5fz",route="docker-
registry",server="10.130.0.89:5000",service="docker-registry"} 0
haproxy_server_bytes_in_total{namespace="default",pod="hello-rc-
vkjqx",route="hello-route",server="10.130.0.90:8080",service="hello-
svc-1"} 0
...
```

- To get metrics in a browser:

1. Delete the following [environment variables](#) from the router deployment configuration file:

```
$ oc edit dc router

- name: ROUTER_LISTEN_ADDR
  value: 0.0.0.0:1936
- name: ROUTER_METRICS_TYPE
  value: haproxy
```

2. Launch the stats window using the following URL in a browser, where the **STATS_PORT** value is **1936** by default:

```
http://admin:<Password>@<router_IP>:<STATS_PORT>
```

You can get the stats in CSV format by adding **;csv** to the URL:

For example:

```
http://admin:<Password>@<router_IP>:1936;csv
```

To get the router IP, admin name, and password:

```
oc describe pod <router_pod>
```

- To suppress metrics collection:

```
$ oc adm router --service-account=router --stats-port=0
```

4.2.21. Preventing Connection Failures During Restarts

If you connect to the router while the proxy is reloading, there is a small chance that your connection will end up in the wrong network queue and be dropped. The issue is being addressed. In the meantime, it is possible to work around the problem by installing **iptables** rules to prevent connections during the reload window. However, doing so means that the router needs to run with elevated privilege so that it can manipulate **iptables** on the host. It also

means that connections that happen during the reload are temporarily ignored and must retransmit their connection start, lengthening the time it takes to connect, but preventing connection failure.

To prevent this, configure the router to use **iptables** by changing the service account, and setting an environment variable on the router.

Use a Privileged SCC

When creating the router, allow it to use the privileged SCC. This gives the router user the ability to create containers with root privileges on the nodes:

```
$ oc adm policy add-scc-to-user privileged -z router
```

Patch the Router Deployment Configuration to Create a Privileged Container

You can now create privileged containers. Next, configure the router deployment configuration to use the privilege so that the router can set the iptables rules it needs. This patch changes the router deployment configuration so that the container that is created runs as privileged (and therefore gets correct capabilities) and run as root:

```
$ oc patch dc router -p '{"spec":{"template":{"spec":{"containers":[{"name":"router","securityContext":{"privileged":true}},{"securityContext":{"runAsUser": 0}}]}}}'
```

Configure the Router to Use iptables

Set the option on the router deployment configuration:

```
$ oc set env dc/router -c router DROP_SYN_DURING_RESTART=true
```

If you used a non-default name for the router, you must change **dc/router** accordingly.

4.2.22. ARP Cache Tuning for Large-scale Clusters

In OpenShift Container Platform clusters with large numbers of routes (greater than the value of **net.ipv4.neigh.default.gc_thresh3**, which is **65536** by default), you must increase the default values of sysctl variables on each node in the cluster running the router pod to allow more entries in the

ARP cache.

When the problem is occurring, the kernel messages would be similar to the following:

```
[ 1738.811139] net_ratelimit: 1045 callbacks suppressed
[ 1743.823136] net_ratelimit: 293 callbacks suppressed
```

When this issue occurs, the **oc** commands might start to fail with the following error:

```
Unable to connect to the server: dial tcp: lookup <hostname> on <ip>:
<port>: write udp <ip>:<port>-><ip>:<port>: write: invalid argument
```

To verify the actual amount of ARP entries for IPv4, run the following:

```
# ip -4 neigh show nud all | wc -l
```

If the number begins to approach the **net.ipv4.neigh.default.gc_thresh3** threshold, increase the values. Get the current value by running:

```
# sysctl net.ipv4.neigh.default.gc_thresh1
net.ipv4.neigh.default.gc_thresh1 = 128
# sysctl net.ipv4.neigh.default.gc_thresh2
net.ipv4.neigh.default.gc_thresh2 = 512
# sysctl net.ipv4.neigh.default.gc_thresh3
net.ipv4.neigh.default.gc_thresh3 = 1024
```

The following `sysctl` sets the variables to the OpenShift Container Platform current default values.

```
# sysctl net.ipv4.neigh.default.gc_thresh1=8192
# sysctl net.ipv4.neigh.default.gc_thresh2=32768
# sysctl net.ipv4.neigh.default.gc_thresh3=65536
```

To make these settings permanent, [see this document](#).

4.2.23. Protecting Against DDoS Attacks

Add **timeout http-request** to the default HAProxy router image to protect the deployment against distributed denial-of-service (DDoS) attacks (for example, slowloris):

```
# and the haproxy stats socket is available at /var/run/haproxy.stats
global
    stats socket ./haproxy.stats level admin

defaults
    option http-server-close
    mode http
    timeout http-request 5s
    timeout connect 5s 1
    timeout server 10s
    timeout client 30s
```

1 **timeout http-request** is set up to 5 seconds. HAProxy gives a client 5 seconds *to send its whole HTTP request. Otherwise, HAProxy shuts the connection with *an error.

Also, when the environment variable **ROUTER_SLOWLORIS_TIMEOUT** is set, it limits the amount of time a client has to send the whole HTTP request. Otherwise, HAProxy will shut down the connection.

Setting the environment variable allows information to be captured as part of the router's deployment configuration and does not require manual modification of the template, whereas manually adding the HAProxy setting requires you to rebuild the router pod and maintain your router template file.

Using annotations implements basic DDoS protections in the HAProxy template router, including the ability to limit the:

- number of concurrent TCP connections
- rate at which a client can request TCP connections
- rate at which HTTP requests can be made

These are enabled on a per route basis because applications can have extremely different traffic patterns.

Table 4.1. HAProxy Template Router Settings

Setting	Description
<code>haproxy.router.openshift.io/rate-limit-connections</code>	Enables the settings be configured (when set to true , for example).
<code>haproxy.router.openshift.io/rate-limit-connections.concurrent-tcp</code>	The number of concurrent TCP connections that can be made by the same IP address on this route.
<code>haproxy.router.openshift.io/rate-limit-connections.rate-tcp</code>	The number of TCP connections that can be opened by a client IP.
<code>haproxy.router.openshift.io/rate-limit-connections.rate-http</code>	The number of HTTP requests that a client IP can make in a 3-second period.

4.3. DEPLOYING A CUSTOMIZED HAPROXY ROUTER

4.3.1. Overview

The default HAProxy router is intended to satisfy the needs of most users. However, it does not expose all of the capability of HAProxy. Therefore, users may need to modify the router for their own needs.

You may need to implement new features within the application back-ends, or modify the current operation. The router plug-in provides all the facilities necessary to make this customization.

The router pod uses a template file to create the needed HAProxy configuration file. The template file is a [golang template](#). When processing the template, the router has access to OpenShift Container Platform information, including the router's deployment configuration, the set of admitted routes, and some helper functions.

When the router pod starts, and every time it reloads, it creates an HAProxy configuration file, and then it starts HAProxy. The [HAProxy configuration manual](#) describes all of the features of HAProxy and how to construct a valid configuration file.

A [configMap](#) can be used to add the new template to the router pod. With this approach, the router deployment configuration is modified to mount the **configMap** as a volume in the router pod. The **TEMPLATE_FILE** environment variable is set to the full path name of the template file in the router pod.

Alternatively, you can build a custom router image and use it when deploying some or all of your routers. There is no need for all routers to run the same image. To do this, modify the **haproxy-template.config** file, and [rebuild](#) the router image. The new image is pushed to the cluster's Docker repository, and the router's deployment configuration **image:** field is updated with the new name. When the cluster is updated, the image needs to be rebuilt and pushed.

In either case, the router pod starts with the template file.

4.3.2. Obtaining the Router Configuration Template

The HAProxy template file is fairly large and complex. For some changes, it may be easier to modify the existing template rather than writing a complete replacement. You can obtain a **haproxy-config.template** file from a running router by running this on master, referencing the router pod:

```
# oc get po
NAME                                READY    STATUS    RESTARTS   AGE
router-2-40fc3                      1/1      Running   0           11d
# oc rsh router-2-40fc3 cat haproxy-config.template > haproxy-
config.template
# oc rsh router-2-40fc3 cat haproxy.config > haproxy.config
```

Alternatively, you can log onto the node that is running the router:

```
# docker run --rm --interactive=true --tty --entrypoint=cat \
    registry.access.redhat.com/openshift3/ose-haproxy-router:v3.7 haproxy-
config.template
```

The image name is from **docker images**.

Save this content to a file for use as the basis of your customized template. The saved **haproxy.config** shows what is actually running.

4.3.3. Modifying the Router Configuration Template

4.3.3.1. Background

The template is based on the [golang template](#). It can reference any of the environment variables in the router's deployment configuration, any configuration information that is described below, and router provided helper functions.

The structure of the template file mirrors the resulting HAProxy configuration file. As the template is processed, anything not surrounded by **{{" something "}}** is directly copied to the configuration file. Passages that are surrounded by **{{" something "}}** are evaluated. The resulting text, if any, is copied to the configuration file.

4.3.3.2. Go Template Actions

The **define** action names the file that will contain the processed template.

```
{{define "/var/lib/haproxy/conf/haproxy.config"}}pipeline{{end}}
```

Table 4.2. Template Router Functions

Function	Meaning
processEndpointsForAlias(alias ServiceAliasConfig, svc ServiceUnit, action string) []Endpoint	Returns the list of valid endpoints. When action is "shuffle", the order of endpoints is randomized.
env(variable, default ...string) string	Tries to get the named environment variable from the pod. If it is not defined or empty, it returns the optional second argument. Otherwise, it returns an empty string.
matchPattern(pattern, s string) bool	The first argument is a string that contains the regular expression, the second argument is the variable to test. Returns a Boolean value indicating whether the regular expression provided as the first argument matches the string provided as the second argument.
isInteger(s string) bool	Determines if a given variable is an integer.
firstMatch(s string, allowedValues ...string) bool	Compares a given string to a list of allowed strings. Returns first match scanning left to right through the list.
matchValues(s string, allowedValues ...string) bool	Compares a given string to a list of allowed strings. Returns "true" if the string is an allowed value, otherwise returns false.
generateRouteRegexp(hostname, path string, wildcard bool) string	Generates a regular expression matching the route hosts (and paths). The first argument is the host name, the second is the path, and the third is a wildcard Boolean.
genCertificateHostName(hostname string, wildcard bool) string	Generates host name to use for serving/matching certificates. First argument is the host name and the second is the wildcard Boolean.
isTrue(s string) bool	Determines if a given variable contains "true".

These functions are provided by the HAProxy template router plug-in.

4.3.3.3. Router Provided Information

This section reviews the OpenShift Container Platform information that the router makes available to the template. The router configuration parameters are the set of data that the HAProxy router plug-in is given. The fields are accessed by **(dot) .Fieldname**.

The tables below the Router Configuration Parameters expand on the definitions of the various fields. In particular, **.State** has the set of admitted routes.

Table 4.3. Router Configuration Parameters

Field	Type	Description
WorkingDir	string	The directory that files will be written to, defaults to <i>/var/lib/containers/router</i>
State	map[string](ServiceAliasConfig)`	The routes.
ServiceUnits	map[string]ServiceUnit	The service lookup.
DefaultCertificate	string	Full path name to the default certificate in pem format.
PeerEndpoints	`[]Endpoint	Peers.
StatsUser	string	User name to expose stats with (if the template supports it).
StatsPassword	string	Password to expose stats with (if the template supports it).
StatsPort	int	Port to expose stats with (if the template supports it).
BindPorts	bool	Whether the router should bind the default ports.

Table 4.4. Router ServiceAliasConfig (A Route)

Field	Type	Description
Name	string	The user-specified name of the route.
Namespace	string	The namespace of the route.
Host	string	The host name. For example, www.example.com .
Path	string	Optional path. For example, www.example.com/myservice where myservice is the path.

Field	Type	Description
TLSTermination	routeapi.TLSTerminationType	The termination policy for this back-end; drives the mapping files and router configuration.
Certificates	map[string]Certificate	Certificates used for securing this back-end. Keyed by the certificate ID.
Status	ServiceAliasConfigStatus	Indicates the status of configuration that needs to be persisted.
PreferPort	string	Indicates the port the user wants to expose. If empty, a port will be selected for the service.
InsecureEdgeTerminationPolicy	routeapi.InsecureEdgeTerminationPolicyType	Indicates desired behavior for insecure connections to an edge-terminated route: none (or disable), allow , or redirect .
RoutingKeyName	string	Hash of the route + namespace name used to obscure the cookie ID.
IsWildcard	bool	Indicates this service unit needing wildcard support.
Annotations	map[string]string	Annotations attached to this route.
ServiceUnitNames	map[string]int32	Collection of services that support this route, keyed by service name and valued on the weight attached to it with respect to other entries in the map.
ActiveServiceUnits	int	Count of the ServiceUnitNames with a non-zero weight.

The **ServiceAliasConfig** is a route for a service. Uniquely identified by host + path. The default template iterates over routes using `{{range $cfgIdx, $cfg := .State }}`. Within such a `{{range}}` block, the template can refer to any field of the current **ServiceAliasConfig** using `$cfg.Field`.

Table 4.5. Router ServiceUnit

Field	Type	Description
Name	string	Name corresponds to a service name + namespace. Uniquely identifies the ServiceUnit .
EndpointTable	[]Endpoint	Endpoints that back the service. This translates into a final back-end implementation for routers.

ServiceUnit is an encapsulation of a service, the endpoints that back that service, and the routes that point to the service. This is the data that drives the creation of the router configuration files

Table 4.6. Router Endpoint

Field	Type
ID	string
IP	string
Port	string
TargetName	string
PortName	string
IdHash	string
NoHealthCheck	bool

Endpoint is an internal representation of a Kubernetes endpoint.

Table 4.7. Router Certificate, ServiceAliasConfigStatus

Field	Type	Description
Certificate	string	Represents a public/private key pair. It is identified by an ID, which will become the file name. A CA certificate will not have a PrivateKey set.

Field	Type	Description
ServiceAliasConfigStatus	string	Indicates that the necessary files for this configuration have been persisted to disk. Valid values: "saved", "".

Table 4.8. Router Certificate Type

Field	Type	Description
ID	string	
Contents	string	The certificate.
PrivateKey	string	The private key.

Table 4.9. Router TLSTerminationType

Field	Type	Description
TLSTerminationType	string	Dictates where the secure communication will stop.
InsecureEdgeTerminationPolicyType	string	Indicates the desired behavior for insecure connections to a route. While each router may make its own decisions on which ports to expose, this is normally port 80.

TLSTerminationType and **InsecureEdgeTerminationPolicyType** dictate where the secure communication will stop.

Table 4.10. Router TLSTerminationType Values

Constant	Value	Meaning
TLSTerminationEdge	edge	Terminate encryption at the edge router.
TLSTerminationPassthrough	passthrough	Terminate encryption at the destination, the destination is responsible for decrypting traffic.
TLSTerminationReencrypt	reencrypt	Terminate encryption at the edge router and re-encrypt it with a new certificate supplied by the destination.

Table 4.11. Router InsecureEdgeTerminationPolicyType Values

Type	Meaning
Allow	Traffic is sent to the server on the insecure port (default).
Disable	No traffic is allowed on the insecure port.
Redirect	Clients are redirected to the secure port.

None ("") is the same as **Disable**.

4.3.3.4. Annotations

Each route can have annotations attached. Each annotation is just a name and a value.

```
apiVersion: v1
kind: Route
metadata:
  annotations:
    haproxy.router.openshift.io/timeout: 5500ms
[...]
```

The name can be anything that does not conflict with existing Annotations. The value is any string. The string can have multiple tokens separated by a space. For example, **aa bb cc**. The template uses `{{index}}` to extract the value of an annotation. For example:

```
{{ $balanceAlgo := index $cfg.Annotations
"haproxy.router.openshift.io/balance" }}
```

This is an example of how this could be used for mutual client authorization.

```
{{ with $cnList := index $cfg.Annotations "whiteListCertCommonName" }}
  {{ if ne $cnList "" }}
    acl test ssl_c_s_dn(CN) -m str {{ $cnList }}
    http-request deny if !test
  {{ end }}
{{ end }}
```

Then, you can handle the white-listed CNs with this command.

```
$ oc annotate route <route-name> --overwrite whiteListCertCommonName="CN1
CN2 CN3"
```

See [Route-specific Annotations](#) for more information.

4.3.3.5. Environment Variables

The template can use any environment variables that exist in the router pod. The environment variables can be set in the deployment configuration. New environment variables can be added.

They are referenced by the **env** function:

```
{{env "ROUTER_MAX_CONNECTIONS" "20000"}}
```

The first string is the variable, and the second string is the default when the variable is missing or **nil**. When **ROUTER_MAX_CONNECTIONS** is not set or is **nil**, 20000 is used. Environment variables are a map where the key is the environment variable name and the content is the value of the variable.

See [Route-specific Environment variables](#) for more information.

4.3.3.6. Example Usage

Here is a simple template based on the HAProxy template file.

Start with a comment:

```
{{/*  
  Here is a small example of how to work with templates  
  taken from the HAProxy template file.  
*/}}
```

The template can create any number of output files. Use a **define** construct to create an output file. The file name is specified as an argument to **define**, and everything inside the **define** block up to the matching end is written as the contents of that file.

```
{{ define "/var/lib/haproxy/conf/haproxy.config" }}  
global  
{{ end }}
```

The above will copy **global** to the **/var/lib/haproxy/conf/haproxy.config** file, and then close the file.

Set up logging based on environment variables.

```
{{ with (env "ROUTER_SYSLOG_ADDRESS" "") }}  
  log {{.}} {{env "ROUTER_LOG_FACILITY" "local1"}} {{env  
"ROUTER_LOG_LEVEL" "warning"}}  
{{ end }}
```

The **env** function extracts the value for the environment variable. If the environment variable is not defined or **nil**, the second argument is returned.

The **with** construct sets the value of "." (dot) within the **with** block to whatever value is provided as an argument to **with**. The **with** action tests **Dot** for **nil**. If not **nil**, the clause is processed up to the **end**. In the above, assume **ROUTER_SYSLOG_ADDRESS** contains **/var/log/msg**, **ROUTER_LOG_FACILITY** is not defined, and **ROUTER_LOG_LEVEL** contains **info**. The following will be copied to the output file:

```
log /var/log/msg local1 info
```

Each admitted route ends up generating lines in the configuration file. Use **range** to go through the admitted routes:

```
{{ range $cfgIdx, $cfg := .State }}
    backend be_http_{{ $cfgIdx }}
{{ end }}
```

.State is a map of **ServiceAliasConfig**, where the key is the route name. **range** steps through the map and, for each pass, it sets **\$cfgIdx** with the **key**, and sets **`\$cfg** to point to the **ServiceAliasConfig** that describes the route. If there are two routes named **myroute** and **hisroute**, the above will copy the following to the output file:

```
    backend be_http_myroute
    backend be_http_hisroute
```

Route Annotations, **\$cfg.Annotations**, is also a map with the annotation name as the key and the content string as the value. The route can have as many annotations as desired and the use is defined by the template author. The user codes the annotation into the route and the template author customized the HAProxy template to handle the annotation.

The common usage is to index the annotation to get the value.

```
{{ $balanceAlgo := index $cfg.Annotations
    "haproxy.router.openshift.io/balance" }}
```

The index extracts the value for the given annotation, if any. Therefore, **`\$balanceAlgo** will contain the string associated with the annotation or **nil**. As above, you can test for a non-**nil** string and act on it with the **with** construct.

```
{{ with $balanceAlgo }}
    balance $balanceAlgo
{{ end }}
```

Here when **\$balanceAlgo** is not **nil**, **balance \$balanceAlgo** is copied to the output file.

In a second example, you want to set a server timeout based on a timeout value set in an annotation.

```
$value := index $cfg.Annotations "haproxy.router.openshift.io/timeout"
```

The **\$value** can now be evaluated to make sure it contains a properly constructed string. The **matchPattern** function accepts a regular expression and returns **true** if the argument satisfies the expression.

```
matchPattern "[1-9][0-9]*(us|ms|s|m|h|d)?" $value
```

This would accept **5000ms** but not **7y**. The results can be used in a test.

```
{{if (matchPattern "[1-9][0-9]*(us|ms|s|m|h|d)?" $value) }}
    timeout server {{ $value }}
{{ end }}
```

It can also be used to match tokens:

```
matchPattern "roundrobin|leastconn|source" $balanceAlgo
```

Alternatively **matchValues** can be used to match tokens:

```
matchValues $balanceAlgo "roundrobin" "leastconn" "source"
```

4.3.4. Using a ConfigMap to Replace the Router Configuration Template

You can use a [ConfigMap](#) to customize the router instance without rebuilding the router image. The ***haproxy-config.template***, ***reload-haproxy***, and other scripts can be modified as well as creating and modifying router environment variables.

1. Copy the ***haproxy-config.template*** that you want to modify as [described above](#). Modify it as desired.
2. Create a ConfigMap:

```
$ oc create configmap customrouter --from-file=haproxy-
config.template
```

The **customrouter** ConfigMap now contains a copy of the modified ***haproxy-config.template*** file.

3. Modify the router deployment configuration to mount the ConfigMap as a file and point the **TEMPLATE_FILE** environment variable to it. This can be done via **oc set env** and **oc volume** commands, or alternatively by editing the router deployment configuration.

Using oc commands

```
$ oc volume dc/router --add --overwrite \
  --name=config-volume \
  --mount-path=/var/lib/haproxy/conf/custom \
  --source='{"configMap": { "name": "customrouter"}}'
$ oc set env dc/router \
  TEMPLATE_FILE=/var/lib/haproxy/conf/custom/haproxy-
config.template
```

Editing the Router Deployment Configuration

Use **oc edit dc router** to edit the router deployment configuration with a text editor.

```
...
  - name: STATS_USERNAME
    value: admin
  - name: TEMPLATE_FILE 1
    value: /var/lib/haproxy/conf/custom/haproxy-
config.template
  image: openshift/origin-haproxy-routerp
...
  terminationMessagePath: /dev/termination-log
  volumeMounts: 2
    - mountPath: /var/lib/haproxy/conf/custom
      name: config-volume
  dnsPolicy: ClusterFirst
...
  terminationGracePeriodSeconds: 30
```

```

    volumes: 3
    - configMap:
        name: customrouter
        name: config-volume
    ...

```

- 1 In the `spec.container.env` field, add the `TEMPLATE_FILE` environment variable to point to the mounted *haproxy-config.template* file.
- 2 Add the `spec.container.volumeMounts` field to create the mount point.
- 3 Add a new `spec.volumes` field to mention the ConfigMap.

Save the changes and exit the editor. This restarts the router.

4.3.5. Using Stick Tables

The following example customization can be used in a [highly-available routing setup](#) to use stick-tables that synchronize between peers.

Adding a Peer Section

In order to synchronize stick-tables amongst peers you must define a peers section in your HAProxy configuration. This section determines how HAProxy will identify and connect to peers. The plug-in provides data to the template under the `.PeerEndpoints` variable to allow you to easily identify members of the router service. You may add a peer section to the *haproxy-config.template* file inside the router image by adding:

```

{{ if (len .PeerEndpoints) gt 0 }}
peers openshift_peers
  {{ range $endpointID, $endpoint := .PeerEndpoints }}
    peer {{$endpoint.TargetName}} {{$endpoint.IP}}:1937
  {{ end }}
{{ end }}

```

Changing the Reload Script

When using stick-tables, you have the option of telling HAProxy what it should consider the name of the local host in the peer section. When creating endpoints, the plug-in attempts to set the `TargetName` to the value of the endpoint's `TargetRef.Name`. If `TargetRef` is not set, it will set the `TargetName` to the IP address. The `TargetRef.Name` corresponds with the Kubernetes host name, therefore you can add the `-L` option to the `reload-haproxy` script to identify the local host in the peer section.

```

peer_name=$HOSTNAME 1

if [ -n "$old_pid" ]; then
  /usr/sbin/haproxy -f $config_file -p $pid_file -L $peer_name -sf
  $old_pid
else
  /usr/sbin/haproxy -f $config_file -p $pid_file -L $peer_name
fi

```

- 1 Must match an endpoint target name that is used in the peer section.

Modifying Back Ends

Finally, to use the stick-tables within back ends, you can modify the HAProxy configuration to use the stick-tables and peer set. The following is an example of changing the existing back end for TCP connections to use stick-tables:

```

        {{ if eq $cfg.TLSTermination "passthrough" }}
backend be_tcp_{{ $cfgIdx }}
    balance leastconn
    timeout check 5000ms
    stick-table type ip size 1m expire 5m{{ if (len $.PeerEndpoints) gt 0 }}
peers openshift_peers {{ end }}
    stick on src
        {{ range $endpointID, $endpoint :=
$serviceUnit.EndpointTable }}
    server {{ $endpointID }} {{ $endpoint.IP }}:{{ $endpoint.Port }} check inter
5000ms
        {{ end }}
    {{ end }}

```

After this modification, you can [rebuild your router](#).

4.3.6. Rebuilding Your Router

In order to rebuild the router, you need copies of several files that are present on a running router. Make a work directory and copy the files from the router:

```

# mkdir -p myrouter/conf
# cd myrouter
# oc get po
NAME                                READY    STATUS    RESTARTS   AGE
router-2-40fc3                      1/1      Running   0           11d
# oc rsh router-2-40fc3 cat haproxy-config.template > conf/haproxy-
config.template
# oc rsh router-2-40fc3 cat error-page-503.http > conf/error-page-503.http
# oc rsh router-2-40fc3 cat default_pub_keys.pem >
conf/default_pub_keys.pem
# oc rsh router-2-40fc3 cat ../Dockerfile > Dockerfile
# oc rsh router-2-40fc3 cat ../reload-haproxy > reload-haproxy

```

You can edit or replace any of these files. However, ***conf/haproxy-config.template*** and ***reload-haproxy*** are the most likely to be modified.

After updating the files:

```

# docker build -t openshift/origin-haproxy-router-myversion .
# docker tag openshift/origin-haproxy-router-myversion
172.30.243.98:5000/openshift/haproxy-router-myversion 1
# docker push 172.30.243.98:5000/openshift/origin-haproxy-router-pc:latest
2

```


- 1 Tag the version with the repository. In this case the repository is **172.30.243.98:5000**.
- 2 Push the tagged version to the repository. It may be necessary to **docker login** to the repository first.

To use the new router, edit the router deployment configuration either by changing the **image:** string or by adding the **--images=<repo>/<image>:<tag>** flag to the **oc adm router** command.

When debugging the changes, it is helpful to set **imagePullPolicy: Always** in the deployment configuration to force an image pull on each pod creation. When debugging is complete, you can change it back to **imagePullPolicy: IfNotPresent** to avoid the pull on each pod start.

4.4. CONFIGURING THE HAPROXY ROUTER TO USE THE PROXY PROTOCOL

4.4.1. Overview

By default, the HAProxy router expects incoming connections to unsecure, edge, and re-encrypt routes to use HTTP. However, you can configure the router to expect incoming requests by using [the PROXY protocol](#) instead. This topic describes how to configure the HAProxy router and an external load balancer to use the PROXY protocol.

4.4.2. Why Use the PROXY Protocol?

When an intermediary service such as a proxy server or load balancer forwards an HTTP request, it appends the source address of the connection to the request's "Forwarded" header in order to provide this information to subsequent intermediaries and to the back-end service to which the request is ultimately forwarded. However, if the connection is encrypted, intermediaries cannot modify the "Forwarded" header. In this case, the HTTP header will not accurately communicate the original source address when the request is forwarded.

To solve this problem, some load balancers encapsulate HTTP requests using the PROXY protocol as an alternative to simply forwarding HTTP. Encapsulation enables the load balancer to add information to the request without modifying the forwarded request itself. In particular, this means that the load balancer can communicate the source address even when forwarding an encrypted connection.

The HAProxy router can be configured to accept the PROXY protocol and decapsulate the HTTP request. Because the router terminates encryption for edge and re-encrypt routes, the router can then update the "Forwarded" HTTP header (and related HTTP headers) in the request, appending any source address that is communicated using the PROXY protocol.



WARNING

The PROXY protocol and HTTP are incompatible and cannot be mixed. If you use a load balancer in front of the router, both must use either the PROXY protocol or HTTP. Configuring one to use one protocol and the other to use the other protocol will cause routing to fail.

4.4.3. Using the PROXY Protocol

By default, the HAProxy router does not use the PROXY protocol. The router can be configured using the **ROUTER_USE_PROXY_PROTOCOL** environment variable to expect the PROXY protocol for incoming connections:

Enable the PROXY Protocol

```
$ oc env dc/router ROUTER_USE_PROXY_PROTOCOL=true
```

Set the variable to any value other than **true** or **TRUE** to disable the PROXY protocol:

Disable the PROXY Protocol

```
$ oc env dc/router ROUTER_USE_PROXY_PROTOCOL=false
```

If you enable the PROXY protocol in the router, you must configure your load balancer in front of the router to use the PROXY protocol as well. Following is an example of configuring Amazon's Elastic Load Balancer (ELB) service to use the PROXY protocol. This example assumes that ELB is forwarding ports 80 (HTTP), 443 (HTTPS), and 5000 (for the image registry) to the router running on one or more EC2 instances.

Configure Amazon ELB to Use the PROXY Protocol

1. To simplify subsequent steps, first set some shell variables:

```
$ lb='infra-lb' 1
$ instances=( 'i-079b4096c654f563c' ) 2
$ secgroups=( 'sg-e1760186' ) 3
$ subnets=( 'subnet-cf57c596' ) 4
```

- 1** The name of your ELB.
- 2** The instance or instances on which the router is running.
- 3** The security group or groups for this ELB.
- 4** The subnet or subnets for this ELB.

2. Next, create the ELB with the appropriate listeners, security groups, and subnets.



NOTE

You must configure all listeners to use the TCP protocol, not the HTTP protocol.

```
$ aws elb create-load-balancer --load-balancer-name "$lb" \
  --listeners \
    'Protocol=TCP,LoadBalancerPort=80,InstanceProtocol=TCP,InstancePort=80' \
    'Protocol=TCP,LoadBalancerPort=443,InstanceProtocol=TCP,InstancePort=5000'
```

```

=443' \

'Protocol=TCP,LoadBalancerPort=5000,InstanceProtocol=TCP,InstancePort=5000' \
  --security-groups $secgroups \
  --subnets $subnets
{
  "DNSName": "infra-lb-2006263232.us-east-1.elb.amazonaws.com"
}

```

3. Register your router instance or instances with the ELB:

```

$ aws elb register-instances-with-load-balancer --load-balancer-name "$lb" \
  --instances $instances
{
  "Instances": [
    {
      "InstanceId": "i-079b4096c654f563c"
    }
  ]
}

```

4. Configure the ELB's health check:

```

$ aws elb configure-health-check --load-balancer-name "$lb" \
  --health-check
'Target=HTTP:1936/healthz,Interval=30,UnhealthyThreshold=2,HealthyThreshold=2,Timeout=5'
{
  "HealthCheck": {
    "HealthyThreshold": 2,
    "Interval": 30,
    "Target": "HTTP:1936/healthz",
    "Timeout": 5,
    "UnhealthyThreshold": 2
  }
}

```

5. Finally, create a load-balancer policy with the **ProxyProtocol** attribute enabled, and configure it on the ELB's TCP ports 80 and 443:

```

$ aws elb create-load-balancer-policy --load-balancer-name "$lb" \
  --policy-name "${lb}-ProxyProtocol-policy" \
  --policy-type-name 'ProxyProtocolPolicyType' \
  --policy-attributes
'AttributeName=ProxyProtocol,AttributeValue=true'
$ for port in 80 443
do
  aws elb set-load-balancer-policies-for-backend-server \
    --load-balancer-name "$lb" \
    --instance-port "$port" \
    --policy-names "${lb}-ProxyProtocol-policy"
done

```

Verify the Configuration

You can examine the load balancer as follows to verify that the configuration is correct:

```
$ aws elb describe-load-balancers --load-balancer-name "$lb" |
jq '.LoadBalancerDescriptions| [.]|.ListenerDescriptions|'
[
  [
    {
      "Listener": {
        "InstancePort": 80,
        "LoadBalancerPort": 80,
        "Protocol": "TCP",
        "InstanceProtocol": "TCP"
      },
      "PolicyNames": ["infra-lb-ProxyProtocol-policy"] 1
    },
    {
      "Listener": {
        "InstancePort": 443,
        "LoadBalancerPort": 443,
        "Protocol": "TCP",
        "InstanceProtocol": "TCP"
      },
      "PolicyNames": ["infra-lb-ProxyProtocol-policy"] 2
    },
    {
      "Listener": {
        "InstancePort": 5000,
        "LoadBalancerPort": 5000,
        "Protocol": "TCP",
        "InstanceProtocol": "TCP"
      },
      "PolicyNames": [] 3
    }
  ]
]
```

1 The listener for TCP port 80 should have the policy for using the PROXY protocol.

2 The listener for TCP port 443 should have the same policy.

3 The listener for TCP port 5000 should **not** have the policy.

Alternatively, if you already have an ELB configured, but it is not configured to use the PROXY protocol, you will need to change the existing listener for TCP port 80 to use the TCP protocol instead of HTTP (TCP port 443 should already be using the TCP protocol):

```
$ aws elb delete-load-balancer-listeners --load-balancer-name "$lb" \
--load-balancer-ports 80
$ aws elb create-load-balancer-listeners --load-balancer-name "$lb" \
--listeners
'Protocol=TCP,LoadBalancerPort=80,InstanceProtocol=TCP,InstancePort=80'
```

Verify the Protocol Updates

Verify that the protocol has been updated as follows:

```
$ aws elb describe-load-balancers --load-balancer-name "$lb" |
jq '[.LoadBalancerDescriptions[]|.ListenerDescriptions]'
[
  [
    {
      "Listener": {
        "InstancePort": 443,
        "LoadBalancerPort": 443,
        "Protocol": "TCP",
        "InstanceProtocol": "TCP"
      },
      "PolicyNames": []
    },
    {
      "Listener": {
        "InstancePort": 5000,
        "LoadBalancerPort": 5000,
        "Protocol": "TCP",
        "InstanceProtocol": "TCP"
      },
      "PolicyNames": []
    },
    {
      "Listener": {
        "InstancePort": 80,
        "LoadBalancerPort": 80,
        "Protocol": "TCP", 1
        "InstanceProtocol": "TCP"
      },
      "PolicyNames": []
    }
  ]
]
```

1 All listeners, including the listener for TCP port 80, should be using the TCP protocol.

Then, create a load-balancer policy and add it to the ELB as described in Step 5 above.

4.5. USING THE F5 ROUTER PLUG-IN


4.5.1. Overview



NOTE

The F5 router plug-in is available starting in OpenShift Container Platform 3.0.2.

The F5 router plug-in is provided as a container image and run as a pod, just like the [default HAProxy router](#).



IMPORTANT

Support relationships between F5 and Red Hat provide a full scope of support for F5 integration. F5 provides support for the **F5 BIG-IP®** product. Both F5 and Red Hat jointly support the integration with Red Hat OpenShift. While Red Hat helps with bug fixes and feature enhancements, all get communicated to F5 Networks where they are managed as part of their development cycles.

4.5.2. Prerequisites and Supportability

When deploying the F5 router plug-in, ensure you meet the following requirements:

- A F5 host IP with:
 - Credentials for API access
 - SSH access via a private key
- An F5 user with Advanced Shell access
- A virtual server for HTTP routes:
 - *HTTP profile* must be *http*.
- A virtual server with HTTP profile routes:
 - *HTTP profile* must be *http*
 - *SSL Profile (client)* must be *clientssl*
 - *SSL Profile (server)* must be *serverssl*
- For edge integration (not recommended):
 - A working ramp node
 - A working tunnel to the ramp node
- For native integration:
 - A host-internal IP capable of communicating with all nodes on the port 4789/UDP
 - The sdn-services add-on license installed on the F5 host.

OpenShift Container Platform supports only the following **F5 BIG-IP®** versions:

- 11.x
- 12.x

IMPORTANT

The following features are not supported with **F5 BIG-IP®**:

- Wildcard routes together with re-encrypt routes - you must supply a certificate and a key in the route. If you provide a certificate, a key, and a certificate authority (CA), the CA is never used.
- A pool is created for all services, even for the ones with no associated route.
- [Idling applications](#)
- Unencrypted HTTP traffic in *redirect* mode, with edge TLS termination. (**insecureEdgeTerminationPolicy: Redirect**)
- Sharding, that is, having multiple **vservers** on the F5.
- SSL cipher (**ROUTER_CIPHERS=modern/old**)
- Customizing the endpoint health checks for time-intervals and the type of checks.
- Serving F5 metrics by using a metrics server.
- Specifying a different target port (**PreferPort/TargetPort**) rather than the ones specified in the service.
- Customizing the source IP whitelists, that is, allowing traffic for a route only from specific IP addresses.
- Customizing timeout values, such as **max connect time**, or **tcp FIN timeout**.
- HA mode for the **F5 BIG-IP®**.

4.5.2.1. Configuring the Virtual Servers

As a prerequisite to working with the **openshift-F5** integrated router, two virtual servers (one virtual server each for HTTP and HTTPS profiles, respectively) need to be set up in the **F5 BIG-IP®** appliance.

To set up a virtual server in the **F5 BIG-IP®** appliance, follow the [instructions from F5](#).

While creating the virtual server, ensure the following settings are in place:

- For the HTTP server, set the **ServicePort** to **'http'/80**.
- For the HTTPS server, set the **ServicePort** to **'https'/443**.
- In the basic configuration, set the HTTP profile to **/Common/http** for both of the virtual servers.
- For the HTTPS server, create a default **client-ssl** profile and select it for the **SSL Profile (Client)**.
 - To create the default client SSL profile, follow the [instructions from F5](#), especially the **Configuring the fallback (default) client SSL profile** section, which discusses that the certificate/key pair is the default that will be served in the case that custom certificates are not provided for a route or server name.

4.5.3. Deploying the F5 Router



IMPORTANT

The F5 router must be run in privileged mode, because route certificates are copied using the **scp** command:

```
$ oc adm policy remove-scc-from-user hostnetwork -z router
$ oc adm policy add-scc-to-user privileged -z router
```

Deploy the F5 router with the **oc adm router** command, but provide additional flags (or environment variables) specifying the following parameters for the **F5 BIG-IP®** host:

Flag	Description
--type=f5-router	Specifies that an F5 router should be launched (the default --type is haproxy-router).
--external-host	Specifies the F5 BIG-IP® host's management interface's host name or IP address.
--external-host-username	Specifies the F5 BIG-IP® user name (typically admin). The F5 BIG-IP user account must have access to the Advanced Shell (Bash) on the F5 BIG-IP system.
--external-host-password	Specifies the F5 BIG-IP® password.
--external-host-http-vserver	Specifies the name of the F5 virtual server for HTTP connections. This must be configured by the user prior to launching the router pod.
--external-host-https-vserver	Specifies the name of the F5 virtual server for HTTPS connections. This must be configured by the user prior to launching the router pod.
--external-host-private-key	Specifies the path to the SSH private key file for the F5 BIG-IP® host. Required to upload and delete key and certificate files for routes.
--external-host-insecure	A Boolean flag that indicates that the F5 router should skip strict certificate verification with the F5 BIG-IP® host.
--external-host-partition-path	Specifies the F5 BIG-IP® partition path (the default is /Common).

For example:

```
$ oc adm router \
  --type=f5-router \
  --external-host=10.0.0.2 \
  --external-host-username=admin \
  --external-host-password=mypassword \
  --external-host-http-vserver=ose-vserver \
  --external-host-https-vserver=https-ose-vserver \
  --external-host-private-key=/path/to/key \
  --host-network=false \
  --service-account=router
```

As with the HAProxy router, the **oc adm router** command creates the service and deployment configuration objects, and thus the replication controllers and pod(s) in which the F5 router itself runs. The replication controller restarts the F5 router in case of crashes. Because the F5 router is watching routes, endpoints, and nodes and configuring **F5 BIG-IP®** accordingly, running the F5 router in this way, along with an appropriately configured **F5 BIG-IP®** deployment, should satisfy high-availability requirements.

4.5.4. F5 Router Partition Paths

Partition paths allow you to store your OpenShift Container Platform routing configuration in a custom **F5 BIG-IP®** administrative partition, instead of the default **/Common** partition. You can use custom administrative partitions to secure **F5 BIG-IP®** environments. This means that an OpenShift Container Platform-specific configuration stored in **F5 BIG-IP®** system objects reside within a logical container, allowing administrators to define access control policies on that specific administrative partition.

See the [F5 BIG-IP® documentation](#) for more information about administrative partitions.

To configure your OpenShift Container Platform for partition paths:

1. Optionally, perform some cleaning steps:
 - a. Ensure F5 is configured to be able to switch to the **/Common** and **/Custom** paths.
 - b. Delete the static FDB of **vxlan5000**. See the [F5 BIG-IP® documentation](#) for more information.
2. [Configure a virtual server](#) for the custom partition.
3. Deploy the F5 router using the **--external-host-partition-path** flag to specify a partition path:

```
$ oc adm router --external-host-partition-path=/OpenShift/zone1 ...
```

4.5.5. Setting Up F5 Native Integration



NOTE

This section reviews how to set up F5 native integration with OpenShift Container Platform. The concepts of F5 appliance and OpenShift Container Platform connection and data flow of F5 native integration are discussed in the [F5 Native Integration](#) section.

**NOTE**

Only **F5 BIG-IP®** appliance version 12.x and above works with the native integration presented in this section. You also need sdn-services add-on license for the integration to work properly. For version 11.x, follow the instructions to set up a [ramp node](#).

As of OpenShift Container Platform version 3.4, using native integration of F5 with OpenShift Container Platform does not require configuring a ramp node for F5 to be able to reach the pods on the overlay network as created by OpenShift SDN.

The F5 controller pod needs to be launched with enough information so that it can successfully directly connect to pods.

1. Create a ghost **hostsubnet** on the OpenShift Container Platform cluster:

```
$ cat > f5-hostsubnet.yaml << EOF
{
  "kind": "HostSubnet",
  "apiVersion": "v1",
  "metadata": {
    "name": "openshift-f5-node",
    "annotations": {
      "pod.network.openshift.io/assign-subnet": "true",
      "pod.network.openshift.io/fixed-vnid-host": "0" 1
    }
  },
  "host": "openshift-f5-node",
  "hostIP": "10.3.89.213" 2
} EOF
$ oc create -f f5-hostsubnet.yaml
```

- 1 Make F5 global.
- 2 The internal IP of the F5 appliance.

2. Determine the subnet allocated for the ghost **hostsubnet** just created:

```
$ oc get hostsubnets
```

NAME	HOST	HOST IP
SUBNET		
openshift-f5-node	openshift-f5-node	10.3.89.213
10.131.0.0/23		
openshift-master-node	openshift-master-node	172.17.0.2
10.129.0.0/23		
openshift-node-1	openshift-node-1	172.17.0.3
10.128.0.0/23		
openshift-node-2	openshift-node-2	172.17.0.4
10.130.0.0/23		

3. Check the **SUBNET** for the newly created **hostsubnet**. In this example, **10.131.0.0/23**.
4. Get the entire pod network's CIDR:

```
$ oc get clusternetwork
```

This value will be something like **10.128.0.0/14**, noting the mask (**14** in this example).

5. To construct the gateway address, pick any IP address from the **hostsubnet** (for example, **10.131.0.5**). Use the mask of the pod network (**14**). The gateway address becomes: **10.131.0.5/14**.
6. Launch the F5 controller pod, following [these instructions](#). Additionally, allow the access to 'node' cluster resource for the service account and use the two new additional options for VXLAN native integration.

```
$ # Add policy to allow router to access nodes using the sdn-reader
role
$ oc adm policy add-cluster-role-to-user system:sdn-reader
system:serviceaccount:default:router
$ # Launch the router pod with vxlan-gw and F5's internal IP as
extra arguments
$ #--external-host-internal-ip=10.3.89.213
$ #--external-host-vxlan-gw=10.131.0.5/14
$ oc adm router \
  --type=f5-router \
  --external-host=10.3.89.90 \
  --external-host-username=admin \
  --external-host-password=mypassword \
  --external-host-http-vserver=ose-vserver \
  --external-host-https-vserver=https-ose-vserver \
  --external-host-private-key=/path/to/key \
  --service-account=router \
  --host-network=false \
  --external-host-internal-ip=10.3.89.213 \
  --external-host-vxlan-gw=10.131.0.5/14
```



NOTE

The **external-host-username** is a **F5 BIG-IP** user account with access to the Advanced Shell (Bash) on the F5 BIG-IP system.

The F5 setup is now ready, without the need to set up the ramp node.

CHAPTER 5. MASTER AND NODE CONFIGURATION

5.1. OVERVIEW

The **openshift start** command is used to launch OpenShift Container Platform servers. The command and its subcommands (**master** to launch a [master server](#) and **node** to launch a [node server](#)) all take a limited set of arguments that are sufficient for launching servers in a development or experimental environment.

However, these arguments are insufficient to describe and control the full set of configuration and security options that are necessary in a production environment. To provide those options, it is necessary to use the dedicated master and node configuration files.

[Master configuration files](#) and [node configuration files](#) are fully specified with no default values. Therefore, any empty value indicates that you want to start up with an empty value for that parameter. This makes it easy to reason about exactly what your configuration is, but it also makes it difficult to remember all of the options to specify. To make this easier, the configuration files can be created with the **--write-config** option and then used with the **--config** option.

5.2. MASTER CONFIGURATION FILES

This section reviews parameters mentioned in the **master-config.yaml** file.

You can [create a new master configuration file](#) to see the valid options for your installed version of OpenShift Container Platform.



IMPORTANT

Whenever you modify the **master-config.yaml** file, you must restart the master for the changes to take effect. See [Restarting OpenShift Container Platform services](#).

5.2.1. Admission Control Configuration

Table 5.1. Admission Control Configuration Parameters

Parameter Name	Description
AdmissionConfig	Contains admission control plug-in configuration.
APIServerArguments	Key-value pairs that will be passed directly to the Kube API server that match the API servers' command line arguments. These are not migrated, but if you reference a value that does not exist the server will not start. These values may override other settings in KubernetesMasterConfig , which may cause invalid configurations.
ControllerArguments	Key-value pairs that will be passed directly to the Kube controller manager that match the controller manager's command line arguments. These are not migrated, but if you reference a value that does not exist the server will not start. These values may override other settings in KubernetesMasterConfig , which may cause invalid configurations.

Parameter Name	Description
DefaultAdmissionConfig	Used to enable or disable various admission plug-ins. When this type is present as the configuration object under pluginConfig and if the admission plug-in supports it, this will cause an off by default admission plug-in to be enabled.
PluginConfig	Allows specifying a configuration file per admission control plug-in.
PluginOrderOverride	A list of admission control plug-in names that will be installed on the master. Order is significant. If empty, a default list of plug-ins is used.
SchedulerArguments	Key-value pairs that will be passed directly to the Kube scheduler that match the scheduler's command line arguments. These are not migrated, but if you reference a value that does not exist the server will not start. These values may override other settings in KubernetesMasterConfig , which may cause invalid configurations.

5.2.2. Asset Configuration

Table 5.2. Asset Configuration Parameters

Parameter Name	Description
AssetConfig	Holds the necessary configuration options for serving assets.
corsAllowedOrigins	To access the API server from a web application using a different host name, you must whitelist that host name by specifying corsAllowedOrigins in the configuration field or by specifying the --cors-allowed-origins option on openshift start . No pinning or escaping is done to the value. See Web Console for example usage.
DisabledFeatures	A list of features that should not be started. You will likely want to set this as null . It is very unlikely that anyone will want to manually disable features and that is not encouraged.
Extensions	Files to serve from the asset server file system under a subcontext.
ExtensionDevelopment	When set to true , tells the asset server to reload extension scripts and stylesheets for every request rather than only at startup. It lets you develop extensions without having to restart the server for every change.
ExtensionProperties	Key- (string) and value- (string) pairs that will be injected into the console under the global variable OPENSIFT_EXTENSION_PROPERTIES .
ExtensionScripts	File paths on the asset server files to load as scripts when the web console loads.

Parameter Name	Description
ExtensionStylesheets	File paths on the asset server files to load as style sheets when the web console loads.
LoggingPublicURL	The public endpoint for logging (optional).
LogoutURL	An optional, absolute URL to redirect web browsers to after logging out of the web console. If not specified, the built-in logout page is shown.
MasterPublicURL	How the web console can access the OpenShift Container Platform server.
MetricsPublicURL	The public endpoint for metrics (optional).
PublicURL	URL of the the asset server.

5.2.3. Authentication and Authorization Configuration

Table 5.3. Authentication and Authorization Parameters

Parameter Name	Description
authConfig	Holds authentication and authorization configuration options.
AuthenticationCacheSize	Indicates how many authentication results should be cached. If 0, the default cache size is used.
AuthorizationCacheTTL	Indicates how long an authorization result should be cached. It takes a valid time duration string (e.g. "5m"). If empty, you get the default timeout. If zero (e.g. "0m"), caching is disabled.

5.2.4. Controller Configuration

Table 5.4. Controller Configuration Parameters

Parameter Name	Description
Controllers	List of the controllers that should be started. If set to none , no controllers will start automatically. The default value is * which will start all controllers. When using * , you may exclude controllers by prepending a - in front of their name. No other values are recognized at this time.
ControllerLeaseTTL	Enables controller election, instructing the master to attempt to acquire a lease before controllers start and renewing it within a number of seconds defined by this value. Setting this value non-negative forces pauseControllers=true . This value defaults off (0, or omitted) and controller election can be disabled with -1.

Parameter Name	Description
PauseControllers	Instructs the master to not automatically start controllers, but instead to wait until a notification to the server is received before launching them.

5.2.5. etcd Configuration

Table 5.5. etcd Configuration Parameters

Parameter Name	Description
Address	The advertised host:port for client connections to etcd.
etcdClientInfo	Contains information about how to connect to etcd.
etcdConfig	Holds the necessary configuration options for connecting with an etcd database.
etcdStorageConfig	Contains information about how API resources are stored in etcd. These values are only relevant when etcd is the backing store for the cluster.
KubernetesStoragePrefix	The path within etcd that the Kubernetes resources will be rooted under. This value, if changed, will mean existing objects in etcd will no longer be located. The default value is kubernetes.io .
KubernetesStorageVersion	The API version that Kubernetes resources in etcd should be serialized to. This value should not be advanced until all clients in the cluster that read from etcd have code that allows them to read the new version.
OpenShiftStoragePrefix	The path within etcd that the OpenShift Container Platform resources will be rooted under. This value, if changed, will mean existing objects in etcd will no longer be located. The default value is openshift.io .
OpenShiftStorageVersion	API version that OS resources in etcd should be serialized to. This value should not be advanced until all clients in the cluster that read from etcd have code that allows them to read the new version.
PeerAddress	The advertised host:port for peer connections to etcd .
PeerServingInfo	Describes how to start serving the etcd peer.
ServingInfo	Describes how to start serving the etcd master.
StorageDir	The path to the etcd storage directory.

5.2.6. Grant Configuration

Table 5.6. Grant Configuration Parameters

Parameter Name	Description
GrantConfig	Describes how to handle grants.
GrantHandlerAuto	Auto-approves client authorization grant requests.
GrantHandlerDeny	Auto-denies client authorization grant requests.
GrantHandlerPrompt	Prompts the user to approve new client authorization grant requests.
Method	<p>Determines the default strategy to use when an OAuth client requests a grant. This method will be used only if the specific OAuth client does not provide a strategy of their own. Valid grant handling methods are:</p> <ul style="list-style-type: none"> • auto: always approves grant requests, useful for trusted clients • prompt: prompts the end user for approval of grant requests, useful for third-party clients • deny: always denies grant requests, useful for black-listed clients

5.2.7. Image Configuration

Table 5.7. Image Configuration Parameters

Parameter Name	Description
Format	The format of the name to be built for the system component.
Latest	Determines if the latest tag will be pulled from the registry.

5.2.8. Image Policy Configuration

Table 5.8. Image Policy Configuration Parameters

Parameter Name	Description
DisableScheduledImport	Allows scheduled background import of images to be disabled.
MaxImagesBulkImportedPerRepository	Controls the number of images that are imported when a user does a bulk import of a Docker repository. This number defaults to 5 to prevent users from importing large numbers of images accidentally. Set -1 for no limit.
MaxScheduledImageImportsPerMinute	The maximum number of scheduled image streams that will be imported in the background per minute. The default value is 60.

Parameter Name	Description
ScheduledImageImportMinimumIntervalSeconds	The minimum number of seconds that can elapse between when image streams scheduled for background import are checked against the upstream repository. The default value is 15 minutes.
AllowedRegistriesForImport	Limits the docker registries that normal users may import images from. Set this list to the registries that you trust to contain valid Docker images and that you want applications to be able to import from. Users with permission to create Images or ImageStreamMappings via the API are not affected by this policy - typically only administrators or system integrations will have those permissions.
InternalRegistryHostname	Sets the hostname for the default internal image registry. The value must be in hostname[:port] format. For backward compatibility, users can still use OPENSIFT_DEFAULT_REGISTRY environment variable but this setting overrides the environment variable. When this is set, the internal registry must have its hostname set as well. See setting the registry hostname for more details.
ExternalRegistryHostname	ExternalRegistryHostname sets the hostname for the default external image registry. The external hostname should be set only when the image registry is exposed externally. The value is used in publicDockerImageRepository field in ImageStreams. The value must be in hostname[:port] format.

5.2.9. Kubernetes Master Configuration

Table 5.9. Kubernetes Master Configuration Parameters

Parameter Name	Description
APILevels	A list of API levels that should be enabled on startup, v1 as examples.
DisabledAPIGroupVersions	A map of groups to the versions (or *) that should be disabled.
KubeletClientInfo	Contains information about how to connect to kubelets.
KubernetesMasterConfig	Holds the necessary configuration options for the Kubernetes master.
MasterCount	The number of expected masters that should be running. This value defaults to 1 and may be set to a positive integer, or if set to -1, indicates this is part of a cluster.
MasterIP	The public IP address of Kubernetes resources. If empty, the first result from net.InterfaceAddrs will be used.
MasterKubeConfig	File name for the .kubeconfig file that describes how to connect this node to the master.

Parameter Name	Description
ServicesNodePortRange	The range to use for assigning service public ports on a host. Default 30000-32767.
ServicesSubnet	The subnet to use for assigning service IPs.
StaticNodeNames	The list of nodes that are statically known.

5.2.10. Network Configuration

Choose the CIDRs in the following parameters carefully, because the IPv4 address space is shared by all users of the nodes. OpenShift Container Platform reserves CIDRs from the IPv4 address space for its own use, and reserves CIDRs from the IPv4 address space for addresses that are shared between the external user and the cluster.

Table 5.10. Network Configuration Parameters

Parameter Name	Description
ClusterNetworkCIDR	The CIDR string to specify the global overlay network's L3 space. This is reserved for the internal use of the cluster networking.
externalIPNetworkCIDRs	Controls what values are acceptable for the service external IP field. If empty, no externalIP may be set. It may contain a list of CIDRs which are checked for access. If a CIDR is prefixed with ! , IPs in that CIDR will be rejected. Rejections will be applied first, then the IP checked against one of the allowed CIDRs. You must ensure this range does not overlap with your nodes, pods, or service CIDRs for security reasons.
HostSubnetLength	The number of bits to allocate to each host's subnet. For example, 8 would mean a /24 network on the host.
ingressIPNetworkCIDR	Controls the range to assign ingress IPs from for services of type LoadBalancer on bare metal. It may contain a single CIDR that it will be allocated from. By default 172.46.0.0/16 is configured. For security reasons, you should ensure that this range does not overlap with the CIDRs reserved for external IPs, nodes, pods, or services.
HostSubnetLength	The number of bits to allocate to each host's subnet. For example, 8 would mean a /24 network on the host.
NetworkConfig	Provides network options for the node.
NetworkPluginName	The name of the network plug-in to use.
ServiceNetwork	The CIDR string to specify the service networks.

5.2.11. OAuth Authentication Configuration

Table 5.11. OAuth Configuration Parameters

Parameter Name	Description
AlwaysShowProviderSelection	Forces the provider selection page to render even when there is only a single provider.
AssetPublicURL	Used for building valid client redirect URLs for external access.
Error	A path to a file containing a go template used to render error pages during the authentication or grant flow. If unspecified, the default error page is used.
IdentityProviders	Ordered list of ways for a user to identify themselves.
Login	A path to a file containing a go template used to render the login page. If unspecified, the default login page is used.
MasterCA	CA for verifying the TLS connection back to the MasterURL .
MasterPublicURL	Used for building valid client redirect URLs for external access.
MasterURL	Used for making server-to-server calls to exchange authorization codes for access tokens.
OAuthConfig	Holds the necessary configuration options for OAuth authentication.
OAuthTemplates	Allows for customization of pages like the login page.
ProviderSelection	A path to a file containing a go template used to render the provider selection page. If unspecified, the default provider selection page is used.
SessionConfig	Holds information about configuring sessions.
Templates	Allows you to customize pages like the login page.
TokenConfig	Contains options for authorization and access tokens.

5.2.12. Project Configuration

Table 5.12. Project Configuration Parameters

Parameter Name	Description
DefaultNodeSelector	Holds default project node label selector.

Parameter Name	Description
ProjectConfig	Holds information about project creation and defaults.
ProjectRequestMessage	The string presented to a user if they are unable to request a project via the project request API endpoint.
ProjectRequestTemplate	The template to use for creating projects in response to projectrequest . It is in the format namespace/template and it is optional. If it is not specified, a default template is used.

5.2.13. Scheduler Configuration

Table 5.13. Scheduler Configuration Parameters

Parameter Name	Description
SchedulerConfigFile	Points to a file that describes how to set up the scheduler. If empty, you get the default scheduling rules

5.2.14. Security Allocator Configuration

Table 5.14. Security Allocator Parameters

Parameter Name	Description
MCSAllocatorRange	Defines the range of MCS categories that will be assigned to namespaces. The format is <prefix>/<numberOfLabels>[, <maxCategory>] . The default is s0/2 and will allocate from c0 to c1023, which means a total of 535k labels are available (1024 choose 2 ~ 535k). If this value is changed after startup, new projects may receive labels that are already allocated to other projects. Prefix may be any valid SELinux set of terms (including user, role, and type), although leaving them as the default will allow the server to set them automatically.
SecurityAllocator	Controls the automatic allocation of UIDs and MCS labels to a project. If nil, allocation is disabled.
UIDAllocatorRange	Defines the total set of Unix user IDs (UIDs) that will be allocated to projects automatically, and the size of the block each namespace gets. For example, 1000-1999/10 will allocate ten UIDs per namespace, and will be able to allocate up to 100 blocks before running out of space. The default is to allocate from 1 billion to 2 billion in 10k blocks (which is the expected size of the ranges container images will use once user namespaces are started).

5.2.15. Service Account Configuration

Table 5.15. Service Account Configuration Parameters

Parameter Name	Description
LimitSecretReferences	Controls whether or not to allow a service account to reference any secret in a namespace without explicitly referencing them.
ManagedNames	A list of service account names that will be auto-created in every namespace. If no names are specified, the ServiceAccountsController will not be started.
MasterCA	The CA for verifying the TLS connection back to the master. The service account controller will automatically inject the contents of this file into pods so they can verify connections to the master.
PrivateKeyFile	A file containing a PEM-encoded private RSA key, used to sign service account tokens. If no private key is specified, the service account TokensController will not be started.
PublicKeyFiles	A list of files, each containing a PEM-encoded public RSA key. If any file contains a private key, the public portion of the key is used. The list of public keys is used to verify presented service account tokens. Each key is tried in order until the list is exhausted or verification succeeds. If no keys are specified, no service account authentication will be available.
ServiceAccountConfig	Holds the necessary configuration options for a service account.

5.2.16. Serving Information Configuration

Table 5.16. Serving Information Configuration Parameters

Parameter Name	Description
AllowRecursiveQueries	Allows the DNS server on the master to answer queries recursively. Note that open resolvers can be used for DNS amplification attacks and the master DNS should not be made accessible to public networks.
BindAddress	The ip:port to serve on.
BindNetwork	Controls limits and behavior for importing images.
CertFile	A file containing a PEM-encoded certificate.
CertInfo	TLS cert information for serving secure traffic.
ClientCA	The certificate bundle for all the signers that you recognize for incoming client certificates.
dnsConfig	Holds the necessary configuration options for DNS.

Parameter Name	Description
DNSDomain	Holds the domain suffix.
DNSIP	Holds the IP.
KeyFile	A file containing a PEM-encoded private key for the certificate specified by CertFile .
MasterClientConnection Overrides	Provides overrides to the client connection used to connect to the master.
MaxRequestsInFlight	The number of concurrent requests allowed to the server. If zero, no limit.
NamedCertificates	A list of certificates to use to secure requests to specific host names.
RequestTimeoutSecond	The number of seconds before requests are timed out. The default is 60 minutes. If -1, there is no limit on requests.
ServingInfo	The HTTP serving information for the assets.

5.2.17. Volume Configuration

Table 5.17. Volume Configuration Parameters

Parameter Name	Description
DynamicProvisioningEnabled	A boolean to enable or disable dynamic provisioning. Default is true .
FSGroup	Can be specified to enable a quota on local storage use per unique FSGroup ID. At present this is only implemented for emptyDir volumes, and if the underlying volumeDirectory is on an XFS filesystem.
LocalQuota	Contains options for controlling local volume quota on the node.
MasterVolumeConfig	Contains options for configuring volume plug-ins in the master node.
NodeVolumeConfig	Contains options for configuring volumes on the node.
VolumeConfig	Contains options for configuring volumes on the node.
VolumeDirectory	The directory that volumes are stored under.

5.2.18. Audit Configuration

Audit provides a security-relevant chronological set of records documenting the sequence of activities that have affected system by individual users, administrators, or other components of the system.

Audit works at the API server level, logging all requests coming to the server. Each audit log contains two entries:

1. The request line containing:
 - a. A Unique ID allowing to match the response line (see #2)
 - b. The source IP of the request
 - c. The HTTP method being invoked
 - d. The original user invoking the operation
 - e. The impersonated user for the operation (**self** meaning himself)
 - f. The impersonated group for the operation (**lookup** meaning user's group)
 - g. The namespace of the request or <none>
 - h. The URI as requested
2. The response line containing:
 - a. The the unique ID from #1
 - b. The response code

Example output for user **admin** asking for a list of pods:

```
AUDIT: id="5c3b8227-4af9-4322-8a71-542231c3887b" ip="127.0.0.1"
method="GET" user="admin" as="<self>" asgroups="<lookup>"
namespace="default" uri="/api/v1/namespaces/default/pods"
AUDIT: id="5c3b8227-4af9-4322-8a71-542231c3887b" response="200"
```

The **openshift_master_audit_config** variable enables API service auditing. It takes an array of the following options:

Table 5.18. Audit Configuration Parameters

Parameter Name	Description
enabled	A boolean to enable or disable audit logs. Default is false .
auditFilePath	File path where the requests should be logged to. If not set, logs are printed to master logs.
maximumFileRetentionDays	Specifies maximum number of days to retain old audit log files based on the time stamp encoded in their filename.
maximumRetainedFiles	Specifies the maximum number of old audit log files to retain.

Parameter Name	Description
maximumFileSizeMegabytes	Specifies maximum size in megabytes of the log file before it gets rotated. Defaults to 100MB.

Example Audit Configuration

```
auditConfig:
  auditFilePath: "/var/log/audit-ocp.log"
  enabled: true
  maximumFileRetentionDays: 10
  maximumFileSizeMegabytes: 10
  maximumRetainedFiles: 10
```

Advanced Setup for the Audit Log


If you want more advanced setup for the audit log, you can use:

```
openshift_master_audit_config={"enabled": true}
```

The directory in **auditFilePath** will be created if it does not exist.

```
openshift_master_audit_config={"enabled": true, "auditFilePath":
"/var/log/openpaas-ocsp-audit/openpaas-ocsp-audit.log",
"maximumFileRetentionDays": 14, "maximumFileSizeMegabytes": 500,
"maximumRetainedFiles": 5}
```

5.2.19. Advanced Audit



IMPORTANT

Advanced audit is a Technology Preview feature and it is subject to change in future releases. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offerings/techpreview/>.


The advanced audit feature provides several improvements over the [basic audit functionality](#), including fine-grained events filtering and multiple output back ends.

To enable the advanced audit feature, provide the following values in the **openshift_master_audit_config** parameter

```
openshift_master_audit_config={"enabled": true, "auditFilePath":
"/var/log/ocsp-audit/-ocsp-audit.log", "maximumFileRetentionDays": 14,
"maximumFileSizeMegabytes": 500, "maximumRetainedFiles": 5, "policyFile":
```



```
"/etc/security/adv-audit.yaml", "logFormat":"json"}
```



IMPORTANT

The policy file `/etc/security/adv-audit.yaml` must be available on each master node.

The following table contains additional options you can use.

Table 5.19. Advanced Audit Configuration Parameters

Parameter Name	Description
policyFile	Path to the file that defines the audit policy configuration.
policyConfiguration	An embedded audit policy configuration.
logFormat	Specifies the format of the saved audit logs. Allowed values are legacy (the format used in basic audit), and json .
webHookKubeConfig	Path to a .kubeconfig -formatted file that defines the audit webhook configuration, where the events are sent to.
webHookMode	Specifies the strategy for sending audit events. Allowed values are block (blocks processing another event until the previous has fully processed) and batch (buffers events and delivers in batches).



IMPORTANT

To enable the advanced audit feature, you must provide either **policyFile** or **policyConfiguration** describing the audit policy rules:

Sample Audit Policy Configuration

```
apiVersion: audit.k8s.io/v1alpha1
kind: Policy
rules:

  # A catch-all rule to log all other requests at the Metadata level.
  - level: Metadata ❶

  # Do not log watch requests by the "system:kube-proxy" on endpoints or
  services
  - level: None ❷
    users: ["system:kube-proxy"] ❸
    verbs: ["watch"] ❹
    resources: ❺
      - group: ""
        resources: ["endpoints", "services"]

  # Do not log authenticated requests to certain non-resource URL paths.
  - level: None
```

```

userGroups: ["system:authenticated"] ❹
nonResourceURLs: ❺
- "/api*" # Wildcard matching.
- "/version"

# Log the request body of configmap changes in kube-system.
- level: Request
  resources:
  - group: "" # core API group
    resources: ["configmaps"]
  # This rule only applies to resources in the "kube-system" namespace.
  # The empty string "" can be used to select non-namespaced resources.
  namespaces: ["kube-system"] ❻

# Log configmap and secret changes in all other namespaces at the
# metadata level.
- level: Metadata
  resources:
  - group: "" # core API group
    resources: ["secrets", "configmaps"]

# Log all other resources in core and extensions at the request level.
- level: Request
  resources:
  - group: "" # core API group
  - group: "extensions" # Version of group should NOT be included.

# Log login failures from the web console or CLI. Review the logs and
# refine your policies.
- level: Metadata
  nonResourceURLs:
  - /login* ❸
  - /oauth* ❿

```

❶ ❷ There are four possible levels every event can be logged at:

- **None** - Do not log events that match this rule.
- **Metadata** - Log request metadata (requesting user, time stamp, resource, verb, etc.), but not request or response body. This is the same level as the one used in basic audit.
- **Request** - Log event metadata and request body, but not response body.
- **RequestResponse** - Log event metadata, request, and response bodies.

❸ A list of users the rule applies to. An empty list implies every user.

❹ A list of verbs this rule applies to. An empty list implies every verb. This is Kubernetes verb associated with API requests (including **get**, **list**, **watch**, **create**, **update**, **patch**, **delete**, **deletecollection**, and **proxy**).

❺ A list of resources the rule applies to. An empty list implies every resource. Each resource is specified as a group it is assigned to (for example, an empty for Kubernetes core API, batch, build.openshift.io, etc.), and a resource list from that group.

- 6 A list of groups the rule applies to. An empty list implies every group.
- 7 A list of non-resources URLs the rule applies to.
- 8 A list of namespaces the rule applies to. An empty list implies every namespace.
- 9 Endpoint used by the web console.
- 10 Endpoint used by the CLI.

For more information on advanced audit, see the [Kubernetes documentation](#)

5.2.20. Specifying TLS ciphers for etcd

You can specify the [supported TLS ciphers](#) to use in communication between the master and etcd servers.

1. On each etcd node, upgrade etcd:

```
# yum update etcd iptables-services
```

2. Confirm that your etcd version is 3.2.22 or later:

```
# etcd --version
etcd Version: 3.2.22
```

3. On each master host, specify the ciphers to enable in the `/etc/origin/master/master-config.yaml` file:

```
servingInfo:
  ...
  minTLSVersion: VersionTLS12
  cipherSuites:
  - TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256
  - TLS_RSA_WITH_AES_256_CBC_SHA
  - TLS_RSA_WITH_AES_128_CBC_SHA
  ...
```

4. On each master host, restart the master service:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

5. Confirm that the cipher is applied. For example, for TLSv1.2 cipher **ECDHE-RSA-AES128-GCM-SHA256**, run the following command:

```
# openssl s_client -connect etcd1.example.com:2379 1
CONNECTED(00000003)
depth=0 CN = etcd1.example.com
verify error:num=20:unable to get local issuer certificate
verify return:1
depth=0 CN = etcd1.example.com
verify error:num=21:unable to verify the first certificate
```

```

verify return:1
139905367488400:error:14094412:SSL routines:ssl3_read_bytes:sslv3
alert bad certificate:s3_pkt.c:1493:SSL alert number 42
139905367488400:error:140790E5:SSL routines:ssl23_write:ssl
handshake failure:s23_lib.c:177:
---
Certificate chain
 0 s:/CN=etcd1.example.com
  i:/CN=etcd-signer@1529635004
---
Server certificate
-----BEGIN CERTIFICATE-----
MIIEKjCCAnqgAwIBAgIBATANBgkqhkiG9w0BAQsFADAhMR8wHQYDVQDDbZldGNk
.....
....
eif87qttt0Sl1vS8DG1KQ01o0BlNkg==
-----END CERTIFICATE-----
subject=/CN=etcd1.example.com
issuer=/CN=etcd-signer@1529635004
---
Acceptable client certificate CA names
/CN=etcd-signer@1529635004
Client Certificate Types: RSA sign, ECDSA sign
Requested Signature Algorithms:
RSA+SHA256:ECDSA+SHA256:RSA+SHA384:ECDSA+SHA384:RSA+SHA1:ECDSA+SHA1
Shared Requested Signature Algorithms:
RSA+SHA256:ECDSA+SHA256:RSA+SHA384:ECDSA+SHA384:RSA+SHA1:ECDSA+SHA1
Peer signing digest: SHA384
Server Temp Key: ECDH, P-256, 256 bits
---
SSL handshake has read 1666 bytes and written 138 bytes
---
New, TLSv1/SSLv3, Cipher is ECDHE-RSA-AES128-GCM-SHA256
Server public key is 2048 bit
Secure Renegotiation IS supported
Compression: NONE
Expansion: NONE
No ALPN negotiated
SSL-Session:
    Protocol   : TLSv1.2
    Cipher     : ECDHE-RSA-AES128-GCM-SHA256
    Session-ID:
    Session-ID-ctx:
    Master-Key:
1EFA00A91EE5FC5EDDCFC67C8ECD060D44FD3EB23D834EDED929E4B74536F273C0F9
299935E5504B562CD56E76ED208D
    Key-Arg    : None
    Krb5 Principal: None
    PSK identity: None
    PSK identity hint: None
    Start Time: 1529651744
    Timeout    : 300 (sec)
    Verify return code: 21 (unable to verify the first certificate)

```

1 **etcd1.example.com** is the name of an etcd host.

5.3. NODE CONFIGURATION FILES

The following *node-config.yaml* file is a sample node configuration file that was generated with the default values as of writing. You can [create a new node configuration file](#) to see the valid options for your installed version of OpenShift Container Platform.

Example 5.1. Sample Node Configuration File

```
allowDisabledDocker: false
apiVersion: v1
authConfig:
  authenticationCacheSize: 1000
  authenticationCacheTTL: 5m
  authorizationCacheSize: 1000
  authorizationCacheTTL: 5m
dnsDomain: cluster.local
dnsIP: 10.0.2.15 ❶
dockerConfig:
  execHandlerName: native
imageConfig:
  format: openshift/origin-${component}:${version}
  latest: false
iptablesSyncPeriod: 5s
kind: NodeConfig
masterKubeConfig: node.kubeconfig
networkConfig:
  mtu: 1450
  networkPluginName: ""
nodeIP: ""
nodeName: node1.example.com
podManifestConfig: ❷
  path: "/path/to/pod-manifest-file" ❸
  fileCheckIntervalSeconds: 30 ❹
proxyArguments:
  proxy-mode:
    - iptables ❺
volumeConfig:
  localQuota:
    perFSGroup: null ❻
servingInfo:
  bindAddress: 0.0.0.0:10250
  bindNetwork: tcp4
  certFile: server.crt
  clientCA: node-client-ca.crt
  keyFile: server.key
  namedCertificates: null
volumeDirectory: /root/openshift.local.volumes
```

❶ Configures an IP address to be prepended to a pod's */etc/resolv.conf* by adding the address here.

❷ Allows pods to be placed directly on certain set of nodes, or on all nodes without going through the scheduler. You can then use pods to perform the same administrative tasks and support the same services on each node.

- 3 Specifies the path for the [pod manifest file](#) or directory. If it is a directory, then it is expected to contain one or more manifest files. This is used by the Kubelet to create pods on the node.
- 4 This is the interval (in seconds) for checking the manifest file for new data. The interval must be a positive value.
- 5 The [service proxy implementation](#) to use.
- 6 Preliminary support for local emptyDir volume quotas, set this value to a resource quantity representing the desired quota per FSGroup, per node. (i.e. 1Gi, 512Mi, etc) Currently requires that the **volumeDirectory** be on an XFS filesystem mounted with the 'gquota' option, and the matching security context constraint's fsGroup type set to 'MustRunAs'.

The node configuration file determines the resources of a node. See the [Allocating node resources section in the Cluster Administrator guide](#) for more information.

5.3.1. Pod and Node Configuration

Table 5.20. Pod and Node Configuration Parameters

Parameter Name	Description
NodeConfig	The fully specified configuration starting an OpenShift Container Platform node.
NodeIP	Node may have multiple IPs, so this specifies the IP to use for pod traffic routing. If not specified, network parse/lookup on the nodeName is performed and the first non-loopback address is used.
NodeName	The value used to identify this particular node in the cluster. If possible, this should be your fully qualified hostname. If you are describing a set of static nodes to the master, this value must match one of the values in the list.
PodEvictionTimeout	Controls grace period for deleting pods on failed nodes. It takes valid time duration string. If empty, you get the default pod eviction timeout.
ProxyClientInfo	Specifies the client cert/key to use when proxying to pods.

5.3.2. Docker Configuration

Table 5.21. Docker Configuration Parameters

Parameter Name	Description
AllowDisabledDocker	If true, the kubelet will ignore errors from Docker. This means that a node can start on a machine that does not have docker started.
DockerConfig	Holds Docker related configuration options

Parameter Name	Description
ExecHandlerName	The handler to use for executing commands in Docker containers.

5.3.3. Parallel Image Pulls with Docker 1.9+

If you are using Docker 1.9+, you may want to consider enabling parallel image pulling, as the default is to pull images one at a time.



NOTE

There is a potential issue with data corruption prior to Docker 1.9. However, starting with 1.9, the corruption issue is resolved and it is safe to switch to parallel pulls.

```
kubeletArguments:
  serialize-image-pulls:
    - "false" 1
```

1 Change to true to disable parallel pulls. (This is the default config)

5.4. PASSWORDS AND OTHER SENSITIVE DATA

For some [authentication configurations](#), an LDAP **bindPassword** or OAuth **clientSecret** value is required. Instead of specifying these values directly in the master configuration file, these values may be provided as environment variables, external files, or in encrypted files.

Environment Variable Example

```
...
bindPassword:
  env: BIND_PASSWORD_ENV_VAR_NAME
```

External File Example

```
...
bindPassword:
  file: bindPassword.txt
```

Encrypted External File Example

```
...
bindPassword:
  file: bindPassword.encrypted
  keyFile: bindPassword.key
```

To create the encrypted file and key file for the above example:

```
$ oc adm ca encrypt --genkey=bindPassword.key --out=bindPassword.encrypted
> Data to encrypt: B1ndPass0rd!
```

Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.



WARNING

Encrypted data is only as secure as the decrypting key. Care should be taken to limit filesystem permissions and access to the key file.

5.5. CREATING NEW CONFIGURATION FILES

When defining an OpenShift Container Platform configuration from scratch, start by creating new configuration files.

For master host configuration files, use the **openshift start** command with the **--write-config** option to write the configuration files. For node hosts, use the **oc adm create-node-config** command to write the configuration files.

The following commands write the relevant launch configuration file(s), certificate files, and any other necessary files to the specified **--write-config** or **--node-dir** directory.

Generated certificate files are valid for two years, while the certification authority (CA) certificate is valid for five years. This can be altered with the **--expire-days** and **--signer-expire-days** options, but for security reasons, it is recommended to not make them greater than these values.

To create configuration files for an all-in-one server (a master and a node on the same host) in the specified directory:

```
$ openshift start --write-config=/openshift.local.config
```

To create a [master configuration file](#) and other required files in the specified directory:

```
$ openshift start master --write-config=/openshift.local.config/master
```

To create a [node configuration file](#) and other related files in the specified directory:

```
$ oc adm create-node-config \
  --node-dir=/openshift.local.config/node-<node_hostname> \
  --node=<node_hostname> \
  --hostnames=<node_hostname>,<ip_address> \
  --certificate-authority="/path/to/ca.crt" \
  --signer-cert="/path/to/ca.crt" \
  --signer-key="/path/to/ca.key" \
  --signer-serial="/path/to/ca.serial.txt" \
  --node-client-certificate-authority="/path/to/ca.crt"
```

When creating node configuration files, the **--hostnames** option accepts a comma-delimited list of every host name or IP address you want server certificates to be valid for.

5.6. LAUNCHING SERVERS USING CONFIGURATION FILES

Once you have modified the master and/or node configuration files to your specifications, you can use them when launching servers by specifying them as an argument. Keep in mind that if you specify a configuration file, none of the other command line options you pass are respected.

To launch an all-in-one server using a master configuration and a node configuration file:

```
$ openshift start --master-config=/openshift.local.config/master/master-
config.yaml --node-config=/openshift.local.config/node-
<node_hostname>/node-config.yaml
```

To launch a master server using a master configuration file:

```
$ openshift start master --config=/openshift.local.config/master/master-
config.yaml
```

To launch a node server using a node configuration file:

```
$ openshift start node --config=/openshift.local.config/node-
<node_hostname>/node-config.yaml
```

5.7. CONFIGURING LOGGING LEVELS

OpenShift Container Platform uses the **systemd-journald.service** to collect log messages for debugging, using five log message severities. The logging levels are based on Kubernetes logging conventions, as follows:

Table 5.22. Log Level Options

Option	Description
0	Errors and warnings only
2	Normal information
4	Debugging-level information
6	API-level debugging information (request / response)
8	Body-level API debugging information

You can control which INFO messages are logged by setting the `loglevel` option in the in **`/etc/sysconfig/atomic-openshift-node`**, the **`/etc/sysconfig/atomic-openshift-master-api`** file and the **`/etc/sysconfig/atomic-openshift-master-controllers`** file. Configuring the logs to collect all messages can lead to large logs that are difficult to interpret and can take up excessive space. Collecting all messages should only be used in debug situations.

**NOTE**

Messages with FATAL, ERROR, WARNING and some INFO severities appear in the logs regardless of the log configuration.

You can view logs for the master or the node system using the following command:

```
# journalctl -r -u <journal_name>
```

Use the **-r** option to show the newest entries first.

For example:

```
# journalctl -r -u atomic-openshift-master-controllers
# journalctl -r -u atomic-openshift-master-api
# journalctl -r -u atomic-openshift-node.service
```

To change the logging level:

1. Edit the **/etc/sysconfig/atomic-openshift-master** file for the master or **/etc/sysconfig/atomic-openshift-node** file for the nodes.
2. Enter a value from the **Log Level Options** table above in the **OPTIONS= -loglevel=** field.
For example:

```
OPTIONS= -loglevel=4
```

3. Restart the master or node host as appropriate. See [Restarting OpenShift Container Platform services](#).

After the restart, all new log messages will conform to the new setting. Older messages do not change.

**NOTE**

The default log level can be set using the Advanced Install. For more information, see [Cluster Variables](#).

The following examples are excerpts from a master **journald** log at various log levels. Timestamps and system information have been removed from these examples.

Excerpt of journalctl -u atomic-openshift-master-controllers.service output at loglevel=0

```
4897 plugins.go:77] Registered admission plugin "NamespaceLifecycle"
4897 start_master.go:290] Warning: assetConfig.loggingPublicURL: Invalid
value: "": required to view aggregated container logs in the console,
master start will continue.
4897 start_master.go:290] Warning: assetConfig.metricsPublicURL: Invalid
value: "": required to view cluster metrics in the console, master start
will continue.
4897 start_master.go:290] Warning: aggregatorConfig.proxyClientInfo:
Invalid value: "": if no client certificate is specified, the aggregator
will be unable to proxy to remote servers,
4897 start_master.go:412] Starting controllers on 0.0.0.0:8444 (v3.7.14)
4897 start_master.go:416] Using images from "openshift3/ose-
```

```

<component>:v3.7.14"
4897 standalone_apiserver.go:106] Started health checks at 0.0.0.0:8444
4897 plugins.go:77] Registered admission plugin "NamespaceLifecycle"
4897 configgetter.go:53] Initializing cache sizes based on 0MB limit
4897 leaderelection.go:105] Attempting to acquire openshift-master-
controllers lease as master-bkr-hv03-guest44.dsal.lab.eng.bos.redhat.com-
10.19.41.74-xtz6lbqb, renewing every 3s, hold
4897 leaderelection.go:179] attempting to acquire leader lease...
systemd[1]: Started Atomic OpenShift Master Controllers.
4897 leaderelection.go:189] successfully acquired lease kube-
system/openshift-master-controllers
4897 event.go:218] Event(v1.ObjectReference{Kind:"ConfigMap",
Namespace:"kube-system", Name:"openshift-master-controllers",
UID:"aca86731-ffbe-11e7-8d33-525400c845a8", APIVersion:"v1",
4897 start_master.go:627] Started serviceaccount-token controller
4897 factory.go:351] Creating scheduler from configuration: {{ }
[{NoVolumeZoneConflict <nil>} {MaxEBSVolumeCount <nil>}
{MaxGCEPDVolumeCount <nil>} {MaxAzureDiskVolumeCount <nil>} {Mat
4897 factory.go:360] Registering predicate: NoVolumeZoneConflict
4897 plugins.go:145] Predicate type NoVolumeZoneConflict already
registered, reusing.
4897 factory.go:360] Registering predicate: MaxEBSVolumeCount
4897 plugins.go:145] Predicate type MaxEBSVolumeCount already registered,
reusing.
4897 factory.go:360] Registering predicate: MaxGCEPDVolumeCount

```

Excerpt of `journalctl -u atomic-openshift-master-controllers.service` output at `loglevel=2`

```

4897 master.go:47] Initializing SDN master of type "redhat/openshift-ovs-
subnet"
4897 master.go:107] Created ClusterNetwork default (network:
"10.128.0.0/14", hostSubnetBits: 9, serviceNetwork: "172.30.0.0/16",
pluginName: "redhat/openshift-ovs-subnet")
4897 start_master.go:690] Started "openshift.io/sdn"
4897 start_master.go:680] Starting "openshift.io/service-serving-cert"
4897 controllermanager.go:466] Started "namespace"
4897 controllermanager.go:456] Starting "daemonset"
4897 controller_utils.go:1025] Waiting for caches to sync for namespace
controller
4897 shared_informer.go:298] resyncPeriod 1200000000000 is smaller than
resyncCheckPeriod 6000000000000 and the informer has already started.
Changing it to 6000000000000
4897 start_master.go:690] Started "openshift.io/service-serving-cert"
4897 start_master.go:680] Starting "openshift.io/image-signature-import"
4897 start_master.go:690] Started "openshift.io/image-signature-import"
4897 start_master.go:680] Starting "openshift.io/templateinstance"
4897 controllermanager.go:466] Started "daemonset"
4897 controllermanager.go:456] Starting "statefulset"
4897 daemoncontroller.go:222] Starting daemon sets controller
4897 controller_utils.go:1025] Waiting for caches to sync for daemon sets
controller
4897 controllermanager.go:466] Started "statefulset"
4897 controllermanager.go:456] Starting "cronjob"
4897 stateful_set.go:147] Starting stateful set controller
4897 controller_utils.go:1025] Waiting for caches to sync for stateful set
controller

```

```
4897 start_master.go:690] Started "openshift.io/templateinstance"
4897 start_master.go:680] Starting "openshift.io/horizontalpodautoscaling"
```

Excerpt of `journalctl -u atomic-openshift-master-controllers.service` output at `loglevel=4`

```
4897 factory.go:366] Registering priority: Zone
4897 factory.go:401] Creating scheduler with fit predicates
'map[GeneralPredicates:{} CheckNodeMemoryPressure:{}
CheckNodeDiskPressure:{} NoVolumeNodeConflict:{} Region:{} NoVolumeZoneC
4897 controller_utils.go:1025] Waiting for caches to sync for tokens
controller
4897 controllermanager.go:108] Version: v1.7.6+a08f5eeb62
4897 leaderelection.go:179] attempting to acquire leader lease...
4897 leaderelection.go:189] successfully acquired lease kube-system/kube-
controller-manager
4897 event.go:218] Event(v1.ObjectReference{Kind:"ConfigMap",
Namespace:"kube-system", Name:"kube-controller-manager", UID:"acb3e9c6-
ffbe-11e7-8d33-525400c845a8", APIVersion:"v1", Resou
4897 controller_utils.go:1032] Caches are synced for tokens controller
4897 plugins.go:101] No cloud provider specified.
4897 controllermanager.go:481] "serviceaccount-token" is disabled
4897 controllermanager.go:450] "bootstrapsigner" is disabled
4897 controllermanager.go:450] "tokencleaner" is disabled
4897 controllermanager.go:456] Starting "garbagecollector"
4897 start_master.go:680] Starting "openshift.io/build"
4897 controllermanager.go:466] Started "garbagecollector"
4897 controllermanager.go:456] Starting "deployment"
4897 garbagecollector.go:126] Starting garbage collector controller
4897 controller_utils.go:1025] Waiting for caches to sync for garbage
collector controller
4897 controllermanager.go:466] Started "deployment"
4897 controllermanager.go:450] "horizontalpodautoscaling" is disabled
4897 controllermanager.go:456] Starting "disruption"
4897 deployment_controller.go:152] Starting deployment controller
```

Excerpt of `journalctl -u atomic-openshift-master-controllers.service` output at `loglevel=8`

```
4897 plugins.go:77] Registered admission plugin "NamespaceLifecycle"
4897 start_master.go:290] Warning: assetConfig.loggingPublicURL: Invalid
value: "": required to view aggregated container logs in the console,
master start will continue.
4897 start_master.go:290] Warning: assetConfig.metricsPublicURL: Invalid
value: "": required to view cluster metrics in the console, master start
will continue.
4897 start_master.go:290] Warning: aggregatorConfig.proxyClientInfo:
Invalid value: "": if no client certificate is specified, the aggregator
will be unable to proxy to remote serv
4897 start_master.go:412] Starting controllers on 0.0.0.0:8444 (v3.7.14)
4897 start_master.go:416] Using images from "openshift3/ose-
<component>:v3.7.14"
4897 standalone_apiserver.go:106] Started health checks at 0.0.0.0:8444
4897 plugins.go:77] Registered admission plugin "NamespaceLifecycle"
4897 configgetter.go:53] Initializing cache sizes based on OMB limit
4897 leaderelection.go:105] Attempting to acquire openshift-master-
controllers lease as master-bkr-hv03-guest44.dsdl.lab.eng.bos.redhat.com-
```

```

10.19.41.74-xtz6lbqb, renewing every 3s,
4897 leaderelection.go:179] attempting to acquire leader lease...
systemd[1]: Started Atomic OpenShift Master Controllers.
4897 leaderelection.go:189] successfully acquired lease kube-
system/openshift-master-controllers
4897 event.go:218] Event(v1.ObjectReference{Kind:"ConfigMap",
Namespace:"kube-system", Name:"openshift-master-controllers",
UID:"aca86731-ffbe-11e7-8d33-525400c845a8", APIVersion:"
4897 start_master.go:627] Started serviceaccount-token controller

```

Excerpt of `journalctl -u atomic-openshift-master-api.service` output at `loglevel=2`

```

4613 plugins.go:77] Registered admission plugin "NamespaceLifecycle"
4613 master.go:320] Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
4613 master.go:329] Starting OAuth2 API at /oauth
4613 master.go:320] Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
4613 master.go:329] Starting OAuth2 API at /oauth
4613 master.go:320] Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
4613 master.go:329] Starting OAuth2 API at /oauth
4613 swagger.go:38] No API exists for predefined swagger description
/oapi/v1
4613 swagger.go:38] No API exists for predefined swagger description
/api/v1
[restful] 2018/01/22 16:53:14 log.go:33: [restful/swagger] listing is
available at https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/swaggerapi
[restful] 2018/01/22 16:53:14 log.go:33: [restful/swagger] https://bkr-
hv03-guest44.dsal.lab.eng.bos.redhat.com:8443/swaggerui/ is mapped to
folder /swagger-ui/
4613 master.go:320] Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
4613 master.go:329] Starting OAuth2 API at /oauth
4613 swagger.go:38] No API exists for predefined swagger description
/oapi/v1
4613 swagger.go:38] No API exists for predefined swagger description
/api/v1
[restful] 2018/01/22 16:53:14 log.go:33: [restful/swagger] listing is
available at https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/swaggerapi
[restful] 2018/01/22 16:53:14 log.go:33: [restful/swagger] https://bkr-
hv03-guest44.dsal.lab.eng.bos.redhat.com:8443/swaggerui/ is mapped to
folder /swagger-ui/
Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
Starting OAuth2 API at /oauth
No API exists for predefined swagger description /oapi/v1
No API exists for predefined swagger description /api/v1

```

5.8. RESTARTING OPENSIFT CONTAINER PLATFORM SERVICES

To apply configuration changes, you must restart OpenShift Container Platform services.

- To restart master, run the command:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

- To restart node hosts, on each node, run the command:

```
# systemctl restart atomic-openshift-node
```

CHAPTER 6. OPENSIFT ANSIBLE BROKER CONFIGURATION

6.1. OVERVIEW

When the [OpenShift Ansible broker](#) (OAB) is deployed in a cluster, its behavior is largely dictated by the broker's configuration file loaded on startup. The broker's configuration is stored as a ConfigMap object in the broker's namespace (**openshift-ansible-service-broker** by default).

Example OpenShift Ansible Broker Configuration File

```
registry: ❶
  - type: dockerhub
    name: docker
    url: https://registry.hub.docker.com
    org: <dockerhub_org>
    fail_on_error: false
  - type: rhcc
    name: rhcc
    url: https://registry.access.redhat.com
    fail_on_error: true
    white_list:
      - "^foo.*-apb$"
      - ".*-apb$"
    black_list:
      - "bar.*-apb$"
      - "^my-apb$"
  - type: local_openshift
    name: lo
    namespaces:
      - openshift
    white_list:
      - ".*-apb$"
dao: ❷
  etcd_host: localhost
  etcd_port: 2379
log: ❸
  logfile: /var/log/ansible-service-broker/asb.log
  stdout: true
  level: debug
  color: true
openshift: ❹
  host: ""
  ca_file: ""
  bearer_token_file: ""
  image_pull_policy: IfNotPresent
  sandbox_role: "edit"
  keep_namespace: false
  keep_namespace_on_error: true
broker: ❺
  bootstrap_on_startup: true
  dev_broker: true
  launch_apb_on_bind: false
  recovery: true
  output_request: true
```

```

ssl_cert_key: /path/to/key
ssl_cert: /path/to/cert
refresh_interval: "600s"
auth:
  - type: basic
    enabled: true
secrets: 6
  - title: Database credentials
    secret: db_creds
    apb_name: dh-rhsc1-postgresql-apb

```

- 1 See [Registry Configuration](#) for details.
- 2 See [DAO Configuration](#) for details.
- 3 See [Log Configuration](#) for details.
- 4 See [OpenShift Configuration](#) for details.
- 5 See [Broker Configuration](#) for details.
- 6 See [Secrets Configuration](#) for details.

6.2. MODIFYING THE OPENSIFT ANSIBLE BROKER CONFIGURATION

To modify the OAB's default broker configuration after it has been deployed:

1. Edit the the **broker-config** ConfigMap object in the OAB's namespace as a user with **cluster-admin** privileges:

```
$ oc edit configmap broker-config -n openshift-ansible-service-broker
```

2. After saving any updates, redeploy the OAB's deployment configuration for the changes to take effect:

```
$ oc rollout latest dc/asb -n openshift-ansible-service-broker
```

6.3. REGISTRY CONFIGURATION

The **registry** section allows you to define the registries that the broker should look at for APBs.

Table 6.1. registry Section Configuration Options

Field	Description	Required
name	The name of the registry. Used by the broker to identify APBs from this registry.	Y

Field	Description	Required
auth_type	How the broker should read the registry credentials. Can be config (uses user and pass as defined in the registry section), secret (uses a secret in the broker namespace), or file (uses a mounted file).	N [a]
auth_name	Name of the secret or file storing the registry credentials that should be read. Used when auth_type is set to secret .	N [a]
user	The user name for authenticating to the registry when using auth_type: config .	N
pass	The password for authenticating to the registry when using auth_type: config .	N
org	The namespace or organization that the image is contained in.	N
type	The type of registry. Available adapters are mock , rhcc , openshift , dockerhub , and local_openshift .	Y
namespaces	The list of namespaces to configure the local_openshift registry type with. By default, a user should use openshift .	N
url	The URL that is used to retrieve image information. Used extensively for RHCC while the dockerhub type uses hard-coded URLs.	N
fail_on_error	Should this registry fail, the bootstrap request if it fails. Will stop the execution of other registries loading.	N
white_list	The list of regular expressions used to define which image names should be allowed through. Must have a white list to allow APBs to be added to the catalog. The most permissive regular expression that you can use is . *-apb\$ if you would want to retrieve all APBs in a registry. See APB Filtering for more details.	N
black_list	The list of regular expressions used to define which images names should never be allowed through. See APB Filtering for more details.	N
images	The list of images to be used with an OpenShift Container Registry.	N
<p>[a] auth_type is currently required for the openshift registry type, due to a bug that will be addressed in an upcoming release (BZ#1526949). auth_name is only required in this case if auth_type is set to secret or file. See ISV Registry.</p>		

6.3.1. Production or Development

A *production* broker configuration is designed to be pointed at a trusted container distribution registry, such as the Red Hat Container Catalog (RHCC):

```
registry:
  - name: rhcc
    type: rhcc
    url: https://registry.access.redhat.com
    tag: v3.7
    white_list:
      - ".*-apb$"
  - type: local_openshift
    name: localregistry
    namespaces:
      - openshift
    white_list: []
```

However, a *development* broker configuration is primarily used by developers working on the broker. To enable developer settings, set the registry name to **dev** and the **dev_broker** field in the **broker** section to **true**:

```
registry:
  name: dev

broker:
  dev_broker: true
```

6.3.2. Storing Registry Credentials

The **auth_type** field in the **registry** section of the broker configuration determines how the broker should read the registry credentials, either the **config**, **secret**, or **file** type.

With the **config** type, the registry credentials are read from the broker configuration's **user** and **pass** values in the **registry** section, for example:

```
registry:
  - name: isv
    type: openshift
    url: https://registry.connect.redhat.com
    auth_type: config
    user: <user>
    pass: <password>
  ...
```

If you want to ensure these credentials are not publicly accessible, you can use the **secret** type to configure a registry to use a secret from the broker's namespace. Alternatively, you can use the **file** to configure a registry to use a secret mounted as a volume.

To use the **secret** or **file** type:

1. The associated secret should have the values **username** and **password** defined. When using a secret, you must ensure that the **openshift-ansible-service-broker** namespace exists, as this is where the secret will be read from.
For example, create a **reg-creds.yaml** file:

```
$ cat reg-creds.yaml
---
username: <username>
password: <password>
```

2. Create a secret from this file in the **openshift-ansible-service-broker** namespace:

```
$ oc create secret generic \
  registry-credentials-secret \
  --from-file reg-creds.yaml \
  -n openshift-ansible-service-broker
```

3. Choose whether you want to use the **secret** or **file** type:

- To use the **secret** type, in the broker configuration, set **auth_type** to **secret** and **auth_name** to the name of the secret:

```
registry:
  - name: isv
    type: openshift
    url: https://registry.connect.redhat.com
    auth_type: secret
    auth_name: registry-credentials-secret
```

- To use the **file** type:
 - a. Edit the **asb** deployment configuration to mount your file into **/tmp/registry-credentials/reg-creds.yaml**:

```
$ oc edit dc/asb -n openshift-ansible-service-broker
```

In the **containers.volumeMounts** section, add:

```
volumeMounts:
  - name: reg-auth
    mountPath: /tmp/registry-credentials
```

In the **volumes** section, add:

```
volumes:
  - name: reg-auth
    secret:
      defaultMode: 420
      secretName: registry-credentials-secret
```

- b. In the broker configuration, set **auth_type** to **file** and **auth_name** to the location of the file:

```
registry:
  - name: isv
    type: openshift
```

```
url: https://registry.connect.redhat.com
auth_type: file
auth_name: /tmp/registry-credentials/reg-creds.yaml
```

6.3.3. Mock Registry

A mock registry is useful for reading local APB specs. Instead of going out to a registry to search for image specs, this uses a list of local specs. Set the name of the registry to **mock** to use the mock registry.

```
registry:
  - name: mock
    type: mock
```

6.3.4. Dockerhub Registry

The **dockerhub** type allows you to load APBs from a specific organization in the DockerHub. For example, the [ansibleplaybookbundle](#) organization.

```
registry:
  - name: dockerhub
    type: dockerhub
    org: ansibleplaybookbundle
    user: <user>
    pass: <password>
    white_list:
      - ".*-apb$"
```

6.3.5. APB Filtering

APBs can be filtered out by their image name using a combination of the **white_list** or **black_list** parameters, set on a registry basis inside the broker's configuration.

Both are optional lists of regular expressions that will be run over the total set of discovered APBs for a given registry to determine matches.

Table 6.2. APB Filter Behavior

Present	Allowed	Blocked
Only whitelist	Matches a regex in list.	Any APB that does not match.
Only blacklist	All APBs that do not match.	APBs that match a regex in list.
Both present	Matches regex in whitelist but not in blacklist.	APBs that match a regex in blacklist.
None	No APBs from the registry.	All APBs from that registry.

For example:

Whitelist Only

```
white_list:
- "foo.*-apb$"
- "^my-apb$"
```

Anything matching on **foo.*-apb\$** and only **my-apb** will be allowed through in this case. All other APBs will be rejected.

Blacklist Only

```
black_list:
- "bar.*-apb$"
- "^foobar-apb$"
```

Anything matching on **bar.*-apb\$** and only **foobar-apb** will be blocked in this case. All other APBs will be allowed through.

Whitelist and Blacklist

```
white_list:
- "foo.*-apb$"
- "^my-apb$"
black_list:
- "^foo-rootkit-apb$"
```

Here, **foo-rootkit-apb** is specifically blocked by the blacklist despite its match in the whitelist because the whitelist match is overridden.

Otherwise, only those matching on **foo.*-apb\$** and **my-apb** will be allowed through.

Example Broker Configuration registry Section:

```
registry:
- type: dockerhub
  name: dockerhub
  url: https://registry.hub.docker.com
  user: <user>
  pass: <password>
  org: <org>
  white_list:
    - "foo.*-apb$"
    - "^my-apb$"
  black_list:
    - "bar.*-apb$"
    - "^foobar-apb$"
```

6.3.6. Local OpenShift Container Registry

Using the **local_openshift** type will allow you to load APBs from the OpenShift Container Registry that is internal to the OpenShift Container Platform cluster. You can configure the namespaces in which you want to look for published APBs.

```
registry:
  - type: local_openshift
    name: lo
    namespaces:
      - openshift
    white_list:
      - ".*-apb$"
```

6.3.7. Red Hat Container Catalog Registry

Using the **rhcc** type will allow you to load APBs that are published to the [Red Hat Container Catalog](#) (RHCC) registry.

```
registry:
  - name: rhcc
    type: rhcc
    url: https://registry.access.redhat.com
    white_list:
      - ".*-apb$"
```

6.3.8. ISV Registry

Using the **openshift** type allows you to load APBs that are published to the ISV container registry at registry.connect.redhat.com.

```
registry:
  - name: isv
    type: openshift
    auth_type: config 1
    user: <user>
    pass: <password>
    url: https://registry.connect.redhat.com
    images: 2
      - <image_1>
      - <image_2>
    white_list:
      - ".*-apb$"
```

- 1** Using the **openshift** registry type currently requires that **auth_type** be declared in the configuration (to **config**, **secret**, or **file**) due to a bug that will be addressed in a future release (BZ#1526949). See [Storing Registry Credentials](#) for options.
- 2** Because the **openshift** type currently cannot search the configured registry, it is required that you configure the broker with a list of images you would like to source from for when the broker bootstraps. The image names must be the fully qualified name without the registry URL.

6.3.9. Multiple Registries

You can use more than one registry to separate APBs into logical organizations and be able to manage them from the same broker. The registries must have a unique, non-empty name. If there is no unique name, the service broker will fail to start with an error message alerting you to the problem.

■

```

registry:
  - name: dockerhub
    type: dockerhub
    org: ansibleplaybookbundle
    user: <user>
    pass: <password>
    white_list:
      - ".*-apb$"
  - name: rhcc
    type: rhcc
    url: <rhcc_url>
    white_list:
      - ".*-apb$"

```

6.4. DAO CONFIGURATION

Field	Description	Required
etcd_host	The URL of the etcd host.	Y
etcd_port	The port to use when communicating with etcd_host .	Y

6.5. LOG CONFIGURATION

Field	Description	Required
logfile	Where to write the broker's logs.	Y
stdout	Write logs to stdout.	Y
level	Level of the log output.	Y
color	Color the logs.	Y

6.6. OPENSIFT CONFIGURATION

Field	Description	Required
host	OpenShift Container Platform host.	N
ca_file	Location of the certificate authority file.	N
bearer_token_file	Location of bearer token to be used.	N

Field	Description	Required
image_pull_policy	When to pull the image.	Y
sandbox_role	Role to give to an APB sandbox environment.	Y
keep_namespace	Always keep namespace after an APB execution.	N
keep_namespace_on_error	Keep namespace after an APB execution has an error.	N

6.7. BROKER CONFIGURATION

The **broker** section tells the broker what functionality should be enabled and disabled. It will also tell the broker where to find files on disk that will enable the full functionality.



NOTE

With the absence of async bind, setting **launch_apb_on_bind** to **true** can cause the bind action to timeout and will span a retry. The broker will handle this with "409 Conflicts" because it is the same bind request with different parameters.

Field	Description	Default Value	Required
dev_broker	Allow development routes to be accessible.	false	N
launch_apb_on_bind	Allow bind to be a no-op.	false	N
bootstrap_on_startup	Allow the broker attempt to bootstrap itself on start up. Will retrieve the APBs from configured registries.	false	N
recovery	Allow the broker to attempt to recover itself by dealing with pending jobs noted in etcd.	false	N
output_request	Allow the broker to output the requests to the log file as they come in for easier debugging.	false	N
ssl_cert_key	Tells the broker where to find the TLS key file. If not set, the API server will attempt to create one.	""	N
ssl_cert	Tells the broker where to find the TLS .crt file. If not set, the API server will attempt to create one.	""	N
refresh_interval	The interval to query registries for new image specs.	"600s"	N

Field	Description	Default Value	Required
auto_escalate	Allows the broker to escalate the permissions of a user while running the APB.	false	N
cluster_url	Sets the prefix for the URL that the broker is expecting.	ansible-service-broker	N

6.8. SECRETS CONFIGURATION

The **secrets** section creates associations between secrets in the broker's namespace and APBs the broker runs. The broker uses these rules to mount secrets into running APBs, allowing the user to use secrets to pass parameters without exposing them to the catalog or users.

The section is a list where each entry has the following structure:

Field	Description	Required
title	The title of the rule. This is just for display and output purposes.	Y
apb_name	The name of the APB to associate with the specified secret. This is the fully qualified name (<registry_name>-<image_name>).	Y
secret	The name of the secret to pull parameters from.	Y

You can download and use the [create_broker_secret.py](#) file to create and format this configuration section.

```
secrets:
- title: Database credentials
  secret: db_creds
  apb_name: dh-rhsc1-postgresql-apb
```


CHAPTER 7. ADDING HOSTS TO AN EXISTING CLUSTER

7.1. OVERVIEW

Depending on how your OpenShift Container Platform cluster was installed, you can add new hosts (either nodes or masters) to your installation by using the install tool for quick installations, or by using the ***scaleup.yml*** playbook for advanced installations.

7.2. ADDING HOSTS USING THE QUICK INSTALLER TOOL


If you used the quick install tool to install your OpenShift Container Platform cluster, you can use the quick install tool to add a new node host to your existing cluster.



NOTE

Currently, you can not use the quick installer tool to add new master hosts. You must use the [advanced installation](#) method to do so.

If you used the installer in either [interactive](#) or [unattended](#) mode, you can re-run the installation as long as you have an [installation configuration file](#) at `~/config/openshift/installer.cfg.yml` (or specify a different location with the `-c` option).



IMPORTANT

See the [cluster limits](#) section for the recommended maximum number of nodes.

To add nodes to your installation:

1. Ensure you have the latest installer and playbooks by updating the **atomic-openshift-utils** package:

```
# yum update atomic-openshift-utils
```

2. Run the installer with the **scaleup** subcommand in interactive or unattended mode:

```
# atomic-openshift-installer [-u] [-c </path/to/file>] scaleup
```

3. The installer detects your current environment and allows you to add additional nodes:

```
*** Installation Summary ***
```

```
Hosts:
```

```
- 100.100.1.1
  - OpenShift master
  - OpenShift node
  - Etcd (Embedded)
  - Storage
```

```
Total OpenShift masters: 1
```

```
Total OpenShift nodes: 1
```

```
---
```

```
We have detected this previously installed OpenShift environment.
```


```
This tool will guide you through the process of adding additional
nodes to your cluster.
```

```
Are you ready to continue? [y/N]:
```

Choose (y) and follow the on-screen instructions to complete your desired task.

7.3. ADDING HOSTS

You can add new hosts to your cluster by running the ***scaleup.yml*** playbook. This playbook queries the master, generates and distributes new certificates for the new hosts, and then runs the configuration playbooks on only the new hosts. Before running the ***scaleup.yml*** playbook, complete all prerequisite [host preparation](#) steps.



IMPORTANT

The ***scaleup.yml*** playbook configures only the new host. It does not update ***NO_PROXY*** in master services, and it does not restart master services.

You must have an existing inventory file, for example ***/etc/ansible/hosts***, that is representative of your current cluster configuration in order to run the ***scaleup.yml*** playbook. If you previously used the ***atomic-openshift-installer*** command to run your installation, you can check ***~/.config/openshift/hosts*** for the last inventory file that the installer generated and use that file as your inventory file. You can modify this file as required. You must then specify the file location with ***-i*** when you run the ***ansible-playbook***.



IMPORTANT

See the [cluster limits](#) section for the recommended maximum number of nodes.

Procedure

1. Ensure you have the latest playbooks by updating the ***atomic-openshift-utils*** package:

```
# yum update atomic-openshift-utils
```

2. Edit your ***/etc/ansible/hosts*** file and add ***new_<host_type>*** to the ***[OSEv3:children]*** section:
For example, to add a new node host, add ***new_nodes***:

```
[OSEv3:children]
masters
nodes
new_nodes
```

To add new master hosts, add ***new_masters***.

3. Create a ***[new_<host_type>]*** section to specify host information for the new hosts. Format this section like an existing section, as shown in the following example of adding a new node:

```
[nodes]
master[1:3].example.com
node1.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'east' }"
node2.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'west' }"
infra-node1.example.com openshift_node_labels="{ 'region': 'infra',
'zone': 'default' }"
infra-node2.example.com openshift_node_labels="{ 'region': 'infra',
'zone': 'default' }"

[new_nodes]
node3.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'west' }"
```

See [Configuring Host Variables](#) for more options.

When adding new masters, add hosts to both the **[new_masters]** section and the **[new_nodes]** section to ensure that the new master host is part of the OpenShift SDN.

```
[masters]
master[1:2].example.com

[new_masters]
master3.example.com

[nodes]
master[1:2].example.com
node1.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'east' }"
node2.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'west' }"
infra-node1.example.com openshift_node_labels="{ 'region': 'infra',
'zone': 'default' }"
infra-node2.example.com openshift_node_labels="{ 'region': 'infra',
'zone': 'default' }"

[new_nodes]
master3.example.com
```



IMPORTANT

If you label a master host with the **region=infra** label and have no other dedicated infrastructure nodes, you must also explicitly mark the host as schedulable by adding **openshift_schedulable=true** to the entry. Otherwise, the registry and router pods cannot be placed anywhere.

4. Run the **scaleup.yml** playbook. If your inventory file is located somewhere other than the default of **/etc/ansible/hosts**, specify the location with the **-i** option.
 - For additional nodes:

```
# ansible-playbook [-i /path/to/file] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
node/scaleup.yml
```

- For additional masters:

```
# ansible-playbook [-i /path/to/file] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
master/scaleup.yml
```

5. After the playbook runs, [verify the installation](#).
6. Move any hosts that you defined in the **[new_<host_type>]** section to their appropriate section. By moving these hosts, subsequent playbook runs that use this inventory file treat the nodes correctly. You can keep the empty **[new_<host_type>]** section. For example, when adding new nodes:

```
[nodes]
master[1:3].example.com
node1.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'east' }"
node2.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'west' }"
node3.example.com openshift_node_labels="{ 'region': 'primary',
'zone': 'west' }"
infra-node1.example.com openshift_node_labels="{ 'region': 'infra',
'zone': 'default' }"
infra-node2.example.com openshift_node_labels="{ 'region': 'infra',
'zone': 'default' }"

[new_nodes]
```

7.4. ADDING ETCD HOSTS TO EXISTING CLUSTER

You can add new etcd hosts to your cluster by running the *etcd scaleup* playbook. This playbook queries the master, generates and distributes new certificates for the new hosts, and then runs the configuration playbooks on the new hosts only. Before running the etcd **scaleup.yml** playbook, complete all prerequisite [host preparation](#) steps.

To add an etcd host to an existing cluster:

1. Ensure you have the latest playbooks by updating the **atomic-openshift-utils** package:

```
$ yum update atomic-openshift-utils
```

2. Edit your **/etc/ansible/hosts** file, add **new_<host_type>** to the **[OSEv3:children]** group and add hosts under the **new_<host_type>** group:
For example, to add a new etcd, add **new_etcd**:

```
[OSEv3:children]
masters
nodes
etcd
new_etcd
```

```
[etcd]
etcd1.example.com
etcd2.example.com

[new_etcd]
etcd3.example.com
```

3. Run the etcd **scaleup.yml** playbook. If your inventory file is located somewhere other than the default of **/etc/ansible/hosts**, specify the location with the **-i** option.


```
$ ansible-playbook [-i /path/to/file] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    etcd/scaleup.yml
```

4. After the playbook completes successfully, [verify the installation](#).

7.5. REPLACING EXISTING MASTERS WITH ETCD COLOCATED

Follow these steps when you are migrating your machines to a different data center and the network and IPs assigned to it will change.

1. Back up the primary [etcd](#) and [master](#) nodes.



IMPORTANT

Ensure that you back up the **/etc/etcd/** directory, as noted in the [etcd backup](#) instructions.

2. Provision as many new machines as there are masters to replace.
3. Add or expand the cluster. for example, if you want to add 3 masters with etcd colocated, scale up 3 master nodes or 3 etcd nodes.

- a. Add a [master](#). In step 3 of that process, add the host of the new data center in **[new_masters]** and **[new_nodes]** and run the master **scaleup.yml** playbook.

- b. Put the same host in the [etcd](#) section and run the etcd **scaleup.yml** playbook.

- c. Verify that the host was added:

```
# oc get nodes
```

- d. Verify that the master host IP was added:

```
# oc get ep kubernetes
```

- e. Verify that etcd was added. The value of **ETCDCTL_API** depends on the version being used:

```
# source /etc/etcd/etcd.conf
# ETCDCTL_API=2 etcdctl --cert-file=$ETCD_PEER_CERT_FILE --key-
file=$ETCD_PEER_KEY_FILE \
    --ca-file=/etc/etcd/ca.crt --endpoints=$ETCD_LISTEN_CLIENT_URLS
member list
```

-
- f. Copy **/etc/origin/master/ca.serial.txt** from the **/etc/origin/master** directory to the new master host that is listed first in your inventory file. By default, this is **/etc/ansible/hosts**.

4. Remove the etcd hosts.

- a. Copy the **/etc/etcd/ca** directory to the new etcd host that is listed first in your inventory file. By default, this is **/etc/ansible/hosts**.

- b. Remove the old etcd clients from the **master-config.yaml** file:

```
# grep etcdClientInfo -A 11 /etc/origin/master/master-config.yaml
```

- c. Restart the masters:

```
# systemctl restart atomic-openshift-master-*
```

- d. Remove the old etcd members from the cluster. The value of **ETCDCTL_API** depends on the version being used:

```
# source /etc/etcd/etcd.conf
# ETCDCTL_API=2 etcdctl --cert-file=$ETCD_PEER_CERT_FILE --key-
file=$ETCD_PEER_KEY_FILE \
  --ca-file=/etc/etcd/ca.crt --endpoints=$ETCD_LISTEN_CLIENT_URLS
member list
```

- e. Take the IDs from the output of the command above and remove the old members using the IDs:

```
# etcdctl --cert-file=$ETCD_PEER_CERT_FILE --key-
file=$ETCD_PEER_KEY_FILE \
  --ca-file=/etc/etcd/ca.crt --endpoints=$ETCD_LISTEN_CLIENT_URL
member remove 1609b5a3a078c227
```

- f. Stop and disable the etcd services on the old etcd hosts:

```
# systemctl stop etcd
# systemctl disable etcd
```

5. Shut down old master API and controller services:

```
# systemctl stop atomic-openshift-master-api
```

6. Remove the master nodes from the HA proxy configuration, which was installed as a load balancer by default during the native installation process.

7. Decommission the machine.

- a. Stop the **atomic-openshift-node** service on the master to be removed:

```
# systemctl stop atomic-openshift-node
```

- b. Delete the node resource:

–

```
# oc delete node
```

7.6. MIGRATING THE NODES

You can migrate nodes individually or in groups (of 2, 5, 10, and so on), depending on what you are comfortable with and how the services on the node are run and scaled.

1. For the migration node or nodes, provision new VMs for the node's use in the new data center.
2. To add the new node, [scale up the infrastructure](#). Ensure the labels for the new node are set properly and that your new API servers are added to your load balancer and successfully serving traffic.
3. Evaluate and scale down.
 - a. Mark the current node (in the old data center) [unscheduled](#).
 - b. [Evacuate the node](#), so that pods on it are scheduled to other nodes.
 - c. Verify that the evacuated services are running on the new nodes.
4. Remove the node.
 - a. Verify that the node is empty and does not have running processes.
 - b. Stop the service or delete the node.

CHAPTER 8. LOADING THE DEFAULT IMAGE STREAMS AND TEMPLATES

8.1. OVERVIEW

Your OpenShift Container Platform installation includes useful sets of Red Hat-provided [image streams](#) and [templates](#) to make it easy for developers to create new applications. By default, the [quick](#) and [advanced installation](#) methods automatically create these sets in the **openshift** project, which is a default global project to which all users have view access.

8.2. OFFERINGS BY SUBSCRIPTION TYPE

Depending on the active subscriptions on your Red Hat account, the following sets of image streams and templates are provided and supported by Red Hat. Contact your Red Hat sales representative for further subscription details.

8.2.1. OpenShift Container Platform Subscription

The core set of image streams and templates are provided and supported with an active *OpenShift Container Platform subscription*. This includes the following technologies:

Type	Technology
Languages & Frameworks	<ul style="list-style-type: none"> • .NET Core • Node.js • Perl • PHP • Python • Ruby
Databases	<ul style="list-style-type: none"> • MongoDB • MySQL • PostgreSQL
Middleware Services	<ul style="list-style-type: none"> • Red Hat JBoss Web Server (Tomcat) • Red Hat Single Sign-on
Other Services	<ul style="list-style-type: none"> • Jenkins

8.2.2. xPaaS Middleware Add-on Subscriptions

Support for xPaaS middleware images are provided by *xPaaS Middleware add-on subscriptions*, which are separate subscriptions for each xPaaS product. If the relevant subscription is active on your account, image streams and templates are provided and supported for the following technologies:

Type	Technology
Middleware Services	<ul style="list-style-type: none"> • Red Hat JBoss A-MQ • Red Hat JBoss BPM Suite Intelligent Process Server • Red Hat JBoss BRMS Decision Server • Red Hat JBoss Data Grid • Red Hat JBoss EAP • Red Hat JBoss Fuse Integration Services • Red Hat JBoss Data Virtualization

8.3. BEFORE YOU BEGIN

Before you consider performing the tasks in this topic, confirm if these image streams and templates are already registered in your OpenShift Container Platform cluster by doing one of the following:

- Log into the web console and click **Add to Project**.
- List them for the **openshift** project using the CLI:

```
$ oc get is -n openshift
$ oc get templates -n openshift
```

If the default image streams and templates are ever removed or changed, you can follow this topic to create the default objects yourself. Otherwise, the following instructions are not necessary.

8.4. PREREQUISITES

Before you can create the default image streams and templates:

- The [integrated Docker registry](#) service must be deployed in your OpenShift Container Platform installation.
- You must be able to run the **oc create** command with [cluster-admin privileges](#), because they operate on the default **openshiftproject**.
- You must have installed the **atomic-openshift-utils** RPM package. See [Software Prerequisites](#) for instructions.
- Define shell variables for the directories containing image streams and templates. This significantly shortens the commands in the following sections. To do this:

```
$ IMAGESTREAMDIR="/usr/share/ansible/openshift-
```

```

ansible/roles/openshift_examples/files/examples/v3.7/image-streams";
\
    XPAASSTREAMDIR="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.7/xpaas-streams";
\
    XPAASTEMPLATES="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.7/xpaas-
templates"; \
    DBTEMPLATES="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.7/db-templates";
\
    QSTEMPLATES="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.7/quickstart-
templates"

```

8.5. CREATING IMAGE STREAMS FOR OPENSIFT CONTAINER PLATFORM IMAGES

If your node hosts are subscribed using Red Hat Subscription Manager and you want to use the core set of image streams that used Red Hat Enterprise Linux (RHEL) 7 based images:

```
$ oc create -f $IMAGESTREAMDIR/image-streams-rhel7.json -n openshift
```

Alternatively, to create the core set of image streams that use the CentOS 7 based images:

```
$ oc create -f $IMAGESTREAMDIR/image-streams-centos7.json -n openshift
```

Creating both the CentOS and RHEL sets of image streams is not possible, because they use the same names. To have both sets of image streams available to users, either create one set in a different project, or edit one of the files and modify the image stream names to make them unique.

8.6. CREATING IMAGE STREAMS FOR XPAAS MIDDLEWARE IMAGES

The xPaaS Middleware image streams provide images for **JBoss EAP**, **JBoss JWS**, **JBoss A-MQ**, **JBoss Fuse Integration Services**, **Decision Server**, **JBoss Data Virtualization** and **JBoss Data Grid**. They can be used to build applications for those platforms using the provided templates.

To create the xPaaS Middleware set of image streams:

```
$ oc create -f $XPAASSTREAMDIR/jboss-image-streams.json -n openshift
```



NOTE

Access to the images referenced by these image streams requires the relevant xPaaS Middleware subscriptions.

8.7. CREATING DATABASE SERVICE TEMPLATES

The database service templates make it easy to run a database image which can be utilized by other components. For each database ([MongoDB](#), [MySQL](#), and [PostgreSQL](#)), two templates are defined.

One template uses ephemeral storage in the container which means data stored will be lost if the container is restarted, for example if the pod moves. This template should be used for demonstration purposes only.

The other template defines a persistent volume for storage, however it requires your OpenShift Container Platform installation to have [persistent volumes](#) configured.

To create the core set of database templates:

```
$ oc create -f $DBTEMPLATES -n openshift
```

After creating the templates, users are able to easily instantiate the various templates, giving them quick access to a database deployment.

8.8. CREATING INSTANT APP AND QUICKSTART TEMPLATES

The Instant App and Quickstart templates define a full set of objects for a running application. These include:

- [Build configurations](#) to build the application from source located in a GitHub public repository
- [Deployment configurations](#) to deploy the application image after it is built.
- [Services](#) to provide load balancing for the application [pods](#).
- [Routes](#) to provide external access to the application.

Some of the templates also define a database deployment and service so the application can perform database operations.



NOTE

The templates which define a database use ephemeral storage for the database content. These templates should be used for demonstration purposes only as all database data will be lost if the database pod restarts for any reason.

Using these templates, users are able to easily instantiate full applications using the various language images provided with OpenShift Container Platform. They can also customize the template parameters during instantiation so that it builds source from their own repository rather than the sample repository, so this provides a simple starting point for building new applications.

To create the core Instant App and Quickstart templates:

```
$ oc create -f $QSTEMPLATES -n openshift
```

There is also a set of templates for creating applications using various xPaaS Middleware products (**JBoss EAP**, **JBoss JWS**, **JBoss A-MQ**, **JBoss Fuse Integration Services**, **Decision Server**, and **JBoss Data Grid**), which can be registered by running:

```
$ oc create -f $XPAASTEMPLATES -n openshift
```

**NOTE**

The xPaaS Middleware templates require the [xPaaS Middleware image streams](#), which in turn require the relevant xPaaS Middleware subscriptions.

**NOTE**

The templates which define a database use ephemeral storage for the database content. These templates should be used for demonstration purposes only as all database data will be lost if the database pod restarts for any reason.

8.9. WHAT'S NEXT?

With these artifacts created, developers can now [log into the web console](#) and follow the flow for [creating from a template](#). Any of the database or application templates can be selected to create a running database service or application in the current project. Note that some of the application templates define their own database services as well.

The example applications are all built out of GitHub repositories which are referenced in the templates by default, as seen in the **SOURCE_REPOSITORY_URL** parameter value. Those repositories can be forked, and the fork can be provided as the **SOURCE_REPOSITORY_URL** parameter value when creating from the templates. This allows developers to experiment with creating their own applications.

You can direct your developers to the [Using the Instant App and Quickstart Templates](#) section in the Developer Guide for these instructions.

CHAPTER 9. CONFIGURING CUSTOM CERTIFICATES

9.1. OVERVIEW

Administrators can configure custom serving certificates for the public host names of the OpenShift Container Platform API and [web console](#). This can be done during an [advanced installation](#) or configured after installation.

9.2. CONFIGURING CUSTOM CERTIFICATES DURING INSTALLATION

During [advanced installations](#), custom certificates can be configured using the `openshift_master_named_certificates` and `openshift_master_overwrite_named_certificates` parameters, which are configurable in the inventory file. More details are available about [configuring custom certificates with Ansible](#).

Custom Certificate Configuration Parameters

```
openshift_master_overwrite_named_certificates=true ❶
openshift_master_named_certificates=[{"certfile": "/path/on/host/to/crt-
file", "keyfile": "/path/on/host/to/key-file", "names": ["public-master-
host.com"], "cafile": "/path/on/host/to/ca-file"}] ❷
openshift_hosted_router_certificate={"certfile": "/path/on/host/to/app-
crt-file", "keyfile": "/path/on/host/to/app-key-file", "cafile":
"/path/on/host/to/app-ca-file"} ❸
```

- ❶ If you provide a value for the `openshift_master_named_certificates` parameter, set this parameter to **true**.
- ❷ Provisions a [master API certificate](#).
- ❸ Provisions a [wildcard API certificate](#).

Example parameters for a master API certificate:

```
openshift_master_overwrite_named_certificates=true
openshift_master_named_certificates=[{"names":
["master.148.251.233.173.nip.io"], "certfile": "/home/cloud-user/master-
bundle.cert.pem", "keyfile": "/home/cloud-
user/master.148.251.233.173.nip.io.key.pem" ]
```

Example parameters for a wildcard API certificate:

```
openshift_hosted_router_certificate={"certfile": "/home/cloud-user/star-
apps.148.251.233.173.nip.io.cert.pem", "keyfile": "/home/cloud-user/star-
apps.148.251.233.173.nip.io.key.pem", "cafile": "/home/cloud-user/ca-
chain.cert.pem"}
```


9.3. CONFIGURING CUSTOM CERTIFICATES FOR THE WEB CONSOLE OR CLI

You can specify custom certificates for the web console and for the CLI through the **servingInfo** section of the [master configuration file](#):

- The **servingInfo.namedCertificates** section serves up custom certificates for the web console.
- The **servingInfo** section serves up custom certificates for the CLI and other API calls.

You can configure multiple certificates this way, and each certificate can be associated with [multiple host names](#), [multiple routers](#), or the [OpenShift Container Platform image registry](#).

A default certificate must be configured in the **servingInfo.certFile** and **servingInfo.keyFile** configuration sections in addition to **namedCertificates**.



NOTE

The **namedCertificates** section should be configured for only the host name associated with the **masterPublicURL**, **assetConfig.publicURL**, and **oauthConfig.assetPublicURL** settings. Using a custom serving certificate for the host name associated with the **masterURL** will result in TLS errors as infrastructure components will attempt to contact the master API using the internal **masterURL** host.

Custom Certificates Configuration

```
servingInfo:
  logoutURL: ""
  masterPublicURL: https://openshift.example.com:8443
  publicURL: https://openshift.example.com:8443/console/
  bindAddress: 0.0.0.0:8443
  bindNetwork: tcp4
  certFile: master.server.crt 1
  clientCA: ""
  keyFile: master.server.key 2
  maxRequestsInFlight: 0
  requestTimeoutSeconds: 0
  namedCertificates:
    - certFile: wildcard.example.com.crt 3
      keyFile: wildcard.example.com.key 4
      names:
        - "openshift.example.com"
  metricsPublicURL: "https://metrics.os.example.com/hawkular/metrics"
```

1 2 Path to certificate and key files for the CLI and other API calls.

3 4 Path to certificate and key files for the web console.

The **openshift_master_cluster_public_hostname** and **openshift_master_cluster_hostname** parameters in the [Ansible inventory file](#), by default **/etc/ansible/hosts**, must be different. If they are the same, the named certificates will fail and you will need to re-install them.

```
# Native HA with External LB VIPs
openshift_master_cluster_hostname=internal.paas.example.com
openshift_master_cluster_public_hostname=external.paas.example.com
```

For more information on using DNS with OpenShift Container Platform, see the [DNS installation prerequisites](#).

This approach allows you to take advantage of the self-signed certificates generated by OpenShift Container Platform and add custom trusted certificates to individual components as needed.

Note that the internal infrastructure certificates remain self-signed, which might be perceived as bad practice by some security or PKI teams. However, any risk here is minimal, as the only clients that trust these certificates are other components within the cluster. All external users and systems use custom trusted certificates.

Relative paths are resolved based on the location of the master configuration file. Restart the server to pick up the configuration changes.

9.4. CONFIGURING A CUSTOM MASTER HOST CERTIFICATE

In order to facilitate trusted connections with external users of OpenShift Container Platform, you can provision a named certificate that matches the domain name provided in the **openshift_master_cluster_public_hostname** parameter in the [Ansible inventory file](#), by default **/etc/ansible/hosts**.

You must place this certificate in a directory accessible to Ansible and add the path in the Ansible inventory file, as follows:

```
openshift_master_named_certificates=[{"certfile": "/path/to/console.ocp-c1.myorg.com.crt", "keyfile": "/path/to/console.ocp-c1.myorg.com.key", "names": ["console.ocp-c1.myorg.com"]}]
```

Where the parameter values are:

- **certfile** is the path to the file that contains the OpenShift Container Platform router certificate.
- **keyfile** is the path to the file that contains the OpenShift Container Platform wildcard key.
- **names** is the cluster public hostname.

The file paths must be local to the system where Ansible runs. Certificates are copied to master hosts and are deployed within the **/etc/origin/master/named_certificates/** directory.

When securing the registry, add the service hostnames and IP addresses to the server certificate for the registry. The Subject Alternative Names (SAN) must contain the following.

- Two service hostnames:

```
docker-registry.default.svc.cluster.local
docker-registry.default.svc
```

- Service IP address.
For example:

```
172.30.252.46
```


■

Use the following command to get the Docker registry service IP address:

```
oc get service docker-registry --template='{{.spec.clusterIP}}'
```

- Public hostname.

```
docker-registry-default.apps.example.com
```

Use the following command to get the Docker registry public hostname:

```
oc get route docker-registry --template '{{.spec.host}}'
```

For example, the server certificate should contain SAN details similar to the following:

```
X509v3 Subject Alternative Name:
                DNS:docker-registry-public.openshift.com, DNS:docker-
registry.default.svc, DNS:docker-registry.default.svc.cluster.local,
DNS:172.30.2.98, IP Address:172.30.2.98
```

9.5. CONFIGURING A CUSTOM WILDCARD CERTIFICATE FOR THE DEFAULT ROUTER

You can configure the OpenShift Container Platform default router with a default wildcard certificate. A default wildcard certificate provides a convenient way for applications that are deployed in OpenShift Container Platform to use default encryption without needing custom certificates.



NOTE

Default wildcard certificates are recommended for non-production environments only.

In order to configure a default wildcard certificate, provision a certificate that is valid for `.<app_domain>`, where `<app_domain>` is the value of `openshift_master_default_subdomain` in the [Ansible inventory file](#), by default `/etc/ansible/hosts`. Once provisioned, place the certificate, key, and ca certificate files on your Ansible host, and add the following line to your Ansible inventory file.

```
openshift_hosted_router_certificate={"certfile": "/path/to/apps.c1-
ocp.myorg.com.crt", "keyfile": "/path/to/apps.c1-ocp.myorg.com.key",
"cafile": "/path/to/apps.c1-ocp.myorg.com.ca.crt"}
```

For example:

```
openshift_hosted_router_certificate={"certfile": "/home/cloud-user/star-
apps.148.251.233.173.nip.io.cert.pem", "keyfile": "/home/cloud-user/star-
apps.148.251.233.173.nip.io.key.pem", "cafile": "/home/cloud-user/ca-
chain.cert.pem"}
```

Where the parameter values are:

- **certfile** is the path to the file that contains the OpenShift Container Platform router certificate.

- **keyfile** is the path to the file that contains the OpenShift Container Platform wildcard key.
- **cafile** is the path to the file that contains the root CA for this key and certificate. If an intermediate CA is in use, the file should contain both the intermediate and root CA.

If these certificate files are new to your OpenShift Container Platform cluster, run the Ansible **byo/config.yml** playbook to add these files to the OpenShift Container Platform configuration files. The playbook adds the certificate files to the **/etc/origin/master/** directory.

```
# ansible-playbook [-i /path/to/inventory] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/config.yml
```

If [the certificates are not new](#), for example, you want to change existing certificates or replace expired certificates, run the following playbook:

```
ansible-playbook /usr/share/ansible/openshift-ansible/playbooks/redeploy-
certificates.yml
```



NOTE

For this playbook to run, the certificate names must not change. If the certificate names change, rerun the Ansible **byo/config.yml** playbook as if the certificates were new.

9.6. CONFIGURING A CUSTOM CERTIFICATE FOR THE IMAGE REGISTRY

The OpenShift Container Platform image registry is an internal service that facilitates builds and deployments. Most of the communication with the registry is handled by internal components in OpenShift Container Platform. As such, you should not need to replace the certificate used by the registry service itself.

However, by default, the registry uses routes to allow external systems and users to do pulls and pushes of images. You can use a *re-encrypt route* with a custom certificate that is presented to external users instead of using the internal, self-signed certificate.

To configure this, add the [following lines](#) of code to the [OSEv3:vars] section of the Ansible inventory file, by default **/etc/ansible/hosts** file. Specify the certificates to use with the registry route.

```
openshift_hosted_registry_routehost=registry.apps.c1-ocp.myorg.com ❶
openshift_hosted_registry_routecertificates={"certfile":
"/path/to/registry.apps.c1-ocp.myorg.com.crt", "keyfile":
"/path/to/registry.apps.c1-ocp.myorg.com.key", "cafile":
"/path/to/registry.apps.c1-ocp.myorg.com-ca.crt"} ❷
openshift_hosted_registry_routetermination=reencrypt ❸
```

❶ The host name of the registry.

❷ The locations of the **cacert**, **root**, and **cafile** files.

- **certfile** is the path to the file that contains the OpenShift Container Platform router certificate.
- **keyfile** is the path to the file that contains the OpenShift Container Platform wildcard key.

- **cafile** is the path to the file that contains the root CA for this key and certificate. If an intermediate CA is in use, the file should contain both the intermediate and root CA.

3 Specify where encryption is performed:

- Set to **reencrypt** with a *re-encrypt route* to terminate encryption at the edge router and re-encrypt it with a new certificate supplied by the destination.
- Set to **passthrough** to terminate encryption at the destination. The destination is responsible for decrypting traffic.

9.7. CONFIGURING A CUSTOM CERTIFICATE FOR A LOAD BALANCER

If your OpenShift Container Platform cluster uses the default load balancer or an enterprise-level load balancer, you can use custom certificates to make the web console and API available externally using a publicly-signed custom certificate. Leaving the existing internal certificates for the internal endpoints.

To configure OpenShift Container Platform to use custom certificates in this way:

1. Edit the **servingInfo** section of the [master configuration file](#):

```
servingInfo:
  logoutURL: ""
  masterPublicURL: https://openshift.example.com:8443
  publicURL: https://openshift.example.com:8443/console/
  bindAddress: 0.0.0.0:8443
  bindNetwork: tcp4
  certFile: master.server.crt
  clientCA: ""
  keyFile: master.server.key
  maxRequestsInFlight: 0
  requestTimeoutSeconds: 0
  namedCertificates:
    - certFile: wildcard.example.com.crt 1
      keyFile: wildcard.example.com.key 2
      names:
        - "openshift.example.com"
  metricsPublicURL:
    "https://metrics.os.example.com/hawkular/metrics"
```

1 Path to the certificate file for the web console.

2 Path to the key file for the web console.



NOTE

Configure the **namedCertificates** section for only the host name associated with the **masterPublicURL** and **oauthConfig.assetPublicURL** settings. Using a custom serving certificate for the host name associated with the **masterURL** causes TLS errors as infrastructure components attempt to contact the master API using the internal masterURL host.

- Specify the `openshift_master_cluster_public_hostname` and `openshift_master_cluster_hostname` parameters in the Ansible inventory file, by default `/etc/ansible/hosts`. These values must be different. If they are the same, the named certificates will fail.

```
# Native HA with External LB VIPs
openshift_master_cluster_hostname=paas.example.com 1
openshift_master_cluster_public_hostname=public.paas.example.com 2
```

- 1 The FQDN for internal load balancer configured for SSL passthrough.
- 2 The FQDN for external the load balancer with custom (public) certificate.

For information specific to your load balancer environment, refer to [the OpenShift Container Platform Reference Architecture for your provider](#) and [Custom Certificate SSL Termination \(Production\)](#).

9.8. RETROFIT CUSTOM CERTIFICATES INTO A CLUSTER

You can retrofit custom master and custom router certificates into an existing OpenShift Container Platform cluster by editing the the Ansible inventory file, by default `/etc/ansible/hosts`, and running a playbook.

9.8.1. Retrofit Custom Master Certificates into a Cluster

To retrofit custom certificates:

- Edit the Ansible inventory file to set the `openshift_master_overwrite_named_certificates=true`.
- Specify the path to the certificate using the `openshift_master_named_certificates` parameter.

```
openshift_master_overwrite_named_certificates=true
openshift_master_named_certificates=[{"certfile":
"/path/on/host/to/crt-file", "keyfile": "/path/on/host/to/key-file",
"names": ["public-master-host.com"], "cafile": "/path/on/host/to/ca-
file"}] 1
```

- 1 Path to a [master API certificate](#).

- Run the following playbook:

```
ansible-playbook /usr/share/ansible/openshift-
ansible/playbooks/redeploy-certificates.yml
```

9.8.2. Retrofit Custom Router Certificates into a Cluster

To retrofit custom router certificates:

- Edit the Ansible inventory file to set the `openshift_master_overwrite_named_certificates=true`.

2. Specify the path to the certificate using the **openshift_hosted_router_certificate** parameter.

```
openshift_master_overwrite_named_certificates=true
openshift_hosted_router_certificate={"certfile":
"/path/on/host/to/app-crt-file", "keyfile": "/path/on/host/to/app-
key-file", "cafile": "/path/on/host/to/app-ca-file"} ❶
```

- ❶ Path to a [wildcard API certificate](#).

3. Run the following playbook:

```
ansible-playbook /usr/share/ansible/openshift-
ansible/playbooks/byo/openshift-cluster/redeploy-router-
certificates.yml
```

9.9. USING CUSTOM CERTIFICATES WITH OTHER COMPONENTS

For information on how other components, such as Logging & Metrics, use custom certificates, see [Certificate Management](#).

CHAPTER 10. REDEPLOYING CERTIFICATES

10.1. OVERVIEW

OpenShift Container Platform uses certificates to provide secure connections for the following components:

- masters (API server and controllers)
- etcd
- nodes
- registry
- router

You can use Ansible playbooks provided with the installer to automate checking expiration dates for cluster certificates. Playbooks are also provided to automate backing up and redeploying these certificates, which can fix common certificate errors.

Possible use cases for redeploying certificates include:

- The installer detected the wrong host names and the issue was identified too late.
- The certificates are expired and you need to update them.
- You have a new CA and want to create certificates using it instead.

10.2. CHECKING CERTIFICATE EXPIRATIONS

You can use the installer to warn you about any certificates expiring within a configurable window of days and notify you about any certificates that have already expired. Certificate expiry playbooks use the Ansible role **openshift_certificate_expiry**.

Certificates examined by the role include:

- Master and node service certificates
- Router and registry service certificates from etcd secrets
- Master, node, router, registry, and *kubeconfig* files for **cluster-admin** users
- etcd certificates (including embedded)

10.2.1. Role Variables

The **openshift_certificate_expiry** role uses the following variables:

Table 10.1. Core Variables

Variable Name	Default Value	Description
<code>openshift_certificate_expiry_config_base</code>	<code>/etc/origin</code>	Base OpenShift Container Platform configuration directory.
<code>openshift_certificate_expiry_warning_days</code>	<code>30</code>	Flag certificates that will expire in this many days from now.
<code>openshift_certificate_expiry_show_all</code>	<code>no</code>	Include healthy (non-expired and non-warning) certificates in results.

Table 10.2. Optional Variables

Variable Name	Default Value	Description
<code>openshift_certificate_expiry_generate_html_report</code>	<code>no</code>	Generate an HTML report of the expiry check results.
<code>openshift_certificate_expiry_html_report_path</code>	<code>/tmp/cert-expiry-report.html</code>	The full path for saving the HTML report.
<code>openshift_certificate_expiry_save_json_results</code>	<code>no</code>	Save expiry check results as a JSON file.
<code>openshift_certificate_expiry_json_results_path</code>	<code>/tmp/cert-expiry-report.json</code>	The full path for saving the JSON report.

10.2.2. Running Certificate Expiration Playbooks

The OpenShift Container Platform installer provides a set of example certificate expiration playbooks, using different sets of configuration for the `openshift_certificate_expiry` role.

These playbooks must be used with an [inventory file](#) that is representative of the cluster. For best results, run **ansible-playbook** with the `-v` option.

Using the ***easy-mode.yaml*** example playbook, you can try the role out before tweaking it to your specifications as needed. This playbook:

- Produces JSON and stylized HTML reports in */tmp/*.
- Sets the warning window very large, so you will almost always get results back.
- Includes all certificates (healthy or not) in the results.

easy-mode.yaml Playbook

```
- name: Check cert expirys
  hosts: nodes:masters:etcd
  become: yes
```

```
gather_facts: no
vars:
  openshift_certificate_expiry_warning_days: 1500
  openshift_certificate_expiry_save_json_results: yes
  openshift_certificate_expiry_generate_html_report: yes
  openshift_certificate_expiry_show_all: yes
roles:
  - role: openshift_certificate_expiry
```

To run the ***easy-mode.yaml*** playbook:

```
$ ansible-playbook -v -i <inventory_file> \
  /usr/share/ansible/openshift-
  ansible/playbooks/certificate_expiry/easy-mode.yaml
```

Other Example Playbooks

The other example playbooks are also available to run directly out of the ***/usr/share/ansible/openshift-ansible/playbooks/certificate_expiry/*** directory.

Table 10.3. Other Example Playbooks

File Name	Usage
<i>default.yaml</i>	Produces the default behavior of the <i>openshift_certificate_expiry</i> role.
<i>html_and_json_default_paths.yaml</i>	Generates HTML and JSON artifacts in their default paths.
<i>longer_warning_period.yaml</i>	Changes the expiration warning window to 1500 days.
<i>longer-warning-period-json-results.yaml</i>	Changes the expiration warning window to 1500 days and saves the results as a JSON file.

To run any of these example playbooks:

```
$ ansible-playbook -v -i <inventory_file> \
  /usr/share/ansible/openshift-
  ansible/playbooks/certificate_expiry/<playbook>
```

10.2.3. Output Formats

As noted above, there are two ways to format your check report. In JSON format for machine parsing, or as a stylized HTML page for easy skimming.

HTML Report

An example of an HTML report is provided with the installer. You can open the following file in your browser to view it:

/usr/share/ansible/openshift-ansible/roles/openshift_certificate_expiry/examples/cert-expiry-report.html

JSON Report

There are two top-level keys in the saved JSON results: **data** and **summary**.

The **data** key is a hash where the keys are the names of each host examined and the values are the check results for the certificates identified on each respective host.

The **summary** key is a hash that summarizes the total number of certificates:

- examined on the entire cluster
- that are OK
- expiring within the configured warning window
- already expired

For an example of the full JSON report, see */usr/share/ansible/openshift-ansible/roles/openshift_certificate_expiry/examples/cert-expiry-report.json*.

The summary from the JSON data can be easily checked for warnings or expirations using a variety of command-line tools. For example, using **grep** you can look for the word **summary** and print out the two lines after the match (**-A2**):

```
$ grep -A2 summary /tmp/cert-expiry-report.json
    "summary": {
        "warning": 16,
        "expired": 0
```

If available, the **jq** tool can also be used to pick out specific values. The first two examples below show how to select just one value, either **warning** or **expired**. The third example shows how to select both values at once:

```
$ jq '.summary.warning' /tmp/cert-expiry-report.json
16

$ jq '.summary.expired' /tmp/cert-expiry-report.json
0

$ jq '.summary.warning, .summary.expired' /tmp/cert-expiry-report.json
16
0
```

10.3. REDEPLOYING CERTIFICATES

Use the following playbooks to redeploy master, etcd, node, registry, and router certificates on all relevant hosts. You can redeploy all of them at once using the current CA, redeploy certificates for specific components only, or redeploy a newly generated or custom CA on its own.

Just like the certificate expiry playbooks, these playbooks must be run with an [inventory file](#) that is representative of the cluster.

In particular, the inventory must specify or override all host names and IP addresses set via the following variables such that they match the current cluster configuration:

- **openshift_hostname**

- `openshift_public_hostname`
- `openshift_ip`
- `openshift_public_ip`
- `openshift_master_cluster_hostname`
- `openshift_master_cluster_public_hostname`


The playbooks you need are provided by:

```
# yum install atomic-openshift-utils
```



NOTE

The validity (length in days until they expire) for any certificates auto-generated while redeploying can be configured via Ansible as well. See [Configuring Certificate Validity](#).



NOTE

OpenShift Container Platform CA and etcd certificates expire after five years. Signed OpenShift Container Platform certificates expire after two years.

10.3.1. Redeploying All Certificates Using the Current OpenShift Container Platform and etcd CA

The ***redeploy-certificates.yml*** playbook does *not* regenerate the OpenShift Container Platform CA certificate. New master, etcd, node, registry, and router certificates are created using the current CA certificate to sign new certificates.

This also includes serial restarts of:

- etcd
- master services
- node services

To redeploy master, etcd, and node certificates using the current OpenShift Container Platform CA, run this playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/redeploy-certificates.yml
```

10.3.2. Redeploying a New or Custom OpenShift Container Platform CA

The ***redeploy-openshift-ca.yml*** playbook redeploys the OpenShift Container Platform CA certificate by generating a new CA certificate and distributing an updated bundle to all components including client ***kubeconfig*** files and the node's database of trusted CAs (the CA-trust).

This also includes serial restarts of:

- master services
- node services
- docker

Additionally, you can specify a [custom CA certificate](#) when redeploying certificates instead of relying on a CA generated by OpenShift Container Platform.

When the master services are restarted, the registry and routers can continue to communicate with the master without being redeployed because the master's serving certificate is the same, and the CA the registry and routers have are still valid.

To redeploy a newly generated or custom CA:

1. If you want to use a custom CA, set the following variable in your inventory file. To use the current CA, skip this step.

```
# Configure custom ca certificate
# NOTE: CA certificate will not be replaced with existing clusters.
# This option may only be specified when creating a new cluster or
# when redeploying cluster certificates with the redeploy-
# certificates
# playbook.
openshift_master_ca_certificate={'certfile': '</path/to/ca.crt>',
'keyfile': '</path/to/ca.key>'}
```

If the CA certificate is issued by an intermediate CA, the bundled certificate must contain the full chain (the intermediate and root certificates) for the CA in order to validate child certificates.

For example:

```
$ cat intermediate/certs/intermediate.cert.pem \
    certs/ca.cert.pem >> intermediate/certs/ca-chain.cert.pem
```

2. Run the ***redploy-openshift-ca.yml*** playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/redeploy-openshift-ca.yml
```

With the new OpenShift Container Platform CA in place, you can then use the [redploy-certificates.yml](#) [playbook](#) at your discretion whenever you want to redeploy certificates signed by the new CA on all components.

10.3.3. Redeploying a New etcd CA

The ***redploy-etcd-ca.yml*** playbook redeploys the etcd CA certificate by generating a new CA certificate and distributing an updated bundle to all etcd peers and master clients.

This also includes serial restarts of:

- etcd
- master services

**NOTE**

The ***redeploy-etcd-ca.yml*** playbook is only available for OpenShift Container Platform v3.5.91-1 and above.

To redeploy a newly generated etcd CA:

1. Run the ***redeploy-etcd-ca.yml*** playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/redeploy-etcd-ca.yml
```

With the new etcd CA in place, you can then use the [redeploy-etcd-certificates.yml](#) [playbook](#) at your discretion whenever you want to redeploy certificates signed by the new etcd CA on etcd peers and master clients. Alternatively, you can use the [redeploy-certificates.yml](#) [playbook](#) to redeploy certificates for OpenShift Container Platform components in addition to etcd peers and master clients.

10.3.4. Redeploying Master Certificates Only

The ***redeploy-master-certificates.yml*** playbook only redeploys master certificates. This also includes serial restarts of master services.

To redeploy master certificates, run this playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/redeploy-master-certificates.yml
```

**NOTE**

After running this playbook, you need to regenerate any [service signing certificate or key pairs](#) by deleting existing secrets that contain service serving certificates or removing and re-adding annotations to appropriate services.

10.3.5. Redeploying etcd Certificates Only

The ***redeploy-etcd-certificates.yml*** playbook only redeploys etcd certificates including master client certificates.

This also include serial restarts of:

- etcd
- master services.

To redeploy etcd certificates, run this playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/redeploy-etcd-certificates.yml
```

10.3.6. Redeploying Node Certificates Only

The ***redeploy-node-certificates.yml*** playbook only redeploys node certificates. This also include serial restarts of node services.

To redeploy node certificates, run this playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/redeploy-node-certificates.yml
```

10.3.7. Redeploying Registry or Router Certificates Only

The ***redeploy-registry-certificates.yml*** and ***redeploy-router-certificates.yml*** playbooks replace installer-created certificates for the registry and router. If custom certificates are in use for these components, see [Redeploying Custom Registry or Router Certificates](#) to replace them manually.

10.3.7.1. Redeploying Registry Certificates Only

To redeploy registry certificates, run the following playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/redeploy-registry-certificates.yml
```

10.3.7.2. Redeploying Router Certificates Only

To redeploy router certificates, run the following playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/redeploy-router-certificates.yml
```

10.3.8. Redeploying Custom Registry or Router Certificates

When nodes are evacuated due to a redeployed CA, registry and router pods are restarted. If the registry and router certificates were not also redeployed with the new CA, this can cause outages because they cannot reach the masters using their old certificates.

The playbooks for redeploying certificates cannot redeploy custom registry or router certificates, so to address this issue, you can manually redeploy the registry and router certificates.

10.3.8.1. Redeploying Registry Certificates Manually

To redeploy registry certificates manually, you must add new registry certificates to a secret named **registry-certificates**, then redeploy the registry:

1. Switch to the **default** project for the remainder of these steps:

```
$ oc project default
```

2. If your registry was initially created on OpenShift Container Platform 3.1 or earlier, it may still be using environment variables to store certificates (which has been deprecated in favor of using secrets).

- a. Run the following and look for the **OPENSIFT_CA_DATA**, **OPENSIFT_CERT_DATA**, **OPENSIFT_KEY_DATA** environment variables:

```
$ oc env dc/docker-registry --list
```

- b. If they do not exist, skip this step. If they do, create the following **ClusterRoleBinding**:

```
$ cat <<EOF |
apiVersion: v1
groupNames: null
kind: ClusterRoleBinding
metadata:
  creationTimestamp: null
  name: registry-registry-role
roleRef:
  kind: ClusterRole
  name: system:registry
subjects:
- kind: ServiceAccount
  name: registry
  namespace: default
userNames:
- system:serviceaccount:default:registry
EOF
oc create -f -
```

Then, run the following to remove the environment variables:

```
$ oc env dc/docker-registry OPENSIFT_CA_DATA-
OPENSIFT_CERT_DATA- OPENSIFT_KEY_DATA- OPENSIFT_MASTER-
```

3. Set the following environment variables locally to make later commands less complex:

```
$ REGISTRY_IP=`oc get service docker-registry -o
jsonpath='{.spec.clusterIP}'`
$ REGISTRY_HOSTNAME=`oc get route/docker-registry -o
jsonpath='{.spec.host}'`
```

4. Create new registry certificates:

```
$ oc adm ca create-server-cert \
--signer-cert=/etc/origin/master/ca.crt \
--signer-key=/etc/origin/master/ca.key \
--hostnames=$REGISTRY_IP,docker-registry.default.svc,docker-
registry.default.svc.cluster.local,$REGISTRY_HOSTNAME
--cert=/etc/origin/master/registry.crt \
--key=/etc/origin/master/registry.key \
--signer-serial=/etc/origin/master/ca.serial.txt
```

Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

5. Update the **registry-certificates** secret with the new registry certificates:

```
$ oc secret new registry-certificates \
  /etc/origin/master/registry.crt \
  /etc/origin/master/registry.key \
  -o json | oc replace -f -
```

6. Redeploy the registry:

```
$ oc deploy dc/docker-registry --latest
```

10.3.8.2. Redeploying Router Certificates Manually

When routers are initially deployed, an annotation is added to the router's service that automatically creates a [service serving certificate secret](#).

To redeploy router certificates manually, that service serving certificate can be triggered to be recreated by deleting the secret, removing and re-adding annotations to the **router** service, then redeploying the router:

1. Switch to the **default** project for the remainder of these steps:

```
$ oc project default
```

2. If your router was initially created on OpenShift Container Platform 3.1 or earlier, it might still use environment variables to store certificates, which has been deprecated in favor of using service serving certificate secret.

- a. Run the following command and look for the **OPENSIFT_CA_DATA**, **OPENSIFT_CERT_DATA**, **OPENSIFT_KEY_DATA** environment variables:

```
$ oc env dc/router --list
```

- b. If those variables exist, create the following **ClusterRoleBinding**:

```
$ cat <<EOF |
apiVersion: v1
groupNames: null
kind: ClusterRoleBinding
metadata:
  creationTimestamp: null
  name: router-router-role
roleRef:
  kind: ClusterRole
  name: system:router
subjects:
- kind: ServiceAccount
  name: router
  namespace: default
userNames:
- system:serviceaccount:default:router
EOF
oc create -f -
```

- c. If those variables exist, run the following command to remove them:

■

```
$ oc env dc/router OPENSIFT_CA_DATA- OPENSIFT_CERT_DATA-
OPENSIFT_KEY_DATA- OPENSIFT_MASTER-
```

3. Obtain a certificate.

- If you use an external Certificate Authority (CA) to sign your certificates, create a new certificate and provide it to OpenShift Container Platform by following your internal processes.
- If you use the internal OpenShift Container Platform CA to sign certificates, run the following commands:



IMPORTANT

The following commands generate a certificate that is internally signed. It will be trusted by only clients that trust the OpenShift Container Platform CA.

```
$ cd /root
$ mkdir cert ; cd cert
$ oc adm ca create-server-cert \
  --signer-cert=/etc/origin/master/ca.crt \
  --signer-key=/etc/origin/master/ca.key \
  --signer-serial=/etc/origin/master/ca.serial.txt \
  --hostnames='*.hostnames.for.the.certificate' \
  --cert=router.crt \
  --key=router.key \
```

These commands generate the following files:

- A new certificate named **router.crt**.
- A copy of the signing CA certificate chain, **/etc/origin/master/ca.crt**. This chain can contain more than one certificate if you use intermediate CAs.
- A corresponding private key named **router.key**.

4. Create a new file that concatenates the generated certificates:

```
$ cat router.crt /etc/origin/master/ca.crt router.key > router.pem
```

5. Before you generate a new secret, back up the current one:

```
$ oc export secret router-certs > ~/old-router-certs-secret.yaml
```

6. Create a new secret to hold the new certificate and key, and replace the contents of the existing secret:

```
$ oc create secret tls router-certs --cert=router.pem \ 1
  --key=router.key -o json --dry-run | \
  oc replace -f -
```

1 **router.pem** is the file that contains the concatenation of the certificates that you generated.

7. Remove the following annotations from the **router** service:

```
$ oc annotate service router \
    service.alpha.openshift.io/serving-cert-secret-name- \
    service.alpha.openshift.io/serving-cert-signed-by-
```

8. Re-add the annotations:

```
$ oc annotate service router \
    service.alpha.openshift.io/serving-cert-secret-name=router-certs
```

9. Redeploy the router:

```
$ oc rollout latest dc/router
```

CHAPTER 11. CONFIGURING AUTHENTICATION AND USER AGENT

11.1. OVERVIEW

The OpenShift Container Platform [master](#) includes a built-in [OAuth server](#). Developers and administrators obtain [OAuth access tokens](#) to authenticate themselves to the API.

As an administrator, you can configure OAuth using the [master configuration file](#) to specify an [identity provider](#). It is a best practice to configure your identity provider during [advanced installation](#), but you can configure it after installation.



NOTE

OpenShift Container Platform user names containing `/`, `:`, and `%` are not supported.

If you installed OpenShift Container Platform using the [Quick Installation](#) or [Advanced Installation](#) method, the [Deny All](#) identity provider is used by default, which denies access for all user names and passwords. To allow access, you must choose a different identity provider and configure the master configuration file appropriately (located at `/etc/origin/master/master-config.yaml` by default).

When you run a master without a configuration file, the [Allow All](#) identity provider is used by default, which allows any non-empty user name and password to log in. This is useful for testing purposes. To use other identity providers, or to modify any [token](#), [grant](#), or [session options](#), you must run the master from a configuration file.



NOTE

[Roles](#) need to be assigned to administer the setup with an external user.



NOTE

After making changes to an identity provider, you must restart the master services for the changes to take effect:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

11.2. IDENTITY PROVIDER PARAMETERS

There are four parameters common to all identity providers:

Parameter	Description
name	The provider name is prefixed to provider user names to form an identity name.

Parameter	Description
challenge	<p>When true, unauthenticated token requests from non-web clients (like the CLI) are sent a WWW-Authenticate challenge header. Not supported by all identity providers.</p> <p>To prevent cross-site request forgery (CSRF) attacks against browser clients Basic authentication challenges are only sent if a X-CSRF-Token header is present on the request. Clients that expect to receive Basic WWW-Authenticate challenges should set this header to a non-empty value.</p>
login	<p>When true, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider. Not supported by all identity providers.</p> <p>If you want users to be sent to a branded page before being redirected to the identity provider's login, then set oauthConfig → alwaysShowProviderSelection: true in the master configuration file. This provider selection page can be customized.</p>
mappingMethod	<p>Defines how new identities are mapped to users when they log in. Enter one of the following values:</p> <p>claim</p> <p>The default value. Provisions a user with the identity's preferred user name. Fails if a user with that user name is already mapped to another identity.</p> <p>lookup</p> <p>Looks up an existing identity, user identity mapping, and user, but does not automatically provision users or identities. This allows cluster administrators to set up identities and users manually, or using an external process. Using this method requires you to manually provision users. See Manually Provisioning a User When Using the Lookup Mapping Method.</p> <p>generate</p> <p>Provisions a user with the identity's preferred user name. If a user with the preferred user name is already mapped to an existing identity, a unique user name is generated. For example, myuser2. This method should not be used in combination with external processes that require exact matches between OpenShift Container Platform user names and identity provider user names, such as LDAP group sync.</p> <p>add</p> <p>Provisions a user with the identity's preferred user name. If a user with that user name already exists, the identity is mapped to the existing user, adding to any existing identity mappings for the user. Required when multiple identity providers are configured that identify the same set of users and map to the same user names.</p>

**NOTE**

When adding or changing identity providers, you can map identities from the new provider to existing users by setting the **mappingMethod** parameter to **add**.

11.3. CONFIGURING IDENTITY PROVIDERS

OpenShift Container Platform supports configuring only a single identity provider. However, you can extend the basic authentication for more complex configurations such as [LDAP failover](#).

You can use these parameters to define the identity provider during installation or after installation.

11.3.1. Configuring identity providers with Ansible

For initial [advanced installations](#), the [Deny All](#) identity provider is configured by default, though it can be [overridden during installation](#) using the [openshift_master_identity_providers](#) parameter, which is configurable in the inventory file. [Session options in the OAuth configuration](#) are also configurable in the inventory file.

Example 11.1. Example identity provider configuration with Ansible

```
# httpasswd auth
openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]
# Defining htpasswd users
#openshift_master_htpasswd_users={'user1': '<pre-hashed password>',
'user2': '<pre-hashed password>'}
# or
#openshift_master_htpasswd_file=<path to local pre-generated htpasswd
file>

# Allow all auth
#openshift_master_identity_providers=[{'name': 'allow_all', 'login':
'true', 'challenge': 'true', 'kind':
'AllowAllPasswordIdentityProvider'}]

# LDAP auth
#openshift_master_identity_providers=[{'name': 'my_ldap_provider',
'challenge': 'true', 'login': 'true', 'kind':
'LDAPPasswordIdentityProvider', 'attributes': {'id': ['dn'], 'email':
['mail'], 'name': ['cn'], 'preferredUsername': ['uid']}, 'bindDN': '',
'bindPassword': '', 'ca': '', 'insecure': 'false', 'url':
'ldap://ldap.example.com:389/ou=users,dc=example,dc=com?uid'}]
# Configuring the ldap ca certificate ❶
#openshift_master_ldap_ca=<ca text>
# or
#openshift_master_ldap_ca_file=<path to local ca file to use>

# Available variables for configuring certificates for other identity
providers:
#openshift_master_openid_ca
#openshift_master_openid_ca_file
#openshift_master_request_header_ca
#openshift_master_request_header_ca_file
```

- ❶ If you specify your CA certificate location in the `openshift_master_identity_providers` parameter, do not specify a certificate value in the `openshift_master_ldap_ca` parameter or path in the `openshift_master_ldap_ca_file` parameter.

11.3.2. Configuring identity providers in the master configuration file

You can configure the master host for authentication using your desired identity provider by modifying the [master configuration file](#).

Example 11.2. Example identity provider configuration in the master configuration file

```
...
oauthConfig:
  identityProviders:
  - name: htpasswd_auth
    challenge: true
    login: true
    mappingMethod: "claim"
...
```

When set to the default **claim** value, OAuth will fail if the identity is mapped to a previously-existing user name.

11.3.3. Configuring an identity provider or method

11.3.3.1. Manually provisioning a user when using the lookup mapping method

When using the **lookup** mapping method, user provisioning is done by an external system, via the API. Typically, identities are automatically mapped to users during login. The 'lookup' mapping method automatically disables this automatic mapping, which requires you to provision users manually.

For more information on identity objects, see the [Identity](#) user API object.

If you are using the **lookup** mapping method, use the following steps for each user after configuring the identity provider:

1. Create an OpenShift Container Platform User, if not created already:

```
$ oc create user <username>
```

For example, the following command creates a OpenShift Container Platform User **bob**:

```
$ oc create user bob
```

2. Create an OpenShift Container Platform Identity, if not created already. Use the name of the identity provider and the name that uniquely represents this identity in the scope of the identity provider:

```
$ oc create identity <identity-provider>:<user-id-from-identity-provider>
```

The **<identity-provider>** is the name of the identity provider in the master configuration, as shown in the appropriate identity provider section below.

For example, the following commands creates an Identity with identity provider **ldap_provider** and the identity provider user name **bob_s**.

```
$ oc create identity ldap_provider:bob_s
```

3. Create a user/identity mapping for the created user and identity:

```
$ oc create useridentitymapping <identity-provider>:<user-id-from-identity-provider> <username>
```

For example, the following command maps the identity to the user:

```
$ oc create useridentitymapping ldap_provider:bob_s bob
```

11.3.4. Allow all

Set **AllowAllPasswordIdentityProvider** in the **identityProviders** stanza to allow any non-empty user name and password to log in.

Example 11.3. Master Configuration Using AllowAllPasswordIdentityProvider

```
oauthConfig:
  ...
  identityProviders:
  - name: my_allow_provider 1
    challenge: true 2
    login: true 3
    mappingMethod: claim 4
    provider:
      apiVersion: v1
      kind: AllowAllPasswordIdentityProvider
```

- 1 This provider name is prefixed to provider user names to form an identity name.
- 2 When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- 3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).

11.3.5. Deny all

Set **DenyAllPasswordIdentityProvider** in the **identityProviders** stanza to deny access for all user names and passwords.

Example 11.4. Master Configuration Using DenyAllPasswordIdentityProvider

```
oauthConfig:
  ...
  identityProviders:
  - name: my_deny_provider 1
```

```
challenge: true 2
login: true 3
mappingMethod: claim 4
provider:
  apiVersion: v1
  kind: DenyAllPasswordIdentityProvider
```

- 1 This provider name is prefixed to provider user names to form an identity name.
- 2 When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- 3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).

11.3.6. HTTPasswd

Set **HTTPasswdPasswordIdentityProvider** in the **identityProviders** stanza to validate user names and passwords against a flat file generated using [htpasswd](#).



NOTE

The **htpasswd** utility is in the **httpd-tools** package:

```
# yum install httpd-tools
```

OpenShift Container Platform supports the Bcrypt, SHA-1, and MD5 cryptographic hash functions, and MD5 is the default for **htpasswd**. Plaintext, encrypted text, and other hash functions are not currently supported.

The flat file is reread if its modification time changes, without requiring a server restart.

To use the **htpasswd** command:

- To create a flat file with a user name and hashed password, run:

```
$ htpasswd -c </path/to/users.htpasswd> <user_name>
```

Then, enter and confirm a clear-text password for the user. The command generates a hashed version of the password.

For example:

```
htpasswd -c users.htpasswd user1
New password:
Re-type new password:
Adding password for user user1
```

**NOTE**

You can include the **-b** option to supply the password on the command line:

```
$ htpasswd -c -b <user_name> <password>
```

For example:

```
$ htpasswd -c -b file user1 MyPassword!
Adding password for user user1
```

- To add or update a login to the file, run:

```
$ htpasswd </path/to/users.htpasswd> <user_name>
```

- To remove a login from the file, run:

```
$ htpasswd -D </path/to/users.htpasswd> <user_name>
```

Example 11.5. Master Configuration Using HTTPasswdPasswordIdentityProvider

```
oauthConfig:
  ...
  identityProviders:
  - name: my_htpasswd_provider ❶
    challenge: true ❷
    login: true ❸
    mappingMethod: claim ❹
    provider:
      apiVersion: v1
      kind: HTTPasswdPasswordIdentityProvider
      file: /path/to/users.htpasswd ❺
```

- ❶ This provider name is prefixed to provider user names to form an identity name.
- ❷ When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- ❸ When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- ❹ Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- ❺ File generated using [htpasswd](#).

11.3.7. Keystone

Set **KeystonePasswordIdentityProvider** in the **identityProviders** stanza to validate user names and passwords against an OpenStack Keystone v3 server. This enables shared authentication with an OpenStack server configured to store users in an internal Keystone database.

Example 11.6. Master Configuration Using KeystonePasswordIdentityProvider

```

oauthConfig:
  ...
  identityProviders:
  - name: my_keystone_provider ❶
    challenge: true ❷
    login: true ❸
    mappingMethod: claim ❹
    provider:
      apiVersion: v1
      kind: KeystonePasswordIdentityProvider
      domainName: default ❺
      url: http://keystone.example.com:5000 ❻
      ca: ca.pem ❼
      certFile: keystone.pem ❽
      keyFile: keystonekey.pem ❾

```

- ❶ This provider name is prefixed to provider user names to form an identity name.
- ❷ When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- ❸ When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- ❹ Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- ❺ Keystone domain name. In Keystone, usernames are domain-specific. Only a single domain is supported.
- ❻ The URL to use to connect to the Keystone server (required).
- ❼ Optional: Certificate bundle to use to validate server certificates for the configured URL.
- ❽ Optional: Client certificate to present when making requests to the configured URL.
- ❾ Key for the client certificate. Required if **certFile** is specified.

11.3.8. LDAP authentication

Set **LDAPPasswordIdentityProvider** in the **identityProviders** stanza to validate user names and passwords against an LDAPv3 server, using simple bind authentication.

**NOTE**

If you require failover for your LDAP server, instead of following these steps, extend the basic authentication method by [configuring SSSD for LDAP failover](#).

During authentication, the LDAP directory is searched for an entry that matches the provided user name. If a single unique match is found, a simple bind is attempted using the distinguished name (DN) of the entry plus the provided password.

These are the steps taken:

1. Generate a search filter by combining the attribute and filter in the configured **url** with the user-provided user name.
2. Search the directory using the generated filter. If the search does not return exactly one entry, deny access.
3. Attempt to bind to the LDAP server using the DN of the entry retrieved from the search, and the user-provided password.
4. If the bind is unsuccessful, deny access.
5. If the bind is successful, build an identity using the configured attributes as the identity, email address, display name, and preferred user name.

The configured **url** is an RFC 2255 URL, which specifies the LDAP host and search parameters to use. The syntax of the URL is:

```
ldap://host:port/basedn?attribute?scope?filter
```

For the above example:

URL Component	Description
ldap	For regular LDAP, use the string ldap . For secure LDAP (LDAPS), use ldaps instead.
host:port	The name and port of the LDAP server. Defaults to localhost:389 for ldap and localhost:636 for LDAPS.
basedn	The DN of the branch of the directory where all searches should start from. At the very least, this must be the top of your directory tree, but it could also specify a subtree in the directory.
attribute	The attribute to search for. Although RFC 2255 allows a comma-separated list of attributes, only the first attribute will be used, no matter how many are provided. If no attributes are provided, the default is to use uid . It is recommended to choose an attribute that will be unique across all entries in the subtree you will be using.
scope	The scope of the search. Can be either either one or sub . If the scope is not provided, the default is to use a scope of sub .

URL Component	Description
filter	A valid LDAP search filter. If not provided, defaults to (objectClass=*)

When doing searches, the attribute, filter, and provided user name are combined to create a search filter that looks like:

```
(<filter>)(<attribute>=<username>))
```

For example, consider a URL of:

```
ldap://ldap.example.com/o=Acme?cn?sub?(enabled=true)
```

When a client attempts to connect using a user name of **bob**, the resulting search filter will be **(&(enabled=true)(cn=bob))**.

If the LDAP directory requires authentication to search, specify a **bindDN** and **bindPassword** to use to perform the entry search.

Master Configuration Using LDAPPasswordIdentityProvider

```
oauthConfig:
  ...
  identityProviders:
    - name: "my_ldap_provider" ❶
      challenge: true ❷
      login: true ❸
      mappingMethod: claim ❹
      provider:
        apiVersion: v1
        kind: LDAPPasswordIdentityProvider
        attributes:
          id: ❺
          - dn
          email: ❻
          - mail
          name: ❼
          - cn
          preferredUsername: ❽
          - uid
        bindDN: "" ❾
        bindPassword: "" ❿
        ca: my-ldap-ca-bundle.crt ❾
        insecure: false ❿
        url: "ldap://ldap.example.com/ou=users,dc=acme,dc=com?uid" ❿
```

- ❶ This provider name is prefixed to the returned user ID to form an identity name.
- ❷ When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.

- 3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5 List of attributes to use as the identity. First non-empty attribute is used. At least one attribute is required. If none of the listed attribute have a value, authentication fails.
- 6 List of attributes to use as the email address. First non-empty attribute is used.
- 7 List of attributes to use as the display name. First non-empty attribute is used.
- 8 List of attributes to use as the preferred user name when provisioning a user for this identity. First non-empty attribute is used.
- 9 Optional DN to use to bind during the search phase.
- 10 Optional password to use to bind during the search phase. This value may also be provided in an [environment variable](#), [external file](#), or [encrypted file](#).
- 11 Certificate bundle to use to validate server certificates for the configured URL. If empty, system trusted roots are used. Only applies if **insecure: false**.
- 12 When **true**, no TLS connection is made to the server. When **false**, **ldaps://** URLs connect using TLS, and **ldap://** URLs are upgraded to TLS.
- 13 An RFC 2255 URL which specifies the LDAP host and search parameters to use, [as described above](#).



NOTE

To whitelist users for an LDAP integration, use the **lookup** mapping method. Before a login from LDAP would be allowed, a cluster administrator must create an identity and user object for each LDAP user.

11.3.9. Basic authentication (remote)

Basic Authentication is a generic backend integration mechanism that allows users to log in to OpenShift Container Platform with credentials validated against a remote identity provider.

Because basic authentication is generic, you can use this identity provider for advanced authentication configurations. You can configure [LDAP failover](#) or use the [containerized basic authentication](#) repository as a starting point for another advanced remote basic authentication configuration.

CAUTION

Basic authentication must use an HTTPS connection to the remote server to prevent potential snooping of the user ID and password and man-in-the-middle attacks.

With **BasicAuthPasswordIdentityProvider** configured, users send their user name and password to OpenShift Container Platform, which then validates those credentials against a remote server by making a server-to-server request, passing the credentials as a Basic Auth header. This requires users to send their credentials to OpenShift Container Platform during login.

Set **BasicAuthPasswordIdentityProvider** in the **identityProviders** stanza to validate user names and passwords against a remote server using a server-to-server Basic authentication request. User names and passwords are validated against a remote URL that is protected by Basic authentication and returns JSON.

A **401** response indicates failed authentication.

A non-**200** status, or the presence of a non-empty "error" key, indicates an error:

```
{"error": "Error message"}
```

A **200** status with a **sub** (subject) key indicates success:

```
{"sub": "userid"} ❶
```

❶ The subject must be unique to the authenticated user and must not be able to be modified.

A successful response may optionally provide additional data, such as:

- A display name using the **name** key. For example:

```
{"sub": "userid", "name": "User Name", ...}
```

- An email address using the **email** key. For example:

```
{"sub": "userid", "email": "user@example.com", ...}
```

- A preferred user name using the **preferred_username** key. This is useful when the unique, unchangeable subject is a database key or UID, and a more human-readable name exists. This is used as a hint when provisioning the OpenShift Container Platform user for the authenticated identity. For example:

```
{"sub": "014fbff9a07c", "preferred_username": "bob", ...}
```

Example 11.7. Master Configuration Using BasicAuthPasswordIdentityProvider

```
oauthConfig:
  ...
  identityProviders:
  - name: my_remote_basic_auth_provider ❶
    challenge: true ❷
    login: true ❸
    mappingMethod: claim ❹
    provider:
      apiVersion: v1
      kind: BasicAuthPasswordIdentityProvider
      url: https://www.example.com/remote-idp ❺
      ca: /path/to/ca.file ❻
      certFile: /path/to/client.crt ❼
      keyFile: /path/to/client.key ❽
```

- 1 This provider name is prefixed to the returned user ID to form an identity name.
- 2 When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- 3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5 URL accepting credentials in Basic authentication headers.
- 6 Optional: Certificate bundle to use to validate server certificates for the configured URL.
- 7 Optional: Client certificate to present when making requests to the configured URL.
- 8 Key for the client certificate. Required if **certFile** is specified.

11.3.10. Request header

Set **RequestHeaderIdentityProvider** in the **identityProviders** stanza to identify users from request header values, such as **X-Remote-User**. It is typically used in combination with an authenticating proxy, which sets the request header value. This is similar to how [the remote user plug-in in OpenShift Enterprise 2](#) allowed administrators to provide Kerberos, LDAP, and many other forms of enterprise authentication.

You can also use the request header identity provider for advanced configurations such as [SAML authentication](#).

For users to authenticate using this identity provider, they must access **https://<master>/oauth/authorize** (and subpaths) via an authenticating proxy. To accomplish this, configure the OAuth server to redirect unauthenticated requests for OAuth tokens to the proxy endpoint that proxies to **https://<master>/oauth/authorize**.

To redirect unauthenticated requests from clients expecting browser-based login flows:

1. Set the **login** parameter to **true**.
2. Set the **provider.loginURL** parameter to the authenticating proxy URL that will authenticate interactive clients and then proxy the request to **https://<master>/oauth/authorize**.

To redirect unauthenticated requests from clients expecting **WWW-Authenticate** challenges:

1. Set the **challenge** parameter to **true**.
2. Set the **provider.challengeURL** parameter to the authenticating proxy URL that will authenticate clients expecting **WWW-Authenticate** challenges and then proxy the request to **https://<master>/oauth/authorize**.

The **provider.challengeURL** and **provider.loginURL** parameters can include the following tokens in the query portion of the URL:

- **\${url}** is replaced with the current URL, escaped to be safe in a query parameter.

For example: `https://www.example.com/sso-login?then=${url}`

- `${query}` is replaced with the current query string, unescaped.

For example: `https://www.example.com/auth-proxy/oauth/authorize?${query}`



WARNING

If you expect unauthenticated requests to reach the OAuth server, a **clientCA** parameter **MUST** be set for this identity provider, so that incoming requests are checked for a valid client certificate before the request's headers are checked for a user name. Otherwise, any direct request to the OAuth server can impersonate any identity from this provider, merely by setting a request header.

Example 11.8. Master Configuration Using RequestHeaderIdentityProvider

```
oauthConfig:
  ...
  identityProviders:
    - name: my_request_header_provider ❶
      challenge: true ❷
      login: true ❸
      mappingMethod: claim ❹
      provider:
        apiVersion: v1
        kind: RequestHeaderIdentityProvider
        challengeURL: "https://www.example.com/challenging-
proxy/oauth/authorize?${query}" ❺
        loginURL: "https://www.example.com/login-proxy/oauth/authorize?
${query}" ❻
        clientCA: /path/to/client-ca.file ❼
        clientCommonNames: ❽
        - my-auth-proxy
        headers: ❾
        - X-Remote-User
        - SSO-User
        emailHeaders: ❿
        - X-Remote-User-Email
        nameHeaders: ⓫
        - X-Remote-User-Display-Name
        preferredUsernameHeaders: ⓫
        - X-Remote-User-Login
```

❶ This provider name is prefixed to the user name in the request header to form an identity name.

❷ **RequestHeaderIdentityProvider** can only respond to clients that request **WWW-Authenticate** challenges by redirecting to a configured **challengeURL**. The configured URL should respond with a **WWW-Authenticate** challenge.

- 3 **RequestHeaderIdentityProvider** can only respond to clients requesting a login flow by redirecting to a configured **loginURL**. The configured URL should respond with a login flow.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5 Optional: URL to redirect unauthenticated **/oauth/authorize** requests to, that will authenticate browser-based clients and then proxy their request to **https://<master>/oauth/authorize**. The URL that proxies to **https://<master>/oauth/authorize** must end with **/authorize** (with no trailing slash), and also proxy subpaths, in order for OAuth approval flows to work properly. **\${url}** is replaced with the current URL, escaped to be safe in a query parameter. **\${query}** is replaced with the current query string.
- 6 Optional: URL to redirect unauthenticated **/oauth/authorize** requests to, that will authenticate clients which expect **WWW-Authenticate** challenges, and then proxy them to **https://<master>/oauth/authorize**. **\${url}** is replaced with the current URL, escaped to be safe in a query parameter. **\${query}** is replaced with the current query string.
- 7 Optional: PEM-encoded certificate bundle. If set, a valid client certificate must be presented and validated against the certificate authorities in the specified file before the request headers are checked for user names.
- 8 Optional: list of common names (**cn**). If set, a valid client certificate with a Common Name (**cn**) in the specified list must be presented before the request headers are checked for user names. If empty, any Common Name is allowed. Can only be used in combination with **clientCA**.
- 9 Header names to check, in order, for the user identity. The first header containing a value is used as the identity. Required, case-insensitive.
- 10 Header names to check, in order, for an email address. The first header containing a value is used as the email address. Optional, case-insensitive.
- 11 Header names to check, in order, for a display name. The first header containing a value is used as the display name. Optional, case-insensitive.
- 12 Header names to check, in order, for a preferred user name, if different than the immutable identity determined from the headers specified in **headers**. The first header containing a value is used as the preferred user name when provisioning. Optional, case-insensitive.

Example 11.9. Apache Authentication Using RequestHeaderIdentityProvider

This example configures an authentication proxy on the same host as the master. Having the proxy and master on the same host is merely a convenience and may not be suitable for your environment. For example, if you were already [running a router](#) on the master, port 443 would not be available.

It is also important to note that while this reference configuration uses Apache's **mod_auth_form**, it is by no means required and other proxies can easily be used if the following requirements are met:

1. Block the **X-Remote-User** header from client requests to prevent spoofing.
2. Enforce client certificate authentication in the **RequestHeaderIdentityProvider** configuration.

3. Require the **X-Csrf-Token** header be set for all authentication request using the challenge flow.
4. Only the **/oauth/authorize** endpoint and its subpaths should be proxied, and redirects should not be rewritten to allow the backend server to send the client to the correct location.
5. The URL that proxies to **https://<master>/oauth/authorize** must end with **/authorize** (with no trailing slash). For example:
 - **https://proxy.example.com/login-proxy/authorize?... → https://<master>/oauth/authorize...**
6. Subpaths of the URL that proxies to **https://<master>/oauth/authorize** must proxy to subpaths of **https://<master>/oauth/authorize**. For example:
 - **https://proxy.example.com/login-proxy/authorize/approve?... → https://<master>/oauth/authorize/approve...**

Installing the Prerequisites

The **mod_auth_form** module is shipped as part of the **mod_session** package that is found in the [Optional channel](#):

```
# yum install -y httpd mod_ssl mod_session apr-util-openssl
```

Generate a CA for validating requests that submit the trusted header. This CA should be used as the file name for **clientCA** in the [master's identity provider configuration](#).

```
# oc adm ca create-signer-cert \
  --cert='/etc/origin/master/proxyca.crt' \
  --key='/etc/origin/master/proxyca.key' \
  --name='openshift-proxy-signer@1432232228' \
  --serial='/etc/origin/master/proxyca.serial.txt'
```

The **oc adm ca create-signer-cert** command generates a certificate that is valid for five years. This can be altered with the **--expire-days** option, but for security reasons, it is recommended to not make it greater than this value.

Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

Generate a client certificate for the proxy. This can be done using any x509 certificate tooling. For convenience, the **oc adm** CLI can be used:

```
# oc adm create-api-client-config \
  --certificate-authority='/etc/origin/master/proxyca.crt' \
  --client-dir='/etc/origin/master/proxy' \
  --signer-cert='/etc/origin/master/proxyca.crt' \
  --signer-key='/etc/origin/master/proxyca.key' \
  --signer-serial='/etc/origin/master/proxyca.serial.txt' \
  --user='system:proxy' 1

# pushd /etc/origin/master
```

```
# cp master.server.crt /etc/pki/tls/certs/localhost.crt 2
# cp master.server.key /etc/pki/tls/private/localhost.key
# cp ca.crt /etc/pki/CA/certs/ca.crt
# cat proxy/system\:proxy.crt \
  proxy/system\:proxy.key > \
  /etc/pki/tls/certs/authproxy.pem
# popd
```

- 1 The user name can be anything, however it is useful to give it a descriptive name as it will appear in logs.
- 2 When running the authentication proxy on a different host name than the master, it is important to generate a certificate that matches the host name instead of using the default master certificate as shown above. The value for **masterPublicURL** in the `/etc/origin/master/master-config.yaml` file must be included in the **X509v3 Subject Alternative Name** in the certificate that is specified for **SSLCertificateFile**. If a new certificate needs to be created, the **oc adm ca create-server-cert** command can be used.

The **oc adm create-api-client-config** command generates a certificate that is valid for two years. This can be altered with the **--expire-days** option, but for security reasons, it is recommended to not make it greater than this value. Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default `/etc/ansible/hosts`.

Configuring Apache

This proxy does not need to reside on the same host as the master. It uses a client certificate to connect to the master, which is configured to trust the **X-Remote-User** header.

1. Create the certificate for the Apache configuration. The certificate that you specify as the **SSLProxyMachineCertificateFile** parameter value is the proxy's client cert that is used to authenticate the proxy to the server. It must use **TLS Web Client Authentication** as the extended key type.
2. Configure Apache per the following:

```
LoadModule auth_form_module modules/mod_auth_form.so
LoadModule session_module modules/mod_session.so
LoadModule request_module modules/mod_request.so

# Nothing needs to be served over HTTP. This virtual host simply
# redirects to
# HTTPS.
<VirtualHost *:80>
    DocumentRoot /var/www/html
    RewriteEngine On
    RewriteRule ^(.*)$ https://%{HTTP_HOST}$1 [R,L]
</VirtualHost>

<VirtualHost *:443>
    # This needs to match the certificates you generated. See the CN and
    X509v3
    # Subject Alternative Name in the output of:
    # openssl x509 -text -in /etc/pki/tls/certs/localhost.crt
    ServerName www.example.com
```

```

DocumentRoot /var/www/html
SSLEngine on
SSLCertificateFile /etc/pki/tls/certs/localhost.crt
SSLCertificateKeyFile /etc/pki/tls/private/localhost.key
SSLCACertificateFile /etc/pki/CA/certs/ca.crt

SSLProxyEngine on
SSLProxyCACertificateFile /etc/pki/CA/certs/ca.crt
# It's critical to enforce client certificates on the Master. Otherwise
# requests could spoof the X-Remote-User header by accessing the
Master's
# /oauth/authorize endpoint directly.
SSLProxyMachineCertificateFile /etc/pki/tls/certs/authproxy.pem

# Send all requests to the console
RewriteEngine On
RewriteRule ^/console(.*)$ https://%{HTTP_HOST}:8443/console$1
[R,L]

# In order to using the challenging-proxy an X-Csrft-Token must be
present.
RewriteCond %{REQUEST_URI} ^/challenging-proxy
RewriteCond %{HTTP:X-Csrft-Token} ^$ [NC]
RewriteRule ^.* - [F,L]

<Location /challenging-proxy/oauth/authorize>
# Insert your backend server name/ip here.
ProxyPass https://[MASTER]:8443/oauth/authorize
AuthType basic
</Location>

<Location /login-proxy/oauth/authorize>
# Insert your backend server name/ip here.
ProxyPass https://[MASTER]:8443/oauth/authorize

# mod_auth_form providers are implemented by mod_authn_dbm,
mod_authn_file,
# mod_authn_dbd, mod_authnz_ldap and mod_authn_socache.
AuthFormProvider file
AuthType form
AuthName openshift
ErrorDocument 401 /login.html
</Location>

<ProxyMatch /oauth/authorize>
AuthUserFile /etc/origin/master/htpasswd
AuthName openshift
Require valid-user
RequestHeader set X-Remote-User %{REMOTE_USER}s env=REMOTE_USER

# For ldap:
# AuthBasicProvider ldap
# AuthLDAPURL "ldap://ldap.example.com:389/ou=People,dc=my-
domain,dc=com?uid?sub?(objectClass=*)"

# It's possible to remove the mod_auth_form usage and replace it with

```

```

    # something like mod_auth_kerb, mod_auth_gssapi or even
    mod_auth_mellon.
    # The former would be able to support both the login and challenge
    flows
    # from the Master. Mellon would likely only support the login flow.

    # For Kerberos
    # yum install mod_auth_gssapi
    # AuthType GSSAPI
    # GssapiCredStore keytab:/etc/httpd.keytab
</ProxyMatch>

</VirtualHost>

RequestHeader unset X-Remote-User

```

Additional mod_auth_form Requirements

A sample login page is available from the [openshift_extras](#) repository. This file should be placed in the **DocumentRoot** location (**/var/www/html** by default).

Creating Users

At this point, you can create the users in the system Apache is using to store accounts information. In this example, file-backed authentication is used:

```

# yum -y install httpd-tools
# touch /etc/origin/master/htpasswd
# htpasswd /etc/origin/master/htpasswd <user_name>

```

Configuring the Master

The **identityProviders** stanza in the **/etc/origin/master/master-config.yaml** file must be updated as well:

```

identityProviders:
- name: requestheader
  challenge: true
  login: true
  provider:
    apiVersion: v1
    kind: RequestHeaderIdentityProvider
    challengeURL: "https://[MASTER]/challenging-proxy/oauth/authorize?
${query}"
    loginURL: "https://[MASTER]/login-proxy/oauth/authorize?${query}"
    clientCA: /etc/origin/master/proxyca.crt
    headers:
    - X-Remote-User

```

Restarting Services

Finally, restart the following services:

```
# systemctl restart httpd
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

Verifying the Configuration

1. Test by bypassing the proxy. You should be able to request a token if you supply the correct client certificate and header:

```
# curl -L -k -H "X-Remote-User: joe" \
  --cert /etc/pki/tls/certs/authproxy.pem \
  https://[MASTER]:8443/oauth/token/request
```

2. If you do not supply the client certificate, the request should be denied:

```
# curl -L -k -H "X-Remote-User: joe" \
  https://[MASTER]:8443/oauth/token/request
```

3. This should show a redirect to the configured **challengeURL** (with additional query parameters):

```
# curl -k -v -H 'X-Csrf-Token: 1' \
  '<masterPublicURL>/oauth/authorize?client_id=openshift-
  challenging-client&response_type=token'
```

4. This should show a 401 response with a **WWW-Authenticate** basic challenge:


```
# curl -k -v -H 'X-Csrf-Token: 1' \
  '<redirected_challengeURL_from_step_3 +query>'
```

5. This should show a redirect with an access token:

```
# curl -k -v -u <your_user>:<your_password> \
  -H 'X-Csrf-Token: 1' '<redirected_challengeURL_from_step_3
  +query>'
```

11.3.11. GitHub

Set **GitHubIdentityProvider** in the **identityProviders** stanza to use [GitHub](#) as an identity provider, using the [OAuth integration](#).



NOTE

Using GitHub as an identity provider requires users to get a token using **<master>/oauth/token/request** to use with command-line tools.

**WARNING**

Using GitHub as an identity provider allows any GitHub user to authenticate to your server. You can limit authentication to members of specific GitHub organizations with the **organizations** configuration attribute, as shown below.

Example 11.10. Master Configuration Using GitHubIdentityProvider

```

oauthConfig:
  ...
  identityProviders:
  - name: github 1
    challenge: false 2
    login: true 3
    mappingMethod: claim 4
    provider:
      apiVersion: v1
      kind: GitHubIdentityProvider
      clientId: ... 5
      clientSecret: ... 6
      organizations: 7
        - myorganization1
        - myorganization2
      teams: 8
        - myorganization1/team-a
        - myorganization2/team-b

```

1 This provider name is prefixed to the GitHub numeric user ID to form an identity name. It is also used to build the callback URL.

2 **GitHubIdentityProvider** cannot be used to send **WWW-Authenticate** challenges.

3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to GitHub to log in.

4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).

5 The client ID of a [registered GitHub OAuth application](#). The application must be configured with a callback URL of `<master>/oauth2callback/<identityProviderName>`.

6 The client secret issued by GitHub. This value may also be provided in an [environment variable, external file, or encrypted file](#).

7 Optional list of organizations. If specified, only GitHub users that are members of at least one of the listed organizations will be allowed to log in. If the GitHub OAuth application configured in **clientId** is not owned by the organization, an organization owner must grant third-party access in order to use this option. This can be done during the first GitHub login by the organization's administrator, or from the GitHub organization settings. Cannot be used in combination with the **teams** field.

- 8 Optional list of teams. If specified, only GitHub users that are members of at least one of the listed teams will be allowed to log in. If the GitHub OAuth application configured in **clientID** is not owned by the team's organization, an organization owner must grant third-party access in order to use this option. This can be done during the first GitHub login by the organization's administrator, or from the GitHub organization settings. Cannot be used in combination with the **organizations** field.

11.3.12. GitLab

Set **GitLabIdentityProvider** in the **identityProviders** stanza to use [GitLab.com](https://gitlab.com) or any other GitLab instance as an identity provider, using the [OAuth integration](#). The OAuth provider feature requires GitLab version 7.7.0 or higher.

Example 11.11. Master Configuration Using GitLabIdentityProvider


```
oauthConfig:
  ...
  identityProviders:
    - name: gitlab 1
      challenge: true 2
      login: true 3
      mappingMethod: claim 4
      provider:
        apiVersion: v1
        kind: GitLabIdentityProvider
        url: ... 5
        clientID: ... 6
        clientSecret: ... 7
        ca: ... 8
```

- 1 This provider name is prefixed to the GitLab numeric user ID to form an identity name. It is also used to build the callback URL.
- 2 When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider. This uses the [Resource Owner Password Credentials](#) grant flow to obtain an access token from GitLab.
- 3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to GitLab to log in.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5 The host URL of a GitLab OAuth provider. This could either be **https://gitlab.com/** or any other self hosted instance of GitLab.
- 6 The client ID of a [registered GitLab OAuth application](#). The application must be configured with a callback URL of **<master>/oauth2callback/<identityProviderName>**.
- 7 The client secret issued by GitLab. This value may also be provided in an [environment variable, external file, or encrypted file](#).

- 8 CA is an optional trusted certificate authority bundle to use when making requests to the GitLab instance. If empty, the default system roots are used.

11.3.13. Google

Set **GoogleIdentityProvider** in the **identityProviders** stanza to use Google as an identity provider, using [Google's OpenID Connect integration](#).



NOTE

Using Google as an identity provider requires users to get a token using **<master>/oauth/token/request** to use with command-line tools.



WARNING

Using Google as an identity provider allows any Google user to authenticate to your server. You can limit authentication to members of a specific hosted domain with the **hostedDomain** configuration attribute, as shown below.

Example 11.12. Master Configuration Using GoogleIdentityProvider

```
oauthConfig:
  ...
  identityProviders:
  - name: google 1
    challenge: false 2
    login: true 3
    mappingMethod: claim 4
    provider:
      apiVersion: v1
      kind: GoogleIdentityProvider
      clientID: ... 5
      clientSecret: ... 6
      hostedDomain: "" 7
```

- 1 This provider name is prefixed to the Google numeric user ID to form an identity name. It is also used to build the redirect URL.
- 2 **GoogleIdentityProvider** cannot be used to send **WWW-Authenticate** challenges.
- 3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to Google to log in.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).

- 5 The client ID of a [registered Google project](#). The project must be configured with a redirect URI of `<master>/oauth2callback/<identityProviderName>`.
- 6 The client secret issued by Google. This value may also be provided in an [environment variable](#), [external file](#), or [encrypted file](#).
- 7 Optional [hosted domain](#) to restrict sign-in accounts to. If empty, any Google account is allowed to authenticate.

11.3.14. OpenID connect

Set **OpenIDIdentityProvider** in the **identityProviders** stanza to integrate with an OpenID Connect identity provider using an [Authorization Code Flow](#).



NOTE

ID Token and **UserInfo** decryptions are not supported.

By default, the **openid** scope is requested. If required, extra scopes can be specified in the **extraScopes** field.

Claims are read from the JWT **id_token** returned from the OpenID identity provider and, if specified, from the JSON returned by the **UserInfo** URL.

At least one claim must be configured to use as the user's identity. The standard identity claim is **sub**.

You can also indicate which claims to use as the user's preferred user name, display name, and email address. If multiple claims are specified, the first one with a non-empty value is used. The standard claims are:

sub	Short for "subject identifier." The remote identity for the user at the issuer.
preferred_username	The preferred user name when provisioning a user. A shorthand name that the user wants to be referred to as, such as janedoe . Typically a value that corresponding to the user's login or username in the authentication system, such as username or email.
email	Email address.
name	Display name.

See the [OpenID claims documentation](#) for more information.



NOTE

Using an OpenID Connect identity provider requires users to get a token using `<master>/oauth/token/request` to use with command-line tools.

Standard Master Configuration Using OpenIDIdentityProvider

```

oauthConfig:
  ...
  identityProviders:
  - name: my_openid_connect ❶
    challenge: true ❷
    login: true ❸
    mappingMethod: claim ❹
    provider:
      apiVersion: v1
      kind: OpenIDIdentityProvider
      clientID: ... ❺
      clientSecret: ... ❻
      claims:
        id: ❼
        - sub
        preferredUsername:
        - preferred_username
        name:
        - name
        email:
        - email
      urls:
        authorize: https://myidp.example.com/oauth2/authorize ❽
        token: https://myidp.example.com/oauth2/token ❾

```

- ❶ This provider name is prefixed to the value of the identity claim to form an identity name. It is also used to build the redirect URL.
- ❷ When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider. This requires the OpenID provider to support the [Resource Owner Password Credentials](#) grant flow.
- ❸ When **true**, unauthenticated token requests from web clients (like the web console) are redirected to the authorize URL to log in.
- ❹ Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- ❺ The client ID of a client registered with the OpenID provider. The client must be allowed to redirect to **<master>/oauth2callback/<identityProviderName>**.
- ❻ The client secret. This value may also be provided in an [environment variable, external file, or encrypted file](#).
- ❼ List of claims to use as the identity. First non-empty claim is used. At least one claim is required. If none of the listed claims have a value, authentication fails. For example, this uses the value of the **sub** claim in the returned **id_token** as the user's identity.
- ❽ [Authorization Endpoint](#) described in the OpenID spec. Must use **https**.
- ❾ [Token Endpoint](#) described in the OpenID spec. Must use **https**.

A custom certificate bundle, extra scopes, extra authorization request parameters, and **userInfo** URL can also be specified:

Example 11.13. Full Master Configuration Using OpenIDIdentityProvider

```

oauthConfig:
  ...
  identityProviders:
  - name: my_openid_connect
    challenge: false
    login: true
    mappingMethod: claim
    provider:
      apiVersion: v1
      kind: OpenIDIdentityProvider
      clientID: ...
      clientSecret: ...
      ca: my-openid-ca-bundle.crt ❶
      extraScopes: ❷
      - email
      - profile
      extraAuthorizeParameters: ❸
        include_granted_scopes: "true"
      claims:
        id: ❹
        - custom_id_claim
        - sub
        preferredUsername: ❺
        - preferred_username
        - email
        name: ❻
        - nickname
        - given_name
        - name
        email: ❼
        - custom_email_claim
        - email
      urls:
        authorize: https://myidp.example.com/oauth2/authorize
        token: https://myidp.example.com/oauth2/token
        userInfo: https://myidp.example.com/oauth2/userinfo ❸

```

- ❶ Certificate bundle to use to validate server certificates for the configured URLs. If empty, system trusted roots are used.
- ❷ Optional list of scopes to request, in addition to the **openid** scope, during the authorization token request.
- ❸ Optional map of extra parameters to add to the authorization token request.
- ❹ List of claims to use as the identity. First non-empty claim is used. At least one claim is required. If none of the listed claims have a value, authentication fails.
- ❺ List of claims to use as the preferred user name when provisioning a user for this identity. First non-empty claim is used.
- ❻ List of claims to use as the display name. First non-empty claim is used.

- 7 List of claims to use as the email address. First non-empty claim is used.
- 8 [UserInfo Endpoint](#) described in the OpenID spec. Must use **https**.

11.4. TOKEN OPTIONS

The OAuth server generates two kinds of tokens:

Access tokens	Longer-lived tokens that grant access to the API.
Authorize codes	Short-lived tokens whose only use is to be exchanged for an access token.

Use the **tokenConfig** stanza to set token options:

Example 11.14. Master Configuration Token Options

```
oauthConfig:
  ...
  tokenConfig:
    accessTokenMaxAgeSeconds: 86400 1
    authorizeTokenMaxAgeSeconds: 300 2
```

- 1 Set **accessTokenMaxAgeSeconds** to control the lifetime of access tokens. The default lifetime is 24 hours.
- 2 Set **authorizeTokenMaxAgeSeconds** to control the lifetime of authorize codes. The default lifetime is five minutes.



NOTE

You can override the **accessTokenMaxAgeSeconds** value [through an OAuthClient object definition](#).

11.5. GRANT OPTIONS

When the OAuth server receives token requests for a client to which the user has not previously granted permission, the action that the OAuth server takes is dependent on the OAuth client's grant strategy.

When the OAuth client requesting token does not provide its own grant strategy, the server-wide default strategy is used. To configure the default strategy, set the **method** value in the **grantConfig** stanza. Valid values for **method** are:

auto	Auto-approve the grant and retry the request.
-------------	---

prompt	Prompt the user to approve or deny the grant.
deny	Auto-deny the grant and return a failure error to the client.

Example 11.15. Master Configuration Grant Options

```
oauthConfig:
  ...
  grantConfig:
    method: auto
```

11.6. SESSION OPTIONS

The OAuth server uses a signed and encrypted cookie-based session during login and redirect flows.

Use the **sessionConfig** stanza to set session options:

Example 11.16. Master Configuration Session Options

```
oauthConfig:
  ...
  sessionConfig:
    sessionMaxAgeSeconds: 300 ❶
    sessionName: ssn ❷
    sessionSecretsFile: "... " ❸
```

- ❶ Controls the maximum age of a session; sessions auto-expire once a token request is complete. If [auto-grant](#) is not enabled, sessions must last as long as the user is expected to take to approve or reject a client authorization request.
- ❷ Name of the cookie used to store the session.
- ❸ File name containing serialized **SessionSecrets** object. If empty, a random signing and encryption secret is generated at each server start.

If no **sessionSecretsFile** is specified, a random signing and encryption secret is generated at each start of the master server. This means that any logins in progress will have their sessions invalidated if the master is restarted. It also means they will not be able to decode sessions generated by one of the other masters.

To specify the signing and encryption secret to use, specify a **sessionSecretsFile**. This allows you separate secret values from the configuration file and keep the configuration file distributable, for example for debugging purposes.

Multiple secrets can be specified in the **sessionSecretsFile** to enable rotation. New sessions are signed and encrypted using the first secret in the list. Existing sessions are decrypted and authenticated by each secret until one succeeds.

Example 11.17. Session Secret Configuration:

```

apiVersion: v1
kind: SessionSecrets
secrets: ❶
- authentication: "..." ❷
  encryption: "..." ❸
- authentication: "..."
  encryption: "..."
...

```

- ❶ List of secrets used to authenticate and encrypt cookie sessions. At least one secret must be specified. Each secret must set an authentication and encryption secret.
- ❷ Signing secret, used to authenticate sessions using HMAC. Recommended to use a secret with 32 or 64 bytes.
- ❸ Encrypting secret, used to encrypt sessions. Must be 16, 24, or 32 characters long, to select AES-128, AES-192, or AES-256.

11.7. PREVENTING CLI VERSION MISMATCH WITH USER AGENT

OpenShift Container Platform implements a user agent that can be used to prevent an application developer's CLI accessing the OpenShift Container Platform API.

User agents for the OpenShift Container Platform CLI are constructed from a set of values within OpenShift Container Platform:

```
<command>/<version> (<platform>/<architecture>) <client>/<git_commit>
```

So, for example, when:

- **<command>** = **oc**
- **<version>** = The client version. For example, **v3.3.0**. Requests made against the Kubernetes API at **/api** receive the Kubernetes version, while requests made against the OpenShift Container Platform API at **/oapi** receive the OpenShift Container Platform version (as specified by **oc version**)
- **<platform>** = **linux**
- **<architecture>** = **amd64**
- **<client>** = **openshift**, or **kubernetes** depending on if the request is made against the Kubernetes API at **/api**, or the OpenShift Container Platform API at **/oapi**
- **<git_commit>** = The Git commit of the client version (for example, **f034127**)

the user agent will be:

```
oc/v3.3.0 (linux/amd64) openshift/f034127
```


As an OpenShift Container Platform administrator, you can prevent clients from accessing the API with the **userAgentMatching** configuration setting of a master configuration. So, if a client is using a particular library or binary, they will be prevented from accessing the API.

The following user agent example denies the Kubernetes 1.2 client binary, OpenShift Origin 1.1.3 binary, and the POST and PUT **httpVerbs**:

```
policyConfig:
  userAgentMatchingConfig:
    defaultRejectionMessage: "Your client is too old. Go to
https://example.org to update it."
    deniedClients:
      - regex: '\w+/v(?:1\.1\.1|1\.0\.1) \(.+/.+\) openshift/\w{7}'
      - regex: '\w+/v(?:1\.1\.3) \(.+/.+\) openshift/\w{7}'
      httpVerbs:
        - POST
        - PUT
      - regex: '\w+/v1\.2\.0 \(.+/.+\) kubernetes/\w{7}'
      httpVerbs:
        - POST
        - PUT
    requiredClients: null
```

Administrators can also deny clients that do not exactly match the expected clients:

```
policyConfig:
  userAgentMatchingConfig:
    defaultRejectionMessage: "Your client is too old. Go to
https://example.org to update it."
    deniedClients: []
    requiredClients:
      - regex: '\w+/v1\.1\.3 \(.+/.+\) openshift/\w{7}'
      - regex: '\w+/v1\.2\.0 \(.+/.+\) kubernetes/\w{7}'
      httpVerbs:
        - POST
        - PUT
```




NOTE

When the client's user agent mismatches the configuration, errors occur. To ensure that mutating requests match, enforce a whitelist. Rules are mapped to specific verbs, so you can ban mutating requests while allowing non-mutating requests.

CHAPTER 12. SYNCING GROUPS WITH LDAP

12.1. OVERVIEW

As an OpenShift Container Platform administrator, you can use groups to manage users, change their permissions, and enhance collaboration. Your organization may have already created user groups and stored them in an LDAP server. OpenShift Container Platform can sync those LDAP records with internal OpenShift Container Platform records, enabling you to manage your groups in one place. OpenShift Container Platform currently supports group sync with LDAP servers using three common schemas for defining group membership: RFC 2307, Active Directory, and augmented Active Directory.



NOTE

You must have [cluster-admin privileges](#) to sync groups.

12.2. CONFIGURING LDAP SYNC

Before you can [run LDAP sync](#), you need a sync configuration file. This file contains LDAP client configuration details:

- Configuration for connecting to your LDAP server.
- Sync configuration options that are dependent on the schema used in your LDAP server.

A sync configuration file can also contain an administrator-defined list of name mappings that maps OpenShift Container Platform Group names to groups in your LDAP server.

12.2.1. LDAP Client Configuration

Example 12.1. LDAP Client Configuration

```
url: ldap://10.0.0.0:389 ①
bindDN: cn=admin,dc=example,dc=com ②
bindPassword: password ③
insecure: false ④
ca: my-ldap-ca-bundle.crt ⑤
```

- ① The connection protocol, IP address of the LDAP server hosting your database, and the port to connect to, formatted as **scheme://host:port**.
- ② Optional distinguished name (DN) to use as the Bind DN. OpenShift Container Platform uses this if elevated privilege is required to retrieve entries for the sync operation.
- ③ Optional password to use to bind. OpenShift Container Platform uses this if elevated privilege is necessary to retrieve entries for the sync operation. This value may also be provided in an [environment variable](#), [external file](#), or [encrypted file](#).
- ④ When **true**, no TLS connection is made to the server. When **false**, secure LDAP (**ldaps://**) URLs connect using TLS, and insecure LDAP (**ldap://**) URLs are upgraded to TLS.
- ⑤ The certificate bundle to use for validating server certificates for the configured URL. If empty, OpenShift Container Platform uses system-trusted roots. This only applies if **insecure** is set to **false**.

12.2.2. LDAP Query Definition

Sync configurations consist of LDAP query definitions for the entries that are required for synchronization. The specific definition of an LDAP query depends on the schema used to store membership information in the LDAP server.

Example 12.2. LDAP Query Definition

```
baseDN: ou=users,dc=example,dc=com ❶
scope: sub ❷
derefAliases: never ❸
timeout: 0 ❹
filter: (objectClass=inetOrgPerson) ❺
pageSize: 0 ❻
```

- ❶ The distinguished name (DN) of the branch of the directory where all searches will start from. It is required that you specify the top of your directory tree, but you can also specify a subtree in the directory.
- ❷ The scope of the search. Valid values are **base**, **one**, or **sub**. If this is left undefined, then a scope of **sub** is assumed. Descriptions of the scope options can be found in the [table below](#).
- ❸ The behavior of the search with respect to aliases in the LDAP tree. Valid values are **never**, **search**, **base**, or **always**. If this is left undefined, then the default is to **always** dereference aliases. Descriptions of the dereferencing behaviors can be found in the [table below](#).
- ❹ The time limit allowed for the search by the client, in seconds. A value of 0 imposes no client-side limit.
- ❺ A valid LDAP search filter. If this is left undefined, then the default is **(objectClass=*)**.
- ❻ The optional maximum size of response pages from the server, measured in LDAP entries. If set to 0, no size restrictions will be made on pages of responses. Setting paging sizes is necessary when queries return more entries than the client or server allow by default.

Table 12.1. LDAP Search Scope Options

LDAP Search Scope	Description
base	Only consider the object specified by the base DN given for the query.
one	Consider all of the objects on the same level in the tree as the base DN for the query.
sub	Consider the entire subtree rooted at the base DN given for the query.

Table 12.2. LDAP Dereferencing Behaviors

Dereferencing Behavior	Description
never	Never dereference any aliases found in the LDAP tree.
search	Only dereference aliases found while searching.
base	Only dereference aliases while finding the base object.
always	Always dereference all aliases found in the LDAP tree.

12.2.3. User-Defined Name Mapping

A user-defined name mapping explicitly maps the names of OpenShift Container Platform Groups to unique identifiers that find groups on your LDAP server. The mapping uses normal YAML syntax. A user-defined mapping can contain an entry for every group in your LDAP server or only a subset of those groups. If there are groups on the LDAP server that do not have a user-defined name mapping, the default behavior during sync is to use the attribute specified as the Group's name.

Example 12.3. User-Defined Name Mapping

```
groupUIDNameMapping:
  "cn=group1,ou=groups,dc=example,dc=com": firstgroup
  "cn=group2,ou=groups,dc=example,dc=com": secondgroup
  "cn=group3,ou=groups,dc=example,dc=com": thirdgroup
```

12.3. RUNNING LDAP SYNC

Once you have created a [sync configuration file](#), then sync can begin. OpenShift Container Platform allows administrators to perform a number of different sync types with the same server.



NOTE

By default, all group synchronization or pruning operations are dry-run, so you must set the **--confirm** flag on the **sync-groups** command in order to make changes to OpenShift Container Platform Group records.


To sync all groups from the LDAP server with OpenShift Container Platform:

```
$ oc adm groups sync --sync-config=config.yaml --confirm
```

To sync all Groups already in OpenShift Container Platform that correspond to groups in the LDAP server specified in the configuration file:

```
$ oc adm groups sync --type=openshift --sync-config=config.yaml --confirm
```

To sync a subset of LDAP groups with OpenShift Container Platform, you can use whitelist files, blacklist files, or both:



NOTE

Any combination of blacklist files, whitelist files, or whitelist literals will work; whitelist literals can be included directly in the command itself. This applies to groups found on LDAP servers, as well as Groups already present in OpenShift Container Platform. Your files must contain one unique group identifier per line.

```
$ oc adm groups sync --whitelist=<whitelist_file> \
    --sync-config=config.yaml \
    --confirm
$ oc adm groups sync --blacklist=<blacklist_file> \
    --sync-config=config.yaml \
    --confirm
$ oc adm groups sync <group_unique_identifier> \
    --sync-config=config.yaml \
    --confirm
$ oc adm groups sync <group_unique_identifier> \
    --whitelist=<whitelist_file> \
    --blacklist=<blacklist_file> \
    --sync-config=config.yaml \
    --confirm
$ oc adm groups sync --type=openshift \
    --whitelist=<whitelist_file> \
    --sync-config=config.yaml \
    --confirm
```

12.4. RUNNING A GROUP PRUNING JOB

An administrator can also choose to remove groups from OpenShift Container Platform records if the records on the LDAP server that created them are no longer present. The prune job will accept the same sync configuration file and white- or black-lists as used for the sync job.

For example, if groups had previously been synchronized from LDAP using some **config.yaml** file, and some of those groups no longer existed on the LDAP server, the following command would determine which Groups in OpenShift Container Platform corresponded to the deleted groups in LDAP and then remove them from OpenShift Container Platform:

```
$ oc adm groups prune --sync-config=config.yaml --confirm
```

12.5. SYNC EXAMPLES

This section contains examples for the [RFC 2307](#), [Active Directory](#), and [augmented Active Directory](#) schemas. All of the following examples synchronize a group named **admins** that has two members: **Jane** and **Jim**. Each example explains:

- How the group and users are added to the LDAP server.
- What the LDAP sync configuration file looks like.
- What the resulting Group record in OpenShift Container Platform will be after synchronization.

**NOTE**

These examples assume that all users are direct members of their respective groups. Specifically, no groups have other groups as members. See [Nested Membership Sync Example](#) for information on how to sync nested groups.

12.5.1. RFC 2307

In the RFC 2307 schema, both users (Jane and Jim) and groups exist on the LDAP server as first-class entries, and group membership is stored in attributes on the group. The following snippet of **ldif** defines the users and group for this schema:

Example 12.4. LDAP Entries Using RFC 2307 Schema: *rfc2307.ldif*

```
dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com

dn: ou=groups,dc=example,dc=com
objectClass: organizationalUnit
ou: groups

dn: cn=admins,ou=groups,dc=example,dc=com 1
objectClass: groupOfNames
cn: admins
owner: cn=admin,dc=example,dc=com
description: System Administrators
member: cn=Jane,ou=users,dc=example,dc=com 2
member: cn=Jim,ou=users,dc=example,dc=com
```

- 1 The group is a first-class entry in the LDAP server.
- 2 Members of a group are listed with an identifying reference as attributes on the group.

To sync this group, you must first create the configuration file. The RFC 2307 schema requires you to provide an LDAP query definition for both user and group entries, as well as the attributes with which to represent them in the internal OpenShift Container Platform records.

For clarity, the Group you create in OpenShift Container Platform should use attributes other than the distinguished name whenever possible for user- or administrator-facing fields. For example, identify the users of a Group by their e-mail, and use the name of the group as the common name. The following configuration file creates these relationships:



NOTE

If using user-defined name mappings, your [configuration file](#) will differ.

Example 12.5. LDAP Sync Configuration Using RFC 2307 Schema: *rfc2307_config.yaml*

```
kind: LDAPSynConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389 ❶
insecure: false ❷
rfc2307:
  groupsQuery:
    baseDN: "ou=groups,dc=example,dc=com"
    scope: sub
    derefAliases: never
    pageSize: 0
  groupUIDAttribute: dn ❸
  groupNameAttributes: [ cn ] ❹
  groupMembershipAttributes: [ member ] ❺
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never
    pageSize: 0
  userUIDAttribute: dn ❻
  userNameAttributes: [ mail ] ❼
  tolerateMemberNotFoundErrors: false
  tolerateMemberOutOfScopeErrors: false
```

- ❶ The IP address and host of the LDAP server where this group's record is stored.
- ❷ When **true**, no TLS connection is made to the server. When **false**, secure LDAP (**ldaps://**) URLs connect using TLS, and insecure LDAP (**ldap://**) URLs are upgraded to TLS.
- ❸ The attribute that uniquely identifies a group on the LDAP server. You cannot specify **groupsQuery** filters when using DN for groupUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).
- ❹ The attribute to use as the name of the Group.
- ❺ The attribute on the group that stores the membership information.
- ❻ The attribute that uniquely identifies a user on the LDAP server. You cannot specify **usersQuery** filters when using DN for userUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).

- 7 The attribute to use as the name of the user in the OpenShift Container Platform Group record.

To run sync with the *rfc2307_config.yaml* file:

```
$ oc adm groups sync --sync-config=rfc2307_config.yaml --confirm
```

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

Example 12.6. OpenShift Container Platform Group Created Using *rfc2307_config.yaml*

```
apiVersion: v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400 1
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com 2
    openshift.io/ldap.url: LDAP_SERVER_IP:389 3
  creationTimestamp:
    name: admins 4
users: 5
- jane.smith@example.com
- jim.adams@example.com
```

- 1 The last time this Group was synchronized with the LDAP server, in ISO 6801 format.
- 2 The unique identifier for the group on the LDAP server.
- 3 The IP address and host of the LDAP server where this Group's record is stored.
- 4 The name of the Group as specified by the sync file.
- 5 The users that are members of the Group, named as specified by the sync file.

12.5.1.1. RFC2307 with User-Defined Name Mappings

When syncing groups with user-defined name mappings, the configuration file changes to contain these mappings as shown below.

Example 12.7. LDAP Sync Configuration Using RFC 2307 Schema With User-Defined Name Mappings: *rfc2307_config_user_defined.yaml*

```
kind: LDAPSyncConfig
apiVersion: v1
groupUIDNameMapping:
  "cn=admins,ou=groups,dc=example,dc=com": Administrators 1
rfc2307:
  groupsQuery:
    baseDN: "ou=groups,dc=example,dc=com"
    scope: sub
```

```

    derefAliases: never
    pageSize: 0
  groupUIDAttribute: dn 2
  groupNameAttributes: [ cn ] 3
  groupMembershipAttributes: [ member ]
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never
    pageSize: 0
  userUIDAttribute: dn 4
  userNameAttributes: [ mail ]
  tolerateMemberNotFoundErrors: false
  tolerateMemberOutOfScopeErrors: false

```

- 1** The user-defined name mapping.
- 2** The unique identifier attribute that is used for the keys in the user-defined name mapping. You cannot specify **groupsQuery** filters when using DN for groupUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).
- 3** The attribute to name OpenShift Container Platform Groups with if their unique identifier is not in the user-defined name mapping.
- 4** The attribute that uniquely identifies a user on the LDAP server. You cannot specify **usersQuery** filters when using DN for userUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).

To run sync with the *rfc2307_config_user_defined.yaml* file:

```
$ oc adm groups sync --sync-config=rfc2307_config_user_defined.yaml --confirm
```

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

Example 12.8. OpenShift Container Platform Group Created Using *rfc2307_config_user_defined.yaml*

```

apiVersion: v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com
    openshift.io/ldap.url: LDAP_SERVER_IP:389
  creationTimestamp:
  name: Administrators 1
users:
- jane.smith@example.com
- jim.adams@example.com

```

- 1 The name of the Group as specified by the user-defined name mapping.

12.5.2. RFC 2307 with User-Defined Error Tolerances

By default, if the groups being synced contain members whose entries are outside of the scope defined in the member query, the group sync fails with an error:

```
Error determining LDAP group membership for "<group>": membership lookup
for user "<user>" in group "<group>" failed because of "search for entry
with dn="<user-dn>" would search outside of the base dn specified (dn="
<base-dn>")".
```

This often indicates a mis-configured **baseDN** in the **usersQuery** field. However, in cases where the **baseDN** intentionally does not contain some of the members of the group, setting **tolerateMemberOutOfScopeErrors: true** allows the group sync to continue. Out of scope members will be ignored.

Similarly, when the group sync process fails to locate a member for a group, it fails outright with errors:

```
Error determining LDAP group membership for "<group>": membership lookup
for user "<user>" in group "<group>" failed because of "search for entry
with base dn="<user-dn>" refers to a non-existent entry".
```

```
Error determining LDAP group membership for "<group>": membership lookup
for user "<user>" in group "<group>" failed because of "search for entry
with base dn="<user-dn>" and filter "<filter>" did not return any results".
```

This often indicates a mis-configured **usersQuery** field. However, in cases where the group contains member entries that are known to be missing, setting **tolerateMemberNotFoundErrors: true** allows the group sync to continue. Problematic members will be ignored.



WARNING

Enabling error tolerances for the LDAP group sync causes the sync process to ignore problematic member entries. If the LDAP group sync is not configured correctly, this could result in synced OpenShift Container Platform groups missing members.

Example 12.9. LDAP Entries Using RFC 2307 Schema With Problematic Group Membership: *rfc2307_problematic_users.ldif*

```
dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
```



```

objectClass: organizationalPerson
objectClass: inetOrgPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com

dn: ou=groups,dc=example,dc=com
objectClass: organizationalUnit
ou: groups

dn: cn=admins,ou=groups,dc=example,dc=com
objectClass: groupOfNames
cn: admins
owner: cn=admin,dc=example,dc=com
description: System Administrators
member: cn=Jane,ou=users,dc=example,dc=com
member: cn=Jim,ou=users,dc=example,dc=com
member: cn=INVALID,ou=users,dc=example,dc=com ❶
member: cn=Jim,ou=OUTOFSCOPE,dc=example,dc=com ❷

```

- ❶ A member that does not exist on the LDAP server.
- ❷ A member that may exist, but is not under the **baseDN** in the user query for the sync job.

In order to tolerate the errors in the above example, the following additions to your sync configuration file must be made:

Example 12.10. LDAP Sync Configuration Using RFC 2307 Schema Tolerating Errors: *rfc2307_config_tolerating.yaml*

```

kind: LDAPSyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389
rfc2307:
  groupsQuery:
    baseDN: "ou=groups,dc=example,dc=com"
    scope: sub
    derefAliases: never
  groupUIDAttribute: dn
  groupNameAttributes: [ cn ]
  groupMembershipAttributes: [ member ]
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"

```

```

    scope: sub
    derefAliases: never
    userUIDAttribute: dn 1
    userNameAttributes: [ mail ]
    tolerateMemberNotFoundErrors: true 2
    tolerateMemberOutOfScopeErrors: true 3

```

- 2** When **true**, the sync job tolerates groups for which some members were not found, and members whose LDAP entries are not found are ignored. The default behavior for the sync job is to fail if a member of a group is not found.
- 3** When **true**, the sync job tolerates groups for which some members are outside the user scope given in the **usersQuery** base DN, and members outside the member query scope are ignored. The default behavior for the sync job is to fail if a member of a group is out of scope.
- 1** The attribute that uniquely identifies a user on the LDAP server. You cannot specify **usersQuery** filters when using DN for userUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).

To run sync with the *rfc2307_config_tolerating.yaml* file:

```
$ oc adm groups sync --sync-config=rfc2307_config_tolerating.yaml --confirm
```

OpenShift Container Platform creates the following group record as a result of the above sync operation:

Example 12.11. OpenShift Container Platform Group Created Using *rfc2307_config.yaml*

```

apiVersion: v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com
    openshift.io/ldap.url: LDAP_SERVER_IP:389
  creationTimestamp:
  name: admins
users: 1
- jane.smith@example.com
- jim.adams@example.com

```

- 1** The users that are members of the group, as specified by the sync file. Members for which lookup encountered tolerated errors are absent.

12.5.3. Active Directory

In the Active Directory schema, both users (Jane and Jim) exist in the LDAP server as first-class entries, and group membership is stored in attributes on the user. The following snippet of **ldif** defines the users and group for this schema:

■

Example 12.12. LDAP Entries Using Active Directory Schema: *active_directory.ldif*

```

dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com
memberOf: admins ❶

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com
memberOf: admins

```

- ❶ The user's group memberships are listed as attributes on the user, and the group does not exist as an entry on the server. The **memberOf** attribute does not have to be a literal attribute on the user; in some LDAP servers, it is created during search and returned to the client, but not committed to the database.

To sync this group, you must first create the configuration file. The Active Directory schema requires you to provide an LDAP query definition for user entries, as well as the attributes to represent them with in the internal OpenShift Container Platform Group records.

For clarity, the Group you create in OpenShift Container Platform should use attributes other than the distinguished name whenever possible for user- or administrator-facing fields. For example, identify the users of a Group by their e-mail, but define the name of the Group by the name of the group on the LDAP server. The following configuration file creates these relationships:

Example 12.13. LDAP Sync Configuration Using Active Directory Schema: *active_directory_config.yaml*

```

kind: LDAPSyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389
activeDirectory:
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never

```

```

    filter: (objectclass=inetOrgPerson)
    pageSize: 0
    userNameAttributes: [ mail ] ❶
    groupMembershipAttributes: [ memberOf ] ❷

```

- ❶ The attribute to use as the name of the user in the OpenShift Container Platform Group record.
- ❷ The attribute on the user that stores the membership information.

To run sync with the ***active_directory_config.yaml*** file:

```
$ oc adm groups sync --sync-config=active_directory_config.yaml --confirm
```

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

Example 12.14. OpenShift Container Platform Group Created Using *active_directory_config.yaml*

```

apiVersion: v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400 ❶
    openshift.io/ldap.uid: admins ❷
    openshift.io/ldap.url: LDAP_SERVER_IP:389 ❸
  creationTimestamp:
    name: admins ❹
  users: ❺
  - jane.smith@example.com
  - jim.adams@example.com

```

- ❶ The last time this Group was synchronized with the LDAP server, in ISO 6801 format.
- ❷ The unique identifier for the group on the LDAP server.
- ❸ The IP address and host of the LDAP server where this Group's record is stored.
- ❹ The name of the group as listed in the LDAP server.
- ❺ The users that are members of the Group, named as specified by the sync file.

12.5.4. Augmented Active Directory

In the augmented Active Directory schema, both users (Jane and Jim) and groups exist in the LDAP server as first-class entries, and group membership is stored in attributes on the user. The following snippet of **ldif** defines the users and group for this schema:

Example 12.15. LDAP Entries Using Augmented Active Directory Schema: *augmented_active_directory.ldif*

```
dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com
memberOf: cn=admins,ou=groups,dc=example,dc=com 1

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com
memberOf: cn=admins,ou=groups,dc=example,dc=com

dn: ou=groups,dc=example,dc=com
objectClass: organizationalUnit
ou: groups

dn: cn=admins,ou=groups,dc=example,dc=com 2
objectClass: groupOfNames
cn: admins
owner: cn=admin,dc=example,dc=com
description: System Administrators
member: cn=Jane,ou=users,dc=example,dc=com
member: cn=Jim,ou=users,dc=example,dc=com
```

- 1 The user's group memberships are listed as attributes on the user.
- 2 The group is a first-class entry on the LDAP server.

To sync this group, you must first create the configuration file. The augmented Active Directory schema requires you to provide an LDAP query definition for both user entries and group entries, as well as the attributes with which to represent them in the internal OpenShift Container Platform Group records.

For clarity, the Group you create in OpenShift Container Platform should use attributes other than the distinguished name whenever possible for user- or administrator-facing fields. For example, identify the users of a Group by their e-mail, and use the name of the Group as the common name. The following configuration file creates these relationships.

Example 12.16. LDAP Sync Configuration Using Augmented Active Directory Schema: *augmented_active_directory_config.yaml*

```

kind: LDAPSyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389
augmentedActiveDirectory:
  groupsQuery:
    baseDN: "ou=groups,dc=example,dc=com"
    scope: sub
    derefAliases: never
    pageSize: 0
  groupUIDAttribute: dn ❶
  groupNameAttributes: [ cn ] ❷
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never
    filter: (objectclass=inetOrgPerson)
    pageSize: 0
  userNameAttributes: [ mail ] ❸
  groupMembershipAttributes: [ memberOf ] ❹

```

- ❶ The attribute that uniquely identifies a group on the LDAP server. You cannot specify **groupsQuery** filters when using DN for groupUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).
- ❷ The attribute to use as the name of the Group.
- ❸ The attribute to use as the name of the user in the OpenShift Container Platform Group record.
- ❹ The attribute on the user that stores the membership information.

To run sync with the ***augmented_active_directory_config.yaml*** file:

```

$ oc adm groups sync --sync-config=augmented_active_directory_config.yaml
--confirm

```

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

Example 12.17. OpenShift Group Created Using *augmented_active_directory_config.yaml*

```

apiVersion: v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400 ❶
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com ❷
    openshift.io/ldap.url: LDAP_SERVER_IP:389 ❸
  creationTimestamp:
  name: admins ❹

```

```
users: 5
- jane.smith@example.com
- jim.adams@example.com
```

- 1 The last time this Group was synchronized with the LDAP server, in ISO 6801 format.
- 2 The unique identifier for the group on the LDAP server.
- 3 The IP address and host of the LDAP server where this Group's record is stored.
- 4 The name of the Group as specified by the sync file.
- 5 The users that are members of the Group, named as specified by the sync file.

12.6. NESTED MEMBERSHIP SYNC EXAMPLE

Groups in OpenShift Container Platform do not nest. The LDAP server must flatten group membership before the data can be consumed. Microsoft's Active Directory Server supports this feature via the [LDAP_MATCHING_RULE_IN_CHAIN](#) rule, which has the OID **1.2.840.113556.1.4.1941**. Furthermore, only explicitly [whitelisted](#) groups can be synced when using this matching rule.

This section has an example for the augmented Active Directory schema, which synchronizes a group named **admins** that has one user **Jane** and one group **otheradmins** as members. The **otheradmins** group has one user member: **Jim**. This example explains:

- How the group and users are added to the LDAP server.
- What the LDAP sync configuration file looks like.
- What the resulting Group record in OpenShift Container Platform will be after synchronization.

In the augmented Active Directory schema, both users (**Jane** and **Jim**) and groups exist in the LDAP server as first-class entries, and group membership is stored in attributes on the user or the group. The following snippet of **ldif** defines the users and groups for this schema:

LDAP Entries Using Augmented Active Directory Schema With Nested Members: *augmented_active_directory_nested.ldif*

```
dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com
memberOf: cn=admins,ou=groups,dc=example,dc=com 1
```

```

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com
memberOf: cn=otheradmins,ou=groups,dc=example,dc=com 2

dn: ou=groups,dc=example,dc=com
objectClass: organizationalUnit
ou: groups

dn: cn=admins,ou=groups,dc=example,dc=com 3
objectClass: group
cn: admins
owner: cn=admin,dc=example,dc=com
description: System Administrators
member: cn=Jane,ou=users,dc=example,dc=com
member: cn=otheradmins,ou=groups,dc=example,dc=com

dn: cn=otheradmins,ou=groups,dc=example,dc=com 4
objectClass: group
cn: otheradmins
owner: cn=admin,dc=example,dc=com
description: Other System Administrators
memberOf: cn=admins,ou=groups,dc=example,dc=com 5 6
member: cn=Jim,ou=users,dc=example,dc=com

```

1 2 5 The user's and group's memberships are listed as attributes on the object.

3 4 The groups are first-class entries on the LDAP server.

6 The **otheradmins** group is a member of the **admins** group.

To sync nested groups with Active Directory, you must provide an LDAP query definition for both user entries and group entries, as well as the attributes with which to represent them in the internal OpenShift Container Platform Group records. Furthermore, certain changes are required in this configuration:

- The **oc adm groups sync** command must explicitly [whitelist](#) groups.
- The user's **groupMembershipAttributes** must include **"memberOf:1.2.840.113556.1.4.1941:"** to comply with the [LDAP_MATCHING_RULE_IN_CHAIN](#) rule.
- The **groupUIDAttribute** must be set to **dn**.
- The **groupsQuery**:
 - Must not set **filter**.
 - Must set a valid **derefAliases**.

- Should not set **baseDN** as that value is ignored.
- Should not set **scope** as that value is ignored.

For clarity, the Group you create in OpenShift Container Platform should use attributes other than the distinguished name whenever possible for user- or administrator-facing fields. For example, identify the users of a Group by their e-mail, and use the name of the Group as the common name. The following configuration file creates these relationships:

LDAP Sync Configuration Using Augmented Active Directory Schema With Nested Members: *augmented_active_directory_config_nested.yaml*

```
kind: LDAPSyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389
augmentedActiveDirectory:
  groupsQuery: ❶
    derefAliases: never
    pageSize: 0
  groupUIDAttribute: dn ❷
  groupNameAttributes: [ cn ] ❸
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never
    filter: (objectclass=inetOrgPerson)
    pageSize: 0
  userNameAttributes: [ mail ] ❹
  groupMembershipAttributes: [ "memberOf:1.2.840.113556.1.4.1941:" ] ❺
```

- ❶ **groupsQuery** filters cannot be specified. The **groupsQuery** base DN and scope values are ignored. **groupsQuery** must set a valid **derefAliases**.
- ❷ The attribute that uniquely identifies a group on the LDAP server. It must be set to **dn**.
- ❸ The attribute to use as the name of the Group.
- ❹ The attribute to use as the name of the user in the OpenShift Container Platform Group record. **mail** or **sAMAccountName** are preferred choices in most installations.
- ❺ The attribute on the user that stores the membership information. Note the use of [LDAP_MATCHING_RULE_IN_CHAIN](#).

To run sync with the *augmented_active_directory_config_nested.yaml* file:

```
$ oc adm groups sync \
  'cn=admins,ou=groups,dc=example,dc=com' \
  --sync-config=augmented_active_directory_config_nested.yaml \
  --confirm
```



NOTE

You must explicitly [whitelist](#) the **cn=admins,ou=groups,dc=example,dc=com** group.

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

OpenShift Group Created Using *augmented_active_directory_config_nested.yaml*

```
apiVersion: v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400 ❶
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com ❷
    openshift.io/ldap.url: LDAP_SERVER_IP:389 ❸
  creationTimestamp:
    name: admins ❹
users: ❺
- jane.smith@example.com
- jim.adams@example.com
```

- ❶ The last time this Group was synchronized with the LDAP server, in ISO 6801 format.
- ❷ The unique identifier for the group on the LDAP server.
- ❸ The IP address and host of the LDAP server where this Group's record is stored.
- ❹ The name of the Group as specified by the sync file.
- ❺ The users that are members of the Group, named as specified by the sync file. Note that members of nested groups are included since the group membership was flattened by the Microsoft Active Directory Server.

12.7. LDAP SYNC CONFIGURATION SPECIFICATION

The object specification for the configuration file is below. Note that the different schema objects have different fields. For example, [v1.ActiveDirectoryConfig](#) has no **groupsQuery** field whereas [v1.RFC2307Config](#) and [v1.AugmentedActiveDirectoryConfig](#) both do.



IMPORTANT

There is no support for binary attributes. All attribute data coming from the LDAP server must be in the format of a UTF-8 encoded string. For example, never use a binary attribute, such as **objectGUID**, as an ID attribute. You must use string attributes, such as **sAMAccountName** or **userPrincipalName**, instead.

12.7.1. v1.LDAPSyncConfig

LDAPSyncConfig holds the necessary configuration options to define an LDAP group sync.

Name	Description	Schema
------	-------------	--------

Name	Description	Schema
kind	String value representing the REST resource this object represents. Servers may infer this from the endpoint the client submits requests to. Cannot be updated. In CamelCase. More info: https://github.com/kubernetes/community/blob/master/contributors/devel/api-conventions.md#types-kinds	string
apiVersion	Defines the versioned schema of this representation of an object. Servers should convert recognized schemas to the latest internal value, and may reject unrecognized values. More info: https://github.com/kubernetes/community/blob/master/contributors/devel/api-conventions.md#resources	string
url	Host is the scheme, host and port of the LDAP server to connect to: scheme://host:port	string
bindDN	Optional DN to bind to the LDAP server with.	string
bindPassword	Optional password to bind with during the search phase.	v1.StringSource
insecure	If true , indicates the connection should not use TLS. Cannot be set to true with a URL scheme of ldaps:// If false , ldaps:// URLs connect using TLS, and ldap:// URLs are upgraded to a TLS connection using StartTLS as specified in https://tools.ietf.org/html/rfc2830 .	boolean
ca	Optional trusted certificate authority bundle to use when making requests to the server. If empty, the default system roots are used.	string

Name	Description	Schema
groupUIDNameMapping	Optional direct mapping of LDAP group UIDs to OpenShift Container Platform Group names.	object
rfc2307	Holds the configuration for extracting data from an LDAP server set up in a fashion similar to RFC2307: first-class group and user entries, with group membership determined by a multi-valued attribute on the group entry listing its members.	v1.RFC2307Config
activeDirectory	Holds the configuration for extracting data from an LDAP server set up in a fashion similar to that used in Active Directory: first-class user entries, with group membership determined by a multi-valued attribute on members listing groups they are a member of.	v1.ActiveDirectoryConfig
augmentedActiveDirectory	Holds the configuration for extracting data from an LDAP server set up in a fashion similar to that used in Active Directory as described above, with one addition: first-class group entries exist and are used to hold metadata but not group membership.	v1.AugmentedActiveDirectoryConfig

12.7.2. v1.StringSource

StringSource allows specifying a string inline, or externally via environment variable or file. When it contains only a string value, it marshals to a simple JSON string.

Name	Description	Schema
value	Specifies the cleartext value, or an encrypted value if keyFile is specified.	string
env	Specifies an environment variable containing the cleartext value, or an encrypted value if the keyFile is specified.	string

Name	Description	Schema
file	References a file containing the cleartext value, or an encrypted value if a keyFile is specified.	string
keyFile	References a file containing the key to use to decrypt the value.	string

12.7.3. v1.LDAPQuery

LDAPQuery holds the options necessary to build an LDAP query.

Name	Description	Schema
baseDN	DN of the branch of the directory where all searches should start from.	string
scope	The (optional) scope of the search. Can be base (only the base object), one (all objects on the base level), sub (the entire subtree). Defaults to sub if not set.	string
derefAliases	The (optional) behavior of the search with regards to aliases. Can be never (never dereference aliases), search (only dereference in searching), base (only dereference in finding the base object), always (always dereference). Defaults to always if not set.	string
timeout	Holds the limit of time in seconds that any request to the server can remain outstanding before the wait for a response is given up. If this is 0 , no client-side limit is imposed.	integer
filter	A valid LDAP search filter that retrieves all relevant entries from the LDAP server with the base DN.	string

Name	Description	Schema
pageSize	Maximum preferred page size, measured in LDAP entries. A page size of 0 means no paging will be done.	integer

12.7.4. v1.RFC2307Config

RFC2307Config holds the necessary configuration options to define how an LDAP group sync interacts with an LDAP server using the RFC2307 schema.

Name	Description	Schema
groupsQuery	Holds the template for an LDAP query that returns group entries.	v1.LDAPQuery
groupUIDAttribute	Defines which attribute on an LDAP group entry will be interpreted as its unique identifier. (ldapGroupUID)	string
groupNameAttributes	Defines which attributes on an LDAP group entry will be interpreted as its name to use for an OpenShift Container Platform group.	string array
groupMembershipAttributes	Defines which attributes on an LDAP group entry will be interpreted as its members. The values contained in those attributes must be queryable by your UserUIDAttribute .	string array
usersQuery	Holds the template for an LDAP query that returns user entries.	v1.LDAPQuery
userUIDAttribute	Defines which attribute on an LDAP user entry will be interpreted as its unique identifier. It must correspond to values that will be found from the GroupMembershipAttributes .	string

Name	Description	Schema
userNameAttributes	Defines which attributes on an LDAP user entry will be used, in order, as its OpenShift Container Platform user name. The first attribute with a non-empty value is used. This should match your PreferredUsername setting for your LDAPPasswordIdentityProvider . The attribute to use as the name of the user in the OpenShift Container Platform Group record. mail or sAMAccountName are preferred choices in most installations.	string array
tolerateMemberNotFoundErrors	Determines the behavior of the LDAP sync job when missing user entries are encountered. If true , an LDAP query for users that does not find any will be tolerated and an only an error will be logged. If false , the LDAP sync job will fail if a query for users doesn't find any. The default value is 'false'. Misconfigured LDAP sync jobs with this flag set to 'true' can cause group membership to be removed, so it is recommended to use this flag with caution.	boolean
tolerateMemberOutOfScopeErrors	Determines the behavior of the LDAP sync job when out-of-scope user entries are encountered. If true , an LDAP query for a user that falls outside of the base DN given for the all user query will be tolerated and only an error will be logged. If false , the LDAP sync job will fail if a user query would search outside of the base DN specified by the all user query. Misconfigured LDAP sync jobs with this flag set to true can result in groups missing users, so it is recommended to use this flag with caution.	boolean

12.7.5. v1.ActiveDirectoryConfig

ActiveDirectoryConfig holds the necessary configuration options to define how an LDAP group sync interacts with an LDAP server using the Active Directory schema.

Name	Description	Schema
usersQuery	Holds the template for an LDAP query that returns user entries.	v1.LDAPQuery
userNameAttributes	Defines which attributes on an LDAP user entry will be interpreted as its OpenShift Container Platform user name. The attribute to use as the name of the user in the OpenShift Container Platform Group record. mail or sAMAccountName are preferred choices in most installations.	string array
groupMembershipAttributes	Defines which attributes on an LDAP user entry will be interpreted as the groups it is a member of.	string array

12.7.6. v1.AugmentedActiveDirectoryConfig

AugmentedActiveDirectoryConfig holds the necessary configuration options to define how an LDAP group sync interacts with an LDAP server using the augmented Active Directory schema.

Name	Description	Schema
usersQuery	Holds the template for an LDAP query that returns user entries.	v1.LDAPQuery
userNameAttributes	Defines which attributes on an LDAP user entry will be interpreted as its OpenShift Container Platform user name. The attribute to use as the name of the user in the OpenShift Container Platform Group record. mail or sAMAccountName are preferred choices in most installations.	string array
groupMembershipAttributes	Defines which attributes on an LDAP user entry will be interpreted as the groups it is a member of.	string array


Name	Description	Schema
groupsQuery	Holds the template for an LDAP query that returns group entries.	v1.LDAPQuery
groupUIDAttribute	Defines which attribute on an LDAP group entry will be interpreted as its unique identifier. (ldapGroupUID)	string
groupNameAttributes	Defines which attributes on an LDAP group entry will be interpreted as its name to use for an OpenShift Container Platform group.	string array

CHAPTER 13. CONFIGURING LDAP FAILOVER

OpenShift Container Platform provides an [authentication provider](#) for use with Lightweight Directory Access Protocol (LDAP) setups, but it can connect to only a single LDAP server. During OpenShift Container Platform installation, you can configure the System Security Services Daemon (SSSD) for LDAP failover to ensure access to your cluster if one LDAP server fails.

The setup for this configuration is advanced and requires a separate authentication server, also called an **remote basic authentication server**, for OpenShift Container Platform to communicate with. You configure this server to pass extra attributes, such as email addresses, to OpenShift Container Platform so it can display them in the web console.

This topic describes how to complete this set up on a dedicated physical or virtual machine (VM), but you can also configure SSSD in containers.



IMPORTANT

You must complete all sections of this topic.

13.1. PREREQUISITES FOR CONFIGURING BASIC REMOTE AUTHENTICATION

- Before starting setup, you need to know the following information about your LDAP server:
 - Whether the directory server is powered by [FreeIPA](#), Active Directory, or another LDAP solution.
 - The Uniform Resource Identifier (URI) for the LDAP server, for example, **ldap.example.com**.
 - The location of the CA certificate for the LDAP server.
 - Whether the LDAP server corresponds to RFC 2307 or RFC2307bis for user groups.
- Prepare the servers:
 - **remote-basic.example.com**: A VM to use as the remote basic authentication server.
 - Select an operating system that includes SSSD version 1.12.0 for this server such as Red Hat Enterprise Linux 7.0 or later.
 - **openshift.example.com**: A new installation of OpenShift Container Platform.
 - You must not have an authentication method configured for this cluster.
 - Do not start OpenShift Container Platform on this cluster.

13.2. GENERATING AND SHARING CERTIFICATES WITH THE REMOTE BASIC AUTHENTICATION SERVER

Complete the following steps on the first master host listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

1. To ensure that communication between the remote basic authentication server and OpenShift Container Platform is trustworthy, create a set of Transport Layer Security (TLS) certificates to use during the other phases of this set up. Run the following command:

```
# openshift start \
  --public-master=https://openshift.example.com:8443 \
  --write-config=/etc/origin/
```

The output includes the **/etc/origin/master/ca.crt** and **/etc/origin/master/ca.key** signing certificates.

2. Use the signing certificate to generate keys to use on the remote basic authentication server:

```
# mkdir -p /etc/origin/remote-basic/
# oc adm ca create-server-cert \
  --cert='/etc/origin/remote-basic/remote-basic.example.com.crt' \
  --key='/etc/origin/remote-basic/remote-basic.example.com.key' \
  --hostnames=remote-basic.example.com \ 1
  --signer-cert='/etc/origin/master/ca.crt' \
  --signer-key='/etc/origin/master/ca.key' \
  --signer-serial='/etc/origin/master/ca.serial.txt'
```


1

A comma-separated list of all the host names and interface IP addresses that need to access the remote basic authentication server.



NOTE

The certificate files that you generate are valid for two years. You can alter this period by changing the **--expire-days** and **--signer-expire-days** values, but for security reasons, do not make them greater than 730.



IMPORTANT

If you do not list all host names and interface IP addresses that need to access the remote basic authentication server, the HTTPS connection will fail.

3. Copy the necessary certificates and key to the remote basic authentication server:

```
# scp /etc/origin/master/ca.crt \
  root@remote-basic.example.com:/etc/pki/CA/certs/

# scp /etc/origin/remote-basic/remote-basic.example.com.crt \
  root@remote-basic.example.com:/etc/pki/tls/certs/

# scp /etc/origin/remote-basic/remote-basic.example.com.key \
  root@remote-basic.example.com:/etc/pki/tls/private/
```

13.3. CONFIGURING SSSD FOR LDAP FAILOVER

Complete these steps on the remote basic authentication server.

You can configure the SSSD to retrieve attributes, such as email addresses and display names, and pass them to OpenShift Container Platform to display in the web interface. In the following steps, you configure the SSSD to provide email addresses to OpenShift Container Platform:

1. Install the required SSSD and the web server components:

```
# yum install -y sssd \
    sssd-dbus \
    realmd \
    httpd \
    mod_session \
    mod_ssl \
    mod_lookup_identity \
    mod_authnz_pam \
    php \
    mod_php
```

2. Set up SSSD to authenticate this VM against the LDAP server. If the LDAP server is a FreeIPA or Active Directory environment, then use **realmd** to join this machine to the domain.

```
# realm join ldap.example.com
```

For more advanced cases, see the [System-Level Authentication Guide](#)

3. To use SSSD to manage failover situations for LDAP, add more entries to the **/etc/sss/sss.conf** file on the **ldap_uri** line. Systems that are enrolled with FreeIPA can automatically handle failover by using DNS SRV records.
4. Modify the **[domain/DOMAINNAME]** section of the **/etc/sss/sss.conf** file and add this attribute:

```
[domain/example.com]
...
ldap_user_extra_attrs = mail ❶
```

- ❶ Specify the correct attribute to retrieve email addresses for your LDAP solution. For IPA, specify **mail**. Other LDAP solutions might use another attribute, such as **email**.

5. Confirm that the **domain** parameter in the **/etc/sss/sss.conf** file contains only the domain name listed in the **[domain/DOMAINNAME]** section.

```
domains = example.com
```

6. Grant Apache permission to retrieve the email attribute. Add the following lines to the **[ifp]** section of the **/etc/sss/sss.conf** file:

```
[ifp]
user_attributes = +mail
allowed_uids = apache, root
```

7. To ensure that all of the changes are applied properly, restart SSSD:

```
$ systemctl restart sssd.service
```

- Test that the user information can be retrieved properly:

```
$ getent passwd <username>
username:*:12345:12345:Example User:/home/username:/usr/bin/bash
```

- Confirm that the mail attribute you specified returns an email address from your domain:

```
# dbus-send --print-reply --system --
dest=org.freedesktop.sssd.infopipe \
  /org/freedesktop/sss/infopipe
org.freedesktop.sssd.infopipe.GetUserAttr \
  string:username \ ❶
  array:string:mail ❷

method return time=1528091855.672691 sender=:1.2787 ->
destination=:1.2795 serial=13 reply_serial=2
array [
  dict entry(
    string "mail"
    variant
      array [
        string "username@example.com"
      ]
  )
]
```

❶ Provide a user name in your LDAP solution.

❷ Specify the attribute that you configured.

- Attempt to log into the VM as an LDAP user and confirm that you can log in using LDAP credentials. You can use either the local console or a remote service like SSH to log in.



IMPORTANT

By default, all users can log into the remote basic authentication server by using their LDAP credentials. You can change this behavior:

- If you use IPA joined systems, [configure host-based access control](#).
- If you use Active Directory joined systems, use a [group policy object](#).
- For other cases, see the [SSSD configuration](#) documentation.

13.4. CONFIGURING APACHE TO USE SSSD

- Create a `/etc/pam.d/openshift` file that contains the following contents:


```
auth required pam_sss.so
account required pam_sss.so
```

This configuration enables PAM, the pluggable authentication module, to use **pam_sss.so** to determine authentication and access control when an authentication request is issued for the **openshift** stack.

2. Edit the `/etc/httpd/conf.modules.d/55-authnz_pam.conf` file and uncomment the following line:

```
LoadModule authnz_pam_module modules/mod_authnz_pam.so
```

3. To configure the Apache `httpd.conf` file for remote basic authentication, create the ***openshift-remote-basic-auth.conf*** file in the `/etc/httpd/conf.d` directory. Use the following template to provide your required settings and values:



IMPORTANT

Carefully review the template and customize its contents to fit your environment.

```
LoadModule request_module modules/mod_request.so
LoadModule php7_module modules/libphp7.so

# Nothing needs to be served over HTTP. This virtual host simply
# redirects to
# HTTPS.
<VirtualHost *:80>
    DocumentRoot /var/www/html
    RewriteEngine On
    RewriteRule ^(.*)$ https://%{HTTP_HOST}$1 [R,L]
</VirtualHost>

<VirtualHost *:443>
    # This needs to match the certificates you generated. See the CN
    # and X509v3
    # Subject Alternative Name in the output of:
    # openssl x509 -text -in /etc/pki/tls/certs/remote-
    # basic.example.com.crt
    ServerName remote-basic.example.com

    DocumentRoot /var/www/html

    # Secure all connections with TLS
    SSLEngine on
    SSLCertificateFile /etc/pki/tls/certs/remote-basic.example.com.crt
    SSLCertificateKeyFile /etc/pki/tls/private/remote-
    basic.example.com.key
    SSLCACertificateFile /etc/pki/CA/certs/ca.crt

    # Require that TLS clients provide a valid certificate
    SSLVerifyClient require
    SSLVerifyDepth 10

    # Other SSL options that may be useful
    # SSLCertificateChainFile ...
    # SSLCARevocationFile ...

    # Send logs to a specific location to make them easier to find
    ErrorLog logs/remote_basic_error_log
    TransferLog logs/remote_basic_access_log
    LogLevel warn

    # PHP script that turns the Apache REMOTE_USER env var
```

```

# into a JSON formatted response that OpenShift understands
<Location /check_user.php>
# all requests not using SSL are denied
SSLRequireSSL
# denies access when SSLRequireSSL is applied
SSLOptions +StrictRequire
# Require both a valid basic auth user (so REMOTE_USER is always
set)
# and that the CN of the TLS client matches that of the
OpenShift master
<RequireAll>
    Require valid-user
    Require expr %{SSL_CLIENT_S_DN_CN} == 'system:openshift-
master'
</RequireAll>
# Use basic auth since OpenShift will call this endpoint with a
basic challenge
AuthType Basic
AuthName openshift
AuthBasicProvider PAM
AuthPAMService openshift

# Store attributes in environment variables. Specify the email
attribute that
# you confirmed.
LookupOutput Env
LookupUserAttr mail REMOTE_USER_MAIL
LookupUserGECOS REMOTE_USER_DISPLAY_NAME

# Other options that might be useful

# While REMOTE_USER is used as the sub field and serves as the
immutable ID,
# REMOTE_USER_PREFERRED_USERNAME could be used to have a
different username
# LookupUserAttr <attr_name> REMOTE_USER_PREFERRED_USERNAME

# Group support may be added in a future release
# LookupUserGroupsIter REMOTE_USER_GROUP
</Location>

# Deny everything else
<Location ~ "^(?!\/check_user\.php)\.*)">
    Deny from all
</Location>
</VirtualHost>

```

4. Create the **check_user.php** script in the **/var/www/html** directory. Include the following code:

```

<?php
// Get the user based on the Apache var, this should always be
// set because we 'Require valid-user' in the configuration
$user = apache_getenv('REMOTE_USER');

// However, we assume it may not be set and
// build an error response by default

```

```

$data = array(
    'error' => 'remote PAM authentication failed'
);

// Build a success response if we have a user
if (!empty($user)) {
    $data = array(
        'sub' => $user
    );
    // Map of optional environment variables to optional JSON fields
    $env_map = array(
        'REMOTE_USER_MAIL' => 'email',
        'REMOTE_USER_DISPLAY_NAME' => 'name',
        'REMOTE_USER_PREFERRED_USERNAME' => 'preferred_username'
    );

    // Add all non-empty environment variables to JSON data
    foreach ($env_map as $env_name => $json_name) {
        $env_data = apache_getenv($env_name);
        if (!empty($env_data)) {
            $data[$json_name] = $env_data;
        }
    }
}

// We always output JSON from this script
header('Content-Type: application/json', true);

// Write the response as JSON
echo json_encode($data);
?>

```

5. Enable Apache to load the module. Modify the `/etc/httpd/conf.modules.d/55-lookup_identity.conf` file and uncomment the following line:

```
LoadModule lookup_identity_module modules/mod_lookup_identity.so
```

6. Set an SELinux boolean so that SELinux allows Apache to connect to SSSD over D-BUS:

```
# setsebool -P httpd_dbus_sssd on
```

7. Set a boolean to tell SELinux that it is acceptable for Apache to contact the PAM subsystem:

```
# setsebool -P allow_httpd_mod_auth_pam on
```

8. Start Apache:

```
# systemctl start httpd.service
```

13.5. CONFIGURING OPENSIFT CONTAINER PLATFORM TO USE SSSD AS THE BASIC REMOTE AUTHENTICATION SERVER

Modify the default configuration of your cluster to use the new identity provider that you created. Complete the following steps on the first master host listed in the Ansible host inventory file.

1. Open the `/etc/origin/master/master-config.yaml` file.
2. Locate the **identityProviders** section and replace it with the following code:

```
identityProviders:
- name: sssd
  challenge: true
  login: true
  mappingMethod: claim
  provider:
    apiVersion: v1
    kind: BasicAuthPasswordIdentityProvider
    url: https://remote-basic.example.com/check_user.php
    ca: /etc/origin/master/ca.crt
    certFile: /etc/origin/master/openshift-master.crt
    keyFile: /etc/origin/master/openshift-master.key
```

3. Start OpenShift Container Platform with the updated configuration:

```
# openshift start \
--public-master=https://openshift.example.com:8443 \
--master-config=/etc/origin/master/master-config.yaml \
--node-config=/etc/origin/node-node1.example.com/node-
config.yaml
```

4. Test a login by using the **oc** CLI:

```
oc login https://openshift.example.com:8443
```

You can log in only with valid LDAP credentials.

5. List the identities and confirm that an email address is displayed for each user name. Run the following command:

```
$ oc get identity -o yaml
```

CHAPTER 14. CONFIGURING THE SDN

14.1. OVERVIEW

The [OpenShift SDN](#) enables communication between pods across the OpenShift Container Platform cluster, establishing a *pod network*. Three [SDN plug-ins](#) are currently available (**ovs-subnet**, **ovs-multitenant**, and **ovs-networkpolicy**), which provide different methods for configuring the pod network.

14.2. AVAILABLE SDN PROVIDERS

The upstream Kubernetes project does not come with a default network solution. Instead, Kubernetes has developed a Container Network Interface (CNI) to allow network providers for integration with their own SDN solutions.

There are several OpenShift SDN plugins available out of the box from Red Hat, as well as third-party plug-ins.

Red Hat has worked with a number of SDN providers to certify their SDN network solution on OpenShift Container Platform via the Kubernetes CNI interface, including a support process for their SDN plug-in through their product's entitlement process. Should you open a support case with OpenShift, Red Hat can facilitate an exchange process so that both companies are involved in meeting your needs.

The following SDN solutions are validated and supported on OpenShift Container Platform directly by the 3rd party vendor:

- Cisco Contiv (™)
- Juniper Contrail (™)
- Nokia Nuage (™)
- Tigera Calico (™)
- VMware NSX-T (™)

Installing VMware NSX-T (™) on OpenShift Container Platform

VMware NSX-T (™) provides an SDN and security infrastructure to build cloud-native application environments. In addition to vSphere hypervisors (ESX), these environments include KVM and native public clouds.

The current integration requires a *new* install of both NSX-T and OpenShift Container Platform. Currently, NSX-T version 2.1 is supported, and only supports the use of ESX and KVM hypervisors at this time.

See the [NSX-T Container Plug-in for OpenShift - Installation and Administration Guide](#) for more information.

14.3. CONFIGURING THE POD NETWORK WITH ANSIBLE

For initial [advanced installations](#), the **ovs-subnet** plug-in is installed and configured by default, though it can be [overridden during installation](#) using the [os_sdn_network_plugin_name parameter](#), which is configurable in the Ansible inventory file.

Example 14.1. Example SDN Configuration with Ansible

–

```
# Configure the multi-tenant SDN plugin (default is 'redhat/openshift-
ovs-subnet')
# os_sdn_network_plugin_name='redhat/openshift-ovs-multitenant'

# Configure the NetworkPolicy SDN plugin
# os_sdn_network_plugin_name='redhat/openshift-ovs-networkpolicy'

# Disable the OpenShift SDN plugin
# openshift_use_openshift_sdn=False

# Configure SDN cluster network CIDR block. This network block should
# be a private block and should not conflict with existing network
# blocks in your infrastructure that pods may require access to.
# Can not be changed after deployment.
#osm_cluster_network_cidr=10.1.0.0/16

# default subdomain to use for exposed routes
#openshift_master_default_subdomain=apps.test.example.com

# Configure SDN cluster network and kubernetes service CIDR blocks.
These
# network blocks should be private and should not conflict with network
# blocks
# in your infrastructure that pods may require access to. Can not be
# changed
# after deployment.
#osm_cluster_network_cidr=10.1.0.0/16
#openshift_portal_net=172.30.0.0/16

# Configure number of bits to allocate to each host's subnet e.g. 8
# would mean a /24 network on the host.
#osm_host_subnet_length=8

# This variable specifies the service proxy implementation to use:
# either iptables for the pure-iptables version (the default),
# or userspace for the userspace proxy.
#openshift_node_proxy_mode=iptables
```

For initial [quick installations](#), the **ovs-subnet** plug-in is installed and configured by default as well, and can be [reconfigured post-installation](#) using the **networkConfig** stanza of the **master-config.yaml** file.

14.4. CONFIGURING THE POD NETWORK ON MASTERS

The cluster administrators can control pod network settings on master hosts by modifying parameters in the **networkConfig** section of the [master configuration file](#) (located at **/etc/origin/master/master-config.yaml** by default):

Configuring a pod network for a single CIDR

```
networkConfig:
  clusterNetworks:
    - cidr: 10.128.0.0/14 1
```

```

    hostSubnetLength: 9 ❷
    networkPluginName: "redhat/openshift-ovs-subnet" ❸
    serviceNetworkCIDR: 172.30.0.0/16 ❹

```

- ❶ Cluster network for node IP allocation
- ❷ Number of bits for pod IP allocation within a node
- ❸ Set to **redhat/openshift-ovs-subnet** for the **ovs-subnet** plug-in, **redhat/openshift-ovs-multitenant** for the **ovs-multitenant** plug-in, or **redhat/openshift-ovs-networkpolicy** for the **ovs-networkpolicy** plug-in
- ❹ Service IP allocation for the cluster

Alternatively, you can create a pod network with multiple CIDR ranges by adding separate ranges into the **clusterNetworks** field with the range and the **hostSubnetLength**.

Multiple ranges can be used at once, and the range can be expanded or contracted. Nodes can be moved from one range to another by evacuating a node, then deleting and re-creating the node. See the [Managing Nodes](#) section for more information. Node allocations occur in the order listed, then when the range is full, move to the next on the list.

Configuring a pod network for multiple CIDRs


```

networkConfig:
  clusterNetworks:
    - cidr: 10.128.0.0/14 ❶
      hostSubnetLength: 9 ❷
    - cidr: 10.132.0.0/14
      hostSubnetLength: 9
  externalIPNetworkCIDRs: null
  hostSubnetLength: 9
  ingressIPNetworkCIDR: 172.29.0.0/16
  networkPluginName: redhat/openshift-ovs-multitenant ❸
  serviceNetworkCIDR: 172.30.0.0/16

```

- ❶ Cluster network for node IP allocation.
- ❷ Number of bits for pod IP allocation within a node.
- ❸ Set to **redhat/openshift-ovs-subnet** for the **ovs-subnet** plug-in, **redhat/openshift-ovs-multitenant** for the **ovs-multitenant** plug-in, or **redhat/openshift-ovs-networkpolicy** for the **ovs-networkpolicy** plug-in.

You can add elements to the **clusterNetworks** value, or remove them if no node is using that CIDR range, but be sure to restart the **atomic-openshift-master-api** and **atomic-openshift-master-controllers** services for any changes to take effect.



IMPORTANT

The **hostSubnetLength** value cannot be changed after the cluster is first created, A **cidr** field can only be changed to be a larger network that still contains the original network if nodes are allocated within it's range , and **serviceNetworkCIDR** can only be expanded. For example, given the default value of **10.128.0.0/14**, you could change **cidr** to **10.128.0.0/9** (i.e., the entire upper half of net 10) but not to **10.64.0.0/16**, because that does not overlap the original value.

You can change **serviceNetworkCIDR** from **172.30.0.0/16** to **172.30.0.0/15**, but not to **172.28.0.0/14**, because even though the original range is entirely inside the new range, the original range must be at the start of the CIDR.

14.5. CONFIGURING THE POD NETWORK ON NODES

The cluster administrators can control pod network settings on nodes by modifying parameters in the **networkConfig** section of the [node configuration file](#) (located at `/etc/origin/node/node-config.yaml` by default):

```
networkConfig:
  mtu: 1450 ❶
  networkPluginName: "redhat/openshift-ovs-subnet" ❷
```

- ❶ Maximum transmission unit (MTU) for the pod overlay network
- ❷ Set to **redhat/openshift-ovs-subnet** for the **ovs-subnet** plug-in, **redhat/openshift-ovs-multitenant** for the **ovs-multitenant** plug-in, or **redhat/openshift-ovs-networkpolicy** for the **ovs-networkpolicy** plug-in



NOTE

You must change the MTU size on all masters and nodes that are part of the OpenShift Container Platform SDN. Also, the MTU size of the tun0 interface must be the same across all nodes that are part of the cluster.

14.6. MIGRATING BETWEEN SDN PLUG-INS

If you are already using one SDN plug-in and want to switch to another:

1. Change the **networkPluginName** parameter on all [masters](#) and [nodes](#) in their configuration files.
2. Restart the **atomic-openshift-master-api** and **atomic-openshift-master-controller** on masters and the **atomic-openshift-node** service on nodes.
3. If you are switching from an OpenShift SDN plug-in to a third-party plug-in, then clean up OpenShift SDN-specific artifacts:

```
$ oc delete clusternetwork --all
$ oc delete hostsubnets --all
$ oc delete netnamespaces --all
```

When switching from the **ovs-subnet** to the **ovs-multitenant** OpenShift SDN plug-in, all the existing projects in the cluster will be fully isolated (assigned unique VNIDs). The cluster administrators can choose to [modify the project networks](#) using the administrator CLI.

Check VNIDs by running:

```
$ oc get netnamespace
```

14.6.1. Migrating from ovs-multitenant to ovs-networkpolicy

In addition to the generic plug-in migration steps above in the [Migrating between SDN plug-ins](#) section, there is one additional step when migrating from the **ovs-multitenant** plug-in to the **ovs-networkpolicy** plug-in; you must ensure that every namespace has a unique **NetID**. This means that if you have previously [joined projects together](#) or [made projects global](#), you will need to undo that before switching to the **ovs-networkpolicy** plug-in, or the NetworkPolicy objects may not function correctly.

A helper script is available that fixes **NetID**'s, creates NetworkPolicy objects to isolate previously-isolated namespaces, and enables connections between previously-joined namespaces.

Use the following steps to migrate to the **ovs-networkpolicy** plugin, by using this helper script, while still running the **ovs-multitenant** plugin:

1. Download the script and add the execution file permission:

```
$ curl -O
https://raw.githubusercontent.com/openshift/origin/master/contrib/mi
gration/migrate-network-policy.sh
$ chmod a+x migrate-network-policy.sh
```

2. Run the script (requires the cluster administrator role).

```
$ ./migrate-network-policy.sh
```

After running this script, every namespace is fully isolated from every other namespace, therefore connection attempts between pods in different namespaces will fail until you complete the migration to the **ovs-networkpolicy** plugin.

If you want newly-created namespaces to also have the same policies by default, you can set [default NetworkPolicy objects](#) to be created matching the **default-deny** and **allow-from-global-namespaces** policies created by the migration script.



NOTE

In case of script failures or other errors, or if you later decide you want to revert back to the **ovs-multitenant** plugin, you can use the [un-migration script](#). This script undoes the changes made by the migration script and re-joins previously-joined namespaces.

14.7. EXTERNAL ACCESS TO THE CLUSTER NETWORK

If a host that is external to OpenShift Container Platform requires access to the cluster network, you have two options:

1. Configure the host as an OpenShift Container Platform node but mark it [unschedulable](#) so that the master does not schedule containers on it.

2. Create a tunnel between your host and a host that is on the cluster network.


Both options are presented as part of a practical use-case in the documentation for configuring [routing from an edge load-balancer to containers within OpenShift SDN](#).

14.8. USING FLANNEL

As an alternate to the default SDN, OpenShift Container Platform also provides Ansible playbooks for installing **flannel**-based networking. This is useful if running OpenShift Container Platform within a cloud provider platform that also relies on SDN, such as Red Hat OpenStack Platform, and you want to avoid encapsulating packets twice through both platforms.


Flannel uses a single IP network space for all of the containers allocating a contiguous subset of the space to each instance. Consequently, nothing prevents a container from attempting to contact any IP address in the same network space. This hinders multi-tenancy because the network cannot be used to isolate containers in one application from another.

Depending on whether you prefer multi-tenancy isolation or performance, you should determine the appropriate choice when deciding between OpenShift SDN (multi-tenancy) and flannel (performance) for internal networks.



IMPORTANT

Flannel is only supported for OpenShift Container Platform on Red Hat OpenStack Platform.



IMPORTANT

The current version of Neutron enforces port security on ports by default. This prevents the port from sending or receiving packets with a MAC address different from that on the port itself. Flannel creates virtual MACs and IP addresses and must send and receive packets on the port, so port security must be disabled on the ports that carry flannel traffic.

To enable flannel within your OpenShift Container Platform cluster:

1. Neutron port security controls must be configured to be compatible with Flannel. The default configuration of Red Hat OpenStack Platform disables user control of **port_security**. Configure Neutron to allow users to control the **port_security** setting on individual ports.
 - a. On the Neutron servers, add the following to the `/etc/neutron/plugins/ml2/ml2_conf.ini` file:

```
[ml2]
...
extension_drivers = port_security
```

- b. Then, restart the Neutron services:

```
service neutron-dhcp-agent restart
service neutron-ovs-cleanup restart
service neutron-metadata-agent restart
service neutron-l3-agent restart
service neutron-plugin-openvswitch-agent restart
service neutron-vpn-agent restart
service neutron-server restart
```

2. When creating the OpenShift Container Platform instances on Red Hat OpenStack Platform, disable both port security and security groups in the ports where the container network flannel interface will be:

```
neutron port-update $port --no-security-groups --port-security-enabled=False
```



NOTE

Flannel gather information from etcd to configure and assign the subnets in the nodes. Therefore, the security group attached to the etcd hosts should allow access from nodes to port 2379/tcp, and nodes security group should allow egress communication to that port on the etcd hosts.

- a. Set the following variables in your Ansible inventory file before running the installation:

```
openshift_use_openshift_sdn=false ❶
openshift_use_flannel=true ❷
flannel_interface=eth0
```

- ❶ Set **openshift_use_openshift_sdn** to **false** to disable the default SDN.
- ❷ Set **openshift_use_flannel** to **true** to enable **flannel** in place.

- b. Optionally, you can specify the interface to use for inter-host communication using the **flannel_interface** variable. Without this variable, the OpenShift Container Platform installation uses the default interface.



NOTE


Custom networking CIDR for pods and services using flannel will be supported in a future release. [BZ#1473858](#)

3. After the OpenShift Container Platform installation, add a set of iptables rules on every OpenShift Container Platform node:

```
iptables -A DOCKER -p all -j ACCEPT
iptables -t nat -A POSTROUTING -o eth1 -j MASQUERADE
```

To persist those changes in the **/etc/sysconfig/iptables** use the following command on every node:

```
cp /etc/sysconfig/iptables{,.orig}
sh -c "tac /etc/sysconfig/iptables.orig | sed -e '0,/:DOCKER -/'
s/:DOCKER -/:DOCKER ACCEPT/' | awk '!\"p && /POSTROUTING/{print \"-
A POSTROUTING -o eth1 -j MASQUERADE\"; p=1} 1' | tac >
/etc/sysconfig/iptables"
```


**NOTE**

The **iptables-save** command saves all the current *in memory* iptables rules. However, because Docker, Kubernetes and OpenShift Container Platform create a high number of iptables rules (services, etc.) not designed to be persisted, saving these rules can become problematic.

To isolate container traffic from the rest of the OpenShift Container Platform traffic, Red Hat recommends creating an isolated tenant network and attaching all the nodes to it. If you are using a different network interface (eth1), remember to configure the interface to start at boot time through the **/etc/sysconfig/network-scripts/ifcfg-eth1** file:

```
DEVICE=eth1
TYPE=Ethernet
BOOTPROTO=dhcp
ONBOOT=yes
DEFROUTE=no
PEERDNS=no
```

CHAPTER 15. CONFIGURING NUAGE SDN

15.1. NUAGE SDN AND OPENSIFT CONTAINER PLATFORM

Nuage Networks Virtualized Services Platform (VSP) provides virtual networking and software-defined networking (SDN) infrastructure to Docker container environments that simplifies IT operations and expands OpenShift Container Platform's native networking capabilities.

Nuage Networks VSP supports Docker-based applications running on OpenShift Container Platform to accelerate the provisioning of virtual networks between pods and traditional workloads, and to enable security policies across the entire cloud infrastructure. VSP allows for the automation of security appliances to include granular security and microsegmentation policies for container applications.

Integrating VSP with the OpenShift Container Platform application workflow allows business applications to be quickly turned up and updated by removing the network lag faced by DevOps teams. VSP supports different workflows with OpenShift Container Platform in order to accommodate scenarios where users can choose ease-of-use or complete control using policy-based automation.

See [Networking](#) for more information on how VSP is integrated with OpenShift Container Platform.

15.2. DEVELOPER WORKFLOW

This workflow is used in developer environments and requires little input from the developer in setting up the networking. In this workflow, **nuage-openshift-monitor** is responsible for creating the VSP constructs (Zone, Subnets, etc.) needed to provide appropriate policies and networking for pods created in an OpenShift Container Platform project. When a project is created, a default zone and default subnet for that project are created by **nuage-openshift-monitor**. When the default subnet created for a given project gets depleted, **nuage-openshift-monitor** dynamically creates additional subnets.



NOTE

A separate VSP Zone is created for each OpenShift Container Platform project ensuring isolation amongst the projects.

15.3. OPERATIONS WORKFLOW

This workflow is used by operations teams rolling out applications. In this workflow, the network and security policies are first configured on the VSD in accordance with the rules set by the organization to deploy applications. Administrative users can potentially create multiple zones and subnets and map them to the same project using labels. While spinning up the pods, the user can use the Nuage Labels to specify what network a pod needs to attach to and what network policies need to be applied to it. This allows for deployments where inter- and intra-project traffic can be controlled in a fine-grained manner. For example, inter-project communication is enabled on a project by project basis. This may be used to connect projects to common services that are deployed in a shared project.

15.4. INSTALLATION

The VSP integration with OpenShift Container Platform works for both virtual machines (VMs) and bare metal OpenShift Container Platform installations.

An environment with High Availability (HA) can be configured with multiple masters and multiple nodes.

Nuage VSP integration in multi-master mode only supports the native HA configuration method

described in this section. This can be combined with any load balancing solution, the default being HAProxy. The inventory file contains three master hosts, the nodes, an etcd server, and a host that functions as the HAProxy to balance the master API on all master hosts. The HAProxy host is defined in the [lb] section of the inventory file enabling Ansible to automatically install and configure HAProxy as the load balancing solution.

In the Ansible nodes file, the following parameters need to be specified in order to setup Nuage VSP as the network plug-in:

```
# Create and OSEv3 group that contains masters, nodes, load-balancers,
and etcd hosts
masters
nodes
etcd
lb

# Nuage specific parameters
openshift_use_openshift_sdn=False
openshift_use_nuage=True
os_sdn_network_plugin_name='nuage/vsp-openshift'
openshift_node_proxy_mode='userspace'

# VSP related parameters
vsd_api_url=https://192.168.103.200:8443
vsp_version=v4_0
enterprise=nuage
domain=openshift
vsc_active_ip=192.168.103.201
vsc_standby_ip=192.168.103.202
uplink_interface=eth0

# rpm locations
nuage_openshift_rpm=http://location_of_rpm_server/openshift/RPMS/x86_64/n
uage-openshift-monitor-4.0.X.1830.el7.centos.x86_64.rpm
vrs_rpm=http://location_of_rpm_server/openshift/RPMS/x86_64/nuage-
openvswitch-4.0.X.225.el7.x86_64.rpm
plugin_rpm=http://location_of_rpm_server/openshift/RPMS/x86_64/vsp-
openshift-4.0.X1830.el7.centos.x86_64.rpm

# Required for Nuage Monitor REST server and HA
openshift_master_cluster_method=native
openshift_master_cluster_hostname=lb.nuageopenshift.com
openshift_master_cluster_public_hostname=lb.nuageopenshift.com
nuage_openshift_monitor_rest_server_port=9443

# Optional parameters
nuage_interface_mtu=1460
nuage_master_adminusername='admin's user-name'
nuage_master_adminuserpasswd='admin's password'
nuage_master_cspadminpasswd='csp admin password'
nuage_openshift_monitor_log_dir=/var/log/nuage-openshift-monitor

# Required for brownfield install (where a {product-title} cluster exists
without Nuage as the networking plugin)
nuage_dockker_bridge=lbr0
```

```
# Specify master hosts
[masters]
fqdn_of_master_1
fqdn_of_master_2
fqdn_of_master_3

# Specify load balancer host
[lb]
fqdn_of_load_balancer
```

CHAPTER 16. CONFIGURING FOR AMAZON WEB SERVICES (AWS)

16.1. OVERVIEW

OpenShift Container Platform can be configured to access an [AWS EC2 infrastructure](#), including [using AWS volumes as persistent storage](#) for application data. After you configure AWS, some additional configurations must be completed on the OpenShift Container Platform hosts.

16.2. PERMISSIONS

Configuring AWS for OpenShift Container Platform requires the following permissions:

Table 16.1. Master Permissions

Elastic Compute Cloud(EC2)	<code>ec2:DescribeVolume</code> , <code>ec2:CreateVolume</code> , <code>ec2:CreateTags</code> , <code>ec2:DescribeInstance</code> , <code>ec2:AttachVolume</code> , <code>ec2:DetachVolume</code> , <code>ec2>DeleteVolume</code> , <code>ec2:DescribeSubnets</code> , <code>ec2:CreateSecurityGroup</code> , <code>ec2:DescribeSecurityGroups</code> , <code>ec2:DescribeRouteTables</code> , <code>ec2:AuthorizeSecurityGroupIngress</code> , <code>ec2:RevokeSecurityGroupIngress</code> , <code>ec2>DeleteSecurityGroup</code>
Elastic Load Balancing	<code>elasticloadbalancing:DescribeTags</code> , <code>elasticloadbalancing:CreateLoadBalancerListeners</code> , <code>elasticloadbalancing:ConfigureHealthCheck</code> , <code>elasticloadbalancing>DeleteLoadBalancerListeners</code> , <code>elasticloadbalancing:RegisterInstancesWithLoadBalancer</code> , <code>elasticloadbalancing:DescribeLoadBalancers</code> , <code>elasticloadbalancing:CreateLoadBalancer</code> , <code>elasticloadbalancing>DeleteLoadBalancer</code> , <code>elasticloadbalancing:ModifyLoadBalancerAttributes</code> , <code>elasticloadbalancing:DescribeLoadBalancerAttributes</code>

Table 16.2. Node Permissions

Elastic Compute Cloud(EC2)	<code>ec2:DescribeInstance*</code>
----------------------------	------------------------------------



IMPORTANT

- Every master host, node host, and subnet must have the **kubernetes.io/cluster/<clusterid>, Value=(owned|shared)** tag.
- One security group, preferably the one linked to the nodes, must have the **kubernetes.io/cluster/<clusterid>, Value=(owned|shared)** tag.
 - Do not tag all security groups with the **kubernetes.io/cluster/<clusterid>, Value=(owned|shared)** tag or the Elastic Load Balancing (ELB) will not be able to create a load balancer.

16.3. CONFIGURING A SECURITY GROUP

When installing OpenShift Container Platform on AWS, ensure that you set up the appropriate security groups.

These are some ports that you must have in your security groups, without which the installation fails. You may need more depending on the cluster configuration you want to install. For more information and to adjust your security groups accordingly, see [Required Ports](#) for more information.

All OpenShift Container Platform Hosts	<ul style="list-style-type: none"> • tcp/22 from host running the installer/Ansible
etcd Security Group	<ul style="list-style-type: none"> • tcp/2379 from masters • tcp/2380 from etcd hosts
Master Security Group	<ul style="list-style-type: none"> • tcp/8443 from 0.0.0.0/0 • tcp/53 from all OpenShift Container Platform hosts for environments installed prior to or upgraded to 3.2 • udp/53 from all OpenShift Container Platform hosts for environments installed prior to or upgraded to 3.2 • tcp/8053 from all OpenShift Container Platform hosts for new environments installed with 3.2 • udp/8053 from all OpenShift Container Platform hosts for new environments installed with 3.2
Node Security Group	<ul style="list-style-type: none"> • tcp/10250 from masters • udp/4789 from nodes
Infrastructure Nodes (ones that can host the OpenShift Container Platform router)	<ul style="list-style-type: none"> • tcp/443 from 0.0.0.0/0 • tcp/80 from 0.0.0.0/0

If configuring external load-balancers (ELBs) for load balancing the masters and/or routers, you also need to configure Ingress and Egress security groups for the ELBs appropriately.

16.3.1. Overriding Detected IP Addresses and Host Names

In AWS, situations that require overriding the variables include:

Variable	Usage
hostname	The user is installing in a VPC that is not configured for both DNS hostnames and DNS resolution .
ip	You have multiple network interfaces configured and want to use one other than the default. You must also set the openshift_set_node_ip parameter to True , or the SDN attempts to use the hostname setting or tries to resolve the host name for the IP address.
public_hostname	<ul style="list-style-type: none"> • A master instance where the VPC subnet is not configured for Auto-assign Public IP. For external access to this master, you need to have an ELB or other load balancer configured that would provide the external access needed, or you need to connect over a VPN connection to the internal name of the host. • A master instance where metadata is disabled. • This value is not actually used by the nodes.
public_ip	<ul style="list-style-type: none"> • A master instance where the VPC subnet is not configured for Auto-assign Public IP. • A master instance where metadata is disabled. • This value is not actually used by the nodes.



WARNING

If **openshift_hostname** is set to a value other than the metadata-provided **private-dns-name** value, the native cloud integration for those providers will no longer work.

For EC2 hosts in particular, they must be deployed in a VPC that has both **DNS host names** and **DNS resolution** enabled, and **openshift_hostname** should not be overridden.

16.4. CONFIGURING AWS VARIABLES

To set the required AWS variables, create a `/etc/origin/cloudprovider/aws.conf` file with the following contents on all of your OpenShift Container Platform hosts, both masters and nodes:

```
[Global]
Zone = us-east-1c 1
```

- 1 This is the Availability Zone of your AWS Instance and where your EBS Volume resides; this information is obtained from the AWS Management Console.

16.5. CONFIGURING OPENSIFT CONTAINER PLATFORM FOR AWS

You can set the AWS configuration on OpenShift Container Platform in two ways:

- using [Ansible](#) or
- manually, by modifying the `master-config.yaml`, `node-config.yaml`, and related `/etc/sysconfig/` files.

16.5.1. Configuring OpenShift Container Platform for AWS with Ansible

During [advanced installations](#), AWS can be configured using the `openshift_cloudprovider_aws_access_key`, `openshift_cloudprovider_aws_secret_key`, `openshift_cloudprovider_kind`, `openshift_clusterid` parameters, which are configurable in the inventory file.

Example AWS Configuration with Ansible

```
# Cloud Provider Configuration
#
# Note: You may make use of environment variables rather than store
# sensitive configuration within the ansible inventory.
# For example:
#openshift_cloudprovider_aws_access_key="{{
lookup('env', 'AWS_ACCESS_KEY_ID') }}"
#openshift_cloudprovider_aws_secret_key="{{
lookup('env', 'AWS_SECRET_ACCESS_KEY') }}"
#
#openshift_clusterid=unique_identifier_per_availability_zone
#
# AWS (Using API Credentials)
#openshift_cloudprovider_kind=aws
#openshift_cloudprovider_aws_access_key=aws_access_key_id
#openshift_cloudprovider_aws_secret_key=aws_secret_access_key
#
# AWS (Using IAM Profiles)
#openshift_cloudprovider_kind=aws
# Note: IAM roles must exist before launching the instances.
```




NOTE

When Ansible configures AWS, it automatically makes the necessary changes to the following files:


- `/etc/origin/cloudprovider/aws.conf`
- `/etc/origin/master/master-config.yaml`
- `/etc/origin/node/node-config.yaml`
- `/etc/sysconfig/atomic-openshift-master-api`
- `/etc/sysconfig/atomic-openshift-master-controllers`
- `/etc/sysconfig/atomic-openshift-node`

16.5.2. Manually Configuring OpenShift Container Platform Masters for AWS

Edit or [create](#) the master configuration file on all masters (`/etc/origin/master/master-config.yaml` by default) and update the contents of the `apiServerArguments` and `controllerArguments` sections:

```
kubernetesMasterConfig:
  ...
  apiServerArguments:
    cloud-provider:
      - "aws"
    cloud-config:
      - "/etc/origin/cloudprovider/aws.conf"
  controllerArguments:
    cloud-provider:
      - "aws"
    cloud-config:
      - "/etc/origin/cloudprovider/aws.conf"
```

Currently, the **nodeName** must match the instance name in AWS in order for the cloud provider integration to work properly. The name must also be RFC1123 compliant.




IMPORTANT

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, `aws.conf` should be in `/etc/origin/` instead of `/etc/`.

16.5.3. Manually Configuring OpenShift Container Platform Nodes for AWS

Edit or [create](#) the node configuration file on all nodes (`/etc/origin/node/node-config.yaml` by default) and update the contents of the `kubeletArguments` section:

```
kubeletArguments:
  cloud-provider:
    - "aws"
  cloud-config:
    - "/etc/origin/cloudprovider/aws.conf"
```

**IMPORTANT**

When triggering a containerized installation, only the directories of */etc/origin* and */var/lib/origin* are mounted to the master and node container. Therefore, *aws.conf* should be in */etc/origin/* instead of */etc/*.

16.5.4. Manually Setting Key-Value Access Pairs

Make sure the following environment variables are set in the */etc/sysconfig/atomic-openshift-master-api* file and */etc/sysconfig/atomic-openshift-master-controllers* file on masters and the */etc/sysconfig/atomic-openshift-node* file on nodes:

```
AWS_ACCESS_KEY_ID=<key_ID>
AWS_SECRET_ACCESS_KEY=<secret_key>
```

**NOTE**

Access keys are obtained when setting up your AWS IAM user.

16.6. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
# systemctl restart atomic-openshift-node
```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

16.7. LABELING CLUSTERS FOR AWS

Starting with OpenShift Container Platform version 3.7 of the **atomic-openshift-installer**, if you configured AWS provider credentials, you must also ensure that all hosts are labeled.

To correctly identify which resources are associated with a cluster, tag resources with the key **kubernetes.io/cluster/<clusterid>**, where:

- **<clusterid>** is a unique name for the cluster.

Set the corresponding value to **owned** if the node belongs exclusively to the cluster or to **shared** if it is a resource shared with other systems.

Tagging all resources with the **kubernetes.io/cluster/<clusterid>, Value=(owned|shared)** tag avoids potential issues with multiple zones or multiple clusters.



NOTE

In versions prior to OpenShift Container Platform version 3.6, this was **Key=KubernetesCluster, Value=clusterid**.

See [Pods and Services](#) to learn more about labeling and tagging in OpenShift Container Platform.

16.7.1. Resources That Need Tags

There are four types of resources that need to be tagged:

- Instances
- Security Groups
- Load Balancers
- EBS Volumes

16.7.2. Tagging an Existing Cluster

A cluster uses the value of the **kubernetes.io/cluster/<clusterid>, Value=(owned|shared)** tag to determine which resources belong to the AWS cluster. This means that all relevant resources must be labeled with the **kubernetes.io/cluster/<clusterid>, Value=(owned|shared)** tag using the same values for that key. These resources include:

- All hosts.
- All relevant load balancers to be used in the AWS instances.
- All EBS volumes. The EBS Volumes that need to be tagged can found with:

```
$ oc get pv -o json|jq '.items[].spec.awsElasticBlockStore.volumeID'
```

- All relevant security groups to be used with the AWS instances.

**NOTE**

Do not tag all existing security groups with the **kubernetes.io/cluster/<name>,Value=<clusterid>** tag, or the Elastic Load Balancing (ELB) will not be able to create a load balancer.

After tagging any resources, restart the master services on the master and the node service on all nodes. See the [Applying Configuration Section](#).

CHAPTER 17. CONFIGURING FOR OPENSTACK

17.1. OVERVIEW

When deployed on [OpenStack](#), OpenShift Container Platform can be configured to access OpenStack infrastructure, including [using OpenStack Cinder volumes as persistent storage](#) for application data.

17.2. PERMISSIONS

Configuring OpenStack for OpenShift Container Platform requires the following role:

member	For creating assets(instances, networking ports, floating ips, volumes, and so on.) you need the member role for the tenant.
--------	--

17.3. CONFIGURING A SECURITY GROUP

When installing OpenShift Container Platform on OpenStack, ensure that you set up the appropriate security groups.

These are some ports that you must have in your security groups, without which the installation fails. You may need more depending on the cluster configuration you want to install. For more information and to adjust your security groups accordingly, see [Required Ports](#) for more information.

All OpenShift Container Platform Hosts	<ul style="list-style-type: none"> • tcp/22 from host running the installer/Ansible
etcd Security Group	<ul style="list-style-type: none"> • tcp/2379 from masters • tcp/2380 from etcd hosts
Master Security Group	<ul style="list-style-type: none"> • tcp/8443 from 0.0.0.0/0 • tcp/53 from all OpenShift Container Platform hosts for environments installed prior to or upgraded to 3.2 • udp/53 from all OpenShift Container Platform hosts for environments installed prior to or upgraded to 3.2 • tcp/8053 from all OpenShift Container Platform hosts for new environments installed with 3.2 • udp/8053 from all OpenShift Container Platform hosts for new environments installed with 3.2
Node Security Group	<ul style="list-style-type: none"> • tcp/10250 from masters • udp/4789 from nodes

Infrastructure Nodes (ones that can host the OpenShift Container Platform router)

- tcp/443 from 0.0.0.0/0
- tcp/80 from 0.0.0.0/0

If configuring external load-balancers (ELBs) for load balancing the masters and/or routers, you also need to configure Ingress and Egress security groups for the ELBs appropriately.

17.4. CONFIGURING OPENSTACK VARIABLES

To set the required OpenStack variables, create a `/etc/cloud.conf` file with the following contents on all of your OpenShift Container Platform hosts, both masters and nodes:

```
[Global]
auth-url = <OS_AUTH_URL>
username = <OS_USERNAME>
password = <password>
domain-id = <OS_USER_DOMAIN_ID>
tenant-id = <OS_TENANT_ID>
region = <OS_REGION_NAME>

[LoadBalancer]
subnet-id = <UUID of the load balancer subnet>

[BlockStorage]
bs-version=v2
```

Consult your OpenStack administrators for values of the **OS_** variables, which are commonly used in OpenStack configuration.

Currently OpenStack Cinder V3 API is not supported. To resolve this issue or disable auto Cinder API version detection, you must force Cinder V2 API by specifying **bs-version=v2**.

17.5. CONFIGURING OPENSIFT CONTAINER PLATFORM MASTERS FOR OPENSTACK

You can set an OpenStack configuration on your OpenShift Container Platform master and node hosts in two different ways:

- [Using Ansible and the advanced installation tool](#)
- Manually, by [modifying the `master-config.yaml`](#) and [node-config.yaml](#) files.

17.5.1. Configuring OpenShift Container Platform for OpenStack with Ansible

During [advanced installations](#), OpenStack can be configured using [the following parameters](#), which are configurable in the inventory file:

- `openshift_cloudprovider_kind`
- `openshift_cloudprovider_openstack_auth_url`
- `openshift_cloudprovider_openstack_username`

- `openshift_cloudprovider_openstack_password`
- `openshift_cloudprovider_openstack_domain_id`
- `openshift_cloudprovider_openstack_domain_name`
- `openshift_cloudprovider_openstack_tenant_id`
- `openshift_cloudprovider_openstack_tenant_name`
- `openshift_cloudprovider_openstack_region`
- `openshift_cloudprovider_openstack_lb_subnet_id`



IMPORTANT

If a parameter value in the Ansible inventory file contains special characters, such as `#`, `{` or `}`, you must double-escape the value (that is enclose the value in both single and double quotation marks). For example, to use `mypasswordwith###hashsigns` as a value for the variable `openshift_cloudprovider_openstack_password`, declare it as

`openshift_cloudprovider_openstack_password='\"mypasswordwith###hashsigns\"'` in the Ansible host inventory file.


Example 17.1. Example OpenStack Configuration with Ansible

```
# Cloud Provider Configuration
#
# Note: You may make use of environment variables rather than store
# sensitive configuration within the ansible inventory.
# For example:
#openshift_cloudprovider_openstack_username="{ lookup('env', 'USERNAME')
#}"
#openshift_cloudprovider_openstack_password="{ lookup('env', 'PASSWORD')
#}"
#
# Openstack
#openshift_cloudprovider_kind=openstack
#openshift_cloudprovider_openstack_auth_url=http://openstack.example.com
#:35357/v2.0/
#openshift_cloudprovider_openstack_username=username
#openshift_cloudprovider_openstack_password=password
#openshift_cloudprovider_openstack_domain_id=domain_id
#openshift_cloudprovider_openstack_domain_name=domain_name
#openshift_cloudprovider_openstack_tenant_id=tenant_id
#openshift_cloudprovider_openstack_tenant_name=tenant_name
#openshift_cloudprovider_openstack_region=region
#openshift_cloudprovider_openstack_lb_subnet_id=subnet_id
```

17.5.2. Manually Configuring OpenShift Container Platform Masters for OpenStack

Edit or [create](#) the master configuration file on all masters (`/etc/origin/master/master-config.yaml` by default) and update the contents of the **apiServerArguments** and **controllerArguments** sections:

```
kubernetesMasterConfig:
  ...
  apiServerArguments:
    cloud-provider:
      - "openstack"
    cloud-config:
      - "/etc/cloud.conf"
  controllerArguments:
    cloud-provider:
      - "openstack"
    cloud-config:
      - "/etc/cloud.conf"
```



IMPORTANT

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, **cloud.conf** should be in `/etc/origin/` instead of `/etc/`.

17.5.3. Manually Configuring OpenShift Container Platform Nodes for OpenStack

Edit or [create](#) the node configuration file on all nodes (`/etc/origin/node/node-config.yaml` by default) and update the contents of the **kubeletArguments** and **nodeName** sections:

```
nodeName:
  <instance_name> 1

kubeletArguments:
  cloud-provider:
    - "openstack"
  cloud-config:
    - "/etc/cloud.conf"
```

1 Name of the OpenStack instance where the node runs (i.e., name of the virtual machine)

Currently, the **nodeName** **must** match the instance name in Openstack in order for the cloud provider integration to work properly. The name must also be RFC1123 compliant.



IMPORTANT

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, **cloud.conf** should be in `/etc/origin/` instead of `/etc/`.

17.6. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):


```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
# systemctl restart atomic-openshift-node
```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?
=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

CHAPTER 18. CONFIGURING FOR GCE

18.1. OVERVIEW

OpenShift Container Platform can be configured to access a [Google Compute Engine \(GCE\) infrastructure](#), including [using GCE volumes as persistent storage](#) for application data. After GCE is configured properly, some additional configurations will need to be completed on the OpenShift Container Platform hosts.

18.2. PERMISSIONS

Configuring GCE for OpenShift Container Platform requires the following role:

roles/owner	To create service accounts, cloud storage, instances, images, templates, Cloud DNS entries, and deploy load balancers and health checks. It is helpful to also have delete permissions to be able to redeploy the environment while testing.
-------------	---

18.3. CONFIGURING MASTERS

You can set the GCE configuration on your OpenShift Container Platform master hosts in two ways:

- [Using Ansible and the advanced installation tool.](#)
- [Manually by modifying the *master-config.yaml* file.](#)

18.3.1. Configuring OpenShift Container Platform Masters for GCE with Ansible

During [advanced installations](#), GCE can be configured using the `openshift_cloudprovider_kind` parameter, which is configurable in the inventory file.

Example GCE Configuration with Ansible

```
# Cloud Provider Configuration
# openshift_cloudprovider_kind=gce
```



NOTE

When Ansible configures GCE, the following files are created for you:

- */etc/origin/cloudprovider/gce.conf*
- */etc/origin/master/master-config.yaml*
- */etc/origin/node/node-config.yaml*


The advanced installation configures single-zone support by default. If you want multizone support, edit the */etc/origin/cloudprovider/gce.conf* as shown in [Configuring Multizone Support in a GCE Deployment](#).

18.3.2. Manually Configuring OpenShift Container Platform Masters for GCE

To configure the OpenShift Container Platform masters for GCE:

1. Edit or [create](#) the master configuration file (`/etc/origin/master/master-config.yaml` by default) on all masters and update the contents of the **apiServerArguments** and **controllerArguments** sections:

```
kubernetesMasterConfig:
  ...
  apiServerArguments:
    cloud-provider:
      - "gce"
    cloud-config:
      - "/etc/origin/cloudprovider/gce.conf"
  controllerArguments:
    cloud-provider:
      - "gce"
    cloud-config:
      - "/etc/origin/cloudprovider/gce.conf"
```



IMPORTANT

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, **master-config.yaml** should be in `/etc/origin/master` instead of `/etc/`.

2. Start or restart the OpenShift Container Platform services:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```


18.4. CONFIGURING NODES

To configure the OpenShift Container Platform nodes for GCE:

1. Edit or [create](#) the node configuration file (`/etc/origin/node/node-config.yaml` by default) on all nodes and update the contents of the **kubeletArguments** section:

```
kubeletArguments:
  cloud-provider:
    - "gce"
  cloud-config:
    - "/etc/origin/cloudprovider/gce.conf"
```

Currently, the **nodeName** **must** match the instance name in GCE in order for the cloud provider integration to work properly. The name must also be RFC1123 compliant.



IMPORTANT

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, **node-config.yaml** should be in `/etc/origin/node` instead of `/etc/`.

1. Start or restart the OpenShift Container Platform services all nodes.

```
# systemctl restart atomic-openshift-node
```

18.5. CONFIGURING MULTIZONE SUPPORT IN A GCE DEPLOYMENT

If manually configuring GCE, multizone support is not configured by default.



NOTE

The advanced installation configures single-zone support by default.

If you want multizone support:

1. Edit or create a `/etc/origin/cloudprovider/gce.conf` file on all of your OpenShift Container Platform hosts, both masters and nodes.
2. Add the following contents:

```
[Global]
multizone = true
```

To return to single-zone support, set the `multizone` value to `false`.

18.6. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
# systemctl restart atomic-openshift-node
```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?
=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

CHAPTER 19. CONFIGURING FOR AZURE

19.1. OVERVIEW

OpenShift Container Platform can be configured to access a [Microsoft Azure infrastructure](#), including [using Azure disk as persistent storage](#) for application data. After Microsoft Azure is configured properly, some additional configurations need to be completed on the OpenShift Container Platform hosts.

19.2. PERMISSIONS

Configuring Microsoft Azure for OpenShift Container Platform requires the following role:

Contributor	To create and manage all types of Microsoft Azure resources.
-------------	--

For more information about adding administrator roles, see [Add or change Azure subscription administrators](#).

19.3. PREREQUISITES

- If you are using Microsoft Azure Disk as a persistent volume on the OpenShift Container Platform version 3.5 or later, you must enable Azure Cloud Provider.
- All OpenShift Container Platform node virtual machines (VMs) running in Microsoft Azure must belong to a single resource group.
- Microsoft Azure VMs must be named the same as OpenShift Container Platform nodes and this cannot include capital letters.
- If you plan to use Azure Managed Disks:
 - OpenShift Container Platform version 3.7 or later is required.
 - You must create VMs with Azure Managed Disks.
- If you plan to use unmanaged disks:
 - You must create VMs with unmanaged disks.
- If you are using a custom DNS configuration for your OpenShift Container Platform cluster or your cluster nodes are in different Microsoft Azure Virtual Networks (VNet), you must configure DNS so that each node in the cluster can resolve IP addresses for other nodes.

19.4. THE AZURE CONFIGURATION FILE

Configuring OpenShift Container Platform for Azure requires the `/etc/azure/azure.conf` file, on each node host.

If the file does not exist, create it, and add the following:

```
tenantId: <> 1
subscriptionId: <> 2
aadClientId: <> 3
```

```

aadClientSecret: <> 4
aadTenantId: <> 5
resourceGroup: <> 6
location: <> 7

```

- 1 The AAD tenant ID for the subscription that the cluster is deployed in.
- 2 The Azure subscription ID that the cluster is deployed in.
- 3 The client ID for an AAD application with RBAC access to talk to Azure RM APIs.
- 4 The client secret for an AAD application with RBAC access to talk to Azure RM APIs.
- 5 Ensure this is the same as tenant ID (optional).
- 6 The Azure Resource Group name that Azure VM belongs to.
- 7 The compact style Azure region, for example **southeastasia** (optional).

19.5. CONFIGURING MASTERS

Edit or [create](#) the master configuration file on all masters (*/etc/origin/master/master-config.yaml* by default) and update the contents of the **apiServerArguments** and **controllerArguments** sections:

```

kubernetesMasterConfig:
  ...
  apiServerArguments:
    cloud-provider:
      - "azure"
    cloud-config:
      - "/etc/azure/azure.conf"
  controllerArguments:
    cloud-provider:
      - "azure"
    cloud-config:
      - "/etc/azure/azure.conf"

```



IMPORTANT

When triggering a containerized installation, only the */etc/origin* and */var/lib/origin* directories are mounted to the master and node container. Therefore, **master-config.yaml** should be in */etc/origin/master* instead of */etc/*.

19.6. CONFIGURING NODES


1. Edit or [create](#) the node configuration file on all nodes (*/etc/origin/node/node-config.yaml* by default) and update the contents of the **kubeletArguments** section:

```

kubeletArguments:
  cloud-provider:
    - "azure"
  cloud-config:
    - "/etc/azure/azure.conf"

```

■

**IMPORTANT**

When triggering a containerized installation, only the */etc/origin* and */var/lib/origin* directories are mounted to the master and node container. Therefore, *node-config.yaml* should be in */etc/origin/node* instead of */etc/*.

19.7. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-  
controllers  
# systemctl restart atomic-openshift-node
```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?  
=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

CHAPTER 20. CONFIGURING FOR VMWARE VSPHERE

20.1. OVERVIEW

OpenShift Container Platform can be configured to access [VMware vSphere](#) VMDK Volumes, including [using VMware vSphere VMDK Volumes as persistent storage](#) for application data.

The vSphere Cloud Provider allows using vSphere managed storage within OpenShift Container Platform and supports:

- Volumes,
- Persistent Volumes, and
- Storage Classes and provisioning of volumes.

20.2. ENABLING VMWARE VSPHERE CLOUD PROVIDER



IMPORTANT

Enabling VMware vSphere requires installing the VMware Tools on each Node VM. See [Installing VMware tools](#) for more information.

To enable VMware vSphere cloud provider for OpenShift Container Platform:

1. Create a [VM folder](#) and move OpenShift Container Platform Node VMs to this folder.
2. Verify that the Node VM names complies with the regex `[a-z]((?)?[0-9a-z])?(\. [a-z0-9]([[-0-9a-z])?[0-9a-z])?)*`.



IMPORTANT

VM Names can not:

- begin with numbers.
- have any capital letters.
- have any special characters except -.
- be shorter than three characters and longer than 63 characters.

3. Set the `disk.EnableUUID` parameter to **TRUE** for each Node VM. This ensures that the VMDK always presents a consistent UUID to the VM, allowing the disk to be mounted properly. For every virtual machine node that will be participating in the cluster, follow the steps below using the [GOVC tool](#):

- a. Set up the GOVC environment:

```
export GOVC_URL='vCenter IP OR FQDN'
export GOVC_USERNAME='vCenter User'
export GOVC_PASSWORD='vCenter Password'
export GOVC_INSECURE=1
```

- b. Find the Node VM paths:

```
govc ls /datacenter/vm/<vm-folder-name>
```

- c. Set disk.EnableUUID to true for all VMs:

```
govc vm.change -e="disk.enableUUID=1" -vm='VM Path'
```



NOTE

If OpenShift Container Platform node VMs are created from a template VM, then **disk.EnableUUID=1** can be set on the template VM. VMs cloned from this template, inherit this property.

4. Create and assign roles to the vSphere Cloud Provider user and vSphere entities. vSphere Cloud Provider requires the following privileges to interact with vCenter. See the [vSphere Documentation Center](#) for steps to create a custom role, user and role assignment.

Roles	Privileges	Entities	Propagate to Children
manage-k8s-node-vms	Resource.AssignVMT oPool System.Anonymous System.Read System.View VirtualMachine.Config. AddExistingDisk VirtualMachine.Config. AddNewDisk VirtualMachine.Config. AddRemoveDevice VirtualMachine.Config. RemoveDisk VirtualMachine.Invent ory.Create VirtualMachine.Invent ory.Delete	Cluster, Hosts, VM Folder	Yes
manage-k8s-volumes	Datastore.AllocateSpa ce Datastore.FileManage ment System.Anonymous System.Read System.View	Datastore	No
k8s-system-read-and- spbm-profile-view	StorageProfile.View System.Anonymous System.Read System.View	vCenter	No

Roles	Privileges	Entities	Propagate to Children
ReadOnly	System.Anonymous System.Read System.View	Datacenter, Datastore Cluster, Datastore Storage Folder	No

**NOTE**


After enabling the vSphere Cloud Provider, Node names are set to the VM names from the vCenter Inventory.

**WARNING**

The **openshift_hostname** variable must match the virtual machine name and its host name. The **openshift_hostname** variable defines the **nodeName** value in the **node-config.yaml** file. This value is compared to the **nodeName** value determined by using the command **uname -n**. In case of a mismatch, the native cloud integration for those providers will not work.

20.3. THE VMWARE VSPHERE CONFIGURATION FILE

Configuring OpenShift Container Platform for VMware vSphere requires the **/etc/origin/cloudprovider/vsphere.conf** file, on each node host.

**IMPORTANT**

If you are upgrading from OpenShift Container Platform version 3.6 to a newer version, place the vSphere Configuration (**vsphere.conf**) file in both **/etc/vsphere/** and the **/etc/origin/cloudprovider/** directories.

If the file does not exist, create it, and add the following:

```
[Global]
user = "username" 1
password = "password" 2
server = "10.10.0.2" 3
port = "443" 4
insecure-flag = "1" 5
datacenter = "datacenter-name" 6
datastore = "datastore-name" 7
working-dir = "vm-folder-path" 8
```

```

    vm-uuid = "vm-uuid" 9
[Disk]
    scsicontrollertype = pvscsi

```

- 1 vCenter username for the vSphere cloud provider.
- 2 vCenter password for the specified user.
- 3 IP Address or FQDN for the vCenter server.
- 4 (Optional) Port number for the vCenter server. Defaults to port **443**.
- 5 Set to **1** if the vCenter uses a self-signed cert.
- 6 Name of the data center on which Node VMs are deployed.
- 7 Name of the datastore to use for provisioning volumes using the storage classes or dynamic provisioning. If datastore is located in a storage folder or datastore is a member of datastore cluster, specify the full datastore path. Verify that vSphere Cloud Provider user has the read privilege set on the datastore cluster or storage folder to be able to find datastore.
- 8 (Optional) The vCenter VM folder path in which the node VMs are located. It can be set to an empty path(**working-dir** = ""), if Node VMs are located in the root VM folder.
- 9 (Optional) VM Instance UUID of the Node VM. It can be set to empty (**vm-uuid** = ""). If this is set to empty, this is retrieved from **/sys/class/dmi/id/product_serial** file on virtual machine (requires root access).

20.4. CONFIGURING MASTERS

Edit or [create](#) the master configuration file on all masters (**/etc/origin/master/master-config.yaml** by default) and update the contents of the **apiServerArguments** and **controllerArguments** sections with the following:

```

kubernetesMasterConfig:
  admissionConfig:
    pluginConfig:
      {}
  apiServerArguments:
    cloud-provider:
      - "vsphere"
    cloud-config:
      - "/etc/origin/cloudprovider/vsphere.conf"
  controllerArguments:
    cloud-provider:
      - "vsphere"
    cloud-config:
      - "/etc/origin/cloudprovider/vsphere.conf"

```




IMPORTANT

When triggering a containerized installation, only the **/etc/origin** and **/var/lib/origin** directories are mounted to the master and node container. Therefore, **master-config.yaml** must be in **/etc/origin/master** rather than **/etc/**.

20.5. CONFIGURING NODES

1. Edit or [create](#) the node configuration file on all nodes (*/etc/origin/node/node-config.yaml* by default) and update the contents of the **kubeletArguments** section:

```
kubeletArguments:
  cloud-provider:
    - "vsphere"
  cloud-config:
    - "/etc/origin/cloudprovider/vsphere.conf"
```



IMPORTANT

When triggering a containerized installation, only the */etc/origin* and */var/lib/origin* directories are mounted to the master and node container. Therefore, **node-config.yaml** must be in */etc/origin/node* rather than */etc/*.

20.6. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
# systemctl restart atomic-openshift-node
```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?
=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

20.7. BACKUP OF PERSISTENT VOLUMES

OpenShift Container Platform provisions new volumes as **independent persistent disks** to freely attach and detach the volume on any node in the cluster. As a consequence, [it is not possible to back up volumes that use snapshots](#).

To create a backup of PVs:

1. Stop the application using the PV.
2. Clone the persistent disk.
3. Restart the application.
4. Create a backup of the cloned disk.
5. Delete the cloned disk.

CHAPTER 21. CONFIGURING FOR LOCAL VOLUME

21.1. OVERVIEW

OpenShift Container Platform can be configured to access [local volumes](#) for application data.

Local volumes are persistent volumes (PV) representing locally-mounted file systems. In the future, they may be extended to raw block devices.

Local volumes are different from a `hostPath`. They have a special annotation that makes any pod that uses the PV to be scheduled on the same node where the local volume is mounted.

In addition, local volume includes a provisioner that automatically creates PVs for locally mounted devices. This provisioner is currently limited and it only scans pre-configured directories. It cannot dynamically provision volumes, which may be implemented in a future release.

The local volume provisioner allows using local storage within OpenShift Container Platform and supports:

- Volumes
- PVs



NOTE

Local volumes is an alpha feature and may change in a future release of OpenShift Container Platform.

21.2. ENABLING LOCAL VOLUMES

Enable the **PersistentLocalVolumes** feature gate on all masters and nodes:

1. Edit or create the master configuration file on all masters (*/etc/origin/master/master-config.yaml* by default) and add **PersistentLocalVolumes=true** under the **apiServerArguments** and **controllerArguments** sections:

```
apiServerArguments:
  feature-gates:
    - PersistentLocalVolumes=true
...

controllerArguments:
  feature-gates:
    - PersistentLocalVolumes=true
...
```

2. On all nodes, edit or create the node configuration file (*/etc/origin/node/node-config.yaml* by default) and add **PersistentLocalVolumes=true** feature gate under **kubeletArguments**:

```
kubeletArguments:
  feature-gates:
    - PersistentLocalVolumes=true
```

21.3. MOUNTING LOCAL VOLUMES

All local volumes must be manually mounted before they can be consumed by OpenShift Container Platform as PVs.

1. Mount all volumes into the `/mnt/local-storage/<storage-class-name>/<volume>` path. Administrators are required to create the local devices as needed (by using any method such as a disk partition or an LVM), create suitable file systems on these devices, and mount them using a script or `/etc/fstab` entries.

Example `/etc/fstab` entries

```
# device name      # mount point          # FS      # options #
extra
/dev/sdb1          /mnt/local-storage/ssd/disk1 ext4      defaults 1 2
/dev/sdb2          /mnt/local-storage/ssd/disk2 ext4      defaults 1 2
/dev/sdb3          /mnt/local-storage/ssd/disk3 ext4      defaults 1 2
/dev/sdc1          /mnt/local-storage/hdd/disk1 ext4      defaults 1 2
/dev/sdc2          /mnt/local-storage/hdd/disk2 ext4      defaults 1 2
```

2. Change the labels of mounted filesystems so that all volumes are accessible to processes that run within Docker containers:

```
---
$ chcon -R unconfined_u:object_r:svirt_sandbox_file_t:s0 /mnt/local-
storage/
---
```

21.4. CONFIGURING THE LOCAL PROVISIONER

OpenShift Container Platform depends on an external provisioner to create PVs for local devices and to clean them up when they are not needed (to enable reuse).



NOTE

- The local volume provisioner is different from most provisioners and does not support dynamic provisioning.
- The local volume provisioner requires that the administrators preconfigure the local volumes on each node and mount them under discovery directories. The provisioner then manages the volumes by creating and cleaning up PVs for each volume.

This external provisioner should be configured using a **ConfigMap** to relate directories with StorageClasses. This configuration must be created before the provisioner is deployed.



NOTE

(Optional) Create a standalone namespace for local volume provisioner and its configuration, for example: **oc new-project local-storage**

apiVersion: v1


```

kind: ConfigMap
metadata:
  name: local-volume-config
data:
  "local-ssd": | ❶
    {
      "hostDir": "/mnt/local-storage/ssd", ❷
      "mountDir": "/mnt/local-storage/ssd" ❸
    }
  "local-hdd": |
    {
      "hostDir": "/mnt/local-storage/hdd",
      "mountDir": "/mnt/local-storage/hdd"
    }

```

- ❶ Name of the StorageClass.
- ❷ Path to the directory on the host. It must be a subdirectory of **/mnt/local-storage**.
- ❸ Path to the directory in the provisioner pod. We recommend using the same directory structure as used on the host.

With this configuration, the provisioner creates:

- One PV with StorageClass **local-ssd** for every subdirectory in **/mnt/local-storage/ssd**.
- One PV with StorageClass **local-hdd** for every subdirectory in **/mnt/local-storage/hdd**.

21.5. DEPLOYING THE LOCAL PROVISIONER



NOTE

Before starting the provisioner, mount all local devices and create a **ConfigMap** with storage classes and their directories.

1. Install the local provisioner from the [local-storage-provisioner-template.yaml](#) file.
2. Create a service account that allows running pods as a root user and use HostPath volumes:

```

$ oc create serviceaccount local-storage-admin
$ oc adm policy add-scc-to-user privileged -z local-storage-admin

```



NOTE

Root privileges are required for the provisioner pod to delete content on local volumes. **hostPath** is required to access the **/mnt/local-storage** path on the host.

3. Install the template:

```

$ oc create -f
https://raw.githubusercontent.com/openshift/origin/master/examples/s
torage-examples/local-examples/local-storage-provisioner-

```

```
template.yaml
```

4. Instantiate the template by specifying values for **configmap** and **account** parameters:

```
$ oc new-app -p CONFIGMAP=local-volume-config \
  -p SERVICE_ACCOUNT=local-storage-admin \
  -p NAMESPACE=local-storage local-storage-provisioner
```

5. Create the SSD and HDD files:

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: local-ssd
provisioner: kubernetes.io/no-provisioner
volumeBindingMode: WaitForFirstConsumer
```

storage-class-hdd.yaml example

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: local-hdd
provisioner: kubernetes.io/no-provisioner
volumeBindingMode: WaitForFirstConsumer
```

6. Add the necessary storage classes:

```
oc create -f ./storage-class-ssd.yaml
oc create -f ./storage-class-hdd.yaml
```


See the [template](#) for other configurable options. This template creates a DaemonSet that runs a pod on every node. The pod watches directories specified in the **ConfigMap** and creates PVs for them automatically.

The provisioner runs as root to be able to clean up the directories when a PV is released and all data needs to be removed.

21.6. ADDING NEW DEVICES

To add a new device:

1. Stop DaemonSet with the provisioner.
2. Create a subdirectory in the right directory on the node with the new device and mount it there.
3. Start the DaemonSet with the provisioner.



IMPORTANT

Omitting any of these steps may result in the wrong PV being created.

CHAPTER 22. CONFIGURING PERSISTENT STORAGE

22.1. OVERVIEW

The Kubernetes [persistent volume](#) framework allows you to provision an OpenShift Container Platform cluster with persistent storage using networked storage available in your environment. This can be done after completing the initial OpenShift Container Platform installation depending on your application needs, giving users a way to request those resources without having any knowledge of the underlying infrastructure.

These topics show how to configure persistent volumes in OpenShift Container Platform using the following supported volume plug-ins:

- [NFS](#)
- [GlusterFS](#)
- [OpenStack Cinder](#)
- [Ceph RBD](#)
- [AWS Elastic Block Store \(EBS\)](#)
- [GCE Persistent Disk](#)
- [iSCSI](#)
- [Fibre Channel](#)
- [Azure Disk](#)
- [Azure File](#)
- [FlexVolume](#)
- [VMWare vSphere](#)
- [Dynamic Provisioning and Creating Storage Classes](#)
- [Volume Security](#)
- [Selector-Label Volume Binding](#)

22.2. PERSISTENT STORAGE USING NFS

22.2.1. Overview

OpenShift Container Platform clusters can be provisioned with [persistent storage](#) using NFS. Persistent volumes (PVs) and persistent volume claims (PVCs) provide a convenient method for sharing a volume across a project. While the NFS-specific information contained in a PV definition could also be defined directly in a pod definition, doing so does not create the volume as a distinct cluster resource, making the volume more susceptible to conflicts.

This topic covers the specifics of using the NFS persistent storage type. Some familiarity with OpenShift Container Platform and [NFS](#) is beneficial. See the [Persistent Storage](#) concept topic for details on the OpenShift Container Platform persistent volume (PV) framework in general.

22.2.2. Provisioning


Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. To provision NFS volumes, a list of NFS servers and export paths are all that is required.

You must first create an object definition for the PV:

Example 22.1. PV Object Definition Using NFS

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 1
spec:
  capacity:
    storage: 5Gi 2
  accessModes:
    - ReadWriteOnce 3
  nfs: 4
    path: /tmp 5
    server: 172.17.0.2 6
  persistentVolumeReclaimPolicy: Recycle 7
```

- 1 The name of the volume. This is the PV identity in various **oc <command> pod** commands.
- 2 The amount of storage allocated to this volume.
- 3 Though this appears to be related to controlling access to the volume, it is actually used similarly to labels and used to match a PVC to a PV. Currently, no access rules are enforced based on the **accessModes**.
- 4 The volume type being used, in this case the **nfs** plug-in.
- 5 The path that is exported by the NFS server.
- 6 The host name or IP address of the NFS server.
- 7 The reclaim policy for the PV. This defines what happens to a volume when released from its claim. Valid options are **Retain** (default) and **Recycle**. See [Reclaiming Resources](#).



NOTE

Each NFS volume must be mountable by all schedulable nodes in the cluster.

Save the definition to a file, for example **nfs-pv.yaml**, and create the PV:

```
$ oc create -f nfs-pv.yaml
persistentvolume "pv0001" created
```

Verify that the PV was created:

```
# oc get pv
NAME                                LABELS            CAPACITY          ACCESSMODES        STATUS
CLAIM          REASON          AGE
pv0001                                     <none>           5368709120        RWO                Available
31s
```

The next step can be to create a PVC, which binds to the new PV:

Example 22.2. PVC Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: nfs-claim1
spec:
  accessModes:
    - ReadWriteOnce ❶
  resources:
    requests:
      storage: 1Gi ❷
```

- ❶ As mentioned above for PVs, the **accessModes** do not enforce security, but rather act as labels to match a PV to a PVC.
- ❷ This claim looks for PVs offering **1Gi** or greater capacity.

Save the definition to a file, for example **nfs-claim.yaml**, and create the PVC:

```
# oc create -f nfs-claim.yaml
```

22.2.3. Enforcing Disk Quotas

You can use disk partitions to enforce disk quotas and size constraints. Each partition can be its own export. Each export is one PV. OpenShift Container Platform enforces unique names for PVs, but the uniqueness of the NFS volume's server and path is up to the administrator.

Enforcing quotas in this way allows the developer to request persistent storage by a specific amount (for example, 10Gi) and be matched with a corresponding volume of equal or greater capacity.

22.2.4. NFS Volume Security

This section covers NFS volume security, including matching permissions and SELinux considerations. The user is expected to understand the basics of POSIX permissions, process UIDs, supplemental groups, and SELinux.

**NOTE**

See the full [Volume Security](#) topic before implementing NFS volumes.

Developers request NFS storage by referencing, in the **volumes** section of their pod definition, either a PVC by name or the NFS volume plug-in directly.

The **/etc/exports** file on the NFS server contains the accessible NFS directories. The target NFS directory has POSIX owner and group IDs. The OpenShift Container Platform NFS plug-in mounts the container's NFS directory with the same POSIX ownership and permissions found on the exported NFS directory. However, the container is not run with its effective UID equal to the owner of the NFS mount, which is the desired behavior.

As an example, if the target NFS directory appears on the NFS server as:

```
# ls -lZ /opt/nfs -d
drwxrws---. nfsnobody 5555 unconfined_u:object_r:usr_t:s0 /opt/nfs

# id nfsnobody
uid=65534(nfsnobody) gid=65534(nfsnobody) groups=65534(nfsnobody)
```

Then the container must match SELinux labels, and either run with a UID of **65534** (**nfsnobody** owner) or with **5555** in its supplemental groups in order to access the directory.

**NOTE**

The owner ID of 65534 is used as an example. Even though NFS's **root_squash** maps **root** (0) to **nfsnobody** (65534), NFS exports can have arbitrary owner IDs. Owner 65534 is not required for NFS exports.

22.2.4.1. Group IDs

The recommended way to handle NFS access (assuming it is not an option to change permissions on the NFS export) is to use supplemental groups. Supplemental groups in OpenShift Container Platform are used for shared storage, of which NFS is an example. In contrast, block storage, such as Ceph RBD or iSCSI, use the **fsGroup** SCC strategy and the **fsGroup** value in the pod's **securityContext**.

**NOTE**

It is generally preferable to use supplemental group IDs to gain access to persistent storage versus using [user IDs](#). Supplemental groups are covered further in the full [Volume Security](#) topic.

Because the group ID on the [example target NFS directory](#) shown above is 5555, the pod can define that group ID using **supplementalGroups** under the pod-level **securityContext** definition. For example:

```
spec:
  containers:
    - name:
      ...
  securityContext: ❶
    supplementalGroups: [5555] ❷
```

- 1 **securityContext** must be defined at the pod level, not under a specific container.
- 2 An array of GIDs defined for the pod. In this case, there is one element in the array; additional GIDs would be comma-separated.

Assuming there are no custom SCCs that might satisfy the pod's requirements, the pod likely matches the **restricted** SCC. This SCC has the **supplementalGroups** strategy set to **RunAsAny**, meaning that any supplied group ID is accepted without range checking.

As a result, the above pod passes admissions and is launched. However, if group ID range checking is desired, a custom SCC, as described in [pod security and custom SCCs](#), is the preferred solution. A custom SCC can be created such that minimum and maximum group IDs are defined, group ID range checking is enforced, and a group ID of 5555 is allowed.



NOTE

To use a custom SCC, you must first add it to the appropriate service account. For example, use the **default** service account in the given project unless another has been specified on the pod specification. See [Add an SCC to a User, Group, or Project](#) for details.

22.2.4.2. User IDs

User IDs can be defined in the container image or in the pod definition. The full [Volume Security](#) topic covers controlling storage access based on user IDs, and should be read prior to setting up NFS persistent storage.



NOTE

It is generally preferable to use [supplemental group IDs](#) to gain access to persistent storage versus using user IDs.

In the [example target NFS directory](#) shown above, the container needs its UID set to 65534 (ignoring group IDs for the moment), so the following can be added to the pod definition:

```
spec:
  containers: 1
  - name:
    ...
    securityContext:
      runAsUser: 65534 2
```

- 1 Pods contain a **securityContext** specific to each container (shown here) and a pod-level **securityContext** which applies to all containers defined in the pod.
- 2 65534 is the **nfsnobody** user.

Assuming the **default** project and the **restricted** SCC, the pod's requested user ID of 65534 is not allowed, and therefore the pod fails. The pod fails for the following reasons:

- It requests 65534 as its user ID.

- All SCCs available to the pod are examined to see which SCC allows a user ID of 65534 (actually, all policies of the SCCs are checked but the focus here is on user ID).
- Because all available SCCs use **MustRunAsRange** for their **runAsUser** strategy, UID range checking is required.
- 65534 is not included in the SCC or project's user ID range.

It is generally considered a good practice not to modify the predefined SCCs. The preferred way to fix this situation is to create a custom SCC, as described in the full [Volume Security](#) topic. A custom SCC can be created such that minimum and maximum user IDs are defined, UID range checking is still enforced, and the UID of 65534 is allowed.



NOTE

To use a custom SCC, you must first add it to the appropriate service account. For example, use the **default** service account in the given project unless another has been specified on the pod specification. See [Add an SCC to a User, Group, or Project](#) for details.

22.2.4.3. SELinux



NOTE

See the full [Volume Security](#) topic for information on controlling storage access in conjunction with using SELinux.

By default, SELinux does not allow writing from a pod to a remote NFS server. The NFS volume mounts correctly, but is read-only.

To enable writing to NFS volumes with SELinux enforcing on each node, run:

```
# setsebool -P virt_use_nfs 1
```

The **-P** option above makes the bool persistent between reboots.

The **virt_use_nfs** boolean is defined by the **docker-selinux** package. If an error is seen indicating that this bool is not defined, ensure this package has been installed.

22.2.4.4. Export Settings

In order to enable arbitrary container users to read and write the volume, each exported volume on the NFS server should conform to the following conditions:

- Each export must be:

```
/<example_fs> *(rw,root_squash)
```

- The firewall must be configured to allow traffic to the mount point.
 - For NFSv4, configure the default port **2049 (nfs)** and port **111 (portmapper)**.

NFSv4

■


```
# iptables -I INPUT 1 -p tcp --dport 2049 -j ACCEPT
# iptables -I INPUT 1 -p tcp --dport 111 -j ACCEPT
```

- For NFSv3, there are three ports to configure: **2049** (**nfs**), **20048** (**mountd**), and **111** (**portmapper**).

NFSv3

```
# iptables -I INPUT 1 -p tcp --dport 2049 -j ACCEPT
# iptables -I INPUT 1 -p tcp --dport 20048 -j ACCEPT
# iptables -I INPUT 1 -p tcp --dport 111 -j ACCEPT
```

- The NFS export and directory must be set up so that it is accessible by the target pods. Either set the export to be owned by the container's primary UID, or supply the pod group access using **supplementalGroups**, as shown in [Group IDs](#) above. See the full [Volume Security](#) topic for additional pod security information as well.

22.2.5. Reclaiming Resources

NFS implements the OpenShift Container Platform **Recyclable** plug-in interface. Automatic processes handle reclamation tasks based on policies set on each persistent volume.

By default, PVs are set to **Retain**. NFS volumes which are set to **Recycle** are scrubbed (i.e., **rm -rf** is run on the volume) after being released from their claim (i.e, after the user's **PersistentVolumeClaim** bound to the volume is deleted). Once recycled, the NFS volume can be bound to a new claim.

Once claim to a PV is released (that is, the PVC is deleted), the PV object should not be re-used. Instead, a new PV should be created with the same basic volume details as the original.

For example, the administrator creates a PV named **nfs1**:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: nfs1
spec:
  capacity:
    storage: 1Mi
  accessModes:
    - ReadWriteMany
  nfs:
    server: 192.168.1.1
    path: "/"
```

The user creates **PVC1**, which binds to **nfs1**. The user then deletes **PVC1**, releasing claim to **nfs1**, which causes **nfs1** to be **Released**. If the administrator wishes to make the same NFS share available, they should create a new PV with the same NFS server details, but a different PV name:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: nfs2
spec:
  capacity:
```

```

storage: 1Mi
accessModes:
  - ReadWriteMany
nfs:
  server: 192.168.1.1
  path: "/"

```

Deleting the original PV and re-creating it with the same name is discouraged. Attempting to manually change the status of a PV from **Released** to **Available** causes errors and potential data loss.



NOTE

A PV with retention policy of **Recycle** scrubs (**rm -rf**) the data and marks it as **Available** for claim. The **Recycle** retention policy is deprecated starting in OpenShift Container Platform 3.6 and should be avoided. Anyone using recycler should use dynamic provision and volume deletion instead.

22.2.6. Automation

Clusters can be provisioned with persistent storage using NFS in the following ways:

- [Enforce storage quotas](#) using disk partitions.
- Enforce security by [restricting volumes](#) to the project that has a claim to them.
- Configure [reclamation of discarded resources](#) for each PV.

There are many ways that you can use scripts to automate the above tasks. You can use an [example Ansible playbook](#) to help you get started.

22.2.7. Additional Configuration and Troubleshooting

Depending on what version of NFS is being used and how it is configured, there may be additional configuration steps needed for proper export and security mapping. The following are some that may apply:

NFSv4 mount incorrectly shows all files with ownership of nobody:nobody	<ul style="list-style-type: none"> • Could be attributed to the ID mapping settings (/etc/idmapd.conf) on your NFS • See this Red Hat Solution.
Disabling ID mapping on NFSv4	<ul style="list-style-type: none"> • On both the NFS client and server, run: <pre># echo 'Y' > /sys/module/nfsd/parameters/nfs4_disable _idmapping</pre>

22.3. PERSISTENT STORAGE USING GLUSTERFS


22.3.1. Overview

You can configure your OpenShift Container Platform cluster to use Red Hat Gluster Storage as persistent storage for containerized applications. There are two deployment solutions available when using Red Hat Gluster Storage, using either a containerized or dedicated storage cluster. This topic focuses mainly on the the persistent volume plug-in solution using a dedicated Red Hat Gluster Storage cluster.

22.3.1.1. Containerized Red Hat Gluster Storage

Starting with the Red Hat Gluster Storage 3.1 update 3 release, you can deploy containerized Red Hat Gluster Storage directly on OpenShift Container Platform. Containerized Red Hat Gluster Storage converged with OpenShift Container Platform addresses the use case where containerized applications require both shared file storage and the flexibility of a converged infrastructure with compute and storage instances being scheduled and run from the same set of hardware.

Figure 22.1. Architecture - Red Hat Gluster Storage Container Converged with OpenShift



OPENSIFT_412816_0716

Step-by-step instructions for this containerized solution are provided separately in the following Red Hat Gluster Storage documentation:

[Container-Native Storage for OpenShift Container Platform](#)

22.3.1.2. Container Native Storage Recommendations

OpenShift Container Platform offers container native storage (CNS) storage, which makes it easier for OpenShift Container Platform users to fulfill their storage needs. With CNS, solution users and

administrators are empowered to have storage and application pods running together on the same infrastructure and sharing the same resources.

See [Container-Native Storage for OpenShift Container Platform](#) for configuring CNS as part of an OpenShift Container Platform cluster.

22.3.1.2.1. Creation Time of Volumes with Container Native Storage

Building environment storage can influence the time it takes for an application to start. For example, if the application pod requires a persistent volume claim (PVC), then extra time might have to be considered for CNS to be created and bound to the corresponding PVC. This effects the build time for an application pod to start.

Creation time of CNS volumes scales linearly up to 100 volumes. In the latest tests, each volume took approximately 6 seconds to be created, allocated, and bound to a pod.

All tests were performed on one trusted storage pool (TSP), using hardware configuration for CNS per the [Container-Native Storage for OpenShift Container Platform](#) guidelines.

Dynamic storage provisioning and storage classes were also configured and used when provisioning the PVC.

22.3.1.2.2. Deletion Time of Volumes with Container Native Storage

When you delete a PVC that is used by an application pod, then that action will trigger the deletion of the CNS volume that was used by the PVC.

PVCs will disappear immediately from the `oc get pvc` output. However, the time to delete and recycle CNS volumes depends on the number of CNS volumes. In the latest tests, the deletion time of CNS volumes proved to scale linearly up to 100 volumes.



NOTE

Deletion time does not affect application users. CNS deletion behavior serves as orientation for CNS storage administrators to be able to estimate how long it will approximately take for CNS volumes to be removed from a CNS cluster.

22.3.1.2.3. Recommended Memory Requirements for Container Native Storage

The recommended memory requirements are 32 GB per OpenShift Container Platform node hosting CNS pods.




IMPORTANT

Follow the [planning guidelines](#) when planning hardware for a CNS storage environment to ensure that you have enough memory.

22.3.1.3. Dedicated Storage Cluster

If you have a dedicated Red Hat Gluster Storage cluster available in your environment, you can configure OpenShift Container Platform's Gluster volume plug-in. The dedicated storage cluster delivers persistent Red Hat Gluster Storage file storage for containerized applications over the network. The applications access storage served out from the storage clusters through common storage protocols.

Figure 22.2. Architecture - Dedicated Red Hat Gluster Storage Cluster Using the OpenShift Container Platform Volume Plug-in




You can also dynamically provision volumes in a dedicated Red Hat Gluster Storage cluster that are enabled by Heketi. See [Managing Volumes Using Heketi](#) in the Red Hat Gluster Storage 3.3 Administration Guide for more information.

This solution is a conventional deployment where containerized compute applications run on an OpenShift Container Platform cluster. The remaining sections in this topic provide the step-by-step instructions for the dedicated Red Hat Gluster Storage solution.

This topic presumes some familiarity with OpenShift Container Platform and GlusterFS:

- See the [Persistent Storage](#) topic for details on the OpenShift Container Platform PV framework in general.
- See the [Red Hat Gluster Storage 3.3 Administration Guide](#) for more on GlusterFS.



IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

22.3.2. Support Requirements

The following requirements must be met to create a supported integration of Red Hat Gluster Storage and OpenShift Container Platform.

22.3.2.1. Supported Operating Systems

The following table lists the supported versions of OpenShift Container Platform with Red Hat Gluster Storage Server.

Red Hat Gluster Storage	OpenShift Container Platform
3.1.3	3.1 or later

22.3.2.2. Environment Requirements

The environment requirements for OpenShift Container Platform and Red Hat Gluster Storage are described in this section.

Red Hat Gluster Storage

- All installations of Red Hat Gluster Storage must have valid subscriptions to Red Hat Network channels and Subscription Management repositories.
- Red Hat Gluster Storage installations must adhere to the requirements laid out in the [Red Hat Gluster Storage 3.3 Installation Guide](#).
- Red Hat Gluster Storage installations must be completely up to date with the latest patches and upgrades. Refer to the [Red Hat Gluster Storage 3.3 Installation Guide](#) to upgrade to the latest version.
- The versions of OpenShift Container Platform and Red Hat Gluster Storage integrated must be compatible, according to the information in [Supported Operating Systems](#).
- A fully-qualified domain name (FQDN) must be set for each hypervisor and Red Hat Gluster Storage server node. Ensure that correct DNS records exist, and that the FQDN is resolvable via both forward and reverse DNS lookup.

Red Hat OpenShift Container Platform

- All installations of OpenShift Container Platform must have valid subscriptions to Red Hat Network channels and Subscription Management repositories.
- OpenShift Container Platform installations must adhere to the requirements laid out in the [Installation and Configuration](#) documentation.
- The OpenShift Container Platform cluster must be up and running.
- A user with **cluster-admin** permissions must be created.
- All OpenShift Container Platform nodes on RHEL systems must have the **glusterfs-fuse** RPM installed, which should match the version of Red Hat Gluster Storage server running in the containers. For more information on installing **glusterfs-fuse**, see [Native Client](#) in the Red Hat Gluster 3.3 Storage Administration Guide.

22.3.3. Provisioning

To provision GlusterFS volumes using the [dedicated storage cluster solution](#), the following are required:

- An existing storage device in your underlying infrastructure.
- A distinct list of servers (IP addresses) in the Gluster cluster, to be defined as endpoints.
- A service, to persist the endpoints (optional).

- An existing Gluster volume to be referenced in the persistent volume object.
- **glusterfs-fuse** installed on each schedulable OpenShift Container Platform node in your cluster:

```
$ yum install glusterfs-fuse
```



NOTE

Persistent volumes (PVs) and persistent volume claims (PVCs) can share volumes across a single project. While the GlusterFS-specific information contained in a PV definition could also be defined directly in a pod definition, doing so does not create the volume as a distinct cluster resource, making the volume more susceptible to conflicts.

22.3.3.1. Creating Gluster Endpoints

An endpoints definition defines the GlusterFS cluster as **EndPoints** and includes the IP addresses of your Gluster servers. The port value can be any numeric value within the accepted range of ports. Optionally, you can create a [service](#) that persists the endpoints.

1. Define the following service:

```
apiVersion: v1
kind: Service
metadata:
  name: glusterfs-cluster 1
spec:
  ports:
  - port: 1
```

- 1 This name must be defined in the endpoints definition. If using a service, then the endpoints name must match the service name.

2. Save the service definition to a file, for example **gluster-service.yaml**, then create the service:

```
$ oc create -f gluster-service.yaml
```

3. Verify that the service was created:

```
$ oc get services
```

NAME	CLUSTER_IP	EXTERNAL_IP	PORT(S)
glusterfs-cluster	172.30.205.34	<none>	1/TCP
<none>			

4. Define the Gluster endpoints:

```
apiVersion: v1
kind: Endpoints
metadata:
  name: glusterfs-cluster 1
subsets:
  - addresses:
    - ip: 192.168.122.221 2
```

```

    ports:
      - port: 1
    - addresses:
      - ip: 192.168.122.222 ③
    ports:
      - port: 1 ④

```

- ① This name must match the service name from step 1.
- ② ③ The **ip** values must be the actual IP addresses of a Gluster server, not fully-qualified host names.
- ④ The port number is ignored.

5. Save the endpoints definition to a file, for example **gluster-endpoints.yaml**, then create the endpoints:

```

$ oc create -f gluster-endpoints.yaml
endpoints "glusterfs-cluster" created

```

6. Verify that the endpoints were created:

```

$ oc get endpoints
NAME                ENDPOINTS                                     AGE
docker-registry     10.1.0.3:5000                                4h
glusterfs-cluster   192.168.122.221:1,192.168.122.222:1         11s
kubernetes           172.16.35.3:8443                             4d

```

22.3.3.2. Creating the Persistent Volume



NOTE

GlusterFS does not support the 'Recycle' reclaim policy.

1. Next, define the PV in an object definition before creating it in OpenShift Container Platform:

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-default-volume ①
spec:
  capacity:
    storage: 2Gi ②
  accessModes: ③
    - ReadWriteMany
  glusterfs: ④
    endpoints: glusterfs-cluster ⑤
    path: myVol1 ⑥
    readOnly: false
  persistentVolumeReclaimPolicy: Retain ⑦

```


- 1 The name of the volume. This is how it is identified via [persistent volume claims](#) or from pods.
- 2 The amount of storage allocated to this volume.
- 3 **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control.
- 4 The volume type being used, in this case the **glusterfs** plug-in.
- 5 The endpoints name that defines the Gluster cluster created in [Creating Gluster Endpoints](#).
- 6 The Gluster volume that will be accessed, as shown in the **gluster volume status** command.
- 7 The volume reclaim policy **Retain** indicates that the volume will be preserved after the pods accessing it terminates. For GlusterFS, the accepted values include **Retain**, and **Delete**.



NOTE

Endpoints are name-spaced. Each project accessing the Gluster volume needs its own endpoints.

1. Save the definition to a file, for example **gluster-pv.yaml**, and create the persistent volume:

```
$ oc create -f gluster-pv.yaml
```

2. Verify that the persistent volume was created:

```
$ oc get pv
NAME                                LABELS            CAPACITY    ACCESSMODES
STATUS    CLAIM          REASON      AGE
gluster-default-volume    <none>         2147483648  RWX
Available                                     2s
```

22.3.3.3. Creating the Persistent Volume Claim

Developers request GlusterFS storage by referencing either a PVC or the Gluster volume plug-in directly in the **volumes** section of a pod spec. A PVC exists only in the user's project and can only be referenced by pods within that project. Any attempt to access a PV across a project causes the pod to fail.

1. Create a PVC that will bind to the new PV:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim
spec:
  accessModes:
    - ReadWriteMany 1
```

```
resources:
  requests:
    storage: 1Gi 2
```

- 1 **accessModes** do not enforce security, but rather act as labels to match a PV to a PVC.
- 2 This claim will look for PVs offering **1Gi** or greater capacity.

2. Save the definition to a file, for example **gluster-claim.yaml**, and create the PVC:

```
$ oc create -f gluster-claim.yaml
```



NOTE

PVs and PVCs make sharing a volume across a project simpler. The gluster-specific information contained in the PV definition can also be defined directly in a pod specification.

22.3.4. Gluster Volume Security

This section covers Gluster volume security, including matching permissions and SELinux considerations. Understanding the basics of POSIX permissions, process UIDs, supplemental groups, and SELinux is presumed.



NOTE

See the full [Volume Security](#) topic before implementing Gluster volumes.

As an example, assume that the target Gluster volume, **HadoopVol** is mounted under **/mnt/glusterfs/**, with the following POSIX permissions and SELinux labels:

```
$ ls -lZ /mnt/glusterfs/
drwxrwx---. yarn hadoop system_u:object_r:fusefs_t:s0    HadoopVol

$ id yarn
uid=592(yarn) gid=590(hadoop) groups=590(hadoop)
```

In order to access the **HadoopVol** volume, containers must match the SELinux label, and run with a UID of 592 or 590 in their supplemental groups. The OpenShift Container Platform GlusterFS plug-in mounts the volume in the container with the same POSIX ownership and permissions found on the target gluster mount, namely the owner will be **592** and group ID will be **590**. However, the container is not run with its effective UID equal to **592**, nor with its GID equal to **590**, which is the desired behavior. Instead, a container's UID and supplemental groups are determined by Security Context Constraints (SCCs) and the project defaults.

22.3.4.1. Group IDs

Configure Gluster volume access by using supplemental groups, assuming it is not an option to change permissions on the Gluster mount. Supplemental groups in OpenShift Container Platform are used for shared storage, such as GlusterFS. In contrast, block storage, such as Ceph RBD or iSCSI, use the **fsGroup** SCC strategy and the **fsGroup** value in the pod's **securityContext**.

**NOTE**

Use supplemental group IDs instead of [user IDs](#) to gain access to persistent storage. Supplemental groups are covered further in the full [Volume Security](#) topic.

The group ID on the [target Gluster mount example above](#) is 590. Therefore, a pod can define that group ID using **supplementalGroups** under the pod-level **securityContext** definition. For example:

```
spec:
  containers:
    - name:
      ...
      securityContext: ❶
        supplementalGroups: [590] ❷
```

❶ **securityContext** must be defined at the pod level, not under a specific container.

❷ An array of GIDs defined at the pod level.

Assuming there are no custom SCCs that satisfy the pod's requirements, the pod matches the **restricted** SCC. This SCC has the **supplementalGroups** strategy set to **RunAsAny**, meaning that any supplied group IDs are accepted without range checking.

As a result, the above pod will pass admissions and can be launched. However, if group ID range checking is desired, use a custom SCC, as described in [pod security and custom SCCs](#). A custom SCC can be created to define minimum and maximum group IDs, enforce group ID range checking, and allow a group ID of **590**.

22.3.4.2. User IDs

User IDs can be defined in the container image or in the pod definition. The full [Volume Security](#) topic covers controlling storage access based on user IDs, and should be read prior to setting up NFS persistent storage.

**NOTE**

Use [supplemental group IDs](#) instead of user IDs to gain access to persistent storage.

In the [target Gluster mount example above](#), the container needs a UID set to **592**, so the following can be added to the pod definition:

```
spec:
  containers: ❶
    - name:
      ...
      securityContext:
        runAsUser: 592 ❷
```

❶ Pods contain a **securityContext** specific to each container and a pod-level **securityContext**, which applies to all containers defined in the pod.

❷ The UID defined on the Gluster mount.

With the **default** project and the **restricted** SCC, a pod's requested user ID of **592** will not be allowed, and the pod will fail. This is because:

- The pod requests **592** as its user ID.
- All SCCs available to the pod are examined to see which SCC will allow a user ID of **592**.
- Because all available SCCs use **MustRunAsRange** for their **runAsUser** strategy, UID range checking is required.
- **592** is not included in the SCC or project's user ID range.

Do not modify the predefined SCCs. Instead, [create a custom SCC](#) so that minimum and maximum user IDs are defined, UID range checking is still enforced, and the UID of **592** will be allowed.

22.3.4.3. SELinux



NOTE

See the full [Volume Security](#) topic for information on controlling storage access in conjunction with using SELinux.

By default, SELinux does not allow writing from a pod to a remote Gluster server.

To enable writing to GlusterFS volumes with SELinux enforcing on each node, run:

```
$ sudo setsebool -P virt_sandbox_use_fusefs on
```



NOTE

The **virt_sandbox_use_fusefs** boolean is defined by the **docker-selinux** package. If you get an error saying it is not defined, ensure that this package is installed.

The **-P** option makes the bool persistent between reboots.

22.4. PERSISTENT STORAGE USING OPENSTACK CINDER

22.4.1. Overview

You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [OpenStack Cinder](#). Some familiarity with Kubernetes and OpenStack is assumed.




IMPORTANT

Before you create persistent volumes (PVs) using Cinder, [configured OpenShift Container Platform for OpenStack](#).

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. You can [provision](#) OpenStack Cinder volumes dynamically.

Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [Persistent volume claims](#), however, are specific to a project or namespace and can be requested by users.



IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

22.4.2. Provisioning Cinder PVs

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring that OpenShift Container Platform is [configured for OpenStack](#), all that is required for Cinder is a Cinder volume ID and the **PersistentVolume** API.

22.4.2.1. Creating the Persistent Volume



NOTE


Cinder does not support the 'Recycle' reclaim policy.

You must define your PV in an object definition before creating it in OpenShift Container Platform:

1. Save your object definition to a file, for example *cinder-pv.yaml*:

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" ❶
spec:
  capacity:
    storage: "5Gi" ❷
  accessModes:
    - "ReadWriteOnce"
  cinder: ❸
    fsType: "ext3" ❹
    volumeID: "f37a03aa-6212-4c62-a805-9ce139fab180" ❺
```

- ❶ The name of the volume that is used by [persistent volume claims](#) or pods.
- ❷ The amount of storage allocated to this volume.
- ❸ The volume type, in this case **cinder**.
- ❹ File system type to mount.
- ❺ The Cinder volume to use.



IMPORTANT

Do not change the **fsType** parameter value after the volume is formatted and provisioned. Changing this value can result in data loss and pod failure.

2. Create the persistent volume:

```
# oc create -f cinder-pv.yaml


persistentvolume "pv0001" created
```

3. Verify that the persistent volume exists:

```
# oc get pv
```

NAME	LABELS	CAPACITY	ACCESSMODES	STATUS	CLAIM
REASON	AGE				
pv0001	<none>	5Gi	RWO	Available	
2s					

Users can then [request storage using persistent volume claims](#), which can now utilize your new persistent volume.



IMPORTANT

Persistent volume claims exist only in the user's namespace and can be referenced by a pod within that same namespace. Any attempt to access a persistent volume from a different namespace causes the pod to fail.

22.4.2.2. Cinder PV format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted Cinder volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

22.4.2.3. Cinder volume security

If you use Cinder PVs in your application, configure security for their deployment configurations.



NOTE

Review the [Volume Security](#) information before implementing Cinder volumes.

1. Create an [SCC](#) that uses the appropriate **fsGroup** strategy.
2. Create a service account and add it to the SCC:

```
[source, bash]
$ oc create serviceaccount <service_account>
$ oc adm policy add-scc-to-user <new_scc> -z <service_account> -n <project>
```

3. In your application's deployment configuration, provide the service account name and **securityContext**:

```

apiVersion: v1
kind: ReplicationController
metadata:
  name: frontend-1
spec:
  replicas: 1 ❶
  selector: ❷
    name: frontend
  template: ❸
    metadata:
      labels: ❹
        name: frontend ❺
    spec:
      containers:
      - image: openshift/hello-openshift
        name: helloworld
        ports:
        - containerPort: 8080
          protocol: TCP
      restartPolicy: Always
      serviceAccountName: <service_account> ❻
      securityContext:
        fsGroup: 7777 ❼

```

- ❶ The number of copies of the pod to run.
- ❷ The label selector of the pod to run.
- ❸ A template for the pod the controller creates.
- ❹ The labels on the pod must include labels from the label selector.
- ❺ The maximum name length after expanding any parameters is 63 characters.
- ❻ Specify the service account you created.
- ❼ Specify an **fsGroup** for the pods.

22.5. PERSISTENT STORAGE USING CEPH RADOS BLOCK DEVICE (RBD)

22.5.1. Overview


OpenShift Container Platform clusters can be provisioned with [persistent storage](#) using Ceph RBD.

Persistent volumes (PVs) and [persistent volume claims \(PVCs\)](#) can share volumes across a single project. While the Ceph RBD-specific information contained in a PV definition could also be defined directly in a pod definition, doing so does not create the volume as a distinct cluster resource, making the volume more susceptible to conflicts.

This topic presumes some familiarity with OpenShift Container Platform and [Ceph RBD](#). See the [Persistent Storage](#) concept topic for details on the OpenShift Container Platform persistent volume (PV) framework in general.

**NOTE**

Project and *namespace* are used interchangeably throughout this document. See [Projects and Users](#) for details on the relationship.

**IMPORTANT**

High-availability of storage in the infrastructure is left to the underlying storage provider.

22.5.2. Provisioning


To provision Ceph volumes, the following are required:

- An existing storage device in your underlying infrastructure.
- The Ceph key to be used in an OpenShift Container Platform secret object.
- The Ceph image name.
- The file system type on top of the block storage (e.g., ext4).
- **ceph-common** installed on each schedulable OpenShift Container Platform node in your cluster:

```
# yum install ceph-common
```

22.5.2.1. Creating the Ceph Secret

Define the authorization key in a secret configuration, which is then converted to base64 for use by OpenShift Container Platform.

**NOTE**

In order to use Ceph storage to back a persistent volume, the secret must be created in the same project as the PVC and pod. The secret cannot simply be in the default project.

1. Run **ceph auth get-key** on a Ceph MON node to display the key value for the **client.admin** user:

```
apiVersion: v1
kind: Secret
metadata:
  name: ceph-secret
data:
  key: QVFB0FF2S1ZheUJQRVJBQWgvs2cwT1laQUhPQno3akZwekxxdGc9PQ==
```

2. Save the secret definition to a file, for example **ceph-secret.yaml**, then create the secret:

```
$ oc create -f ceph-secret.yaml
```

3. Verify that the secret was created:

```
# oc get secret ceph-secret
NAME                TYPE                DATA                AGE
```


ceph-secret	Opaque	1	23d
-------------	--------	---	-----

22.5.2.2. Creating the Persistent Volume



NOTE

Ceph RBD does not support the 'Recycle' reclaim policy.

Developers request Ceph RBD storage by referencing either a PVC, or the Gluster volume plug-in directly in the **volumes** section of a pod specification. A PVC exists only in the user's namespace and can be referenced only by pods within that same namespace. Any attempt to access a PV from a different namespace causes the pod to fail.

1. Define the PV in an object definition before creating it in OpenShift Container Platform:

Example 22.3. Persistent Volume Object Definition Using Ceph RBD

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: ceph-pv 1
spec:
  capacity:
    storage: 2Gi 2
  accessModes:
    - ReadWriteOnce 3
  rbd: 4
    monitors: 5
      - 192.168.122.133:6789
    pool: rbd
    image: ceph-image
    user: admin
    secretRef:
      name: ceph-secret 6
    fsType: ext4 7
    readOnly: false
  persistentVolumeReclaimPolicy: Retain
```

- 1 The name of the PV that is referenced in pod definitions or displayed in various **oc** volume commands.
- 2 The amount of storage allocated to this volume.
- 3 **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control. All block storage is defined to be single user (non-shared storage).
- 4 The volume type being used, in this case the **rbd** plug-in.
- 5 An array of Ceph monitor IP addresses and ports.
- 6 The Ceph secret used to create a secure connection from OpenShift Container Platform to the Ceph server.

- 7** The file system type mounted on the Ceph RBD block device.



IMPORTANT

Changing the value of the **fstype** parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

2. Save your definition to a file, for example ***ceph-pv.yaml***, and create the PV:

```
# oc create -f ceph-pv.yaml
```

3. Verify that the persistent volume was created:

```
# oc get pv
NAME                                LABELS                                CAPACITY    ACCESSMODES
STATUS          CLAIM          REASON      AGE
ceph-pv         Available      <none>      2s
2147483648      RW0
```

4. Create a PVC that will bind to the new PV:

Example 22.4. PVC Object Definition

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: ceph-claim
spec:
  accessModes: 1
    - ReadWriteOnce
  resources:
    requests:
      storage: 2Gi 2
```

- 1** The **accessModes** do not enforce access right, but instead act as labels to match a PV to a PVC.
- 2** This claim looks for PVs offering **2Gi** or greater capacity.

5. Save the definition to a file, for example ***ceph-claim.yaml***, and create the PVC:

```
# oc create -f ceph-claim.yaml
```

22.5.3. Ceph Volume Security



NOTE

See the full [Volume Security](#) topic before implementing Ceph RBD volumes.

A significant difference between shared volumes (NFS and GlusterFS) and block volumes (Ceph RBD, iSCSI, and most cloud storage), is that the user and group IDs defined in the pod definition or container image are applied to the target physical storage. This is referred to as managing ownership of the block device. For example, if the Ceph RBD mount has its owner set to **123** and its group ID set to **567**, and if the pod defines its **runAsUser** set to **222** and its **fsGroup** to be **7777**, then the Ceph RBD physical mount's ownership will be changed to **222:7777**.



NOTE

Even if the user and group IDs are not defined in the pod specification, the resulting pod may have defaults defined for these IDs based on its matching SCC, or its project. See the full [Volume Security](#) topic which covers storage aspects of SCCs and defaults in greater detail.

A pod defines the group ownership of a Ceph RBD volume using the **fsGroup** stanza under the pod's **securityContext** definition:

```
spec:
  containers:
    - name:
      ...
  securityContext: 1
    fsGroup: 7777 2
```

- 1 The **securityContext** must be defined at the pod level, not under a specific container.
- 2 All containers in the pod will have the same fsGroup ID.

22.6. PERSISTENT STORAGE USING AWS ELASTIC BLOCK STORE

22.6.1. Overview


OpenShift Container Platform supports AWS Elastic Block Store volumes (EBS). You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [AWS EC2](#). Some familiarity with Kubernetes and AWS is assumed.



IMPORTANT

Before creating persistent volumes using AWS, OpenShift Container Platform must first be properly [configured for AWS ElasticBlockStore](#).

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. AWS Elastic Block Store volumes can be [provisioned dynamically](#). Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [Persistent volume claims](#), however, are specific to a project or namespace and can be requested by users.



IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

22.6.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring OpenShift is [configured for AWS Elastic Block Store](#), all that is required for OpenShift and AWS is an AWS EBS volume ID and the **PersistentVolume** API.

22.6.2.1. Creating the Persistent Volume



NOTE


AWS does not support the 'Recycle' reclaim policy.

You must define your persistent volume in an object definition before creating it in OpenShift Container Platform:

Example 22.5. Persistent Volume Object Definition Using AWS

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
spec:
  capacity:
    storage: "5Gi" 2
  accessModes:
    - "ReadWriteOnce"
  awsElasticBlockStore: 3
    fsType: "ext4" 4
    volumeID: "vol-f37a03aa" 5
```

- 1 The name of the volume. This will be how it is identified via [persistent volume claims](#) or from pods.
- 2 The amount of storage allocated to this volume.
- 3 This defines the volume type being used, in this case the **awsElasticBlockStore** plug-in.
- 4 File system type to mount.
- 5 This is the AWS volume that will be used.



IMPORTANT

Changing the value of the **fsType** parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

Save your definition to a file, for example **aws-pv.yaml**, and create the persistent volume:

```
# oc create -f aws-pv.yaml
persistentvolume "pv0001" created
```

Verify that the persistent volume was created:

```
# oc get pv
NAME          LABELS          CAPACITY  ACCESSMODES  STATUS   CLAIM          REASON
AGE
pv0001        <none>          5Gi       RWO           Available
2s
```

Users can then [request storage using persistent volume claims](#), which can now utilize your new persistent volume.



IMPORTANT

Persistent volume claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume from a different namespace causes the pod to fail.

22.6.2.2. Volume Format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted AWS volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

22.6.2.3. Maximum Number of EBS Volumes on a Node

By default, OpenShift Container Platform supports a maximum of 39 EBS volumes attached to one node. This limit is consistent with the [AWS Volume Limits](#).

OpenShift Container Platform can be configured to have a higher limit by setting the environment variable **KUBE_MAX_PD_VOLS**. However, AWS requires a particular naming scheme ([AWS Device Naming](#)) for attached devices, which only supports a maximum of 52 volumes. This limits the number of volumes that can be attached to a node via OpenShift Container Platform to 52.

22.7. PERSISTENT STORAGE USING GCE PERSISTENT DISK

22.7.1. Overview

OpenShift Container Platform supports GCE Persistent Disk volumes (gcePD). You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [GCE](#). Some familiarity with Kubernetes and GCE is assumed.




IMPORTANT

Before creating persistent volumes using GCE, OpenShift Container Platform must first be properly [configured for GCE Persistent Disk](#).

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. GCE Persistent Disk volumes can be [provisioned dynamically](#). Persistent

volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [Persistent volume claims](#), however, are specific to a project or namespace and can be requested by users.



IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

22.7.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring OpenShift Container Platform is [configured for GCE PersistentDisk](#), all that is required for OpenShift Container Platform and GCE is an GCE Persistent Disk volume ID and the **PersistentVolume** API.

22.7.2.1. Creating the Persistent Volume



NOTE

GCE does not support the 'Recycle' reclaim policy.

You must define your persistent volume in an object definition before creating it in OpenShift Container Platform:

Example 22.6. Persistent Volume Object Definition Using GCE

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
spec:
  capacity:
    storage: "5Gi" 2
  accessModes:
    - "ReadWriteOnce"
  gcePersistentDisk: 3
    fsType: "ext4" 4
    pdName: "pd-disk-1" 5
```

- 1 The name of the volume. This will be how it is identified via [persistent volume claims](#) or from pods.
- 2 The amount of storage allocated to this volume.
- 3 This defines the volume type being used, in this case the **gcePersistentDisk** plug-in.
- 4 File system type to mount.
- 5 This is the GCE Persistent Disk volume that will be used.

**IMPORTANT**

Changing the value of the **fstype** parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

Save your definition to a file, for example ***gce-pv.yaml***, and create the persistent volume:

```
# oc create -f gce-pv.yaml
persistentvolume "pv0001" created
```

Verify that the persistent volume was created:

```
# oc get pv
NAME          LABELS          CAPACITY  ACCESSMODES  STATUS      CLAIM          REASON
AGE
pv0001        <none>          5Gi       RWO           Available
2s
```

Users can then [request storage using persistent volume claims](#), which can now utilize your new persistent volume.

**IMPORTANT**

Persistent volume claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume from a different namespace causes the pod to fail.

22.7.2.2. Volume Format


Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted GCE volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

22.8. PERSISTENT STORAGE USING ISCSI**22.8.1. Overview**

You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [iSCSI](#). Some familiarity with Kubernetes and iSCSI is assumed.

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.

**IMPORTANT**

High-availability of storage in the infrastructure is left to the underlying storage provider.

22.8.2. Provisioning

Verify that the storage exists in the underlying infrastructure before mounting it as a volume in OpenShift Container Platform. All that is required for the iSCSI is the iSCSI target portal, a valid iSCSI Qualified Name (IQN), a valid LUN number, the filesystem type, and the **PersistentVolume** API.

Optionally, multipath portals and Challenge Handshake Authentication Protocol (CHAP) configuration can be provided.



NOTE

iSCSI does not support the 'Recycle' reclaim policy.

Example 22.7. Persistent Volume Object Definition

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi-pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.16.154.81:3260
    portals: ['10.16.154.82:3260', '10.16.154.83:3260']
    iqn: iqn.2014-12.example.server:storage.target00
    lun: 0
    fsType: 'ext4'
    readOnly: false
    chapAuthDiscovery: true
    chapAuthSession: true
    secretRef:
      name: chap-secret
```

22.8.2.1. Enforcing Disk Quotas

Use LUN partitions to enforce disk quotas and size constraints. Each LUN is one persistent volume. Kubernetes enforces unique names for persistent volumes.

Enforcing quotas in this way allows the end user to request persistent storage by a specific amount (e.g, 10Gi) and be matched with a corresponding volume of equal or greater capacity.

22.8.2.2. iSCSI Volume Security

Users request storage with a **PersistentVolumeClaim**. This claim only lives in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume across a namespace causes the pod to fail.

Each iSCSI LUN must be accessible by all nodes in the cluster.

22.8.2.3. iSCSI Multipathing

For iSCSI-based storage, you can configure multiple paths by using the same IQN for more than one target portal IP address. Multipathing ensures access to the persistent volume when one or more of the components in a path fail.

To specify multi-paths in pod specification use the **portals** field. For example:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi_pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.0.0.1:3260
    portals: ['10.0.2.16:3260', '10.0.2.17:3260', '10.0.2.18:3260'] 1
    iqn: iqn.2016-04.test.com:storage.target00
    lun: 0
    fsType: ext4
    readOnly: false
```

1 Add additional target portals using the **portals** field.

22.9. PERSISTENT STORAGE USING FIBRE CHANNEL

22.9.1. Overview

You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [Fibre Channel](#). Some familiarity with Kubernetes and Fibre Channel is assumed.

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.



IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

22.9.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. All that is required for Fibre Channel persistent storage is the **targetWWNs** (array of Fibre Channel target's World Wide Names), a valid **LUN** number, filesystem type, and the **PersistentVolume** API. Persistent volume and a LUN have one-to-one mapping between them.



NOTE

Fibre Channel does not support the 'Recycle' reclaim policy.

Persistent Volumes Object Definition

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  fc:
    targetWWNs: ['500a0981891b8dc5', '500a0981991b8dc5'] 1
    lun: 2
    fsType: ext4
```

- 1** Fibre Channel WWNs are identified as `/dev/disk/by-path/pci-<IDENTIFIER>-fc-0x<WWN>-lun-<LUN#>`, but you do not need to provide any part of the path leading up to the `WWN`, including the `0x`, and anything after, including the `-` (hyphen).



IMPORTANT

Changing the value of the **fsType** parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

22.9.2.1. Enforcing Disk Quotas

Use LUN partitions to enforce disk quotas and size constraints. Each LUN is one persistent volume. Kubernetes enforces unique names for persistent volumes.

Enforcing quotas in this way allows the end user to request persistent storage by a specific amount (e.g, 10Gi) and be matched with a corresponding volume of equal or greater capacity.

22.9.2.2. Fibre Channel Volume Security

Users request storage with a **PersistentVolumeClaim**. This claim only lives in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume across a namespace causes the pod to fail.

Each Fibre Channel LUN must be accessible by all nodes in the cluster.

22.10. PERSISTENT STORAGE USING AZURE DISK

22.10.1. Overview

OpenShift Container Platform supports [Microsoft Azure Disk](#) volumes. You can provision your OpenShift Container Platform cluster with [persistent storage](#) using Azure. Some familiarity with Kubernetes and Azure is assumed.

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.

Azure Disk volumes can be [provisioned dynamically](#). Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [Persistent volume claims](#), however, are specific to a project or namespace and can be requested by users.



IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

22.10.2. Prerequisites

Before creating persistent volumes using Azure, ensure your OpenShift Container Platform cluster meets the following requirements:

- OpenShift Container Platform must first be [configured for Azure Disk](#).
- Each node host in the infrastructure must match the Azure virtual machine name.
- Each node host must be in the same resource group.

22.10.3. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring OpenShift Container Platform is [configured for Azure Disk](#), all that is required for OpenShift Container Platform and Azure is an Azure Disk Name and Disk URI and the **PersistentVolume** API.

22.10.4. Configuring Azure Disk for regional cloud

Azure has multiple regions on which to deploy an instance. To specify a desired region, add the following to the **azure.conf** file:

```
cloud: <region>
```

The region can be any of the following:

- German cloud: **AZUREGERMANCLOUD**
- China cloud: **AZURECHINACLOUD**
- Public cloud: **AZUREPUBLICCLOUD**
- US cloud: **AZUREUSGOVERNMENTCLOUD**

22.10.4.1. Creating the Persistent Volume



NOTE

Azure does not support the **Recycle** reclaim policy.

You must define your persistent volume in an object definition before creating it in OpenShift Container Platform:


Example 22.8. Persistent Volume Object Definition Using Azure

```

apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" ❶
spec:
  capacity:
    storage: "5Gi" ❷
  accessModes:
    - "ReadWriteOnce"
  azureDisk: ❸
    diskName: test2.vhd ❹
    diskURI: https://someaccount.blob.core.windows.net/vhds/test2.vhd ❺
    cachingMode: ReadWrite ❻
    fsType: ext4 ❼
    readOnly: false ❽

```

- ❶ The name of the volume. This will be how it is identified via [persistent volume claims](#) or from pods.
- ❷ The amount of storage allocated to this volume.
- ❸ This defines the volume type being used (**azureDisk** plug-in, in this example).
- ❹ The name of the data disk in the blob storage.
- ❺ The URI the the data disk in the blob storage.
- ❻ Host caching mode: None, ReadOnly, or ReadWrite.
- ❼ File system type to mount (for example, **ext4**, **xfs**, and so on).
- ❽ Defaults to **false** (read/write). **ReadOnly** here will force the **ReadOnly** setting in **VolumeMounts**.



IMPORTANT

Changing the value of the **fsType** parameter after the volume is formatted and provisioned can result in data loss and pod failure.

1. Save your definition to a file, for example **azure-pv.yaml**, and create the persistent volume:

```
# oc create -f azure-pv.yaml
persistentvolume "pv0001" created
```

2. Verify that the persistent volume was created:

```
# oc get pv
NAME          LABELS          CAPACITY  ACCESSMODES  STATUS      CLAIM
REASON        AGE
pv0001        <none>          5Gi       RW0           Available
2s
```

Now you can [request storage using persistent volume claims](#), which can now use your new persistent volume.



IMPORTANT

For a pod that has a mounted volume through an Azure disk PVC, scheduling the pod to a new node takes a few minutes. Wait for two to three minutes to complete the *Disk Detach* operation, and then start a new deployment. If a new pod creation request is started before completing the *Disk Detach* operation, the *Disk Attach* operation initiated by the pod creation fails, resulting in pod creation failure.



IMPORTANT

Persistent volume claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume from a different namespace causes the pod to fail.

22.10.4.2. Volume Format


Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows unformatted Azure volumes to be used as persistent volumes because OpenShift Container Platform formats them before the first use.

22.11. PERSISTENT STORAGE USING AZURE FILE

22.11.1. Overview

OpenShift Container Platform supports [Microsoft Azure File](#) volumes. You can provision your OpenShift Container Platform cluster with [persistent storage](#) using Azure. Some familiarity with Kubernetes and Azure is assumed.



IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

22.11.2. Before you begin

1. Install **samba-client**, **samba-common**, and **cifs-utils** on all nodes:

```
$ sudo yum install samba-client samba-common cifs-utils
```

2. Enable SELinux booleans on all nodes:

```
$ /usr/sbin/setsebool -P virt_use_samba on
$ /usr/sbin/setsebool -P virt_sandbox_use_samba on
```

**NOTE**

Mount options are not available in OpenShift Container Platform 3.7.43. You cannot use Azure File in OpenShift Container Platform 3.7.43. To use Azure file, upgrade to OpenShift Container Platform 3.7.46.

22.11.3. Configuring Azure File for regional cloud

While [Azure Disk is compatible with multiple regional clouds](#), Azure File supports only the Azure public cloud, because the endpoint is hard-coded.

22.11.4. Creating the PV**NOTE**

Azure File does not support the **Recycle** reclaim policy.

22.11.5. Creating the Azure Storage Account secret

Define the Azure Storage Account name and key in a secret configuration, which is then converted to base64 for use by OpenShift Container Platform.

1. Obtain an Azure Storage Account name and key and encode to base64:

```
apiVersion: v1
kind: Secret
metadata:
  name: azure-secret
type: Opaque
data:
  azurestorageaccountname: azhzdGVzdA==
  azurestorageaccountkey:
eElGMXpKYm5ub2pGTE1Ta0JwNTBteDAyckhzTUyyc2pVN21GdDRMMTNob0I3ZHJBYUo4
akQ2K0E0NDNqSm9nVjd5MkZVT2hRQ1dQbU02WWF0SHk3cWc9PQ==
```

2. Save the secret definition to a file, for example **azure-secret.yaml**, then create the secret:

```
$ oc create -f azure-secret.yaml
```

3. Verify that the secret was created:

```
$ oc get secret azure-secret
NAME          TYPE          DATA      AGE
azure-secret  Opaque        1          23d
```

4. Define the PV in an object definition before creating it in OpenShift Container Platform:

PV object definition using Azure File example

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
```

```
spec:
  capacity:
    storage: "5Gi" ❷
  accessModes:
    - "ReadWriteMany"
  azureFile: ❸
    secretName: azure-secret ❹
    shareName: example ❺
    readOnly: false ❻
```

- ❶ The name of the volume. This is how it is identified via [PV claims](#) or from pods.
- ❷ The amount of storage allocated to this volume.
- ❸ This defines the volume type being used: **azureFile** plug-in.
- ❹ The name of the secret used.
- ❺ The name of the file share.
- ❻ Defaults to **false** (read/write). **ReadOnly** here forces the **ReadOnly** setting in **VolumeMounts**.

5. Save the definition to a file, for example **azure-file-pv.yaml**, and create the PV:

```
$ oc create -f azure-file-pv.yaml
persistentvolume "pv0001" created
```

6. Verify that the PV was created:

```
$ oc get pv
NAME          LABELS      CAPACITY  ACCESSMODES  STATUS      CLAIM
REASON      AGE
pv0001      <none>      5Gi       RWM           Available
2s
```

Now you can [request storage using PV claims](#), which can now use your new PV.



IMPORTANT

PV claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a PV from a different namespace causes the pod to fail.

22.12. PERSISTENT STORAGE USING FLEXVOLUME PLUG-INS

22.12.1. Overview

OpenShift Container Platform has built-in [volume plug-ins](#) to use different storage technologies. To consume storage from a back-end that does not have a built-in plug-in, you can extend OpenShift Container Platform via FlexVolume drivers and provide [persistent storage](#) to applications.

A [FlexVolume driver](#) is an executable file (typically a shell script), deployed to all machines in the cluster (both masters and nodes) as part of the installation.

22.12.2. Installing FlexVolume Drivers

To install the FlexVolume driver, place the executable file at the volume plug-in path:
`/usr/libexec/kubernetes/kubelet-plugins/volume/exec/<vendor>~<driver>/<driver>`. For example, to install the FlexVolume driver for the storage `foo`, place the executable file at:
`/usr/libexec/kubernetes/kubelet-plugins/volume/exec/openshift.com~foo/foo`.



IMPORTANT

Ensure that this file exists on all masters and nodes in the cluster.

22.12.3. Consuming Storage using FlexVolume

Use the **PersistentVolume** object to reference the installed storage. Each **PersistentVolume** object in OpenShift Container Platform represents one storage asset, typically a volume, in the storage back-end.

Persistent Volume Object Definition Using FlexVolume

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 1
spec:
  capacity:
    storage: 1Gi 2
  accessModes:
    - ReadWriteOnce
  flexVolume:
    driver: openshift.com/foo 3
    fsType: "ext4" 4
    secretRef: foo-secret 5
    readOnly: true 6
    options: 7
      fooServer: 192.168.0.1:1234
      fooVolumeName: bar
```

- 1 The name of the volume. This is how it is identified via [persistent volume claims](#) or from pods. This name can be different from the name of the volume on back-end storage.
- 2 The amount of storage allocated to this volume.
- 3 Name of the driver. This field is mandatory.
- 4 Optional file system that is present on the volume.
- 5 Optional reference to a secret. Keys and values from this secret are provided to the FlexVolume driver on invocation.
- 6 Optional read-only flag.

- 7** Additional options for the FlexVolume driver. This is a free-form dictionary of parameters provided to the FlexVolume driver. Typically, it includes details like the name of the volume that this **PersistentVolume** represents and addresses of the storage server(s).

22.12.4. FlexVolume Drivers

A FlexVolume driver is an executable file that resides in a well-defined directory on all machines in the cluster, both masters and nodes. OpenShift Container Platform calls it whenever it needs to attach, detach, mount, or unmount a volume represented by a **PersistentVolume** with **flexVolume** as source.

The first command-line argument of the driver is always an operation name. Other parameters are specific to each operation. Most of the operations takes a JSON(JavaScript Object Notation) string as a parameter. This parameter is a complete JSON string, and not the name of a file with the JSON data.

It contains:

- All **flexVolume.options**.
- Some options from **flexVolume** prefixed by **kubernetes.io/**, such as **fsType** and **readwrite**.
- Content of the referenced secret (if specified) prefixed by **kubernetes.io/secret/**.

Example FlexVolume Driver JSON input

```
{
  "fooServer": "192.168.0.1:1234", 1
  "fooVolumeName": "bar",
  "kubernetes.io/fsType": "ext4", 2
  "kubernetes.io/readwrite": "ro", 3
  "kubernetes.io/secret/<key name>": "<key value>", 4
  "kubernetes.io/secret/<another key name>": "<another key value>",
}
```

- 1** All options from **flexVolume.options**.
- 2** Value of **flexVolume.fsType**.
- 3** **ro/rw** based on **flexVolume.readOnly**.
- 4** All keys and their values from the secret referenced by **flexVolume.secretRef**.

OpenShift Container Platform expects JSON data on standard output of the driver. When not specified, the output describes the result of the operation.

FlexVolume Driver Default Output

```
{
  "status": "<Success/Failure/Not supported>",
  "message": "<Reason for success/failure>"
}
```


Exit code of the driver should be **0** for success and **1** for error.

Operations should be idempotent, which means that the attachment of an already attached volume or the mounting of an already mounted volume should result in a successful operation.

The FlexVolume driver can work in two modes:

- with the master-initiated `attach/detach` operation, or
- without the master-initiated `attach/detach` operation.

The **attach/detach** operation is used by the OpenShift Container Platform master to attach a volume to a node and to detach it from a node. This is useful when a node becomes unresponsive from any reason. Then, the master can kill all pods on the node, detach all volumes from it, and attach the volumes to other nodes to resume the applications while the original node is still not reachable.



IMPORTANT

Not all storage back-end supports master-initiated detachment of a volume from another machine.

22.12.4.1. FlexVolume Drivers with Master-initiated Attach/Detach

A FlexVolume driver that supports master-controlled `attach/detach` must implement the following operations:

init

Initializes the driver. It is called during initialization of masters and nodes.

- Arguments: none
- Executed on: master, node
- Expected output: default JSON

getvolumename

Returns the unique name of the volume. This name must be consistent among all masters and nodes, because it is used in subsequent **detach** call as **<volume-name>**. Any `/` characters in the **<volume-name>** are automatically replaced by `~`.

- Arguments: **<json>**
- Executed on: master, node
- Expected output: default JSON + **volumeName**:

```
{
  "status": "Success",
  "message": "",
  "volumeName": "foo-volume-bar" 1
}
```

- 1** The unique name of the volume in storage back-end **foo**.

attach

Attaches a volume represented by the JSON to a given node. This operation should return the name of the device on the node if it is known (i.e. it has been assigned by the storage back-end before it runs). If the device is not known, the device must be found on the node by the subsequent **waitforattach** operation.

- Arguments: **<json>** **<node-name>**
- Executed on: master
- Expected output: default JSON + **device** (if known):

```
{
  "status": "Success",
  "message": "",
  "device": "/dev/xvda" 1
}
```

1 Name of the device on the node (if known).

waitforattach

Waits until a volume is fully attached to a node and its device emerges. If the previous **attach** operation has returned **<device-name>**, it is provided as an input parameter. Otherwise, **<device-name>** is empty and the operation must find the device on the node.

- Arguments: **<device-name>** **<json>**
- Executed on: node
- Expected output: default JSON + **device**

```
{
  "status": "Success",
  "message": "",
  "device": "/dev/xvda" 1
}
```

1 Name of the device on the node.

detach

Detaches the given volume from a node. **<volume-name>** is the name of the device returned by the **getvolumename** operation. Any / characters in the **<volume-name>** are automatically replaced by ~.

- Arguments: **<volume-name>** **<node-name>**
- Executed on: master
- Expected output: default JSON

isattached

Checks that a volume is attached to a node.

- Arguments: **<json> <node-name>**
- Executed on: master
- Expected output: default JSON + **attached**

```
{
  "status": "Success",
  "message": "",
  "attached": true 1
}
```

- 1** Status of attachment of the volume to the node.

mountdevice

Mounts a volume's device to a directory. **<device-name>** is name of the device as returned by the previous **waitforattach** operation.


- Arguments: **<mount-dir> <device-name> <json>**
- Executed on: node
- Expected output: default JSON

unmountdevice

Unmounts a volume's device from a directory.

- Arguments: **<mount-dir>**
- Executed on: node

All other operations should return JSON with **{"status": "Not supported"}** and exit code **1**.



NOTE

Master-initiated attach/detach operations are enabled by default in OpenShift Container Platform 3.6. They may work in older versions, but must be explicitly enabled. See [Enabling Controller-managed Attachment and Detachment](#). When not enabled, the attach/detach operations are initiated by a node where the volume should be attached to or detached from. Syntax and all parameters of FlexVolume driver invocations are the same in both cases.

22.12.4.2. FlexVolume Drivers Without Master-initiated Attach/Detach

FlexVolume drivers that do not support master-controlled attach/detach are executed only on the node and must implement these operations:

init

Initializes the driver. It is called during initialization of all nodes.

- Arguments: none

- Executed on: node
- Expected output: default JSON

mount

Mounts a volume to directory. This can include anything that is necessary to mount the volume, including attaching the volume to the node, finding the its device, and then mounting the device.

- Arguments: **<mount-dir>** **<json>**
- Executed on: node
- Expected output: default JSON

unmount

Unmounts a volume from a directory. This can include anything that is necessary to clean up the volume after unmounting, such as detaching the volume from the node.

- Arguments: **<mount-dir>**
- Executed on: node
- Expected output: default JSON

All other operations should return JSON with **{"status": "Not supported"}** and exit code **1**.


22.13. USING VMWARE VSPHERE VOLUMES FOR PERSISTENT STORAGE

22.13.1. Overview

OpenShift Container Platform supports VMware vSphere's Virtual Machine Disk (VMDK) volumes. You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [VMware vSphere](#). Some familiarity with Kubernetes and VMware vSphere is assumed.

The OpenShift Container Platform [persistent volume \(PV\)](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. vSphere VMDK volumes can be [provisioned dynamically](#).

PVs are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [PV claims](#), however, are specific to a project or namespace and can be requested by users.



IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

Prerequisites

Before creating PVs using vSphere, ensure your OpenShift Container Platform cluster meets the following requirements:

- OpenShift Container Platform must first be [configured for vSphere](#).
- Each node host in the infrastructure must match the vSphere VM name.
- Each node host must be in the same resource group.

IMPORTANT

Create VMDK using one of the following methods before using them.

- Create using **vmkfstools**:
Access ESX through Secure Shell (SSH) and then use following command to create a VMDK volume:

```
vmkfstools -c 2G
/vmfs/volumes/DatastoreName/volumes/myDisk.vmdk
```

- Create using **vmware-vdiskmanager**:

```
shell vmware-vdiskmanager -c -t 0 -s 40GB -a lsilogic
myDisk.vmdk
```

22.13.2. Provisioning VMware vSphere volumes

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring OpenShift Container Platform is [configured for vSphere](#), all that is required for OpenShift Container Platform and vSphere is a VM folder path, file system type, and the **PersistentVolume** API.

22.13.2.1. Creating persistent volumes

You must define your PV in an object definition before creating it in OpenShift Container Platform:

PV object definition using VMware vSphere example

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 ❶
spec:
  capacity:
    storage: 2Gi ❷
  accessModes:
    - ReadWriteOnce
  persistentVolumeReclaimPolicy: Retain
  vsphereVolume: ❸
    volumePath: "[datastore1] volumes/myDisk" ❹
    fsType: ext4 ❺
```

- ❶ The name of the volume. This must be how it is identified by [PV claims](#) or from pods.
- ❷ The amount of storage allocated to this volume.

- 3 This defines the volume type being used (**vsphereVolume** plug-in, in this example). The **vsphereVolume** label is used to mount a vSphere VMDK volume into pods. The contents of a volume are preserved when it is unmounted. The volume type supports VMFS and VSAN datastore.
- 4 This VMDK volume must exist.
- 5 The file system type to mount (for example, **ext4**, **xfs**, and other file-systems).



IMPORTANT

Changing the value of the **fsType** parameter after the volume is formatted and provisioned can result in data loss and pod failure.

1. Save your definition to a file, for example **vsphere-pv.yaml**, and create the PV:

```
$ oc create -f vsphere-pv.yaml
persistentvolume "pv0001" created
```

2. Verify that the PV was created:

```
$ oc get pv
NAME          LABELS    CAPACITY  ACCESSMODES  STATUS   CLAIM    REASON
AGE
pv0001        <none>    2Gi       RW0           Available
2s
```

Now you can [request storage using PV claims](#), which can now use your PV.



IMPORTANT

PV claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a PV from a different namespace causes the pod to fail.

22.13.2.2. Formatting VMware vSphere volumes

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that the volume contains a file system as specified by the **fsType** parameter in the PV definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows unformatted vSphere volumes to be used as PVs, because OpenShift Container Platform formats them before the first use.

22.14. PERSISTENT STORAGE USING LOCAL VOLUME

22.14.1. Overview

OpenShift Container Platform clusters can be provisioned with [persistent storage](#) by using local volumes. Local persistent volume allows you to access local storage devices such as a disk, partition or directory by using the standard PVC interface.

Local volumes can be used without manually scheduling pods to nodes, because the system is aware of the volume's node constraints. However, local volumes are still subject to the availability of the underlying node and are not suitable for all applications.



NOTE

Local volumes is an alpha feature and may change in a future release of OpenShift Container Platform. See [Feature Status\(Local Volume\)](#) section for details on known issues and workarounds.



WARNING

Local volumes can only be used as a statically created Persistent Volume.

22.14.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. Ensure that OpenShift Container Platform is configured for [Local Volumes](#), before using the **PersistentVolume** API.

22.14.3. Creating Local Persistent Volume Claim

Define the persistent volume claim in an object definition.

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: example-local-claim
spec:
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 5Gi 1
  storageClassName: local-storage 2
```

- 1 The required size of storage volume.
- 2 The name of storage class, which is used for local PVs.

22.14.4. Feature Status

What Works:

- Creating a PV by specifying a directory with node affinity.
- A Pod using the PVC that is bound to the previously mentioned PV always get scheduled to that node.

- External static provisioner daemonset that discovers local directories, creates, cleans up and deletes PVs.

What does not work:

- Multiple local PVCs in a single pod.
- PVC binding does not consider pod scheduling requirements and may make sub-optimal or incorrect decisions.
 - Workarounds:
 - Run those pods first, which requires local volume.
 - Give the pods high priority.
 - Run a workaround controller that unbinds PVCs for pods that are stuck pending.
- If mounts are added after the external provisioner is started, then external provisioner cannot detect the correct capacity of mounts.
 - Workarounds:
 - Before adding any new mount points, first stop the daemonset, add the new mount points, and then start the daemonset.
- **fsgroup** conflict occurs if multiple pods using the same PVC specify different **fsgroup** 's.

22.15. DYNAMIC PROVISIONING AND CREATING STORAGE CLASSES

22.15.1. Overview

The *StorageClass* resource object describes and classifies storage that can be requested, as well as provides a means for passing parameters for **dynamically provisioned storage** on demand.

StorageClass objects can also serve as a management mechanism for controlling different levels of storage and access to the storage. Cluster Administrators (**cluster-admin**) or Storage Administrators (**storage-admin**) define and create the *StorageClass* objects that users can request without needing any intimate knowledge about the underlying storage volume sources.

The OpenShift Container Platform [persistent volume](#) framework enables this functionality and allows administrators to provision a cluster with persistent storage. The framework also gives users a way to request those resources without having any knowledge of the underlying infrastructure.

Many storage types are available for use as persistent volumes in OpenShift Container Platform. While all of them can be statically provisioned by an administrator, some types of storage are created dynamically using the built-in provider and plug-in APIs.

**NOTE**

To enable dynamic provisioning, add the **openshift_master_dynamic_provisioning_enabled** variable to the **[OSEv3:vars]** section of the Ansible inventory file and set its value to **True**.

```
[OSEv3:vars]
```

```
openshift_master_dynamic_provisioning_enabled=True
```

22.15.2. Available dynamically provisioned plug-ins

OpenShift Container Platform provides the following *provisioner plug-ins*, which have generic implementations for dynamic provisioning that use the cluster's configured provider's API to create new storage resources:

Storage Type	Provisioner Plug-in Name	Required Configuration	Notes
OpenStack Cinder	kubernetes.io/cinder	Configuring for OpenStack	
AWS Elastic Block Store (EBS)	kubernetes.io/aws-ebs	Configuring for AWS	For dynamic provisioning when using multiple clusters in different zones, tag each node with Key=kubernetes.io/cluster/xxxx, Value=clusterid where xxxx and clusterid are unique per cluster. In versions prior to 3.6, this was Key=KubernetesCluster, Value=clusterid .
GCE Persistent Disk (gcePD)	kubernetes.io/gce-pd	Configuring for GCE	In multi-zone configurations, it is advisable to run one Openshift cluster per GCE project to avoid PVs from getting created in zones where no node from current cluster exists.
GlusterFS	kubernetes.io/glusterfs	Container Native Storage with GlusterFS	Container Native Storage (CNS) utilizes Heketi to manage Gluster Storage.

Storage Type	Provisioner Plug-in Name	Required Configuration	Notes
Ceph RBD	<code>kubernetes.io/rbd</code>	Configuring Ceph RBD	
Trident from NetApp	<code>netapp.io/trident</code>	Configuring for Trident	Storage orchestrator for NetApp ONTAP, SolidFire, and E-Series storage.
VMWare vSphere	<code>kubernetes.io/vsphere-volume</code>	Getting Started with vSphere and Kubernetes	
Azure Disk	<code>kubernetes.io/azure-disk</code>	Configuring for Azure	



IMPORTANT

Any chosen provisioner plug-in also requires configuration for the relevant cloud, host, or third-party provider as per the relevant documentation.

22.15.3. Defining a StorageClass

StorageClass objects are currently a globally scoped object and need to be created by `cluster-admin` or `storage-admin` users.



NOTE

For GCE and AWS, a default *StorageClass* is created during OpenShift Container Platform installation. You can [change the default StorageClass](#) or delete it.

There are currently six plug-ins that are supported. The following sections describe the basic object definition for a *StorageClass* and specific examples for each of the supported plug-in types.

22.15.3.1. Basic StorageClass object definition

StorageClass Basic object definition

```
kind: StorageClass ❶
apiVersion: storage.k8s.io/v1 ❷
metadata:
  name: foo ❸
  annotations: ❹
  ...
provisioner: kubernetes.io/plug-in-type ❺
parameters: ❻
  param1: value
  ...
  paramN: value
```

- 1 (required) The API object type.
- 2 (required) The current apiVersion.
- 3 (required) The name of the StorageClass.
- 4 (optional) Annotations for the StorageClass
- 5 (required) The type of provisioner associated with this storage class.
- 6 (optional) The parameters required for the specific provisioner, this will change from plug-in to plug-in.

22.15.3.2. StorageClass annotations

To set a *StorageClass* as the cluster-wide default:

```
storageclass.kubernetes.io/is-default-class: "true"
```

This enables any Persistent Volume Claim (PVC) that does not specify a specific volume to automatically be provisioned through the *default* StorageClass



NOTE

Beta annotation **storageclass.beta.kubernetes.io/is-default-class** is still working. However it will be removed in a future release.

To set a *StorageClass* description:

```
kubernetes.io/description: My StorageClass Description
```

22.15.3.3. OpenStack Cinder object definition

cinder-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: gold
provisioner: kubernetes.io/cinder
parameters:
  type: fast 1
  availability: nova 2
  fsType: ext4 3
```

- 1 Volume type created in Cinder. Default is empty.
- 2 Availability Zone. If not specified, volumes are generally round-robined across all active zones where the OpenShift Container Platform cluster has a node.
- 3

File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume

22.15.3.4. AWS ElasticBlockStore (EBS) object definition

aws-ebs-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow
provisioner: kubernetes.io/aws-ebs
parameters:
  type: io1 ❶
  zone: us-east-1d ❷
  iopsPerGB: "10" ❸
  encrypted: "true" ❹
  kmsKeyId: keyvalue ❺
  fsType: ext4 ❻
```

- ❶ Select from **io1**, **gp2**, **sc1**, **st1**. The default is **gp2**. See [AWS documentation](#) for valid Amazon Resource Name (ARN) values.
- ❷ AWS zone. If no zone is specified, volumes are generally round-robin across all active zones where the OpenShift Container Platform cluster has a node. Zone and zones parameters must not be used at the same time.
- ❸ Only for **io1** volumes. I/O operations per second per GiB. The AWS volume plug-in multiplies this with the size of the requested volume to compute IOPS of the volume. The value cap is 20,000 IOPS, which is the maximum supported by AWS. See [AWS documentation](#) for further details.
- ❹ Denotes whether to encrypt the EBS volume. Valid values are **true** or **false**.
- ❺ Optional. The full ARN of the key to use when encrypting the volume. If none is supplied, but **encrypted** is set to **true**, then AWS generates a key. See [AWS documentation](#) for a valid ARN value.
- ❻ File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is **ext4**.

22.15.3.5. GCE PersistentDisk (gcePD) object definition

gce-pd-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow
provisioner: kubernetes.io/gce-pd
parameters:
```

```

type: pd-standard ❶
zone: us-central1-a ❷
zones: us-central1-a, us-central1-b, us-east1-b ❸
fsType: ext4 ❹

```

- ❶ Select either **pd-standard** or **pd-ssd**. The default is **pd-ssd**.
- ❷ GCE zone. If no zone is specified, volumes are generally round-robin across all active zones where the OpenShift Container Platform cluster has a node. Zone and zones parameters must not be used at the same time.
- ❸ A comma-separated list of GCE zone(s). If no zone is specified, volumes are generally round-robin across all active zones where the OpenShift Container Platform cluster has a node. Zone and zones parameters must not be used at the same time.
- ❹ File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is **ext4**.

22.15.3.6. GlusterFS object definition

glusterfs-storageclass.yaml

```

kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow
provisioner: kubernetes.io/glusterfs
parameters:
  resturl: "http://127.0.0.1:8081" ❶
  restuser: "admin" ❷
  secretName: "heketi-secret" ❸
  secretNamespace: "default" ❹
  gidMin: "40000" ❺
  gidMax: "50000" ❻

```

- ❶ Gluster REST service/Heketi service URL that provisions Gluster volumes on demand. The general format should be **{http/https}://{IPaddress}:{Port}**. This is a mandatory parameter for the GlusterFS dynamic provisioner. If the Heketi service is exposed as a routable service in the OpenShift Container Platform, it will have a resolvable fully qualified domain name and Heketi service URL. For additional information and configuration, See [Container-Native Storage for OpenShift Container Platform](#).
- ❷ Gluster REST service/Heketi user who has access to create volumes in the Gluster Trusted Pool.
- ❸ Identification of a Secret instance that contains a user password to use when talking to the Gluster REST service. Optional; an empty password will be used when both **secretNamespace** and **secretName** are omitted. The provided secret must be of type **"kubernetes.io/glusterfs"**.
- ❹ The namespace of mentioned **secretName**. Optional; an empty password will be used when both **secretNamespace** and **secretName** are omitted. The provided secret must be of type **"kubernetes.io/glusterfs"**.

- 5 Optional. The minimum value of GID range for the storage class.
- 6 Optional. The maximum value of GID range for the storage class.

When the **gidMin** and **gidMax** values are not specified, the volume is provisioned with a value between 2000 and 2147483647, which are defaults for **gidMin** and **gidMax** respectively. If specified, a unique value (GID) in this range (**gidMin-gidMax**) is used for dynamically provisioned volumes. The GID of the provisioned volume will be set to this value. It is required to run Heketi version 3 or later to make use of this feature. This GID is released from the pool when the subjected volume is deleted. The GID pool is per storage class, if 2 or more storage classes have GID ranges that overlap there will be duplicate GIDs dispatched by the provisioner.

When the persistent volumes are dynamically provisioned, the Gluster plug-in automatically creates an endpoint and a headless service of the name **gluster-dynamic-**<claimname>****. When the persistent volume claim is deleted, this dynamic endpoint and service is deleted automatically.

Example of a Secret

```
apiVersion: v1
kind: Secret
metadata:
  name: heketi-secret
  namespace: default
data:
  # base64 encoded password. E.g.: echo -n "mypassword" | base64
  key: bXlwYXNzd29yZA==
type: kubernetes.io/glusterfs
```

22.15.3.7. Ceph RBD object definition

ceph-storageclass.yaml

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: fast
provisioner: kubernetes.io/rbd
parameters:
  monitors: 10.16.153.105:6789 1
  adminId: admin 2
  adminSecretName: ceph-secret 3
  adminSecretNamespace: kube-system 4
  pool: kube 5
  userId: kube 6
  userSecretName: ceph-secret-user 7
  fsType: ext4 8
```

- 1 Ceph monitors, comma-delimited. It is required.
- 2 Ceph client ID that is capable of creating images in the pool. Default is "admin".
- 3 Secret Name for **adminId**. It is required. The provided secret must have type "kubernetes.io/rbd".

- 4 The namespace for **adminSecret**. Default is "default".
- 5 Ceph RBD pool. Default is "rbd".
- 6 Ceph client ID that is used to map the Ceph RBD image. Default is the same as **adminId**.
- 7 The name of Ceph Secret for **userId** to map Ceph RBD image. It must exist in the same namespace as PVCs. It is required.
- 8 File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is **ext4**.

22.15.3.8. Trident object definition

trident.yaml

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: gold
provisioner: netapp.io/trident 1
parameters: 2
  media: "ssd"
  provisioningType: "thin"
  snapshots: "true"
```

Trident uses the parameters as selection criteria for the different pools of storage that are registered with it. Trident itself is configured separately.

- 1 For more information about installing Trident with OpenShift Container Platform, see the [Trident documentation](#).
- 2 For more information about supported parameters, see the [storage attributes](#) section of the Trident documentation.

22.15.3.9. VMware vSphere object definition

vsphere-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1beta1
metadata:
  name: slow
provisioner: kubernetes.io/vsphere-volume 1
parameters:
  diskformat: thin 2
```

- 1 For more information about using VMWare vSphere with OpenShift Container Platform, see the [VMWare vSphere documentation](#).

2

diskformat: **thin**, **zeroedthick** and **eagerzeroedthick**. See vSphere docs for details.


Default: **thin**

22.15.3.10. Azure Disk object definition

azure-advanced-disk-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow
provisioner: kubernetes.io/azure-disk
parameters:
  storageAccount: azure_storage_account_name ❶
  storageaccounttype: Standard_LRS ❷
  kind: Dedicated ❸
```

- ❶ Azure storage account name. This must reside in the same resource group as the cluster. If a storage account is specified, the **location** is ignored. If a storage account is not specified, a new storage account gets created in the same resource group as the cluster. If you are specifying a **storageAccount**, the value for **kind** must be **Dedicated**.
- ❷ Azure storage account SKU tier. Default is empty. **Note:** Premium VM can attach both *Standard_LRS* and *Premium_LRS* disks, Standard VM can only attach *Standard_LRS* disks, Managed VM can only attach managed disks, and unmanaged VM can only attach unmanaged disks.
- ❸ Possible values are **Shared** (default), **Dedicated**, and **Managed**.
 - a. If **kind** is set to **Shared**, Azure creates all unmanaged disks in a few shared storage accounts in the same resource group as the cluster.
 - b. If **kind** is set to **Managed**, Azure creates new managed disks.
 - c. If **kind** is set to **Dedicated** and a **storageAccount** is specified, Azure uses the specified storage account for the new unmanaged disk in the same resource group as the cluster. For this to work:
 - The specified storage account must be in the same region.
 - Azure Cloud Provider must have a write access to the storage account.
 - d. If **kind** is set to **Dedicated** and a **storageAccount** is not specified, Azure creates a new dedicated storage account for the new unmanaged disk in the same resource group as the cluster.



IMPORTANT

Azure StorageClass is revised in OpenShift Container Platform version 3.7. If you upgraded from a previous version, either:

- specify the property **kind: dedicated** to continue using the Azure StorageClass created before the upgrade. Or,
- add the location parameter (for example, "**location**": "**southcentralus**",) in the **azure.conf** file to use the default property **kind: shared**. Doing this creates new storage accounts for future use.

22.15.4. Changing the default StorageClass

If you are using GCE and AWS, use the following process to change the default StorageClass:

1. List the StorageClass:

```
$ oc get storageclass
```

NAME	TYPE
gp2 (default)	kubernetes.io/aws-ebs 1
standard	kubernetes.io/gce-pd

1 (default) denotes the default StorageClass.

2. Change the value of the annotation **storageclass.kubernetes.io/is-default-class** to **false** for the default StorageClass:

```
$ oc patch storageclass gp2 -p '{"metadata": {"annotations": \
{"storageclass.kubernetes.io/is-default-class": "false"}}}'
```

3. Make another StorageClass the default by adding or modifying the annotation as **storageclass.kubernetes.io/is-default-class=true**.

```
$ oc patch storageclass standard -p '{"metadata": {"annotations": \
{"storageclass.kubernetes.io/is-default-class": "true"}}}'
```

4. Verify the changes:

```
$ oc get storageclass
```

NAME	TYPE
gp2	kubernetes.io/aws-ebs
standard (default)	kubernetes.io/gce-pd

22.15.5. Additional information and examples

- [Examples and uses of StorageClasses for Dynamic Provisioning](#)
- [Examples and uses of StorageClasses without Dynamic Provisioning](#)

22.16. VOLUME SECURITY

22.16.1. Overview

This topic provides a general guide on pod security as it relates to volume security. For information on pod-level security in general, see [Managing Security Context Constraints \(SCC\)](#) and the [Security Context Constraint](#) concept topic. For information on the OpenShift Container Platform persistent volume (PV) framework in general, see the [Persistent Storage](#) concept topic.

Accessing persistent storage requires coordination between the cluster and/or storage administrator and the end developer. The cluster administrator creates PVs, which abstract the underlying physical storage. The developer creates pods and, optionally, PVCs, which bind to PVs, based on matching criteria, such as capacity.

Multiple persistent volume claims (PVCs) within the same project can bind to the same PV. However, once a PVC binds to a PV, that PV cannot be bound by a claim outside of the first claim's project. If the underlying storage needs to be accessed by multiple projects, then each project needs its own PV, which can point to the same physical storage. In this sense, a bound PV is tied to a project. For a detailed PV and PVC example, see the guide for [WordPress and MySQL using NFS](#).

For the cluster administrator, granting pods access to PVs involves:

- knowing the group ID and/or user ID assigned to the actual storage,
- understanding SELinux considerations, and
- ensuring that these IDs are allowed in the range of legal IDs defined for the project and/or the SCC that matches the requirements of the pod.

Group IDs, the user ID, and SELinux values are defined in the **SecurityContext** section in a pod definition. Group IDs are global to the pod and apply to all containers defined in the pod. User IDs can also be global, or specific to each container. Four sections control access to volumes:

- [supplementalGroups](#)
- [fsGroup](#)
- [runAsUser](#)
- [seLinuxOptions](#)

22.16.2. SCCs, Defaults, and Allowed Ranges

SCCs influence whether or not a pod is given a default user ID, **fsGroup** ID, supplemental group ID, and SELinux label. They also influence whether or not IDs supplied in the pod definition (or in the image) will be validated against a range of allowable IDs. If validation is required and fails, then the pod will also fail.

SCCs define strategies, such as **runAsUser**, **supplementalGroups**, and **fsGroup**. These strategies help decide whether the pod is authorized. Strategy values set to **RunAsAny** are essentially stating that the pod can do what it wants regarding that strategy. Authorization is skipped for that strategy and no OpenShift Container Platform default is produced based on that strategy. Therefore, IDs and SELinux labels in the resulting container are based on container defaults instead of OpenShift Container Platform policies.

For a quick summary of **RunAsAny**:

- Any ID defined in the pod definition (or image) is allowed.
- Absence of an ID in the pod definition (and in the image) results in the container assigning an ID, which is **root** (0) for Docker.
- No SELinux labels are defined, so Docker will assign a unique label.

For these reasons, SCCs with **RunAsAny** for ID-related strategies should be protected so that ordinary developers do not have access to the SCC. On the other hand, SCC strategies set to **MustRunAs** or **MustRunAsRange** trigger ID validation (for ID-related strategies), and cause default values to be supplied by OpenShift Container Platform to the container when those values are not supplied directly in the pod definition or image.

CAUTION

Allowing access to SCCs with a **RunAsAny FSGroup** strategy can also prevent users from accessing their block devices. Pods need to specify an **fsGroup** in order to take over their block devices. Normally, this is done when the SCC **FSGroup** strategy is set to **MustRunAs**. If a user's pod is assigned an SCC with a **RunAsAny FSGroup** strategy, then the user may face **permission denied** errors until they discover that they need to specify an **fsGroup** themselves.

SCCs may define the range of allowed IDs (user or groups). If range checking is required (for example, using **MustRunAs**) and the allowable range is not defined in the SCC, then the project determines the ID range. Therefore, projects support ranges of allowable ID. However, unlike SCCs, projects do not define strategies, such as **runAsUser**.

Allowable ranges are helpful not only because they define the boundaries for container IDs, but also because the minimum value in the range becomes the default value for the ID in question. For example, if the SCC ID strategy value is **MustRunAs**, the minimum value of an ID range is **100**, and the ID is absent from the pod definition, then 100 is provided as the default for this ID.

As part of pod admission, the SCCs available to a pod are examined (roughly, in priority order followed by most restrictive) to best match the requests of the pod. Setting a SCC's strategy type to **RunAsAny** is less restrictive, whereas a type of **MustRunAs** is more restrictive. All of these strategies are evaluated. To see which SCC was assigned to a pod, use the **oc get pod** command:

```
# oc get pod <pod_name> -o yaml
...
metadata:
  annotations:
    openshift.io/scc: nfs-scc ❶
  name: nfs-pod1 ❷
  namespace: default ❸
...
```

- ❶ Name of the SCC that the pod used (in this case, a custom SCC).
- ❷ Name of the pod.
- ❸ Name of the project. "Namespace" is interchangeable with "project" in OpenShift Container Platform. See [Projects and Users](#) for details.

It may not be immediately obvious which SCC was matched by a pod, so the command above can be very useful in understanding the UID, supplemental groups, and SELinux relabeling in a live container.

Any SCC with a strategy set to **RunAsAny** allows specific values for that strategy to be defined in the pod definition (and/or image). When this applies to the user ID (**runAsUser**) it is prudent to restrict access to the SCC to prevent a container from being able to run as root.

Because pods often match the **restricted** SCC, it is worth knowing the security this entails. The **restricted** SCC has the following characteristics:

- User IDs are constrained due to the **runAsUser** strategy being set to **MustRunAsRange**. This forces user ID validation.
- Because a range of allowable user IDs is not defined in the SCC (see **oc export scc restricted** for more details), the project's **openshift.io/sa.scc.uid-range** range will be used for range checking and for a default ID, if needed.
- A default user ID is produced when a user ID is not specified in the pod definition and the matching SCC's **runAsUser** is set to **MustRunAsRange**.
- An SELinux label is required (**seLinuxContext** set to **MustRunAs**), which uses the project's default MCS label.
- **fsGroup** IDs are constrained to a single value due to the **FSGroup** strategy being set to **MustRunAs**, which dictates that the value to use is the minimum value of the first range specified.
- Because a range of allowable **fsGroup** IDs is not defined in the SCC, the minimum value of the project's **openshift.io/sa.scc.supplemental-groups** range (or the same range used for user IDs) will be used for validation and for a default ID, if needed.
- A default **fsGroup** ID is produced when a **fsGroup** ID is not specified in the pod and the matching SCC's **FSGroup** is set to **MustRunAs**.
- Arbitrary supplemental group IDs are allowed because no range checking is required. This is a result of the **supplementalGroups** strategy being set to **RunAsAny**.
- Default supplemental groups are not produced for the running pod due to **RunAsAny** for the two group strategies above. Therefore, if no groups are defined in the pod definition (or in the image), the container(s) will have no supplemental groups predefined.

The following shows the **default** project and a custom SCC (**my-custom-scc**), which summarizes the interactions of the SCC and the project:

```
$ oc get project default -o yaml ❶
...
metadata:
  annotations: ❷
    openshift.io/sa.scc.mcs: s0:c1,c0 ❸
    openshift.io/sa.scc.supplemental-groups: 1000000000/10000 ❹
    openshift.io/sa.scc.uid-range: 1000000000/10000 ❺

$ oc get scc my-custom-scc -o yaml
...
fsGroup:
  type: MustRunAs ❻
  ranges:
    - min: 5000
```

```

    max: 6000
runAsUser:
  type: MustRunAsRange 7
  uidRangeMin: 1000100000
  uidRangeMax: 1000100999
seLinuxContext: 8
  type: MustRunAs
  SELinuxOptions: 9
    user: <selinux-user-name>
    role: ...
    type: ...
    level: ...
supplementalGroups:
  type: MustRunAs 10
  ranges:
    - min: 5000
      max: 6000

```

- 1 **default** is the name of the project.
- 2 Default values are only produced when the corresponding SCC strategy is not **RunAsAny**.
- 3 SELinux default when not defined in the pod definition or in the SCC.
- 4 Range of allowable group IDs. ID validation only occurs when the SCC strategy is **RunAsAny**. There can be more than one range specified, separated by commas. See below for [supported formats](#).
- 5 Same as <4> but for user IDs. Also, only a single range of user IDs is supported.
- 6 10 **MustRunAs** enforces group ID range checking and provides the container's groups default. Based on this SCC definition, the default is 5000 (the minimum ID value). If the range was omitted from the SCC, then the default would be 1000000000 (derived from the project). The other supported type, **RunAsAny**, does not perform range checking, thus allowing any group ID, and produces no default groups.
- 7 **MustRunAsRange** enforces user ID range checking and provides a UID default. Based on this SCC, the default UID is 1000100000 (the minimum value). If the minimum and maximum range were omitted from the SCC, the default user ID would be 1000000000 (derived from the project). **MustRunAsNonRoot** and **RunAsAny** are the other supported types. The range of allowed IDs can be defined to include any user IDs required for the target storage.
- 8 When set to **MustRunAs**, the container is created with the SCC's SELinux options, or the MCS default defined in the project. A type of **RunAsAny** indicates that SELinux context is not required, and, if not defined in the pod, is not set in the container.
- 9 The SELinux user name, role name, type, and labels can be defined here.

Two formats are supported for allowed ranges:

1. **M/N**, where **M** is the starting ID and **N** is the count, so the range becomes **M** through (and including) **M+N - 1**.

2. **M-N**, where **M** is again the starting ID and **N** is the ending ID. The default group ID is the starting ID in the first range, which is **1000000000** in this project. If the SCC did not define a minimum group ID, then the project's default ID is applied.

22.16.3. Supplemental Groups



NOTE

Read [SCCs, Defaults, and Allowed Ranges](#) before working with supplemental groups.

TIP

It is generally preferable to use group IDs (supplemental or [fsGroup](#)) to gain access to persistent storage versus using [user IDs](#).

Supplemental groups are regular Linux groups. When a process runs in Linux, it has a UID, a GID, and one or more supplemental groups. These attributes can be set for a container's main process. The **supplementalGroups** IDs are typically used for controlling access to shared storage, such as NFS and GlusterFS, whereas [fsGroup](#) is used for controlling access to block storage, such as Ceph RBD and iSCSI.

The OpenShift Container Platform shared storage plug-ins mount volumes such that the POSIX permissions on the mount match the permissions on the target storage. For example, if the target storage's owner ID is **1234** and its group ID is **5678**, then the mount on the host node and in the container will have those same IDs. Therefore, the container's main process must match one or both of those IDs in order to access the volume.

For example, consider the following NFS export.

On an OpenShift Container Platform node:



NOTE

showmount requires access to the ports used by **rpcbind** and **rpc.mount** on the NFS server

```
# showmount -e <nfs-server-ip-or-hostname>
Export list for f21-nfs.vm:
/opt/nfs *
```

On the NFS server:

```
# cat /etc/exports
/opt/nfs *(rw,sync,root_squash)
...

# ls -lZ /opt/nfs -d
drwx----- . 1000100001 5555 unconfined_u:object_r:usr_t:s0 /opt/nfs
```

The **/opt/nfs/** export is accessible by UID **1000100001** and the group **5555**. In general, containers should not run as root. So, in this NFS example, containers which are not run as UID **1000100001** and are not members the group **5555** will not have access to the NFS export.

Often, the SCC matching the pod does not allow a specific user ID to be specified, thus using supplemental groups is a more flexible way to grant storage access to a pod. For example, to grant NFS access to the export above, the group **5555** can be defined in the pod definition:

```
apiVersion: v1
kind: Pod
...
spec:
  containers:
    - name: ...
      volumeMounts:
        - name: nfs 1
          mountPath: /usr/share/... 2
      securityContext: 3
        supplementalGroups: [5555] 4
  volumes:
    - name: nfs 5
      nfs:
        server: <nfs_server_ip_or_host>
        path: /opt/nfs 6
```

- 1** Name of the volume mount. Must match the name in the **volumes** section.
- 2** NFS export path as seen in the container.
- 3** Pod global security context. Applies to all containers inside the pod. Each container can also define its **securityContext**, however group IDs are global to the pod and cannot be defined for individual containers.
- 4** Supplemental groups, which is an array of IDs, is set to 5555. This grants group access to the export.
- 5** Name of the volume. Must match the name in the **volumeMounts** section.
- 6** Actual NFS export path on the NFS server.

All containers in the above pod (assuming the matching SCC or project allows the group **5555**) will be members of the group **5555** and have access to the volume, regardless of the container's user ID. However, the assumption above is critical. Sometimes, the SCC does not define a range of allowable group IDs but instead requires group ID validation (a result of **supplementalGroups** set to **MustRunAs**). Note that this is **not** the case for the **restricted** SCC. The project will not likely allow a group ID of **5555**, unless the project has been customized to access this NFS export. So, in this scenario, the above pod will fail because its group ID of **5555** is not within the SCC's or the project's range of allowed group IDs.

Supplemental Groups and Custom SCCs

To remedy the situation in [the previous example](#), a custom SCC can be created such that:

- a minimum and max group ID are defined,
- ID range checking is enforced, and
- the group ID of **5555** is allowed.

It is often better to create a new SCC rather than modifying a predefined SCC, or changing the range of allowed IDs in the predefined projects.


The easiest way to create a new SCC is to export an existing SCC and customize the YAML file to meet the requirements of the new SCC. For example:

1. Use the **restricted** SCC as a template for the new SCC:

```
$ oc export scc restricted > new-scc.yaml
```

2. Edit the **new-scc.yaml** file to your desired specifications.
3. Create the new SCC:

```
$ oc create -f new-scc.yaml
```



NOTE

The **oc edit scc** command can be used to modify an instantiated SCC.

Here is a fragment of a new SCC named **nfs-scc**:


```
$ oc export scc nfs-scc

allowHostDirVolumePlugin: false ❶
...
kind: SecurityContextConstraints
metadata:
  ...
  name: nfs-scc ❷
priority: 9 ❸
...
supplementalGroups:
  type: MustRunAs ❹
  ranges:
    - min: 5000 ❺
      max: 6000
  ...
```

- ❶ The **allow** booleans are the same as for the **restricted** SCC.
- ❷ Name of the new SCC.
- ❸ Numerically larger numbers have greater priority. Nil or omitted is the lowest priority. Higher priority SCCs sort before lower priority SCCs and thus have a better chance of matching a new pod.
- ❹ **supplementalGroups** is a strategy and it is set to **MustRunAs**, which means group ID checking is required.
- ❺ Multiple ranges are supported. The allowed group ID range here is 5000 through 5999, with the default supplemental group being 5000.

When the same pod shown earlier runs against this new SCC (assuming, of course, the pod matches the new SCC), it will start because the group **5555**, supplied in the pod definition, is now allowed by the custom SCC.

22.16.4. fsGroup



NOTE

Read [SCCs, Defaults, and Allowed Ranges](#) before working with supplemental groups.

TIP

It is generally preferable to use group IDs ([supplemental](#) or **fsGroup**) to gain access to persistent storage versus using [user IDs](#).

fsGroup defines a pod's "file system group" ID, which is added to the container's supplemental groups. The **supplementalGroups** ID applies to shared storage, whereas the **fsGroup** ID is used for block storage.

Block storage, such as Ceph RBD, iSCSI, and various cloud storage, is typically dedicated to a single pod which has requested the block storage volume, either directly or using a PVC. Unlike shared storage, block storage is taken over by a pod, meaning that user and group IDs supplied in the pod definition (or image) are applied to the actual, physical block device. Typically, block storage is not shared.

A **fsGroup** definition is shown below in the following pod definition fragment:

```
kind: Pod
...
spec:
  containers:
  - name: ...
    securityContext: ①
      fsGroup: 5555 ②
  ...
```

- ① As with **supplementalGroups**, **fsGroup** must be defined globally to the pod, not per container.
- ② 5555 will become the group ID for the volume's group permissions and for all new files created in the volume.

As with **supplementalGroups**, all containers in the above pod (assuming the matching SCC or project allows the group **5555**) will be members of the group **5555**, and will have access to the block volume, regardless of the container's user ID. If the pod matches the **restricted** SCC, whose **fsGroup** strategy is **MustRunAs**, then the pod will fail to run. However, if the SCC has its **fsGroup** strategy set to **RunAsAny**, then any **fsGroup** ID (including **5555**) will be accepted. Note that if the SCC has its **fsGroup** strategy set to **RunAsAny** and no **fsGroup** ID is specified, the "taking over" of the block storage does not occur and permissions may be denied to the pod.

fsGroups and Custom SCCs

To remedy the situation in the previous example, a custom SCC can be created such that:

- a minimum and maximum group ID are defined,
- ID range checking is enforced, and
- the group ID of **5555** is allowed.

It is better to create new SCCs versus modifying a predefined SCC, or changing the range of allowed IDs in the predefined projects.

Consider the following fragment of a new SCC definition:

```
# oc export scc new-scc
...
kind: SecurityContextConstraints
...
fsGroup:
  type: MustRunAs ❶
  ranges: ❷
  - max: 6000
    min: 5000 ❸
...
```

- ❶ **MustRunAs** triggers group ID range checking, whereas **RunAsAny** does not require range checking.
- ❷ The range of allowed group IDs is 5000 through, and including, 5999. Multiple ranges are supported but not used. The allowed group ID range here is 5000 through 5999, with the default **fsGroup** being 5000.
- ❸ The minimum value (or the entire range) can be omitted from the SCC, and thus range checking and generating a default value will defer to the project's **openshift.io/sa.scc.supplemental-groups** range. **fsGroup** and **supplementalGroups** use the same group field in the project; there is not a separate range for **fsGroup**.

When the pod shown above runs against this new SCC (assuming, of course, the pod matches the new SCC), it will start because the group **5555**, supplied in the pod definition, is allowed by the custom SCC. Additionally, the pod will "take over" the block device, so when the block storage is viewed by a process outside of the pod, it will actually have **5555** as its group ID.

A list of volumes supporting block ownership include:

- AWS Elastic Block Store
- OpenStack Cinder
- Ceph RBD
- GCE Persistent Disk
- iSCSI
- emptyDir
- gitRepo

**NOTE**

This list is potentially incomplete.

22.16.5. User IDs**NOTE**

Read [SCCs, Defaults, and Allowed Ranges](#) before working with supplemental groups.

TIP

It is generally preferable to use group IDs ([supplemental](#) or [fsGroup](#)) to gain access to persistent storage versus using user IDs.

User IDs can be defined in the container image or in the pod definition. In the pod definition, a single user ID can be defined globally to all containers, or specific to individual containers (or both). A user ID is supplied as shown in the pod definition fragment below:

```
spec:
  containers:
  - name: ...
    securityContext:
      runAsUser: 1000100001
```

ID 1000100001 in the above is container-specific and matches the owner ID on the export. If the NFS export's owner ID was **54321**, then that number would be used in the pod definition. Specifying **securityContext** outside of the container definition makes the ID global to all containers in the pod.

Similar to group IDs, user IDs may be validated according to policies set in the SCC and/or project. If the SCC's **runAsUser** strategy is set to **RunAsAny**, then any user ID defined in the pod definition or in the image is allowed.

**WARNING**

This means even a UID of **0** (root) is allowed.

If, instead, the **runAsUser** strategy is set to **MustRunAsRange**, then a supplied user ID will be validated against a range of allowed IDs. If the pod supplies no user ID, then the default ID is set to the minimum value of the range of allowable user IDs.

Returning to the earlier [NFS example](#), the container needs its UID set to **1000100001**, which is shown in the pod fragment above. Assuming the **default** project and the **restricted** SCC, the pod's requested user ID of 1000100001 will not be allowed, and therefore the pod will fail. The pod fails because:

- it requests **1000100001** as its user ID,
- all available SCCs use **MustRunAsRange** for their **runAsUser** strategy, so UID range checking is required, and

- **1000100001** is not included in the SCC or in the project's user ID range.

To remedy this situation, a new SCC can be created with the appropriate user ID range. A new project could also be created with the appropriate user ID range defined. There are also other, less-preferred options:

- The **restricted** SCC could be modified to include **1000100001** within its minimum and maximum user ID range. This is not recommended as you should avoid modifying the predefined SCCs if possible.
- The **restricted** SCC could be modified to use **RunAsAny** for the **runAsUser** value, thus eliminating ID range checking. This is *strongly* not recommended, as containers could run as root.
- The **default** project's UID range could be changed to allow a user ID of **1000100001**. This is not generally advisable because only a single range of user IDs can be specified, and thus other pods may not run if the range is altered.

User IDs and Custom SCCs

It is good practice to avoid modifying the predefined SCCs if possible. The preferred approach is to create a custom SCC that better fits an organization's security needs, or [create a new project](#) that supports the desired user IDs.

To remedy the situation in the previous example, a custom SCC can be created such that:

- a minimum and maximum user ID is defined,
- UID range checking is still enforced, and
- the UID of **1000100001** is allowed.

For example:

```
$ oc export scc nfs-scc

allowHostDirVolumePlugin: false ❶
...
kind: SecurityContextConstraints
metadata:
  ...
  name: nfs-scc ❷
priority: 9 ❸
requiredDropCapabilities: null
runAsUser:
  type: MustRunAsRange ❹
  uidRangeMax: 1000100001 ❺
  uidRangeMin: 1000100001
...
```

- ❶ The **allowXX** bools are the same as for the **restricted** SCC.
- ❷ The name of this new SCC is **nfs-scc**.
- ❸ Numerically larger numbers have greater priority. Nil or omitted is the lowest priority. Higher priority SCCs sort before lower priority SCCs, and thus have a better chance of matching a new pod.

- 4 The **runAsUser** strategy is set to **MustRunAsRange**, which means UID range checking is enforced.
- 5 The UID range is 1000100001 through 1000100001 (a range of one value).

Now, with **runAsUser: 1000100001** shown in the previous pod definition fragment, the pod matches the new **nfs-scc** and is able to run with a UID of 1000100001.

22.16.6. SELinux Options

All predefined SCCs, except for the **privileged** SCC, set the **seLinuxContext** to **MustRunAs**. So the SCCs most likely to match a pod's requirements will force the pod to use an SELinux policy. The SELinux policy used by the pod can be defined in the pod itself, in the image, in the SCC, or in the project (which provides the default).

SELinux labels can be defined in a pod's **securityContext.seLinuxOptions** section, and supports **user**, **role**, **type**, and **level**:



NOTE

Level and MCS label are used interchangeably in this topic.

```
...
securityContext: 1
  seLinuxOptions:
    level: "s0:c123,c456" 2
...
```

- 1 **level** can be defined globally for the entire pod, or individually for each container.
- 2 SELinux level label.

Here are fragments from an SCC and from the **default** project:

```
$ oc export scc scc-name
...
seLinuxContext:
  type: MustRunAs 1

# oc export project default
...
metadata:
  annotations:
    openshift.io/sa.scc.mcs: s0:c1,c0 2
...
```

- 1 **MustRunAs** causes volume relabeling.
- 2 If the label is not provided in the pod or in the SCC, then the default comes from the project.

All predefined SCCs, except for the **privileged** SCC, set the **seLinuxContext** to **MustRunAs**. This forces pods to use MCS labels, which can be defined in the pod definition, the image, or provided as a default.

The SCC determines whether or not to require an SELinux label and can provide a default label. If the **seLinuxContext** strategy is set to **MustRunAs** and the pod (or image) does not define a label, OpenShift Container Platform defaults to a label chosen from the SCC itself or from the project.

If **seLinuxContext** is set to **RunAsAny**, then no default labels are provided, and the container determines the final label. In the case of Docker, the container will use a unique MCS label, which will not likely match the labeling on existing storage mounts. Volumes which support SELinux management will be relabeled so that they are accessible by the specified label and, depending on how exclusionary the label is, only that label.

This means two things for unprivileged containers:

- The volume is given a type that is accessible by unprivileged containers. This type is usually **container_file_t** in Red Hat Enterprise Linux (RHEL) version 7.5 and later. This type treats volumes as container content. In previous RHEL versions, RHEL 7.4, 7.3, and so forth, the volume is given the **svirt_sandbox_file_t** type.
- If a **level** is specified, the volume is labeled with the given MCS label.

For a volume to be accessible by a pod, the pod must have both categories of the volume. So a pod with **s0:c1,c2** will be able to access a volume with **s0:c1,c2**. A volume with **s0** will be accessible by all pods.

If pods fail authorization, or if the storage mount is failing due to permissions errors, then there is a possibility that SELinux enforcement is interfering. One way to check for this is to run:

```
# ausearch -m avc --start recent
```

This examines the log file for AVC (Access Vector Cache) errors.

22.17. SELECTOR-LABEL VOLUME BINDING

22.17.1. Overview

This guide provides the steps necessary to enable binding of persistent volume claims (PVCs) to persistent volumes (PVs) via **selector** and **label** attributes. By implementing selectors and labels, regular users are able to target [provisioned storage](#) by identifiers defined by a cluster administrator.

22.17.2. Motivation

In cases of statically provisioned storage, developers seeking persistent storage are required to know a handful identifying attributes of a PV in order to deploy and bind a PVC. This creates several problematic situations. Regular users might have to contact a cluster administrator to either deploy the PVC or provide the PV values. PV attributes alone do not convey the intended use of the storage volumes, nor do they provide methods by which volumes can be grouped.

Selector and label attributes can be used to abstract away PV details from the user while providing cluster administrators a way of identifying volumes by a descriptive and customizable tag. Through the selector-label method of binding, users are only required to know which labels are defined by the administrator.

**NOTE**

The selector-label feature is currently only available for *statically* provisioned storage and is currently not implemented for storage provisioned dynamically.

22.17.3. Deployment

This section reviews how to define and deploy PVCs.

22.17.3.1. Prerequisites

1. A running OpenShift Container Platform 3.3+ cluster
2. A volume provided by a supported [storage provider](#)
3. A user with a cluster-admin role binding

22.17.3.2. Define the Persistent Volume and Claim

1. As the **cluster-admin** user, define the PV. For this example, we will be using a [GlusterFS](#) volume. See the appropriate [storage provider](#) for your provider's configuration.

Example 22.9. Persistent Volume with Labels

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-volume
  labels: 1
    volume-type: ssd
    aws-availability-zone: us-east-1
spec:
  capacity:
    storage: 2Gi
  accessModes:
    - ReadWriteMany
  glusterfs:
    endpoints: glusterfs-cluster
    path: myVol1
    readOnly: false
  persistentVolumeReclaimPolicy: Recycle
```

- 1** A PVC whose selectors match *all* of a PV's labels will be bound, assuming a PV is available.

2. Define the PVC:

Example 22.10. Persistent Volume Claim with Selectors

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim
spec:
```



```

accessModes:
- ReadWriteMany
resources:
  requests:
    storage: 1Gi
selector: ❶
  matchLabels: ❷
    volume-type: ssd
    aws-availability-zone: us-east-1

```

❶ Begin **selectors** section.

❷ List all labels by which the user is requesting storage. Must match *all* labels of targeted PV.

22.17.3.3. Deploy the Persistent Volume and Claim

As the **cluster-admin** user, create the persistent volume:

Example 22.11. Create the Persistent Volume

```

# oc create -f gluster-pv.yaml
persistentVolume "gluster-volume" created

# oc get pv
NAME                                LABELS      CAPACITY    ACCESSMODES  STATUS
CLAIM      REASON      AGE
gluster-volume      map[]      2147483648  RWX
Available                                     2s

```

Once the PV is created, any user whose selectors match *all* its labels can create their PVC.

Example 22.12. Create the Persistent Volume Claim

```

# oc create -f gluster-pvc.yaml
persistentVolumeClaim "gluster-claim" created
# oc get pvc
NAME            LABELS      STATUS    VOLUME
gluster-claim      Bound      gluster-volume

```

22.18. ENABLING CONTROLLER-MANAGED ATTACHMENT AND DETACHMENT

22.18.1. Overview

As of OpenShift Container Platform 3.4, administrators can enable the controller running on the cluster's master to manage volume attach and detach operations on behalf of a set of nodes, as opposed to letting them manage their own volume attach and detach operations.

Enabling controller-managed attachment and detachment has the following benefits:

- If a node is lost, volumes that were attached to it can be detached by the controller and reattached elsewhere.
- Credentials for attaching and detaching do not need to be made present on every node, improving security.

As of OpenShift Container Platform 3.6, controller-managed attachment and detachment is the default setting.

22.18.2. Determining What Is Managing Attachment and Detachment

If a node has set the annotation `volumes.kubernetes.io/controller-managed-attach-detach` on itself, then its attach and detach operations are being managed by the controller. The controller will automatically inspect all nodes for this annotation and act according to whether it is present or not. Therefore, you may inspect the node for this annotation to determine if it has enabled controller-managed attach and detach.

To further ensure that the node is opting for controller-managed attachment and detachment, its logs can be searched for the following line:

```
Setting node annotation to enable volume controller attach/detach
```

If the above line is not found, the logs should instead contain:

```
Controller attach/detach is disabled for this node; Kubelet will attach and detach volumes
```

To check from the controller's end that it is managing a particular node's attach and detach operations, the logging level must first be set to at least **4**. Then, the following line should be found:

```
processVolumesInUse for node <node_hostname>
```

For information on how to view logs and configure logging levels, see [Configuring Logging Levels](#).

22.18.3. Configuring Nodes to Enable Controller-managed Attachment and Detachment

Enabling controller-managed attachment and detachment is done by configuring individual nodes to opt in and disable their own node-level attachment and detachment management. See [Node Configuration Files](#) for information on what node configuration file to edit and add the following:

```
kubeletArguments:
  enable-controller-attach-detach:
    - "true"
```

Once a node is configured, it must be restarted for the setting to take effect.

CHAPTER 23. PERSISTENT STORAGE EXAMPLES

23.1. OVERVIEW

The following sections provide detailed, comprehensive instructions on setting up and configuring common storage use cases. These examples cover both the administration of persistent volumes and their security, and how to claim against the volumes as a user of the system.


- [Sharing an NFS PV Across Two Pods](#)
- [Ceph-RBD Block Storage Volume](#)
- [Shared Storage Using a GlusterFS Volume](#)
- [Dynamic Provisioning Storage Using GlusterFS](#)
- [Mounting a PV to Privileged Pods](#)
- [Backing Docker Registry with GlusterFS Storage](#)
- [Binding Persistent Volumes by Labels](#)
- [Using StorageClasses for Dynamic Provisioning](#)
- [Using StorageClasses for Existing Legacy Storage](#)
- [Configuring Azure Blob Storage for Integrated Docker Registry](#)

23.2. SHARING AN NFS MOUNT ACROSS TWO PERSISTENT VOLUME CLAIMS

23.2.1. Overview

The following use case describes how a cluster administrator wanting to leverage shared storage for use by two separate containers would configure the solution. This example highlights the use of NFS, but can easily be adapted to other shared storage types, such as GlusterFS. In addition, this example will show configuration of pod security as it relates to shared storage.

[Persistent Storage Using NFS](#) provides an explanation of persistent volumes (PVs), persistent volume claims (PVCs), and using NFS as persistent storage. This topic shows an end-to-end example of using an existing NFS cluster and OpenShift Container Platform persistent store, and assumes an existing NFS server and exports exist in your OpenShift Container Platform infrastructure.



NOTE

All **oc** commands are executed on the OpenShift Container Platform master host.

23.2.2. Creating the Persistent Volume

Before creating the PV object in OpenShift Container Platform, the persistent volume (PV) file is defined:

Example 23.1. Persistent Volume Object Definition Using NFS

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: nfs-pv ❶
spec:
  capacity:
    storage: 1Gi ❷
  accessModes:
    - ReadWriteMany ❸
  persistentVolumeReclaimPolicy: Retain ❹
  nfs: ❺
    path: /opt/nfs ❻
    server: nfs.f22 ❼
    readOnly: false

```

- ❶ The name of the PV, which is referenced in pod definitions or displayed in various **oc** volume commands.
- ❷ The amount of storage allocated to this volume.
- ❸ **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control.
- ❹ The volume reclaim policy **Retain** indicates that the volume will be preserved after the pods accessing it terminates.
- ❺ This defines the volume type being used, in this case the **NFS** plug-in.
- ❻ This is the NFS mount path.
- ❼ This is the NFS server. This can also be specified by IP address.

Save the PV definition to a file, for example **nfs-pv.yaml**, and create the persistent volume:

```

# oc create -f nfs-pv.yaml
persistentvolume "nfs-pv" created

```

Verify that the persistent volume was created:

```

# oc get pv
NAME          LABELS          CAPACITY  ACCESSMODES  STATUS   CLAIM
REASON    AGE
nfs-pv    <none>         1Gi       RWX           Available
37s

```

23.2.3. Creating the Persistent Volume Claim

A persistent volume claim (PVC) specifies the desired access mode and storage capacity. Currently, based on only these two attributes, a PVC is bound to a single PV. Once a PV is bound to a PVC, that PV is essentially tied to the PVC's project and cannot be bound to by another PVC. There is a one-to-

one mapping of PVs and PVCs. However, multiple pods in the same project can use the same PVC. This is the use case we are highlighting in this example.

Example 23.2. PVC Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: nfs-pvc ❶
spec:
  accessModes:
    - ReadWriteMany ❷
  resources:
    requests:
      storage: 1Gi ❸
```

- ❶ The claim name is referenced by the pod under its **volumes** section.
- ❷ As mentioned above for PVs, the **accessModes** do not enforce access right, but rather act as labels to match a PV to a PVC.
- ❸ This claim will look for PVs offering **1Gi** or greater capacity.

Save the PVC definition to a file, for example **nfs-pvc.yaml**, and create the PVC:

```
# oc create -f nfs-pvc.yaml
persistentvolumeclaim "nfs-pvc" created
```

Verify that the PVC was created and bound to the expected PV:

```
# oc get pvc
NAME          LABELS    STATUS    VOLUME    CAPACITY    ACCESSMODES
AGE
nfs-pvc      <none>    Bound     nfs-pv     1Gi         RWX
24s
```

❶

- ❶ The claim, **nfs-pvc**, was bound to the **nfs-pv** PV.

23.2.4. Ensuring NFS Volume Access

Access is necessary to a node in the NFS server. On this node, examine the NFS export mount:

```
[root@nfs nfs]# ls -lZ /opt/nfs/
total 8
-rw-r--r--. 1 root 100003 system_u:object_r:usr_t:s0 10 Oct 12 23:27
test2b
```

❶ ❷

- 1 the owner has ID 0.
- 2 the group has ID 100003.

In order to access the NFS mount, the container must match the SELinux label, and either run with a UID of 0, or with 100003 in its supplemental groups range. Gain access to the volume by matching the NFS mount's groups, which will be defined in the pod definition below.

By default, SELinux does not allow writing from a pod to a remote NFS server. To enable writing to NFS volumes with SELinux enforcing on each node, run:

```
# setsebool -P virt_use_nfs on
```

23.2.5. Creating the Pod

A pod definition file or a template file can be used to define a pod. Below is a pod specification that creates a single container and mounts the NFS volume for read-write access:

Example 23.3. Pod Object Definition

```
apiVersion: v1
kind: Pod
metadata:
  name: hello-openshift-nfs-pod 1
  labels:
    name: hello-openshift-nfs-pod
spec:
  containers:
    - name: hello-openshift-nfs-pod
      image: openshift/hello-openshift 2
      ports:
        - name: web
          containerPort: 80
      volumeMounts:
        - name: nfsvol 3
          mountPath: /usr/share/nginx/html 4
  securityContext:
    supplementalGroups: [100003] 5
    privileged: false
  volumes:
    - name: nfsvol
      persistentVolumeClaim:
        claimName: nfs-pvc 6
```

- 1 The name of this pod as displayed by `oc get pod`.
- 2 The image run by this pod.
- 3 The name of the volume. This name must be the same in both the **containers** and **volumes** sections.
- 4 The mount path as seen in the container.

- 5 The group ID to be assigned to the container.
- 6 The PVC that was created in the previous step.

Save the pod definition to a file, for example *nfs.yaml*, and create the pod:

```
# oc create -f nfs.yaml
pod "hello-openshift-nfs-pod" created
```

Verify that the pod was created:

```
# oc get pods
```

NAME	READY	STATUS	RESTARTS	AGE
hello-openshift-nfs-pod	1/1	Running	0	4s

More details are shown in the **oc describe pod** command:

```
[root@ose70 nfs]# oc describe pod hello-openshift-nfs-pod
Name:      hello-openshift-nfs-pod
Namespace: default 1
Image(s):   fedora/S3
Node:       ose70.rh7/192.168.234.148 2
Start Time: Mon, 21 Mar 2016 09:59:47 -0400
Labels:     name=hello-openshift-nfs-pod
Status:     Running
Reason:
Message:
IP:         10.1.0.4
Replication Controllers: <none>
Containers:
  hello-openshift-nfs-pod:
    Container ID:
docker://a3292104d6c28d9cf49f440b2967a0fc5583540fc3b062db598557b93893bc6f
    Image:      fedora/S3
    Image ID:
docker://403d268c640894cbd76d84a1de3995d2549a93af51c8e16e89842e4c3ed6a00a
    QoS Tier:
      cpu:      BestEffort
      memory:   BestEffort
    State:     Running
      Started:  Mon, 21 Mar 2016 09:59:49 -0400
    Ready:     True
    Restart Count: 0
    Environment Variables:
Conditions:
  Type      Status
  Ready     True
Volumes:
  nfsvol:
    Type: PersistentVolumeClaim (a reference to a PersistentVolumeClaim in
the same namespace)
    ClaimName: nfs-pvc 3
```

```

    ReadOnly: false
  default-token-a06zb:
    Type: Secret (a secret that should populate this volume)
    SecretName: default-token-a06zb
Events: 4
  FirstSeen LastSeen Count From          SubobjectPath
Reason      Message
-----
4m 4m 1 {scheduler }
Scheduled Successfully assigned hello-openshift-nfs-pod to ose70.rh7
4m 4m 1 {kubelet ose70.rh7} implicitly required container POD
Pulled Container image "openshift3/ose-pod:v3.1.0.4" already present on
machine
4m 4m 1 {kubelet ose70.rh7} implicitly required container POD
Created Created with docker id 866a37108041
4m 4m 1 {kubelet ose70.rh7} implicitly required container POD
Started Started with docker id 866a37108041
4m 4m 1 {kubelet ose70.rh7} spec.containers{hello-openshift-nfs-pod}
Pulled Container image "fedora/S3" already present on machine
4m 4m 1 {kubelet ose70.rh7} spec.containers{hello-openshift-nfs-pod}
Created Created with docker id a3292104d6c2
4m 4m 1 {kubelet ose70.rh7} spec.containers{hello-openshift-nfs-pod}
Started Started with docker id a3292104d6c2

```

- 1 The project (namespace) name.
- 2 The IP address of the OpenShift Container Platform node running the pod.
- 3 The PVC name used by the pod.
- 4 The list of events resulting in the pod being launched and the NFS volume being mounted. The container will not start correctly if the volume cannot mount.

There is more internal information, including the SCC used to authorize the pod, the pod's user and group IDs, the SELinux label, and more, shown in the **oc get pod <name> -o yaml** command:

```

[root@ose70 nfs]# oc get pod hello-openshift-nfs-pod -o yaml
apiVersion: v1
kind: Pod
metadata:
  annotations:
    openshift.io/scc: restricted 1
  creationTimestamp: 2016-03-21T13:59:47Z
  labels:
    name: hello-openshift-nfs-pod
    name: hello-openshift-nfs-pod
    namespace: default 2
    resourceVersion: "2814411"
    selflink: /api/v1/namespaces/default/pods/hello-openshift-nfs-pod
    uid: 2c22d2ea-ef6d-11e5-adc7-000c2900f1e3
spec:
  containers:
    - image: fedora/S3
      imagePullPolicy: IfNotPresent

```



```

name: hello-openshift-nfs-pod
ports:
- containerPort: 80
  name: web
  protocol: TCP
resources: {}
securityContext:
  privileged: false
terminationMessagePath: /dev/termination-log
volumeMounts:
- mountPath: /usr/share/S3/html
  name: nfsvol
- mountPath: /var/run/secrets/kubernetes.io/serviceaccount
  name: default-token-a06zb
  readOnly: true
dnsPolicy: ClusterFirst
host: ose70.rh7
imagePullSecrets:
- name: default-dockercfg-xvdew
nodeName: ose70.rh7
restartPolicy: Always
securityContext:
  supplementalGroups:
  - 100003 ③
serviceAccount: default
serviceAccountName: default
terminationGracePeriodSeconds: 30
volumes:
- name: nfsvol
  persistentVolumeClaim:
    claimName: nfs-pvc ④
- name: default-token-a06zb
  secret:
    secretName: default-token-a06zb
status:
  conditions:
  - lastProbeTime: null
    lastTransitionTime: 2016-03-21T13:59:49Z
    status: "True"
    type: Ready
  containerStatuses:
  - containerID:
    docker://a3292104d6c28d9cf49f440b2967a0fc5583540fc3b062db598557b93893bc6f
    image: fedora/S3
    imageID:
    docker://403d268c640894cbd76d84a1de3995d2549a93af51c8e16e89842e4c3ed6a00a
    lastState: {}
    name: hello-openshift-nfs-pod
    ready: true
    restartCount: 0
    state:
      running:
        startedAt: 2016-03-21T13:59:49Z
  hostIP: 192.168.234.148

```

```

phase: Running
podIP: 10.1.0.4
startTime: 2016-03-21T13:59:47Z

```

- 1 The SCC used by the pod.
- 2 The project (namespace) name.
- 3 The supplemental group ID for the pod (all containers).
- 4 The PVC name used by the pod.

23.2.6. Creating an Additional Pod to Reference the Same PVC

This pod definition, created in the same namespace, uses a different container. However, we can use the same backing storage by specifying the claim name in the volumes section below:

Example 23.4. Pod Object Definition

```

apiVersion: v1
kind: Pod
metadata:
  name: busybox-nfs-pod 1
  labels:
    name: busybox-nfs-pod
spec:
  containers:
  - name: busybox-nfs-pod
    image: busybox 2
    command: ["sleep", "60000"]
    volumeMounts:
    - name: nfsvol-2 3
      mountPath: /usr/share/busybox 4
      readOnly: false
  securityContext:
    supplementalGroups: [100003] 5
    privileged: false
  volumes:
  - name: nfsvol-2
    persistentVolumeClaim:
      claimName: nfs-pvc 6

```

- 1 The name of this pod as displayed by `oc get pod`.
- 2 The image run by this pod.
- 3 The name of the volume. This name must be the same in both the **containers** and **volumes** sections.
- 4 The mount path as seen in the container.
- 5 The group ID to be assigned to the container.
- 6 The PVC that was created earlier and is also being used by a different container.

Save the pod definition to a file, for example **nfs-2.yaml**, and create the pod:

```
# oc create -f nfs-2.yaml
pod "busybox-nfs-pod" created
```

Verify that the pod was created:

```
# oc get pods
```

NAME	READY	STATUS	RESTARTS	AGE
busybox-nfs-pod	1/1	Running	0	3s

More details are shown in the **oc describe pod** command:

```
[root@ose70 nfs]# oc describe pod busybox-nfs-pod
Name:      busybox-nfs-pod
Namespace:  default
Image(s):   busybox
Node:       ose70.rh7/192.168.234.148
Start Time: Mon, 21 Mar 2016 10:19:46 -0400
Labels:     name=busybox-nfs-pod
Status:     Running
Reason:
Message:
IP:         10.1.0.5
Replication Controllers: <none>
Containers:
  busybox-nfs-pod:
    Container ID:
docker://346d432e5a4824ebf5a47fceb4247e0568ecc64eadcc160e9bab481aecfb0594
    Image: busybox
    Image ID:
docker://17583c7dd0dae6244203b8029733bdb7d17fccbb2b5d93e2b24cf48b8bfd06e2
    QoS Tier:
      cpu: BestEffort
      memory: BestEffort
    State: Running
      Started: Mon, 21 Mar 2016 10:19:48 -0400
      Ready: True
      Restart Count: 0
    Environment Variables:
Conditions:
  Type      Status
  Ready     True
Volumes:
  nfsvol-2:
    Type: PersistentVolumeClaim (a reference to a PersistentVolumeClaim in
the same namespace)
    ClaimName: nfs-pvc
    ReadOnly: false
  default-token-32d2z:
    Type: Secret (a secret that should populate this volume)
    SecretName: default-token-32d2z
Events:
```

FirstSeen	LastSeen	Count	From	SubobjectPath	Reason	Message
4m	4m	1	{scheduler }		Scheduled	Successfully assigned busybox-nfs-pod to ose70.rh7
4m	4m	1	{kubelet ose70.rh7}		implicitly required container	POD Pulled Container image "openshift3/ose-pod:v3.1.0.4" already present on machine
4m	4m	1	{kubelet ose70.rh7}		implicitly required container	POD Created Created with docker id 249b7d7519b1
4m	4m	1	{kubelet ose70.rh7}		implicitly required container	POD Started Started with docker id 249b7d7519b1
4m	4m	1	{kubelet ose70.rh7}	spec.containers{busybox-nfs-pod}	Pulled	Container image "busybox" already present on machine
4m	4m	1	{kubelet ose70.rh7}	spec.containers{busybox-nfs-pod}	Created	Created with docker id 346d432e5a48
4m	4m	1	{kubelet ose70.rh7}	spec.containers{busybox-nfs-pod}	Started	Started with docker id 346d432e5a48

As you can see, both containers are using the same storage claim that is attached to the same NFS mount on the back end.

23.3. COMPLETE EXAMPLE USING CEPH RBD

23.3.1. Overview

This topic provides an end-to-end example of using an existing Ceph cluster as an OpenShift Container Platform persistent store. It is assumed that a working Ceph cluster is already set up. If not, consult the [Overview of Red Hat Ceph Storage](#).

[Persistent Storage Using Ceph Rados Block Device](#) provides an explanation of persistent volumes (PVs), persistent volume claims (PVCs), and using Ceph RBD as persistent storage.



NOTE

All **oc** ... commands are executed on the OpenShift Container Platform master host.

23.3.2. Installing the ceph-common Package

The **ceph-common** library must be installed on **all schedulable** OpenShift Container Platform nodes:



NOTE

The OpenShift Container Platform all-in-one host is not often used to run pod workloads and, thus, is not included as a schedulable node.

```
# yum install -y ceph-common
```

23.3.3. Creating the Ceph Secret

The **ceph auth get-key** command is run on a Ceph **MON** node to display the key value for the **client.admin** user:

Example 23.5. Ceph Secret Definition

```

apiVersion: v1
kind: Secret
metadata:
  name: ceph-secret
data:
  key: QVFB0FF2S1ZheUJQRVJBQWgvS2cwT1laQUhPQno3akZwekxxdGc9PQ== ❶

```

- ❶ This base64 key is generated on one of the Ceph MON nodes using the **ceph auth get-key client.admin | base64** command, then copying the output and pasting it as the secret key's value.

Save the secret definition to a file, for example **ceph-secret.yaml**, then create the secret:

```

$ oc create -f ceph-secret.yaml
secret "ceph-secret" created

```

Verify that the secret was created:

```

# oc get secret ceph-secret
NAME          TYPE      DATA   AGE
ceph-secret   Opaque    1       23d

```

23.3.4. Creating the Persistent Volume

Next, before creating the PV object in OpenShift Container Platform, define the persistent volume file:

Example 23.6. Persistent Volume Object Definition Using Ceph RBD

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: ceph-pv ❶
spec:
  capacity:
    storage: 2Gi ❷
  accessModes:
    - ReadWriteOnce ❸
  rbd: ❹
    monitors: ❺
      - 192.168.122.133:6789
    pool: rbd
    image: ceph-image
    user: admin
    secretRef:
      name: ceph-secret ❻
    fsType: ext4 ❼
    readOnly: false
  persistentVolumeReclaimPolicy: Recycle

```

- 1 The name of the PV, which is referenced in pod definitions or displayed in various **oc** volume commands.
- 2 The amount of storage allocated to this volume.
- 3 **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control. All block storage is defined to be single user (non-shared storage).
- 4 This defines the volume type being used. In this case, the **rbd** plug-in is defined.
- 5 This is an array of Ceph monitor IP addresses and ports.
- 6 This is the Ceph secret, defined above. It is used to create a secure connection from OpenShift Container Platform to the Ceph server.
- 7 This is the file system type mounted on the Ceph RBD block device.

Save the PV definition to a file, for example **ceph-pv.yaml**, and create the persistent volume:

```
# oc create -f ceph-pv.yaml
persistentvolume "ceph-pv" created
```

Verify that the persistent volume was created:

```
# oc get pv
NAME          CLAIM          REASON          AGE          LABELS          CAPACITY          ACCESSMODES          STATUS
ceph-pv       2s             <none>           2147483648   RWO             Available
```

23.3.5. Creating the Persistent Volume Claim

A persistent volume claim (PVC) specifies the desired access mode and storage capacity. Currently, based on only these two attributes, a PVC is bound to a single PV. Once a PV is bound to a PVC, that PV is essentially tied to the PVC's project and cannot be bound to by another PVC. There is a one-to-one mapping of PVs and PVCs. However, multiple pods in the same project can use the same PVC.

Example 23.7. PVC Object Definition

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: ceph-claim
spec:
  accessModes: 1
    - ReadWriteOnce
  resources:
    requests:
      storage: 2Gi 2
```

- 1 As mentioned above for PVs, the **accessModes** do not enforce access right, but rather act as labels to match a PV to a PVC.

- 2 This claim will look for PVs offering **2Gi** or greater capacity.

Save the PVC definition to a file, for example ***ceph-claim.yaml***, and create the PVC:

```
# oc create -f ceph-claim.yaml
persistentvolumeclaim "ceph-claim" created

#and verify the PVC was created and bound to the expected PV:
# oc get pvc
NAME          LABELS      STATUS    VOLUME    CAPACITY    ACCESSMODES    AGE
ceph-claim    <none>      Bound     ceph-pv    1Gi         RWX            21s
```

- 1 the claim was bound to the **ceph-pv** PV.

23.3.6. Creating the Pod

A pod definition file or a template file can be used to define a pod. Below is a pod specification that creates a single container and mounts the Ceph RBD volume for read-write access:

Example 23.8. Pod Object Definition

```
apiVersion: v1
kind: Pod
metadata:
  name: ceph-pod1
spec:
  containers:
  - name: ceph-busybox
    image: busybox
    command: ["sleep", "60000"]
    volumeMounts:
    - name: ceph-vol1
      mountPath: /usr/share/busybox
      readOnly: false
  volumes:
  - name: ceph-vol1
    persistentVolumeClaim:
      claimName: ceph-claim
```

- 1 The name of this pod as displayed by **oc get pod**.
- 2 The image run by this pod. In this case, we are telling **busybox** to sleep.
- 3 5 The name of the volume. This name must be the same in both the **containers** and **volumes** sections.
- 4 The mount path as seen in the container.
- 6 The PVC that is bound to the Ceph RBD cluster.

Save the pod definition to a file, for example ***ceph-pod1.yaml***, and create the pod:

```
# oc create -f ceph-pod1.yaml
pod "ceph-pod1" created

#verify pod was created
# oc get pod
NAME          READY    STATUS    RESTARTS   AGE
ceph-pod1     1/1      Running   0           2m
```

1

1 After a minute or so, the pod will be in the **Running** state.

23.3.7. Defining Group and Owner IDs (Optional)

When using block storage, such as Ceph RBD, the physical block storage is **managed** by the pod. The group ID defined in the pod becomes the group ID of **both** the Ceph RBD mount inside the container, and the group ID of the actual storage itself. Thus, it is usually unnecessary to define a group ID in the pod specification. However, if a group ID is desired, it can be defined using **fsGroup**, as shown in the following pod definition fragment:

Example 23.9. Group ID Pod Definition

```
...
spec:
  containers:
    - name:
      ...
  securityContext: 1
    fsGroup: 7777 2
  ...
```

1 **securityContext** must be defined at the pod level, not under a specific container.

2 All containers in the pod will have the same **fsGroup** ID.

23.3.8. Setting ceph-user-secret as Default for Projects

If you would like to make the persistent storage available to every project you have to modify the default project template. You can read more on modifying the default project template. Read more on [modifying the default project template](#). Adding this to your default project template allows every user who has access to create a project access to the Ceph cluster.

Example 23.10. Default Project Example

```
...
apiVersion: v1
kind: Template
metadata:
```



```

    creationTimestamp: null
    name: project-request
  objects:
  - apiVersion: v1
    kind: Project
    metadata:
      annotations:
        openshift.io/description: ${PROJECT_DESCRIPTION}
        openshift.io/display-name: ${PROJECT_DISPLAYNAME}
        openshift.io/requester: ${PROJECT_REQUESTING_USER}
      creationTimestamp: null
      name: ${PROJECT_NAME}
    spec: {}
    status: {}
  - apiVersion: v1
    kind: Secret
    metadata:
      name: ceph-user-secret
    data:
      key: yoursupersecretbase64keygoeshere 1
    type:
      kubernetes.io/rbd
  ...

```

1 Place your super secret Ceph user key here in base64 format. See [Creating the Ceph Secret](#).

23.4. USING CEPH RBD FOR DYNAMIC PROVISIONING

23.4.1. Overview

This topic provides a complete example of using an existing Ceph cluster for OpenShift Container Platform persistent storage. It is assumed that a working Ceph cluster is already set up. If not, consult the [Overview of Red Hat Ceph Storage](#).

[Persistent Storage Using Ceph Rados Block Device](#) provides an explanation of persistent volumes (PVs), persistent volume claims (PVCs), and how to use Ceph Rados Block Device (RBD) as persistent storage.



NOTE

- Run all **oc** commands on the OpenShift Container Platform master host.
- The OpenShift Container Platform all-in-one host is not often used to run pod workloads and, thus, is not included as a schedulable node.

23.4.2. Creating a pool for dynamic volumes

1. Install the latest ceph-common package:


```
yum install -y ceph-common
```

**NOTE**

The **ceph-common** library must be installed on **all schedulable** OpenShift Container Platform nodes.

- From an administrator or **MON** node, create a new pool for dynamic volumes, for example:

```
$ ceph osd pool create kube 1024
$ ceph auth get-or-create client.kube mon 'allow r' osd 'allow
class-read object_prefix rbd_children, allow rwx pool=kube' -o
ceph.client.kube.keyring
```

**NOTE**

Using the default pool of RBD is an option, but not recommended.

23.4.3. Using an existing Ceph cluster for dynamic persistent storage

To use an existing Ceph cluster for dynamic persistent storage:

- Generate the client.admin base64-encoded key:

```
$ ceph auth get client.admin
```

Ceph secret definition example

```
apiVersion: v1
kind: Secret
metadata:
  name: ceph-secret
  namespace: kube-system
data:
  key: QVFB0FF2SlZheUJQRVJBQWgvS2cwT1laQUhPQno3akZwekxxdGc9PQ== 1
type: kubernetes.io/rbd 2
```

1 This base64 key is generated on one of the Ceph MON nodes using the **ceph auth get-key client.admin | base64** command, then copying the output and pasting it as the secret key's value.

2 This value is required for Ceph RBD to work with dynamic provisioning.

- Create the Ceph secret for the client.admin:

```
$ oc create -f ceph-secret.yaml
secret "ceph-secret" created
```

- Verify that the secret was created:

```
$ oc get secret ceph-secret
NAME          TYPE                      DATA      AGE
ceph-secret   kubernetes.io/rbd        1          5d
```

4. Create the storage class:

```
$ oc create -f ceph-storageclass.yaml
storageclass "dynamic" created
```

Ceph storage class example

```
apiVersion: storage.k8s.io/v1beta1
kind: StorageClass
metadata:
  name: dynamic
  annotations:
    storageclass.beta.kubernetes.io/is-default-class: "true"
provisioner: kubernetes.io/rbd
parameters:
  monitors: 192.168.1.11:6789,192.168.1.12:6789,192.168.1.13:6789 ❶
  adminId: admin ❷
  adminSecretName: ceph-secret ❸
  adminSecretNamespace: kube-system ❹
  pool: kube ❺
  userId: kube ❻
  userSecretName: ceph-user-secret ❼
```

- ❶ A comma-delimited list of IP addresses Ceph monitors. This value is required.
- ❷ The Ceph client ID that is capable of creating images in the pool. The default is **admin**.
- ❸ The secret name for **adminId**. This value is required. The secret that you provide must have **kubernetes.io/rbd**.
- ❹ The namespace for **adminSecret**. The default is **default**.
- ❺ The Ceph RBD pool. The default is **rbd**, but this value is not recommended.
- ❻ The Ceph client ID used to map the Ceph RBD image. The default is the same as the secret name for **adminId**.
- ❼ The name of the Ceph secret for **userId** to map the Ceph RBD image. It must exist in the same namespace as the PVCs. Unless you set the Ceph secret as the default in new projects, you must provide this parameter value.

5. Verify that the storage class was created:

```
$ oc get storageclasses
NAME                                TYPE
dynamic (default)                  kubernetes.io/rbd
```

6. Create the PVC object definition:

PVC object definition example

```
kind: PersistentVolumeClaim
apiVersion: v1
```

```

metadata:
  name: ceph-claim-dynamic
spec:
  accessModes: ❶
    - ReadWriteOnce
  resources:
    requests:
      storage: 2Gi ❷

```

- ❶ The **accessModes** do not enforce access rights but instead act as labels to match a PV to a PVC.
- ❷ This claim looks for PVs that offer **2Gi** or greater capacity.

7. Create the PVC:

```

$ oc create -f ceph-pvc.yaml
persistentvolumeclaim "ceph-claim-dynamic" created

```

8. Verify that the PVC was created and bound to the expected PV:

```

$ oc get pvc
NAME          STATUS  VOLUME
CAPACITY ACCESSMODES  AGE
ceph-claim    Bound   pvc-f548d663-3cac-11e7-9937-0024e8650c7a 2Gi
RW0           1m

```

9. Create the pod object definition:

Pod object definition example

```

apiVersion: v1
kind: Pod
metadata:
  name: ceph-pod1 ❶
spec:
  containers:
    - name: ceph-busybox
      image: busybox ❷
      command: ["sleep", "60000"]
      volumeMounts:
        - name: ceph-vol1 ❸
          mountPath: /usr/share/busybox ❹
          readOnly: false
  volumes:
    - name: ceph-vol1
      persistentVolumeClaim:
        claimName: ceph-claim ❺

```

- ❶ The name of this pod as displayed by **oc get pod**.
- ❷ The image run by this pod. In this case, **busybox** is set to **sleep**.

- 3 The name of the volume. This name must be the same in both the **containers** and **volumes** sections.
- 4 The mount path in the container.
- 5 The PVC that is bound to the Ceph RBD cluster.

10. Create the pod:

```
$ oc create -f ceph-pod1.yaml
pod "ceph-pod1" created
```

11. Verify that the pod was created:

```
$ oc get pod
NAME          READY   STATUS    RESTARTS   AGE
ceph-pod1     1/1     Running   0           2m
```

After a minute or so, the pod status changes to **Running**.

23.4.4. Setting ceph-user-secret as the default for projects

To make persistent storage available to every project, you must modify the default project template. Adding this to your default project template allows every user who has access to create a project access to the Ceph cluster. See [modifying the default project template](#) for more information.

Default project example

```
...
apiVersion: v1
kind: Template
metadata:
  creationTimestamp: null
  name: project-request
objects:
- apiVersion: v1
  kind: Project
  metadata:
    annotations:
      openshift.io/description: ${PROJECT_DESCRIPTION}
      openshift.io/display-name: ${PROJECT_DISPLAYNAME}
      openshift.io/requester: ${PROJECT_REQUESTING_USER}
    creationTimestamp: null
    name: ${PROJECT_NAME}
  spec: {}
  status: {}
- apiVersion: v1
  kind: Secret
  metadata:
    name: ceph-user-secret
  data:
```

```
key: QVFCbEV40VpmaGJtQ0JBQW55d2Z0NHZtcS96cE42SW1JVUQvekE9PQ== 1
type:
  kubernetes.io/rbd
...
```

1 Place your Ceph user key here in base64 format.

23.5. COMPLETE EXAMPLE USING GLUSTERFS

23.5.1. Overview

This topic provides an end-to-end example of how to use an existing Gluster cluster as an OpenShift Container Platform persistent store. It is assumed that a working Gluster cluster is already set up. If not, consult the [Red Hat Gluster Storage Administration Guide](#).

[Persistent Storage Using GlusterFS](#) provides an explanation of persistent volumes (PVs), persistent volume claims (PVCs), and using GlusterFS as persistent storage.

For an end-to-end example of how to dynamically provision GlusterFS volumes, see [Complete Example of Dynamic Provisioning Using GlusterFS](#). The persistent volume (PV) and endpoints are both created dynamically by GlusterFS.



NOTE

All **oc** ... commands are executed on the OpenShift Container Platform master host.

23.5.2. Installing the glusterfs-fuse Package

The **glusterfs-fuse** library must be installed on all **schedulable** OpenShift Container Platform nodes:

```
# yum install -y glusterfs-fuse
```



NOTE

The OpenShift Container Platform all-in-one host is often not used to run pod workloads and, thus, is not included as a schedulable node.

23.5.3. Creating the Gluster Endpoints and Gluster Service for Persistence

The named endpoints define each node in the Gluster-trusted storage pool:

Example 23.11. GlusterFS Endpoint Definition

```
apiVersion: v1
kind: Endpoints
metadata:
  name: gluster-cluster 1
subsets:
- addresses: 2
  - ip: 192.168.122.21
  ports: 3
```

```
- port: 1
  protocol: TCP
- addresses:
  - ip: 192.168.122.22
    ports:
    - port: 1
      protocol: TCP
```


- 1 The endpoints name. If using a service, then the endpoints name must match the service name.
- 2 An array of IP addresses for each node in the Gluster pool. Currently, host names are not supported.
- 3 The port numbers are ignored, but must be legal port numbers. The value 1 is commonly used.

Save the endpoints definition to a file, for example ***gluster-endpoints.yaml***, then create the endpoints object:

```
# oc create -f gluster-endpoints.yaml
endpoints "gluster-cluster" created
```

Verify that the endpoints were created:

```
# oc get endpoints gluster-cluster
NAME                ENDPOINTS                                     AGE
gluster-cluster     192.168.122.21:1,192.168.122.22:1          1m
```



NOTE

To persist the Gluster endpoints, you also need to create a service.



NOTE

Endpoints are name-spaced. Each project accessing the Gluster volume needs its own endpoints.

Example 23.12. GlusterFS Service Definition

```
apiVersion: v1
kind: Service
metadata:
  name: gluster-cluster 1
spec:
  ports:
  - port: 1 2
```

- 1 The name of the service. If using a service, then the endpoints name must match the service name.
- 2 The port should match the same port used in the endpoints.

Save the service definition to a file, for example **gluster-service.yaml**, then create the endpoints object:

```
# oc create -f gluster-service.yaml
endpoints "gluster-cluster" created
```

Verify that the service was created:

```
# oc get service gluster-cluster
NAME                CLUSTER-IP      EXTERNAL-IP      PORT(S)    AGE
gluster-cluster     10.0.0.130      <none>           1/TCP      9s
```

23.5.4. Creating the Persistent Volume

Next, before creating the PV object, define the persistent volume in OpenShift Container Platform:

Persistent Volume Object Definition Using GlusterFS

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-pv ①
spec:
  capacity:
    storage: 1Gi ②
  accessModes:
    - ReadWriteMany ③
  glusterfs: ④
    endpoints: gluster-cluster ⑤
    path: /HadoopVol ⑥
    readOnly: false
  persistentVolumeReclaimPolicy: Retain ⑦
```

- ① The name of the PV, which is referenced in pod definitions or displayed in various **oc** volume commands.
- ② The amount of storage allocated to this volume.
- ③ **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control.
- ④ This defines the volume type being used. In this case, the **glusterfs** plug-in is defined.
- ⑤ This references the endpoints named above.
- ⑥ This is the Gluster volume name, preceded by **/**.
- ⑦ The volume reclaim policy **Retain** indicates that the volume will be preserved after the pods accessing it terminates. For GlusterFS, the accepted values include **Retain**, and **Delete**.

Save the PV definition to a file, for example **gluster-pv.yaml**, and create the persistent volume:

■


```
# oc create -f gluster-pv.yaml
persistentvolume "gluster-pv" created
```

Verify that the persistent volume was created:

```
# oc get pv
NAME          LABELS          CAPACITY  ACCESSMODES  STATUS    CLAIM
REASON    AGE
gluster-pv    <none>         1Gi       RWX           Available
37s
```

23.5.5. Creating the Persistent Volume Claim

A persistent volume claim (PVC) specifies the desired access mode and storage capacity. Currently, based on only these two attributes, a PVC is bound to a single PV. Once a PV is bound to a PVC, that PV is essentially tied to the PVC's project and cannot be bound to by another PVC. There is a one-to-one mapping of PVs and PVCs. However, multiple pods in the same project can use the same PVC.

Example 23.13. PVC Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim ❶
spec:
  accessModes:
    - ReadWriteMany    ❷
  resources:
    requests:
      storage: 1Gi      ❸
```

- ❶ The claim name is referenced by the pod under its **volumes** section.
- ❷ As mentioned above for PVs, the **accessModes** do not enforce access rights, but rather act as labels to match a PV to a PVC.
- ❸ This claim will look for PVs offering **1Gi** or greater capacity.

Save the PVC definition to a file, for example **gluster-claim.yaml**, and create the PVC:

```
# oc create -f gluster-claim.yaml
persistentvolumeclaim "gluster-claim" created
```

Verify the PVC was created and bound to the expected PV:

```
# oc get pvc
NAME          LABELS          STATUS    VOLUME          CAPACITY  ACCESSMODES
AGE
gluster-claim  <none>         Bound     gluster-pv      1Gi       RWX
24s
```

❶

- 1 The claim was bound to the **gluster-pv** PV.

23.5.6. Defining GlusterFS Volume Access

Access is necessary to a node in the Gluster-trusted storage pool. On this node, examine the **glusterfs-fuse** mount:

```
# ls -lZ /mnt/glusterfs/
drwxrwx---. yarn hadoop system_u:object_r:fusefs_t:s0      HadoopVol

# id yarn
uid=592(yarn) gid=590(hadoop) groups=590(hadoop)
```

- 1 The owner has ID 592.

- 2 The group has ID 590.

In order to access the **HadoopVol** volume, the container must match the SELinux label, and either run with a UID of 592, or with 590 in its supplemental groups. It is recommended to gain access to the volume by matching the Gluster mount's groups, which is defined in the pod definition below.

By default, SELinux does not allow writing from a pod to a remote Gluster server. To enable writing to GlusterFS volumes with SELinux enforcing on each node, run:

```
# setsebool -P virt_sandbox_use_fusefs on
```



NOTE

The **virt_sandbox_use_fusefs** boolean is defined by the **docker-selinux** package. If you get an error saying it is not defined, ensure that this package is installed.

23.5.7. Creating the Pod using NGINX Web Server image

A pod definition file or a template file can be used to define a pod. Below is a pod specification that creates a single container and mounts the Gluster volume for read-write access:



NOTE

The NGINX image may require to run in privileged mode to create the mount and run properly. An easy way to accomplish this is to simply add your user to the **privileged** Security Context Constraint (SCC):

```
$ oc adm policy add-scc-to-user privileged myuser
```

Then, add the **privileged: true** to the containers **securityContext:** section of the YAML file (as seen in the example below).

[Managing Security Context Constraints](#) provides additional information regarding SCCs.

Example 23.14. Pod Object Definition using NGINX image

```

apiVersion: v1
kind: Pod
metadata:
  name: gluster-pod1
  labels:
    name: gluster-pod1 ❶
spec:
  containers:
    - name: gluster-pod1
      image: nginx ❷
      ports:
        - name: web
          containerPort: 80
      securityContext:
        privileged: true
      volumeMounts:
        - name: gluster-vol1 ❸
          mountPath: /usr/share/nginx/html ❹
          readOnly: false
  securityContext:
    supplementalGroups: [590] ❺
  volumes:
    - name: gluster-vol1 ❻
      persistentVolumeClaim:
        claimName: gluster-claim ❼

```

- ❶ The name of this pod as displayed by **oc get pod**.
- ❷ The image run by this pod. In this case, we are using a standard NGINX image.
- ❸❹ The name of the volume. This name must be the same in both the **containers** and **volumes** sections.
- ❹ The mount path as seen in the container.
- ❺ The **SupplementalGroup** ID (Linux Groups) to be assigned at the pod level and as discussed this should match the POSIX permissions on the Gluster volume.
- ❼ The PVC that is bound to the Gluster cluster.

Save the pod definition to a file, for example **gluster-pod1.yaml**, and create the pod:

```

# oc create -f gluster-pod1.yaml
pod "gluster-pod1" created

```

Verify the pod was created:

```

# oc get pod
NAME          READY   STATUS    RESTARTS   AGE
gluster-pod1  1/1     Running   0           31s

```

1

- 1 After a minute or so, the pod will be in the **Running** state.

More details are shown in the **oc describe pod** command:

```
# oc describe pod gluster-pod1
Name:      gluster-pod1
Namespace: default 1
Security Policy: privileged
Node:      ose1.rhs/192.168.122.251
Start Time: Wed, 24 Aug 2016 12:37:45 -0400
Labels:    name=gluster-pod1
Status:    Running
IP:        172.17.0.2 2
Controllers: <none>
Containers:
  gluster-pod1:
    Container ID:
docker://e67ed01729e1dc7369c5112d07531a27a7a02a7eb942f17d1c5fce32d8c31a2d
    Image: nginx
    Image ID:
docker://sha256:4efb2fcdb1ab05fb03c9435234343c1cc65289eeb016be86193e88d3a5d84f6b
    Port: 80/TCP
    State: Running
      Started: Wed, 24 Aug 2016 12:37:52 -0400
    Ready: True
    Restart Count: 0
    Volume Mounts:
      /usr/share/nginx/html/test from glustervol (rw)
      /var/run/secrets/kubernetes.io/serviceaccount from default-token-1n70u (ro)
    Environment Variables: <none>
Conditions:
  Type      Status
  Initialized True
  Ready     True
  PodScheduled True
Volumes:
  glustervol:
    Type: PersistentVolumeClaim (a reference to a PersistentVolumeClaim in the same namespace)
    ClaimName: gluster-claim 3
    ReadOnly: false
  default-token-1n70u:
    Type: Secret (a volume populated by a Secret)
    SecretName: default-token-1n70u
QoS Tier: BestEffort
Events: 4
  FirstSeen LastSeen Count From          SubobjectPath  Type    Reason  Message
  ---
  ---
```

```

10s 10s 1 {default-scheduler }      Normal  Scheduled Successfully
assigned gluster-pod1 to ose1.rhs
 9s 9s 1 {kubelet ose1.rhs} spec.containers{gluster-pod1} Normal
Pulling pulling image "nginx"
 4s 4s 1 {kubelet ose1.rhs} spec.containers{gluster-pod1} Normal
Pulled Successfully pulled image "nginx"
 3s 3s 1 {kubelet ose1.rhs} spec.containers{gluster-pod1} Normal
Created Created container with docker id e67ed01729e1
 3s 3s 1 {kubelet ose1.rhs} spec.containers{gluster-pod1} Normal
Started Started container with docker id e67ed01729e1

```

- ❶ The project (namespace) name.
- ❷ The IP address of the OpenShift Container Platform node running the pod.
- ❸ The PVC name used by the pod.
- ❹ The list of events resulting in the pod being launched and the Gluster volume being mounted.

There is more internal information, including the SCC used to authorize the pod, the pod's user and group IDs, the SELinux label, and more shown in the **oc get pod <name> -o yaml** command:

```

# oc get pod gluster-pod1 -o yaml
apiVersion: v1
kind: Pod
metadata:
  annotations:
    openshift.io/scc: privileged ❶
  creationTimestamp: 2016-08-24T16:37:45Z
  labels:
    name: gluster-pod1
  name: gluster-pod1
  namespace: default ❷
  resourceVersion: "482"
  selfLink: /api/v1/namespaces/default/pods/gluster-pod1
  uid: 15afda77-6a19-11e6-aadb-525400f7256d
spec:
  containers:
  - image: nginx
    imagePullPolicy: Always
    name: gluster-pod1
    ports:
    - containerPort: 80
      name: web
      protocol: TCP
    resources: {}
    securityContext:
      privileged: true ❸
    terminationMessagePath: /dev/termination-log
    volumeMounts:
    - mountPath: /usr/share/nginx/html
      name: glustervol
    - mountPath: /var/run/secrets/kubernetes.io/serviceaccount
      name: default-token-1n70u
      readOnly: true

```

```

dnsPolicy: ClusterFirst
host: ose1.rhs
imagePullSecrets:
- name: default-dockercfg-20xg9
nodeName: ose1.rhs
restartPolicy: Always
securityContext:
  supplementalGroups:
  - 590 ❹
serviceAccount: default
serviceAccountName: default
terminationGracePeriodSeconds: 30
volumes:
- name: glustervol
  persistentVolumeClaim:
    claimName: gluster-claim ❺
- name: default-token-1n70u
  secret:
    secretName: default-token-1n70u
status:
  conditions:
  - lastProbeTime: null
    lastTransitionTime: 2016-08-24T16:37:45Z
    status: "True"
    type: Initialized
  - lastProbeTime: null
    lastTransitionTime: 2016-08-24T16:37:53Z
    status: "True"
    type: Ready
  - lastProbeTime: null
    lastTransitionTime: 2016-08-24T16:37:45Z
    status: "True"
    type: PodScheduled
  containerStatuses:
  - containerID:
docker://e67ed01729e1dc7369c5112d07531a27a7a02a7eb942f17d1c5f3ce32d8c31a2d
    image: nginx
    imageID:
docker://sha256:4efb2fcdb1ab05fb03c9435234343c1cc65289eeb016be86193e88d3a5
d84f6b
    lastState: {}
    name: gluster-pod1
    ready: true
    restartCount: 0
    state:
      running:
        startedAt: 2016-08-24T16:37:52Z
  hostIP: 192.168.122.251
  phase: Running
  podIP: 172.17.0.2
  startTime: 2016-08-24T16:37:45Z

```

❶ The SCC used by the pod.

❷ The project (namespace) name.

- 3 The security context level requested, in this case privileged
- 4 The supplemental group ID for the pod (all containers).
- 5 The PVC name used by the pod.

23.6. COMPLETE EXAMPLE OF DYNAMIC PROVISIONING USING CONTAINERIZED GLUSTERFS

23.6.1. Overview



NOTE

This example assumes a functioning OpenShift Container Platform cluster along with Heketi and GlusterFS. All `oc` commands are executed on the OpenShift Container Platform master host.

This topic provides an end-to-end example of how to dynamically provision GlusterFS volumes. In this example, a simple NGINX HelloWorld application is deployed using the [Red Hat Container Native Storage \(CNS\)](#) solution. CNS hyper-converges GlusterFS storage by containerizing it into the OpenShift Container Platform cluster.

The [Red Hat Gluster Storage Administration Guide](#) can also provide additional information about GlusterFS.

To get started, follow the [gluster-kubernetes quickstart guide](#) for an easy Vagrant-based installation and deployment of a working OpenShift Container Platform cluster with Heketi and GlusterFS containers.

23.6.2. Verify the Environment and Gather Needed Information



NOTE

At this point, there should be a working OpenShift Container Platform cluster deployed, and a working Heketi server with GlusterFS.

1. Verify and view the cluster environment, including nodes and pods:

```
$ oc get nodes,pods
NAME          STATUS    AGE
master        Ready     22h
node0         Ready     22h
node1         Ready     22h
node2         Ready     22h
```

NAME	RESTARTS	AGE	1/1	READY	STATUS	
1d				Running		0
glusterfs-node0-2509304327-vpce1			1/1		Running	0
1d		192.168.10.100	node0			
glusterfs-node1-3290690057-hhq92			1/1		Running	0
1d		192.168.10.101	node1			
glusterfs-node2-4072075787-okzjv			1/1		Running	0

```

1d          192.168.10.102    node2
heketi-3017632314-yyng 1/1      Running    0
1d          10.42.0.0         node0 2

```

- 1 Example of GlusterFS storage pods running. There are three in this example.
- 2 Heketi server pod.

2. If not already set in the environment, export the **HEKETI_CLI_SERVER**:

```
$ export HEKETI_CLI_SERVER=$(oc describe svc/heketi | grep
"Endpoints:" | awk '{print "http://"$2}')
```

3. Identify the Heketi REST URL and server IP address:

```
$ echo $HEKETI_CLI_SERVER
http://10.42.0.0:8080
```

4. Identify the Gluster endpoints that are needed to pass in as a parameter into the storage class, which is used in a later step (**heketi-storage-endpoints**).

```
$ oc get endpoints
NAME                                ENDPOINTS
AGE
heketi                             10.42.0.0:8080
22h
heketi-storage-endpoints
192.168.10.100:1,192.168.10.101:1,192.168.10.102:1 22h 1
kubernetes                         192.168.10.90:6443
23h
```

- 1 The defined GlusterFS endpoints. In this example, they are called **heketi-storage-endpoints**.



NOTE

By default, **user_authorization** is disabled. If enabled, you may need to find the rest user and rest user secret key. (This is not applicable for this example, as any values will work).

23.6.3. Create a Storage Class for Your GlusterFS Dynamic Provisioner

[Storage classes](#) manage and enable persistent storage in OpenShift Container Platform. Below is an example of a *Storage class* requesting 5GB of on-demand storage to be used with your *HelloWorld* application.

```

apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: gluster-heketi 1
provisioner: kubernetes.io/glusterfs 2

```



```
parameters:
  endpoint: "heketi-storage-endpoints"
  resturl: "http://10.42.0.0:8080"
  restuser: "joe"
  restuserkey: "My Secret Life"
```

- 1 Name of the storage class.
- 2 The provisioner.
- 3 The GlusterFS-defined endpoint (**oc get endpoints**).
- 4 Heketi REST URL, taken from Step 1 above (**echo \$HEKETI_CLI_SERVER**).
- 5 Rest username. This can be any value since authorization is turned off.
- 6 Rest user key. This can be any value.

1. Create the Storage Class YAML file, save it, then submit it to OpenShift Container Platform:

```
$ oc create -f gluster-storage-class.yaml
storageclass "gluster-heketi" created
```

2. View the storage class:

```
$ oc get storageclass
NAME                                TYPE
gluster-heketi                     kubernetes.io/glusterfs
```

23.6.4. Create a PVC to Request Storage for Your Application

1. Create a persistent volume claim (PVC) requesting 5GB of storage.
During that time, the Dynamic Provisioning Framework and Heketi will automatically provision a new GlusterFS volume and generate the persistent volume (PV) object:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster1
spec:
  accessModes:
    - ReadWriteOnce
  storageClassName: gluster-heketi
  resources:
    requests:
      storage: 5Gi
```

- 1 The name of the storage class.
- 2 The amount of storage requested.

1. Create the PVC YAML file, save it, then submit it to OpenShift Container Platform:

```
$ oc create -f gluster-pvc.yaml
persistentvolumeclaim "gluster1" created
```

2. View the PVC:

```
$ oc get pvc
NAME          STATUS      VOLUME
CAPACITY      ACCESSMODES  AGE
gluster1      Bound       pvc-7d37c7bd-bb5b-11e6-b81e-525400d87180    5Gi
RW0           14h
```

Notice that the PVC is bound to a dynamically created volume.

3. View the persistent volume (PV):

```
$ oc get pv
NAME          CAPACITY      ACCESSMODES
RECLAIMPOLICY STATUS      CLAIM          REASON    AGE
pvc-7d37c7bd-bb5b-11e6-b81e-525400d87180    5Gi        RW0
Delete       Bound       default/gluster1    14h
```

23.6.5. Create a NGINX Pod That Uses the PVC

At this point, you have a dynamically created GlusterFS volume, bound to a PVC. Now, you can use this claim in a pod. Create a simple NGINX pod:

```
apiVersion: v1
kind: Pod
metadata:
  name: nginx-pod
  labels:
    name: nginx-pod
spec:
  containers:
    - name: nginx-pod
      image: gcr.io/google_containers/nginx-slim:0.8
      ports:
        - name: web
          containerPort: 80
      securityContext:
        privileged: true
      volumeMounts:
        - name: gluster-vol1
          mountPath: /usr/share/nginx/html
  volumes:
    - name: gluster-vol1
      persistentVolumeClaim:
        claimName: gluster1 ❶
```

❶ The name of the PVC created in the previous step.

1. Create the Pod YAML file, save it, then submit it to OpenShift Container Platform:

```
$ oc create -f nginx-pod.yaml
pod "gluster-pod1" created
```

2. View the pod:

```
$ oc get pods -o wide
```

NAME	READY	STATUS	RESTARTS
nginx-pod	1/1	Running	0
glusterfs-node0-2509304327-vpce1	1/1	Running	0
glusterfs-node1-3290690057-hhq92	1/1	Running	0
glusterfs-node2-4072075787-okzjv	1/1	Running	0
heketi-3017632314-yyng	1/1	Running	0



NOTE

This may take a few minutes, as the the pod may need to download the image if it does not already exist.

3. **oc exec** into the container and create an *index.html* file in the **mountPath** definition of the pod:

```
$ oc exec -ti nginx-pod /bin/sh
$ cd /usr/share/nginx/html
$ echo 'Hello World from GlusterFS!!!' > index.html
$ ls
index.html
$ exit
```

4. Using the **curl** command from the master node, **curl** the URL of the pod:

```
$ curl http://10.38.0.0
Hello World from GlusterFS!!!
```

5. Check your Gluster pod to ensure that the *index.html* file was written. Choose any of the Gluster pods:

```
$ oc exec -ti glusterfs-node1-3290690057-hhq92 /bin/sh
$ mount | grep heketi
/dev/mapper/VolGroup00-LogVol00 on /var/lib/heketi type xfs
(rw,relatime,seclabel,attr2,inode64,noquota)
/dev/mapper/vg_f92e09091f6b20ab12b02a2513e4ed90-
brick_1e730a5462c352835055018e1874e578 on
/var/lib/heketi/mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_1e7
30a5462c352835055018e1874e578 type xfs
(rw,noatime,seclabel,nouuid,attr2,inode64,logbsize=256k,sunit=512,sw
idth=512,noquota)
/dev/mapper/vg_f92e09091f6b20ab12b02a2513e4ed90-
```

```
brick_d8c06e606ff4cc29ccb9d018c73ee292 on
/var/lib/heketi/mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_d8c
06e606ff4cc29ccb9d018c73ee292 type xfs
(rw,noatime,seclabel,nouuid,attr2,inode64,logbsize=256k,sunit=512,sw
idth=512,noquota)

$ cd
/var/lib/heketi/mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_d8c
06e606ff4cc29ccb9d018c73ee292/brick
$ ls
index.html
$ cat index.html
Hello World from GlusterFS!!!
```

23.7. COMPLETE EXAMPLE OF DYNAMIC PROVISIONING USING DEDICATED GLUSTERFS

23.7.1. Overview



NOTE

This example assumes a functioning OpenShift Container Platform cluster along with Heketi and GlusterFS. All **oc** commands are executed on the OpenShift Container Platform master host.

[Container Native Storage \(CNS\) using GlusterFS and Heketi](#) is a great way to perform dynamic provisioning for shared filesystems in a Kubernetes-based cluster like OpenShift Container Platform. However, if an existing, [dedicated Gluster cluster](#) is available external to the OpenShift Container Platform cluster, you can also provision storage from it rather than a containerized GlusterFS implementation.

This example:

- Shows how simple it is to install and configure a Heketi server to work with OpenShift Container Platform to perform dynamic provisioning.
- Assumes some familiarity with Kubernetes and the [Kubernetes Persistent Storage](#) model.
- Assumes you have access to an existing, dedicated GlusterFS cluster that has raw devices available for consumption and management by a Heketi server. If you do not have this, you can create a three node cluster using your virtual machine solution of choice. Ensure sure you create a few raw devices and give plenty of space (at least 100GB recommended). See [Red Hat Gluster Storage Installation Guide](#).

23.7.2. Environment and Prerequisites

This example uses the following environment and prerequisites:

- GlusterFS cluster running Red Hat Gluster Storage (RHGS) 3.1. Three nodes, each with at least two 100GB RAW devices:
 - **gluster23.rhs** (192.168.1.200)
 - **gluster24.rhs** (192.168.1.201)

- **gluster25.rhs** (192.168.1.202)
- Heketi service/client node running Red Hat Enterprise Linux (RHEL) 7.x or RHGS 3.1. Heketi can be installed on one of the Gluster nodes:
 - **glusterclient2.rhs** (192.168.1.203)
- OpenShift Container Platform node. This example uses an all-in-one OpenShift Container Platform cluster (master and node on a single host), though it can work using a standard, multi-node cluster as well.
 - **k8dev2.rhs** (192.168.1.208)

23.7.3. Installing and Configuring Heketi

Heketi is used to manage the Gluster cluster storage (adding volumes, removing volumes, etc.). As stated, this can be RHEL or RHGS, and can be installed on one of the existing Gluster storage nodes. This example uses a stand-alone RHGS 3.1 node running Heketi.

The [Red Hat Gluster Storage Administration Guide](#) can be used a reference during this process.

1. Install Heketi and the Heketi client. From the host designated to run Heketi and the Heketi client, run:

```
# yum install heketi heketi-client -y
```



NOTE

The Heketi server can be any of the existing hosts, though typically this will be the OpenShift Container Platform master host. This example, however, uses a separate host not part of the GlusterFS or OpenShift Container Platform cluster.

2. Create and install Heketi private keys on each GlusterFS cluster node. From the host that is running Heketi:

```
# ssh-keygen -f /etc/heketi/heketi_key -t rsa -N ''
# ssh-copy-id -i /etc/heketi/heketi_key.pub root@gluster23.rhs
# ssh-copy-id -i /etc/heketi/heketi_key.pub root@gluster24.rhs
# ssh-copy-id -i /etc/heketi/heketi_key.pub root@gluster25.rhs
# chown heketi:heketi /etc/heketi/heketi_key*
```

3. Edit the **/etc/heketi/heketi.json** file to setup the SSH executor. Below is an excerpt from the **/etc/heketi/heketi.json** file; the parts to configure are the **executor** and SSH sections:

```
"executor": "ssh", ❶

"_sshexec_comment": "SSH username and private key file
information",
"sshexec": {
  "keyfile": "/etc/heketi/heketi_key", ❷
  "user": "root", ❸
  "port": "22", ❹
  "fstab": "/etc/fstab" ❺
},
```

- 1 Change **executor** from **mock** to **ssh**.
- 2 Add in the public key directory specified in previous step.
- 3 Update **user** to a user that has **sudo** or root access.
- 4 Set **port** to **22** and remove all other text.
- 5 Set **fstab** to the default, **/etc/fstab** and remove all other text.

4. Restart and enable service:

```
# systemctl restart heketi
# systemctl enable heketi
```

5. Test the connection to Heketi:

```
# curl http://glusterclient2.rhs:8080/hello
Hello from Heketi
```

6. Set an environment variable for the Heketi server:

```
# export HEKETI_CLI_SERVER=http://glusterclient2.rhs:8080
```

23.7.4. Loading Topology

Topology is used to tell Heketi about the environment and what nodes and devices it will manage.



NOTE

Heketi is currently limited to managing raw devices only. If a device is already a Gluster volume, it will be skipped and ignored.

1. Create and load the topology file. There is a sample file located in **/usr/share/heketi/topology-sample.json** by default, or **/etc/heketi** depending on how it was installed.

```
{
  "clusters": [
    {
      "nodes": [
        {
          "node": {
            "hostnames": {
              "manage": [
                "gluster23.rhs"
              ],
            },
            "storage": [
              "192.168.1.200"
            ]
          },
          "zone": 1
        },
        {
          "devices": [
```

```

        "/dev/sde",
        "/dev/sdf"
    ]
},
{
    "node": {
        "hostnames": {
            "manage": [
                "gluster24.rhs"
            ],
            "storage": [
                "192.168.1.201"
            ]
        },
        "zone": 1
    },
    "devices": [
        "/dev/sde",
        "/dev/sdf"
    ]
},
{
    "node": {
        "hostnames": {
            "manage": [
                "gluster25.rhs"
            ],
            "storage": [
                "192.168.1.202"
            ]
        },
        "zone": 1
    },
    "devices": [
        "/dev/sde",
        "/dev/sdf"
    ]
}
]
}
}

```

2. Using **heketi-cli**, run the following command to load the topology of your environment.

```
# heketi-cli topology load --json=topology.json
```

```

Found node gluster23.rhs on cluster
bdf9d8ca3fa269ff89854faf58f34b9a
Adding device /dev/sde ... OK
Adding device /dev/sdf ... OK
Creating node gluster24.rhs ... ID:
8e677d8bebe13a3f6846e78a67f07f30
Adding device /dev/sde ... OK

```

```

    Adding device /dev/sdf ... OK
    ...
    ...

```

3. Create a Gluster volume to verify Heketi:

```
# heketi-cli volume create --size=50
```

4. View the volume information from one of the the Gluster nodes:

```

# gluster volume info

Volume Name: vol_335d247ac57ecdf40ac616514cc6257f ❶
Type: Distributed-Replicate
Volume ID: 75be7940-9b09-4e7f-bfb0-a7eb24b411e3
Status: Started
...
...

```

- ❶ Volume created by **heketi-cli**.

23.7.5. Dynamically Provision a Volume

1. Create a **StorageClass** object definition. The definition below is based on the minimum requirements needed for this example to work with OpenShift Container Platform. See [Dynamic Provisioning and Creating Storage Classes](#) for additional parameters and specification definitions.

```

kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: gluster-dyn
provisioner: kubernetes.io/glusterfs
parameters:
  resturl: "http://glusterclient2.rhs:8080" ❶
  restauthenabled: "false" ❷

```

- ❶ The Heketi server from the **HEKETI_CLI_SERVER** environment variable.

- ❷ Since authentication is not turned on in this example, set to **false**.

2. From the OpenShift Container Platform master host, create the storage class:

```

# oc create -f glusterfs-storageclass1.yaml
storageclass "gluster-dyn" created

```

3. Create a persistent volume claim (PVC), requesting the newly-created storage class. For example:

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:

```



```

name: gluster-dyn-pvc
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 30Gi
  storageClassName: gluster-dyn

```

4. From the OpenShift Container Platform master host, create the PVC:

```

# oc create -f glusterfs-pvc-storageclass.yaml
persistentvolumeclaim "gluster-dyn-pvc" created

```

5. View the PVC to see that the volume was dynamically created and bound to the PVC:

```

# oc get pvc
NAME                                STATUS VOLUME
CAPACITY  ACCESSMODES  STORAGECLASS  AGE
gluster-dyn-pvc Bound pvc-78852230-d8e2-11e6-a3fa-0800279cf26f
30Gi      RWX          gluster-dyn  42s

```

6. Verify and view the new volume on one of the Gluster nodes:

```

# gluster volume info

Volume Name: vol_335d247ac57ecdf40ac616514cc6257f ❶
Type: Distributed-Replicate
Volume ID: 75be7940-9b09-4e7f-bfb0-a7eb24b411e3
Status: Started
...
Volume Name: vol_f1404b619e6be6ef673e2b29d58633be ❷
Type: Distributed-Replicate
Volume ID: 7dc234d0-462f-4c6c-add3-fb9bc7e8da5e
Status: Started
Number of Bricks: 2 x 2 = 4
...

```

- ❶ Volume created by **heketi-cli**.
- ❷ New dynamically created volume triggered by Kubernetes and the storage class.

23.7.6. Creating a NGINX Pod That Uses the PVC

At this point, you have a dynamically created GlusterFS volume bound to a PVC. You can now now utilize this PVC in a pod. In this example, create a simple NGINX pod.

1. Create the pod object definition:

```

apiVersion: v1
kind: Pod
metadata:
  name: gluster-pod1

```

```

labels:
  name: gluster-pod1
spec:
  containers:
  - name: gluster-pod1
    image: gcr.io/google_containers/nginx-slim:0.8
    ports:
    - name: web
      containerPort: 80
    securityContext:
      privileged: true
    volumeMounts:
    - name: gluster-vol1
      mountPath: /usr/share/nginx/html
  volumes:
  - name: gluster-vol1
    persistentVolumeClaim:
      claimName: gluster-dyn-pvc ❶

```

❶ The name of the PVC created in the previous step.

- From the OpenShift Container Platform master host, create the pod:

```

# oc create -f nginx-pod.yaml
pod "gluster-pod1" created

```

- View the pod. Give it a few minutes, as it might need to download the image if it does not already exist:

```

# oc get pods -o wide

```

NAME	READY	STATUS	RESTARTS
gluster-pod1	1/1	Running	0

```


```

- Now remote into the container with **oc exec** and create an *index.html* file:

```

# oc exec -ti gluster-pod1 /bin/sh
$ cd /usr/share/nginx/html
$ echo 'Hello World from GlusterFS!!!' > index.html
$ ls
index.html
$ exit

```

- Now **curl** the URL of the pod:

```

# curl http://10.38.0.0
Hello World from GlusterFS!!!

```

23.8. EXAMPLE: CONTAINERIZED HEKETI FOR MANAGING DEDICATED GLUSTERFS STORAGE

23.8.1. Overview

This example provides information about the integration, deployment, and management of GlusterFS containerized storage nodes by using Heketi running on OpenShift Container Platform.

This example:

- Shows how to install and configure a Heketi server on OpenShift to perform dynamic provisioning.
- Assumes you have familiarity with Kubernetes and the Kubernetes Persistent Storage model.
- Assumes you have access to an existing, dedicated GlusterFS cluster that has raw devices available for consumption and management by a Heketi server. If you do not have this, you can create a three node cluster using your virtual machine solution of choice. Ensure sure you create a few raw devices and give plenty of space (at least 100GB recommended). See [Red Hat Gluster Storage Installation Guide](#).

23.8.2. Environment and Prerequisites

This example uses the following environment and prerequisites:

- GlusterFS cluster running Red Hat Gluster Storage (RHGS) 3.1. Three nodes, each with at least two 100GB RAW devices:
 - **gluster23.rhs** (192.168.1.200)
 - **gluster24.rhs** (192.168.1.201)
 - **gluster25.rhs** (192.168.1.202)
- This example uses an all-in-one OpenShift Container Platform cluster (master and node on a single host), though it can work using a standard, multi-node cluster as well.
 - **k8dev2.rhs** (192.168.1.208)

23.8.3. Installing and Configuring Heketi

Heketi is used to manage the Gluster cluster storage (adding volumes, removing volumes, etc.). Download [deploy-heketi-template](#) to install Heketi on OpenShift.



NOTE

This template file places the database in an EmptyDir volume. Adjust the database accordingly for a reliable persistent storage.

1. Create a new project:

```
$ oc new-project <project-name>
```

2. Enable privileged containers in the new project:

```
$ oc adm policy add-scc-to-user privileged -z default
```

3. Register the **deploy-heketi** template:

```
$ oc create -f <template-path>/deploy-heketi-template
```

4. Deploy the bootstrap Heketi container:

```
$ oc process deploy-heketi -v \
    HEKETI_KUBE_NAMESPACE=<project-name> \
    HEKETI_KUBE_APIHOST=<master-url-and-port> \
    HEKETI_KUBE_INSECURE=y \
    HEKETI_KUBE_USER=<cluster-admin-username> \
    HEKETI_KUBE_PASSWORD=<cluster-admin-password> | oc create -
f -
```

5. Wait until the **deploy-heketi** pod starts and all services are running. Then get Heketi service details:

```
$ oc get svc
```

NAME	CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE
deploy-heketi	172.30.96.173	<none>	8080/TCP	2m

6. Check if Heketi services are running properly, it must return **Hello from Heketi**.

```
$ curl http://<cluster-ip>:8080/hello
Hello from Heketi
```

7. Set an environment variable for the Heketi server:

```
$ export HEKETI_CLI_SERVER=http://<cluster-ip>:8080
```

23.8.4. Loading Topology

Topology is used to tell Heketi about the environment and what nodes and devices it will manage.



NOTE

Heketi is currently limited to managing raw devices only. If a device is already a Gluster volume, it is skipped and ignored.

1. Create and load the topology file. There is a sample file located in ***/usr/share/heketi/topology-sample.json*** by default, or ***/etc/heketi*** depending on how it was installed.



NOTE

Depending upon your method of installation this file may not exist. If it is missing, manually create the ***topology-sample.json*** file, as shown in the following example.

```
{
  "clusters": [
    {
      "nodes": [
        {
```

```

    "node": {
      "hostnames": {
        "manage": [
          "gluster23.rhs"
        ],
        "storage": [
          "192.168.1.200"
        ]
      },
      "zone": 1
    },
    "devices": [
      "/dev/sde",
      "/dev/sdf"
    ]
  },
  {
    "node": {
      "hostnames": {
        "manage": [
          "gluster24.rhs"
        ],
        "storage": [
          "192.168.1.201"
        ]
      },
      "zone": 1
    },
    "devices": [
      "/dev/sde",
      "/dev/sdf"
    ]
  },
  {
    "node": {
      "hostnames": {
        "manage": [
          "gluster25.rhs"
        ],
        "storage": [
          "192.168.1.202"
        ]
      },
      "zone": 1
    },
    "devices": [
      "/dev/sde",
      "/dev/sdf"
    ]
  }
]
}

```

2. Run the following command to load the topology of your environment.

```
$ heketi-cli topology load --json=topology-sample.json

Found node gluster23.rhs on cluster
bdf9d8ca3fa269ff89854faf58f34b9a
Adding device /dev/sde ... OK
Adding device /dev/sdf ... OK
Creating node gluster24.rhs ... ID:
8e677d8bebe13a3f6846e78a67f07f30
Adding device /dev/sde ... OK
Adding device /dev/sdf ... OK
...
```

3. Create a Gluster volume to verify Heketi:

```
$ heketi-cli volume create --size=50
```

4. View the volume information from one of the the Gluster nodes:

```
$ gluster volume info

Volume Name: vol_335d247ac57ecdf40ac616514cc6257f 1
Type: Distributed-Replicate
Volume ID: 75be7940-9b09-4e7f-bfb0-a7eb24b411e3
Status: Started
...
```

- 1** Volume created by **heketi-cli**.

23.8.5. Dynamically Provision a Volume



NOTE

If you installed OpenShift Container Platform by using the [BYO \(Bring your own\) OpenShift Ansible inventory configuration files](#) for either [native](#) or [external](#) GlusterFS instance, the GlusterFS StorageClass automatically get created during the installation. For such cases you can skip the following storage class creation steps and directly proceed with creating persistent volume claim instruction.

1. Create a **StorageClass** object definition. The following definition is based on the minimum requirements needed for this example to work with OpenShift Container Platform. See [Dynamic Provisioning and Creating Storage Classes](#) for additional parameters and specification definitions.

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: gluster-dyn
provisioner: kubernetes.io/glusterfs
parameters:
  resturl: "http://glusterclient2.rhs:8080" 1
  restauthenabled: "false" 2
```

1 The Heketi server from the **HEKETI_CLI_SERVER** environment variable.

2 Since authentication is not turned on in this example, set to **false**.

2. From the OpenShift Container Platform master host, create the storage class:

```
$ oc create -f glusterfs-storageclass1.yaml
storageclass "gluster-dyn" created
```

3. Create a persistent volume claim (PVC), requesting the newly-created storage class. For example:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-dyn-pvc
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 30Gi
  storageClassName: gluster-dyn
```

4. From the OpenShift Container Platform master host, create the PVC:

```
$ oc create -f glusterfs-pvc-storageclass.yaml
persistentvolumeclaim "gluster-dyn-pvc" created
```

5. View the PVC to see that the volume was dynamically created and bound to the PVC:

```
$ oc get pvc
NAME                                STATUS VOLUME
CAPACITY  ACCESSMODES  STORAGECLASS  AGE
gluster-dyn-pvc Bound pvc-78852230-d8e2-11e6-a3fa-0800279cf26f
30Gi      RWX          gluster-dyn  42s
```

6. Verify and view the new volume on one of the Gluster nodes:

```
$ gluster volume info

Volume Name: vol_335d247ac57ecdf40ac616514cc6257f 1
Type: Distributed-Replicate
Volume ID: 75be7940-9b09-4e7f-bfb0-a7eb24b411e3
Status: Started
...
Volume Name: vol_f1404b619e6be6ef673e2b29d58633be 2
Type: Distributed-Replicate
Volume ID: 7dc234d0-462f-4c6c-add3-fb9bc7e8da5e
Status: Started
Number of Bricks: 2 x 2 = 4
...
```

- 1 Volume created by **heketi-cli**.
- 2 New dynamically created volume triggered by Kubernetes and the storage class.

23.8.6. Creating a NGINX Pod That Uses the PVC

At this point, you have a dynamically created GlusterFS volume bound to a PVC. You can now now utilize this PVC in a pod. In this example, create a simple NGINX pod.

1. Create the pod object definition:

```
apiVersion: v1
kind: Pod
metadata:
  name: gluster-pod1
  labels:
    name: gluster-pod1
spec:
  containers:
  - name: gluster-pod1
    image: gcr.io/google_containers/nginx-slim:0.8
    ports:
    - name: web
      containerPort: 80
    securityContext:
      privileged: true
    volumeMounts:
    - name: gluster-vol1
      mountPath: /usr/share/nginx/html
  volumes:
  - name: gluster-vol1
    persistentVolumeClaim:
      claimName: gluster-dyn-pvc 1
```

- 1 The name of the PVC created in the previous step.

2. From the OpenShift Container Platform master host, create the pod:

```
$ oc create -f nginx-pod.yaml
pod "gluster-pod1" created
```

3. View the pod. Give it a few minutes, as it might need to download the image if it does not already exist:

```
$ oc get pods -o wide
```

NAME	READY	STATUS	RESTARTS
gluster-pod1	1/1	Running	0

4. Now remote into the container with **oc exec** and create an **index.html** file:

```
$ oc exec -ti gluster-pod1 /bin/sh
```



```
$ cd /usr/share/nginx/html
$ echo 'Hello World from GlusterFS!!!' > index.html
$ ls
index.html
$ exit
```

5. Now **curl** the URL of the pod:

```
$ curl http://10.38.0.0
Hello World from GlusterFS!!!
```

23.9. MOUNTING VOLUMES ON PRIVILEGED PODS

23.9.1. Overview

Persistent volumes can be mounted to pods with the **privileged** security context constraint (SCC) attached.



NOTE

While this topic uses GlusterFS as a sample use-case for mounting volumes onto privileged pods, it can be adapted to use any [supported storage plug-in](#).

23.9.2. Prerequisites

- An existing Gluster volume.
- **glusterfs-fuse** installed on all hosts.
- Definitions for GlusterFS:
 - [Endpoints and services](#): **gluster-endpoints-service.yaml** and **gluster-endpoints.yaml**
 - [Persistent volumes](#): **gluster-pv.yaml**
 - [Persistent volume claims](#): **gluster-pvc.yaml**
 - [Privileged pods](#): **gluster-S3-pod.yaml**
- A user with the **cluster-admin** role binding. For this guide, that user is called **admin**.

23.9.3. Creating the Persistent Volume

Creating the **PersistentVolume** makes the storage accessible to users, regardless of projects.

1. As the admin, create the service, endpoint object, and persistent volume:

```
$ oc create -f gluster-endpoints-service.yaml
$ oc create -f gluster-endpoints.yaml
$ oc create -f gluster-pv.yaml
```

2. Verify that the objects were created:

```
$ oc get svc
NAME                                CLUSTER_IP          EXTERNAL_IP    PORT(S)    SELECTOR
AGE
gluster-cluster                    172.30.151.58       <none>         1/TCP      <none>
24s
```

```
$ oc get ep
NAME                                ENDPOINTS                                AGE
gluster-cluster                    192.168.59.102:1,192.168.59.103:1      2m
```

```
$ oc get pv
NAME                                LABELS    CAPACITY    ACCESSMODES    STATUS
CLAIM      REASON    AGE
gluster-default-volume <none>    2Gi        RWX
Available                                     2d
```

23.9.4. Creating a Regular User

Adding a [regular user](#) to the **privileged** SCC (or to a group given access to the SCC) allows them to run **privileged** pods:

1. As the admin, add a user to the SCC:

```
$ oc adm policy add-scc-to-user privileged <username>
```

2. Log in as the regular user:

```
$ oc login -u <username> -p <password>
```

3. Then, create a new project:

```
$ oc new-project <project_name>
```

23.9.5. Creating the Persistent Volume Claim

1. As a regular user, create the **PersistentVolumeClaim** to access the volume:

```
$ oc create -f gluster-pvc.yaml -n <project_name>
```

2. Define your pod to access the claim:

Example 23.15. Pod Definition

```
apiVersion: v1
id: gluster-S3-pvc
kind: Pod
metadata:
  name: gluster-nginx-priv
spec:
  containers:
    - name: gluster-nginx-priv
      image: fedora/nginx
      volumeMounts:
```

```

        - mountPath: /mnt/gluster ❶
          name: gluster-volume-claim
        securityContext:
          privileged: true
      volumes:
        - name: gluster-volume-claim
          persistentVolumeClaim:
            claimName: gluster-claim ❷

```

❶ Volume mount within the pod.

❷ The **gluster-claim** must reflect the name of the **PersistentVolume**.

3. Upon pod creation, the mount directory is created and the volume is attached to that mount point.

As regular user, create a pod from the definition:

```
$ oc create -f gluster-S3-pod.yaml
```

4. Verify that the pod created successfully:

```
$ oc get pods
NAME                READY   STATUS    RESTARTS   AGE
gluster-S3-pod      1/1     Running   0           36m

```

It can take several minutes for the pod to create.

23.9.6. Verifying the Setup

23.9.6.1. Checking the Pod SCC

1. Export the pod configuration:

```
$ oc export pod <pod_name>
```

2. Examine the output. Check that **openshift.io/scc** has the value of **privileged**:

Example 23.16. Export Snippet

```

metadata:
  annotations:
    openshift.io/scc: privileged

```

23.9.6.2. Verifying the Mount

1. Access the pod and check that the volume is mounted:

```
$ oc rsh <pod_name>
[root@gluster-S3-pvc /]# mount

```

2. Examine the output for the Gluster volume:

Example 23.17. Volume Mount

```
192.168.59.102:gv0 on /mnt/gluster type fuse.gluster
(rw,relatime,user_id=0,group_id=0,default_permissions,allow_other,
max_read=131072)
```

23.10. BACKING DOCKER REGISTRY WITH GLUSTERFS STORAGE

23.10.1. Overview

This topic reviews how to attach a GlusterFS persistent volume to the Docker Registry.

It is assumed that the Docker registry service has already been started and the Gluster volume has been created.

23.10.2. Prerequisites

- The [docker-registry](#) was deployed **without** configuring storage.
- A Gluster volume exists and **glusterfs-fuse** is installed on schedulable nodes.
- Definitions written for GlusterFS [endpoints and service](#), [persistent volume \(PV\)](#), and [persistent volume claim \(PVC\)](#).
 - For this guide, these will be:
 - ***gluster-endpoints-service.yaml***
 - ***gluster-endpoints.yaml***
 - ***gluster-pv.yaml***
 - ***gluster-pvc.yaml***
- A user with the [cluster-admin](#) role binding.
 - For this guide, that user is **admin**.

**NOTE**

All **oc** commands are executed on the master node as the **admin** user.

23.10.3. Create the Gluster Persistent Volume

First, make the Gluster volume available to the registry.

```
$ oc create -f gluster-endpoints-service.yaml
$ oc create -f gluster-endpoints.yaml
$ oc create -f gluster-pv.yaml
$ oc create -f gluster-pvc.yaml
```

Check to make sure the PV and PVC were created and bound successfully. The expected output should resemble the following. Note that the PVC status is **Bound**, indicating that it has bound to the PV.

```
$ oc get pv
NAME          LABELS      CAPACITY  ACCESSMODES  STATUS      CLAIM
REASON      AGE
gluster-pv    <none>     1Gi       RWX           Available
37s
$ oc get pvc
NAME          LABELS      STATUS     VOLUME        CAPACITY  ACCESSMODES
AGE
gluster-claim <none>     Bound      gluster-pv    1Gi       RWX
24s
```



NOTE

If either the PVC or PV failed to create or the PVC failed to bind, refer back to the [GlusterFS Persistent Storage](#) guide. **Do not** proceed until they initialize and the PVC status is **Bound**.

23.10.4. Attach the PVC to the Docker Registry

Before moving forward, ensure that the **docker-registry** service is running.

```
$ oc get svc
NAME          CLUSTER_IP      EXTERNAL_IP  PORT(S)
SELECTOR      AGE
docker-registry 172.30.167.194  <none>       5000/TCP
docker-registry=default 18m
```



NOTE

If either the **docker-registry** service or its associated pod is not running, refer back to the [docker-registry](#) setup instructions for troubleshooting before continuing.

Then, attach the PVC:

```
$ oc volume deploymentconfigs/docker-registry --add --name=registry-storage -t pvc \
    --claim-name=gluster-claim --overwrite
```

[Deploying a Docker Registry](#) provides more information on using the Docker registry.

23.10.5. Known Issues

23.10.5.1. Pod Cannot Resolve the Volume Host

In non-production cases where the **dnsmasq** server is located on the same node as the OpenShift Container Platform master service, pods might not resolve to the host machines when mounting the volume, causing errors in the **docker-registry-1-deploy** pod. This can happen when **dnsmasq.service** fails to start because of a collision with OpenShift Container Platform DNS on port 53. To run the DNS server on the master host, some configurations needs to be changed.

In **/etc/dnsmasq.conf**, add:

```
# Reverse DNS record for master
host-record=master.example.com,<master-IP>
# Wildcard DNS for OpenShift Applications - Points to Router
address=/apps.example.com/<master-IP>
# Forward .local queries to SkyDNS
server=/local/127.0.0.1#8053
# Forward reverse queries for service network to SkyDNS.
# This is for default OpenShift SDN - change as needed.
server=/17.30.172.in-addr.arpa/127.0.0.1#8053
```

With these settings, **dnsmasq** will pull from the **/etc/hosts** file on the master node.

Add the appropriate host names and IPs for all necessary hosts.

In **master-config.yaml**, change **bindAddress** to:

```
dnsConfig:
  bindAddress: 127.0.0.1:8053
```

When pods are created, they receive a copy of **/etc/resolv.conf**, which typically contains only the master DNS server so they can resolve external DNS requests. To enable internal DNS resolution, insert the **dnsmasq** server at the top of the server list. This way, **dnsmasq** will attempt to resolve requests internally first.

In **/etc/resolv.conf** all scheduled nodes:

```
nameserver 192.168.1.100 ❶
nameserver 192.168.1.1   ❷
```

- ❶ Add the internal DNS server.
- ❷ Pre-existing external DNS server.

Once the configurations are changed, restart the OpenShift Container Platform master and **dnsmasq** services.

```
$ systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
$ systemctl restart dnsmasq
```

23.11. BINDING PERSISTENT VOLUMES BY LABELS

23.11.1. Overview

This topic provides an end-to-end example for binding [persistent volume claims \(PVCs\)](#) to [persistent volumes \(PVs\)](#), by defining labels in the PV and matching selectors in the PVC. This feature is available for all [storage options](#). It is assumed that a OpenShift Container Platform cluster contains persistent storage resources which are available for binding by PVCs.

A Note on Labels and Selectors

Labels are an OpenShift Container Platform feature that support user-defined tags (key-value pairs) as part of an object's specification. Their primary purpose is to enable the arbitrary grouping of objects by defining identical labels among them. These labels can then be targeted by selectors to match all objects with specified label values. It is this functionality we will take advantage of to enable our PVC to bind to our PV. For a more in-depth look at labels, see [Pods and Services](#).



NOTE


For this example, we will be using modified [GlusterFS](#) PV and PVC specifications. However, implementation of selectors and labels is generic across for all storage options. See the [relevant storage option](#) for your volume provider to learn more about its unique configuration.

23.11.1.1. Assumptions

It is assumed that you have:

- An existing OpenShift Container Platform cluster with at least one **master** and one **node**
- At least one supported [storage volume](#)
- A user with **cluster-admin** privileges

23.11.2. Defining Specifications



NOTE

These specifications are tailored to **GlusterFS**. Consult the [relevant storage option](#) for your volume provider to learn more about its unique configuration.

23.11.2.1. Persistent Volume with Labels

Example 23.18. glusterfs-pv.yaml

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-volume
  labels: ❶
    storage-tier: gold
    aws-availability-zone: us-east-1
spec:
  capacity:
    storage: 2Gi
  accessModes:
    - ReadWriteMany
  glusterfs:
    endpoints: glusterfs-cluster ❷
    path: myVol1
    readOnly: false
  persistentVolumeReclaimPolicy: Retain
```

- 1 Use labels to identify common attributes or characteristics shared among volumes. In this case, we defined the Gluster volume to have a custom attribute (key) named **storage-tier** with a value of **gold** assigned. A claim will be able to select a PV with **storage-tier=gold** to match this PV.
- 2 Endpoints define the Gluster trusted pool and are discussed below.

23.11.2.2. Persistent Volume Claim with Selectors

A claim with a **selector** stanza (see example below) attempts to match existing, unclaimed, and non-prebound PVs. The existence of a PVC selector ignores a PV's capacity. However, **accessModes** are still considered in the matching criteria.

It is important to note that a claim must match **all** of the key-value pairs included in its **selector** stanza. If no PV matches the claim, then the PVC will remain unbound (Pending). A PV can subsequently be created and the claim will automatically check for a label match.

Example 23.19. glusterfs-pvc.yaml

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 1Gi
  selector: 1
    matchLabels:
      storage-tier: gold
      aws-availability-zone: us-east-1
```

- 1 The **selector** stanza defines all labels necessary in a PV in order to match this claim.

23.11.2.3. Volume Endpoints

To attach the PV to the Gluster volume, endpoints should be configured before creating our objects.

Example 23.20. glusterfs-ep.yaml

```
apiVersion: v1
kind: Endpoints
metadata:
  name: glusterfs-cluster
subsets:
  - addresses:
      - ip: 192.168.122.221
    ports:
```



```

- port: 1
- addresses:
  - ip: 192.168.122.222
ports:
  - port: 1

```

23.11.2.4. Deploy the PV, PVC, and Endpoints

For this example, run the **oc** commands as a **cluster-admin** privileged user. In a production environment, cluster clients might be expected to define and create the PVC.

```

# oc create -f glusterfs-ep.yaml
endpoints "glusterfs-cluster" created
# oc create -f glusterfs-pv.yaml
persistentvolume "gluster-volume" created
# oc create -f glusterfs-pvc.yaml
persistentvolumeclaim "gluster-claim" created

```

Lastly, confirm that the PV and PVC bound successfully.

```

# oc get pv,pvc
NAME                                CAPACITY  ACCESSMODES  STATUS  CLAIM
REASON  AGE
gluster-volume  2Gi       RWX          Bound   gfs-
trial/gluster-claim              7s
NAME                                STATUS  VOLUME  CAPACITY  ACCESSMODES
AGE
gluster-claim  Bound   gluster-volume  2Gi       RWX
7s

```



NOTE

PVCs are local to a project, whereas PVs are a cluster-wide, global resource. Developers and non-administrator users may not have access to see all (or any) of the available PVs.

23.12. USING STORAGE CLASSES FOR DYNAMIC PROVISIONING

23.12.1. Overview

In these examples we will walk through a few scenarios of various configurations of [StorageClasses](#) and Dynamic Provisioning using Google Cloud Platform Compute Engine (GCE). These examples assume some familiarity with Kubernetes, GCE and Persistent Disks and OpenShift Container Platform is installed and [properly configured to use GCE](#).

- [Basic Dynamic Provisioning](#)
- [Defaulting Cluster Dynamic Provisioning Behavior](#)

23.12.2. Scenario 1: Basic Dynamic Provisioning with Two Types of *StorageClasses*

StorageClasses can be used to differentiate and delineate storage levels and usages. In this case, the **cluster-admin** or **storage-admin** sets up two distinct classes of storage in GCE.

- **slow**: Cheap, efficient, and optimized for sequential data operations (slower reading and writing)
- **fast**: Optimized for higher rates of random IOPS and sustained throughput (faster reading and writing)

By creating these *StorageClasses*, the **cluster-admin** or **storage-admin** allows users to create claims requesting a particular level or service of *StorageClass*.

Example 23.21. StorageClass Slow Object Definitions

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow ❶
provisioner: kubernetes.io/gce-pd ❷
parameters:
  type: pd-standard ❸
  zone: us-east1-d ❹
```

- ❶ Name of the *StorageClass*.
- ❷ The provisioner plug-in to be used. This is a required field for *StorageClasses*.
- ❸ PD type. This example uses **pd-standard**, which has a slightly lower cost, rate of sustained IOPS, and throughput versus **pd-ssd**, which carries more sustained IOPS and throughput.
- ❹ The zone is required.

Example 23.22. StorageClass Fast Object Definition


```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: fast
provisioner: kubernetes.io/gce-pd
parameters:
  type: pd-ssd
  zone: us-east1-d
```

As a **cluster-admin** or **storage-admin**, save both definitions as YAML files. For example, **slow-gce.yaml** and **fast-gce.yaml**. Then create the *StorageClasses*.

```
# oc create -f slow-gce.yaml
storageclass "slow" created

# oc create -f fast-gce.yaml
storageclass "fast" created
```

```
# oc get storageclass
NAME          TYPE
fast          kubernetes.io/gce-pd
slow          kubernetes.io/gce-pd
```



IMPORTANT

cluster-admin or **storage-admin** users are responsible for relaying the correct *StorageClass* name to the correct users, groups, and projects.

As a regular user, create a new project:

```
# oc new-project rh-eng
```

Create the claim YAML definition, save it to a file (**pvc-fast.yaml**):


```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-engineering
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 10Gi
  storageClassName: fast
```

Add the claim with the **oc create** command:

```
# oc create -f pvc-fast.yaml
persistentvolumeclaim "pvc-engineering" created
```

Check to see if your claim is bound:

```
# oc get pvc
NAME          STATUS    VOLUME
CAPACITY     ACCESSMODES  AGE
pvc-engineering  Bound      pvc-e9b4fef7-8bf7-11e6-9962-42010af00004
10Gi         RWX          2m
```




IMPORTANT

Since this claim was created and bound in the *rh-eng* project, it can be shared by any user in the same project.

As a **cluster-admin** or **storage-admin** user, view the recent dynamically provisioned Persistent Volume (PV).

```
# oc get pv
NAME          CAPACITY  ACCESSMODES
```

RECLAIMPOLICY	STATUS	CLAIM	REASON	AGE
pvc-e9b4fef7-8bf7-11e6-9962-42010af00004	10Gi			
Delete	Bound	rh-eng/pvc-engineering	RWX	5m



IMPORTANT

Notice the [RECLAIMPOLICY](#) is *Delete* by default for all dynamically provisioned volumes. This means the volume only lasts as long as the claim still exists in the system. If you delete the claim, the volume is also deleted and all data on the volume is lost.

Finally, check the GCE console. The new disk has been created and is ready for use.

```
kubernetes-dynamic-pvc-e9b4fef7-8bf7-11e6-9962-42010af00004  SSD
persistent disk 10 GB us-east1-d
```

Pods can now reference the persistent volume claim and start using the volume.

23.12.3. Scenario 2: How to enable Default *StorageClass* behavior for a Cluster

In this example, a **cluster-admin** or **storage-admin** enables a *default* storage class for all other users and projects that do not implicitly specify a *StorageClass* in their claim. This is useful for a **cluster-admin** or **storage-admin** to provide easy management of a storage volume without having to set up or communicate specialized *StorageClasses* across the cluster.

This example builds upon [Section 23.12.2, “Scenario 1: Basic Dynamic Provisioning with Two Types of *StorageClasses*”](#). The **cluster-admin** or **storage-admin** will create another *StorageClass* for designation as the *defaultStorageClass*.

Example 23.23. Default *StorageClass* Object Definition

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: generic ①
  annotations:
    storageclass.kubernetes.io/is-default-class: "true" ②
provisioner: kubernetes.io/gce-pd
parameters:
  type: pd-standard
  zone: us-east1-d
```

- ① Name of the *StorageClass*, which needs to be unique in the cluster.
- ② Annotation that marks this *StorageClass* as the default class. You must use **"true"** quoted in this version of the API. Without this annotation, OpenShift Container Platform considers this not the *default StorageClass*.

As a **cluster-admin** or **storage-admin** save the definition to a YAML file (**generic-gce.yaml**), then create the *StorageClasses*:

```
# oc create -f generic-gce.yaml
```

```
storageclass "generic" created

# oc get storageclass
NAME          TYPE
generic       kubernetes.io/gce-pd
fast          kubernetes.io/gce-pd
slow          kubernetes.io/gce-pd
```

As a regular user, create a new claim definition without any *StorageClass* requirement and save it to a file (**generic-pvc.yaml**).

Example 23.24. *default* Storage Claim Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-engineering2
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 5Gi
```

Execute it and check the claim is bound:

```
# oc create -f generic-pvc.yaml
persistentvolumeclaim "pvc-engineering2" created

# oc get pvc
NAME          STATUS    VOLUME
CAPACITY    ACCESSMODES  AGE
pvc-engineering  Bound      pvc-e9b4fef7-8bf7-11e6-9962-42010af00004
10Gi         RWX         41m
pvc-engineering2  Bound      pvc-a9f70544-8bfd-11e6-9962-42010af00004
5Gi          RWX         7s  ❶
```

❶ **pvc-engineering2** is bound to a dynamically provisioned Volume by *default*.

As a **cluster-admin** or **storage-admin**, view the Persistent Volumes defined so far:

```
# oc get pv
NAME          CAPACITY    ACCESSMODES
RECLAIMPOLICY STATUS    CLAIM
pvc-a9f70544-8bfd-11e6-9962-42010af00004  5Gi         RWX
Delete       Bound      rh-eng/pvc-engineering2
pvc-ba4612ce-8b4d-11e6-9962-42010af00004  5Gi         RWX
Delete       Bound      mytest/gce-dyn-claim1
pvc-e9b4fef7-8bf7-11e6-9962-42010af00004  10Gi        RWX
Delete       Bound      rh-eng/pvc-engineering
```

- 1 This PV was bound to our *default* dynamic volume from the *default StorageClass*.
- 2 This PV was bound to our first PVC from [Section 23.12.2, “Scenario 1: Basic Dynamic Provisioning with Two Types of StorageClasses”](#) with our *fast StorageClass*.

Create a manually provisioned disk using [GCE](#) (not dynamically provisioned). Then create a [Persistent Volume](#) that connects to the new GCE disk (**pv-manual-gce.yaml**).

Example 23.25. Manual PV Object Definition

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv-manual-gce
spec:
  capacity:
    storage: 35Gi
  accessModes:
    - ReadWriteMany
  gcePersistentDisk:
    readOnly: false
    pdName: the-newly-created-gce-PD
    fsType: ext4
```

Execute the object definition file:

```
# oc create -f pv-manual-gce.yaml
```

Now view the PVs again. Notice that a **pv-manual-gce** volume is *Available*.

```
# oc get pv
NAME                                CAPACITY  ACCESSMODES  REASON  AGE
RECLAIMPOLICY  STATUS      CLAIM
pv-manual-gce  35Gi       RWX
Retain         Available
pvc-a9f70544-8bfd-11e6-9962-42010af00004  5Gi       RWX
Delete         Bound       rh-eng/pvc-engineering2  12m
pvc-ba4612ce-8b4d-11e6-9962-42010af00004  5Gi       RW0
Delete         Bound       mytest/gce-dyn-claim1    21h
pvc-e9b4fef7-8bf7-11e6-9962-42010af00004  10Gi      RWX
Delete         Bound       rh-eng/pvc-engineering    53m
```

Now create another claim identical to the **generic-pvc.yaml** PVC definition but change the name and do not set a storage class name.

Example 23.26. Claim Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-engineering3
spec:
```

```

accessModes:
  - ReadWriteMany
resources:
  requests:
    storage: 15Gi

```

Because *default StorageClass* is enabled in this instance, the manually created PV does not satisfy the claim request. The user receives a new dynamically provisioned Persistent Volume.

```

# oc get pvc
NAME                                STATUS    VOLUME
CAPACITY  ACCESSMODES  AGE
pvc-engineering    Bound      pvc-e9b4fef7-8bf7-11e6-9962-42010af00004
10Gi          RWX          1h
pvc-engineering2    Bound      pvc-a9f70544-8bfd-11e6-9962-42010af00004
5Gi          RWX          19m
pvc-engineering3    Bound      pvc-6fa8e73b-8c00-11e6-9962-42010af00004
15Gi          RWX          6s

```



IMPORTANT

Since the *default StorageClass* is enabled on this system, for the manually created Persistent Volume to get bound by the above claim and not have a new dynamic provisioned volume be bound, the PV would need to have been created in the *default StorageClass*.

Since the *default StorageClass* is enabled on this system, you would need to create the PV in the *default StorageClass* for the manually created Persistent Volume to get bound to the above claim and not have a new dynamic provisioned volume bound to the claim.

To fix this, the **cluster-admin** or **storage-admin** user simply needs to create another GCE disk or delete the first manual PV and use a PV object definition that assigns a *StorageClass* name (**pv-manual-gce2.yaml**) if necessary:

Example 23.27. Manual PV Spec with *default StorageClass* name

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv-manual-gce2
spec:
  capacity:
    storage: 35Gi
  accessModes:
    - ReadWriteMany
  gcePersistentDisk:
    readOnly: false
    pdName: the-newly-created-gce-PD
    fsType: ext4
  storageClassName: generic ❶

```

❶ The name for previously created *generic StorageClass*.

Execute the object definition file:

```
# oc create -f pv-manual-gce2.yaml
```

List the PVs:

```
# oc get pv
NAME                                     CAPACITY  ACCESSMODES
RECLAIMPOLICY  STATUS      CLAIM                                     REASON  AGE
pv-manual-gce  Retain      Available                                     4s 1
pv-manual-gce2  Retain      Bound      rh-eng/pvc-engineering3               4s 2
pvc-a9f70544-8bfd-11e6-9962-42010af00004  5Gi       RWX
Delete         Bound      rh-eng/pvc-engineering2               12m
pvc-ba4612ce-8b4d-11e6-9962-42010af00004  5Gi       RW0
Delete         Bound      mytest/gce-dyn-claim1                 21h
pvc-e9b4fef7-8bf7-11e6-9962-42010af00004  10Gi      RWX
Delete         Bound      rh-eng/pvc-engineering                 53m
```

- 1** The original manual PV, still unbound and Available. This is because it was not created in the *default StorageClass*.
- 2** The second PVC (other than the name) is bound to the Available manually created PV **pv-manual-gce2**.



IMPORTANT

Notice that all dynamically provisioned volumes by default have a *RECLAIMPOLICY* of *Delete*. Once the PVC dynamically bound to the PV is deleted, the GCE volume is deleted and all data is lost. However, the manually created PV has a default *RECLAIMPOLICY* of *Retain*.

23.13. USING STORAGE CLASSES FOR EXISTING LEGACY STORAGE

23.13.1. Overview

In this example, a legacy data volume exists and a **cluster-admin** or **storage-admin** needs to make it available for consumption in a particular project. Using *StorageClasses* decreases the likelihood of other users and projects gaining access to this volume from a claim because the claim would have to have an exact matching value for the *StorageClass* name. This example also disables dynamic provisioning. This example assumes:

- Some familiarity with OpenShift Container Platform, GCE, and Persistent Disks
- OpenShift Container Platform is [properly configured to use GCE](#).

23.13.1.1. Scenario 1: Link StorageClass to existing Persistent Volume with Legacy Data

As a **cluster-admin** or **storage-admin**, define and create the *StorageClass* for historical financial data.

Example 23.28. StorageClass finance-history Object Definitions


```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: finance-history ❶
provisioner: no-provisioning ❷
parameters: ❸
```

- ❶ Name of the StorageClass.
- ❷ This is a required field, but since there is to be no dynamic provisioning, a value must be put here as long as it is not an actual provisioner plug-in type.
- ❸ Parameters can simply be left blank, since these are only used for the dynamic provisioner.

Save the definitions to a YAML file (**finance-history-storageclass.yaml**) and create the *StorageClass*.

```
# oc create -f finance-history-storageclass.yaml
storageclass "finance-history" created

# oc get storageclass
NAME                TYPE
finance-history     no-provisioning
```



IMPORTANT

cluster-admin or **storage-admin** users are responsible for relaying the correct *StorageClass* name to the correct users, groups, and projects.

The *StorageClass* exists. A **cluster-admin** or **storage-admin** can create the Persistent Volume (PV) for use with the *StorageClass*. Create a manually provisioned disk using [GCE](#) (not dynamically provisioned) and a [Persistent Volume](#) that connects to the new GCE disk (**gce-pv.yaml**).

Example 23.29. Finance History PV Object

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv-finance-history
spec:
  capacity:
    storage: 35Gi
  accessModes:
    - ReadWriteMany
  gcePersistentDisk:
```

```
readOnly: false
pdName: the-existing-PD-volume-name-that-contains-the-valuable-data
1 fsType: ext4
storageClassName: finance-history 2
```

2 The *StorageClass* name, that must match exactly.

1 The name of the GCE disk that already exists and contains the legacy data.

As a **cluster-admin** or **storage-admin**, create and view the PV.

```
# oc create -f gce-pv.yaml
persistentvolume "pv-finance-history" created

# oc get pv
NAME                                CAPACITY  ACCESSMODES  RECLAIMPOLICY  STATUS
CLAIM                                REASON    AGE
pv-finance-history 35Gi      RWX          Retain         Available
2d
```

Notice you have a **pv-finance-history** Available and ready for consumption.

As a user, create a Persistent Volume Claim (PVC) as a YAML file and specify the correct *StorageClass* name:

Example 23.30. Claim for finance-history Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-finance-history
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 20Gi
storageClassName: finance-history 1
```

1 The *StorageClass* name, that must match exactly or the claim will go unbound until it is deleted or another *StorageClass* is created that matches the name.

Create and view the PVC and PV to see if it is bound.

```
# oc create -f pvc-finance-history.yaml
persistentvolumeclaim "pvc-finance-history" created

# oc get pvc
NAME                                STATUS  VOLUME  CAPACITY
```

```

ACCESSMODES   AGE
pvc-finance-history   Bound      pv-finance-history   35Gi      RWX
9m

# oc get pv (cluster/storage-admin)
NAME              CAPACITY   ACCESSMODES   RECLAIMPOLICY   STATUS
CLAIM              REASON     AGE
pv-finance-history   35Gi      RWX           Retain          Bound
default/pvc-finance-history              5m

```



IMPORTANT

You can use *StorageClasses* in the same cluster for both legacy data (no dynamic provisioning) and with [dynamic provisioning](#).

23.14. CONFIGURING AZURE BLOB STORAGE FOR INTEGRATED DOCKER REGISTRY

23.14.1. Overview

This topic reviews how to configure [Microsoft Azure Blob Storage](#) for [OpenShift integrated Docker registry](#).

23.14.2. Before You Begin

- Create a storage container using Microsoft Azure Portal, Microsoft Azure CLI, or Microsoft Azure Storage Explorer. Keep a note of the **storage account name**, **storage account key** and **container name**.
- [Deploy the integrated Docker registry](#) if it is not deployed.

23.14.3. Overriding Registry Configuration

To create a new registry pod and replace the old pod automatically:

1. Create a new registry configuration file called **registryconfig.yaml** and add the following information:

```

version: 0.1
log:
  level: debug
http:
  addr: :5000
storage:
  cache:
    blobdescriptor: inmemory
  delete:
    enabled: true
azure: ❶
  accountname: azureblobacc
  accountkey: azureblobacckey
  container: azureblobname

```

```

    realm: core.windows.net 2
  auth:
    openshift:
      realm: openshift
  middleware:
    registry:
      - name: openshift
  repository:
    - name: openshift
    options:
      acceptschema2: false
      pullthrough: true
      enforcequota: false
      projectcachettl: 1m
      blobrepositorycachettl: 10m
  storage:
    - name: openshift

```

- 1 Replace the values for **accountname**, **accountkey**, and **container** with **storage account name**, **storage account key**, and **storage container name** respectively.
- 2 If using Azure regional cloud, set to the desired realm. For example, **core.cloudapi.de** for the Germany regional cloud.

2. Create a new registry configuration:

```
$ oc secrets new registry-config config.yaml=registryconfig.yaml
```

3. Add the secret:

```
$ oc volume dc/docker-registry --add --type=secret \
  --secret-name=registry-config -m /etc/docker/registry/
```

4. Set the **REGISTRY_CONFIGURATION_PATH** environment variable:

```
$ oc set env dc/docker-registry \
  REGISTRY_CONFIGURATION_PATH=/etc/docker/registry/config.yaml
```

5. If you already created a registry configuration:

a. Delete the secret:

```
$ oc delete secret registry-config
```

b. Create a new registry configuration:

```
$ oc secrets new registry-config config.yaml=registryconfig.yaml
```

c. Update the configuration by starting a new rollout:

```
$ oc rollout latest docker-registry
```

CHAPTER 24. WORKING WITH HTTP PROXIES

24.1. OVERVIEW

Production environments can deny direct access to the Internet and instead have an HTTP or HTTPS proxy available. Configuring OpenShift Container Platform to use these proxies can be as simple as setting standard environment variables in configuration or JSON files. This can be done during an [advanced installation](#) or configured after installation.

The proxy configuration must be the same on each host in the cluster. Therefore, when setting up the proxy or modifying it, you must update the files on each OpenShift Container Platform host to the same values. Then, you must restart OpenShift Container Platform services on each host in the cluster.

The **NO_PROXY**, **HTTP_PROXY**, and **HTTPS_PROXY** environment variables are found in each host's */etc/sysconfig/atomic-openshift-master-api* or */etc/sysconfig/atomic-openshift-master-controllers* files and */etc/sysconfig/atomic-openshift-node* file.

24.2. CONFIGURING NO_PROXY

The **NO_PROXY** environment variable lists all of the OpenShift Container Platform components and all IP addresses that are managed by OpenShift Container Platform.

On the OpenShift service accepting the CIDR, **NO_PROXY** accepts a comma-separated list of hosts, IP addresses, or IP ranges in CIDR format:

For master hosts

- Node host name
- Master IP or host name
- IP address of etcd hosts

For node hosts

- Master IP or host name

For the Docker service

- Registry service IP and host name
- Registry service URL **docker-registry.default.svc.cluster.local**
- Registry route host name (if created)



NOTE

When using Docker, Docker accepts a comma-separated list of hosts, domain extensions, or IP addresses, but does not accept IP ranges in CIDR format, which are only accepted by OpenShift services. The `no_proxy` variable should contain a comma-separated list of domain extensions that the proxy should *not* be used for.

For example, if **no_proxy** is set to **.school.edu**, the proxy will not be used to retrieve documents from the specific school.

NO_PROXY also includes the SDN network and service IP addresses as found in the **master-config.yaml** file.

/etc/origin/master/master-config.yaml

```
networkConfig:
  clusterNetworks:
  - cidr: 10.1.0.0/16
    hostSubnetLength: 9
  serviceNetworkCIDR: 172.30.0.0/16
```

OpenShift Container Platform does not accept ***** as a wildcard attached to a domain suffix. For example, the following would be accepted:


```
NO_PROXY=.example.com
```

However, the following would not be:

```
NO_PROXY=*.example.com
```

The only wildcard **NO_PROXY** accepts is a single ***** character, which matches all hosts, and effectively disables the proxy.

Each name in this list is matched as either a domain which contains the host name as a suffix, or the host name itself.



NOTE

When scaling up nodes, use a domain name rather than a list of hostnames.

For instance, **example.com** would match **example.com**, **example.com:80**, and **www.example.com**.

24.3. CONFIGURING HOSTS FOR PROXIES

1. Edit the proxy environment variables in the OpenShift Container Platform control files. Ensure all of the files in the cluster are correct.

```
HTTP_PROXY=http://<user>:<password>@<ip_addr>:<port>/
HTTPS_PROXY=https://<user>:<password>@<ip_addr>:<port>/
NO_PROXY=master.hostname.example.com,10.1.0.0/16,172.30.0.0/16 1
```

- 1** Supports host names and CIDRs. Must include the SDN network and service IP ranges **10.1.0.0/16**, **172.30.0.0/16** by default.

2. Restart the master or node host as appropriate:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
# systemctl restart atomic-openshift-node
```

For multi-master installations:

■

```
# systemctl restart atomic-openshift-master-controllers
# systemctl restart atomic-openshift-master-api
```

24.4. CONFIGURING HOSTS FOR PROXIES USING ANSIBLE

During [advanced installations](#), the **NO_PROXY**, **HTTP_PROXY**, and **HTTPS_PROXY** environment variables can be configured using the [openshift_no_proxy](#), [openshift_http_proxy](#), and [openshift_https_proxy](#) parameters, which are configurable in the inventory file.

Example Proxy Configuration with Ansible

```
# Global Proxy Configuration
# These options configure HTTP_PROXY, HTTPS_PROXY, and NO_PROXY environment
# variables for docker and master services.
openshift_http_proxy=http://<user>:<password>@<ip_addr>:<port>
openshift_https_proxy=https://<user>:<password>@<ip_addr>:<port>
openshift_no_proxy='.hosts.example.com,some-host.com'
#
# Most environments do not require a proxy between OpenShift masters,
# nodes, and
# etcd hosts. So automatically add those host names to the
# openshift_no_proxy list.
# If all of your hosts share a common domain you may wish to disable this
# and
# specify that domain above.
# openshift_generate_no_proxy_hosts=True
```

NOTE

There are [additional proxy settings](#) that can be [configured for builds](#) using Ansible parameters. For example:

The **openshift_builddefaults_git_http_proxy** and **openshift_builddefaults_git_https_proxy** parameters allow you to [use a proxy for Git cloning](#)

The **openshift_builddefaults_http_proxy** and **openshift_builddefaults_https_proxy** parameters can make environment variables available to the [Docker build strategy](#) and [Custom build strategy](#) processes.

24.5. PROXYING DOCKER PULL

OpenShift Container Platform node hosts need to perform push and pull operations to Docker registries. If you have a registry that does not need a proxy for nodes to access, include the **NO_PROXY** parameter with:

- the registry's host name,
- the registry service's IP address, and
- the service name.

This blacklists that registry, leaving the external HTTP proxy as the only option.

1. Retrieve the registry service's IP address **docker_registry_ip** by running:

```
$ oc describe svc/docker-registry -n default

Name:      docker-registry
Namespace: default
Labels:    docker-registry=default
Selector:  docker-registry=default
Type:      ClusterIP
IP:        172.30.163.183 1
Port:      5000-tcp 5000/TCP
Endpoints: 10.1.0.40:5000
Session Affinity: ClientIP
No events.
```

- 1** Registry service IP.

2. Edit the **/etc/sysconfig/docker** file and add the **NO_PROXY** variables in shell format, replacing **<docker_registry_ip>** with the IP address from the previous step.

```
HTTP_PROXY=http://<user>:<password>@<ip_addr>:<port>/
HTTPS_PROXY=https://<user>:<password>@<ip_addr>:<port>/
NO_PROXY=master.hostname.example.com,<docker_registry_ip>,docker-
registry.default.svc.cluster.local
```

3. Restart the Docker service:

```
# systemctl restart docker
```

24.6. USING MAVEN BEHIND A PROXY

Using Maven with proxies requires using the **HTTP_PROXY_NONPROXYHOSTS** variable.

See the [Red Hat JBoss Enterprise Application Platform for OpenShift documentation](#) for information about configuring your OpenShift Container Platform environment for Red Hat JBoss Enterprise Application Platform, including the step for setting up Maven behind a proxy.

24.7. CONFIGURING S2I BUILDS FOR PROXIES

S2I builds fetch dependencies from various locations. You can [use a `.s2i/environment` file](#) to specify simple shell variables and OpenShift Container Platform will react accordingly when seeing build images.

The following are the supported proxy environment variables with example values:

```
HTTP_PROXY=http://USERNAME:PASSWORD@10.0.1.1:8080/
HTTPS_PROXY=https://USERNAME:PASSWORD@10.0.0.1:8080/
NO_PROXY=master.hostname.example.com
```

24.8. CONFIGURING DEFAULT TEMPLATES FOR PROXIES

The [example templates](#) available in OpenShift Container Platform by default do not include settings for HTTP proxies. For existing applications based on these templates, modify the **source** section of the application's build configuration and add proxy settings:

```
...
source:
  type: Git
  git:
    uri: https://github.com/openshift/ruby-hello-world
    httpProxy: http://proxy.example.com
    httpsProxy: https://proxy.example.com
    noProxy: somedomain.com, otherdomain.com
...
```

This is similar to the process for [using proxies for Git cloning](#).

24.9. SETTING PROXY ENVIRONMENT VARIABLES IN PODS

You can set the **NO_PROXY**, **HTTP_PROXY**, and **HTTPS_PROXY** environment variables in the **templates.spec.containers** stanza in a deployment configuration to pass proxy connection information. The same can be done for configuring a Pod's proxy at runtime:

```
...
containers:
- env:
  - name: "HTTP_PROXY"
    value: "http://<user>:<password>@<ip_addr>:<port>"
...
```


You can also use the **oc set env** command to update an existing deployment configuration with a new environment variable:

```
$ oc set env dc/frontend HTTP_PROXY=http://<user>:<password>@<ip_addr>:
<port>
```

If you have a [ConfigChange trigger](#) set up in your OpenShift Container Platform instance, the changes happen automatically. Otherwise, manually redeploy your application for the changes to take effect.

24.10. GIT REPOSITORY ACCESS

If your Git repository can only be accessed using a proxy, you can define the proxy to use in the **source** section of the **BuildConfig**. You can configure both a HTTP and HTTPS proxy to use. Both fields are optional. Domains for which no proxying should be performed can also be specified via the **NoProxy** field.



NOTE

Your source URI must use the HTTP or HTTPS protocol for this to work.

```
source:
  git:
    uri: "https://github.com/openshift/ruby-hello-world"
```

```
httpProxy: http://proxy.example.com
httpsProxy: https://proxy.example.com
noProxy: somedomain.com, otherdomain.com
```

CHAPTER 25. CONFIGURING GLOBAL BUILD DEFAULTS AND OVERRIDES

25.1. OVERVIEW


Developers can define settings in specific build configurations within their projects, such as [configuring a proxy for Git cloning](#). Rather than requiring developers to define certain settings in each build configuration, administrators can use admission control plug-ins to configure global build defaults and overrides that automatically use these settings in any build.

The settings from these plug-ins are used only during the build process but are not set in the build configurations or builds themselves. Configuring the settings through the plug-ins allows administrators to change the global configuration at any time, and any builds that are re-run from existing build configurations or builds are assigned the new settings.

- The **BuildDefaults** admission control plug-in allows administrators to set global defaults for settings such as the Git HTTP and HTTPS proxy, as well as default environment variables. These defaults do not overwrite values that have been configured for a specific build. However, if those values are not present on the build definition, they are set to the default value.
- The **BuildOverrides** admission control plug-in allows administrators to override a setting in a build, regardless of the value stored in the build. The plug-in currently supports [overriding the forcePull flag on a build strategy](#) to force refreshing the local image from the registry during a build. Refreshing ensures that users can build only with images that they are allowed to pull. The plug-in can also be configured to apply a set of image labels to every built image. For information on configuring the **BuildOverrides** admission control plug-in and the values you can override, see [Manually Setting Global Build Overrides](#).

The default node selectors and the **BuildDefaults** or **BuildOverride** admission plug-ins work together as follows:

- The default project node selector, defined in the **projectConfig.defaultNodeSelector** field in the master configuration file, is applied to the pods created in all projects without a specified **nodeSelector** value. These settings are applied to builds with **nodeSelector="null"** on clusters where the **BuildDefaults** or **BuildOverride** nodeSelector is not set.
- The cluster-wide default build node selector, **admissionConfig.pluginConfig.BuildDefaults.configuration.nodeSelector**, is applied only if the **nodeSelector="null"** parameter is set in the build configuration. **nodeSelector=null** is the default setting.
- With a default project or cluster-wide node selector, the default setting is added as an AND to the build node selector, which is set by the **BuildDefaults** or **BuildOverride** admission plug-ins. These settings mean that the build will be scheduled only to nodes that satisfy the **BuildOverrides** node selector AND the project default node selector.



NOTE

You can define a hard limit on how long build pods can run by using the [RunOnceDuration](#) plugin.

25.2. SETTING GLOBAL BUILD DEFAULTS

You can set global build defaults two ways:

- [using Ansible and the advanced installation tool](#)
- [manually by modifying the *master-config.yaml* file](#)

25.2.1. Configuring Global Build Defaults with Ansible

During [advanced installations](#), the **BuildDefaults** plug-in can be configured using [the following parameters](#), which are configurable in the inventory file:

- **openshift_builddefaults_http_proxy**
- **openshift_builddefaults_https_proxy**
- **openshift_builddefaults_no_proxy**
- **openshift_builddefaults_git_http_proxy**
- **openshift_builddefaults_git_https_proxy**
- **openshift_builddefaults_git_no_proxy**
- **openshift_builddefaults_image_labels**
- **openshift_builddefaults_nodeselectors**
- **openshift_builddefaults_annotations**
- **openshift_builddefaults_resources_requests_cpu**
- **openshift_builddefaults_resources_requests_memory**
- **openshift_builddefaults_resources_limits_cpu**
- **openshift_builddefaults_resources_limits_memory**

Example 25.1. Example Build Defaults Configuration with Ansible

```
# These options configure the BuildDefaults admission controller which
# injects
# configuration into Builds. Proxy related values will default to the
# global proxy
# config values. You only need to set these if they differ from the
# global proxy settings.
openshift_builddefaults_http_proxy=http://USER:PASSWORD@HOST:PORT
openshift_builddefaults_https_proxy=https://USER:PASSWORD@HOST:PORT
openshift_builddefaults_no_proxy=mycorp.com
openshift_builddefaults_git_http_proxy=http://USER:PASSWORD@HOST:PORT
openshift_builddefaults_git_https_proxy=https://USER:PASSWORD@HOST:PORT
openshift_builddefaults_git_no_proxy=mycorp.com
openshift_builddefaults_image_labels=
[{'name': 'imagelabelname1', 'value': 'imagelabelvalue1'}]
openshift_builddefaults_nodeselectors={'nodelabel1': 'nodelabelvalue1'}
openshift_builddefaults_annotations=
{'annotationkey1': 'annotationvalue1'}
```

```

openshift_builddefaults_resources_requests_cpu=100m
openshift_builddefaults_resources_requests_memory=256Mi
openshift_builddefaults_resources_limits_cpu=1000m
openshift_builddefaults_resources_limits_memory=512Mi

# Or you may optionally define your own build defaults configuration
serialized as json
#openshift_builddefaults_json='{ "BuildDefaults": { "configuration":
{ "apiVersion": "v1", "env":
[ { "name": "HTTP_PROXY", "value": "http://proxy.example.com.redhat.com:3128"
}, { "name": "NO_PROXY", "value": "ose3-
master.example.com" } ], "gitHTTPProxy": "http://proxy.example.com:3128", "gi
tNoProxy": "ose3-master.example.com", "kind": "BuildDefaultsConfig" } } }'
```

25.2.2. Manually Setting Global Build Defaults

To configure the **BuildDefaults** plug-in:

1. Add a configuration for it in the */etc/origin/master/master-config.yaml* file on the master nodes:

```

admissionConfig:
  pluginConfig:
    BuildDefaults:
      configuration:
        apiVersion: v1
        kind: BuildDefaultsConfig
        gitHTTPProxy: http://my.proxy:8080 ①
        gitHTTPSProxy: https://my.proxy:8443 ②
        gitNoProxy: somedomain.com, otherdomain.com ③
        env:
          - name: HTTP_PROXY ④
            value: http://my.proxy:8080
          - name: HTTPS_PROXY ⑤
            value: https://my.proxy:8443
          - name: BUILD_LOGLEVEL ⑥
            value: 4
          - name: CUSTOM_VAR ⑦
            value: custom_value
        imageLabels:
          - name: url ⑧
            value: https://containers.example.org
          - name: vendor
            value: ExampleCorp Ltd.
        nodeSelector: ⑨
          key1: value1
          key2: value2
        annotations: ⑩
          key1: value1
          key2: value2
        resources: ⑪
          requests:
            cpu: "100m"
```

```
memory: "256Mi"
limits:
  cpu: "100m"
  memory: "256Mi"
```

- 1 Sets the HTTP proxy to use when cloning source code from a Git repository.
- 2 Sets the HTTPS proxy to use when cloning source code from a Git repository.
- 3 Sets the list of domains for which proxying should not be performed.
- 4 Default environment variable that sets the HTTP proxy to use during the build. This can be used for downloading dependencies during the assemble and build phases.
- 5 Default environment variable that sets the HTTPS proxy to use during the build. This can be used for downloading dependencies during the assemble and build phases.
- 6 Default environment variable that sets the build log level during the build.
- 7 Additional default environment variable that will be added to every build.
- 8 Labels to be applied to every image built. Users can override these in their **BuildConfig**.
- 9 Build pods will only run on nodes with the **key1=value2** and **key2=value2** labels. Users can define a different set of **nodeSelectors** for their builds in which case these values will be ignored.
- 10 Build pods will have these annotations added to them.
- 11 Sets the default resources to the build pod if the **BuildConfig** does not have related resource defined.

2. Restart the master services for the changes to take effect:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

25.3. SETTING GLOBAL BUILD OVERRIDES

You can set global build overrides two ways:

- using [Ansible and the advanced installation tool](#)
- manually by modifying the *master-config.yaml* file

25.3.1. Configuring Global Build Overrides with Ansible

During [advanced installations](#), the **BuildOverrides** plug-in can be configured using the following parameters, which are configurable in the inventory file:

- **openshift_buildoverrides_force_pull**
- **openshift_buildoverrides_image_labels**

- `openshift_buildoverrides_nodeselectors`
- `openshift_buildoverrides_annotations`

Example 25.2. Example Build Overrides Configuration with Ansible

```
# These options configure the BuildOverrides admission controller which
# injects
# configuration into Builds.
openshift_buildoverrides_force_pull=true
openshift_buildoverrides_image_labels=
[{'name':'imagelabelname1','value':'imagelabelvalue1'}]
openshift_buildoverrides_nodeselectors={'nodelabel1':'nodelabelvalue1'}
openshift_buildoverrides_annotations=
{'annotationkey1':'annotationvalue1'}

# Or you may optionally define your own build overrides configuration
# serialized as json
#openshift_buildoverrides_json='{"BuildOverrides":{"configuration":
#{"apiVersion":"v1","kind":"BuildDefaultsConfig","forcePull":"true"}}}'
```

25.3.2. Manually Setting Global Build Overrides

To configure the **BuildOverrides** plug-in:

1. Add a configuration for it in the `/etc/origin/master/master-config.yaml` file on masters:

```
admissionConfig:
  pluginConfig:
    BuildOverrides:
      configuration:
        apiVersion: v1
        kind: BuildOverridesConfig
        forcePull: true ①
        imageLabels:
          - name: distribution-scope ②
            value: private
        nodeSelector: ③
          key1: value1
          key2: value2
        annotations: ④
          key1: value1
          key2: value2
```

- ① Force all builds to pull their builder image and any source images before starting the build.
- ② Additional labels to be applied to every image built. Labels defined here take precedence over labels defined in **BuildConfig**.
- ③ Build pods will only run on nodes with the **key1=value1** and **key2=value2** labels. Users can define additional key/value labels to further constrain the set of nodes a build runs on, but the **node** must have at least these labels.

4 Build pods will have these annotations added to them.

2. Restart the master services for the changes to take effect:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-  
master-controllers
```


CHAPTER 26. CONFIGURING PIPELINE EXECUTION

26.1. OVERVIEW

The first time a user creates a build configuration using the [Pipeline](#) build strategy, OpenShift Container Platform looks for a template named **jenkins-ephemeral** in the **openshift** namespace and instantiates it within the user's project. The **jenkins-ephemeral** template that ships with OpenShift Container Platform creates, upon instantiation:

- a deployment configuration for Jenkins using the official OpenShift Container Platform Jenkins image
- a service and route for accessing the Jenkins deployment
- a new Jenkins service account
- rolebindings to grant the service account edit access to the project

Cluster administrators can control what is created by either modifying the content of the built-in template, or by editing the cluster configuration to direct the cluster to a different template location.

To modify the content of the default template:

```
$ oc edit template jenkins-ephemeral -n openshift
```

To use a different template, such as the **jenkins-persistent** template which uses persistent storage for Jenkins, add the following to your master configuration file:

```
jenkinsPipelineConfig:
  autoProvisionEnabled: true 1
  templateNamespace: openshift 2
  templateName: jenkins-persistent 3
  serviceName: jenkins-persistent-svc 4
  parameters: 5
    key1: value1
    key2: value2
```

- 1 Defaults to **true** if unspecified. If **false**, then no template will be instantiated.
- 2 Namespace containing the template to be instantiated.
- 3 Name of the template to be instantiated.
- 4 Name of the service to be created by the template upon instantiation.
- 5 Optional values to pass to the template during instantiation.

When a Pipeline build configuration is created, OpenShift Container Platform looks for a Service matching **serviceName**. This means **serviceName** must be chosen such that it is unique in the project. If no Service is found, OpenShift Container Platform instantiates the **jenkinsPipelineConfig** template. If this is not desirable (if you would like to use a Jenkins server external to OpenShift Container Platform, for example), there are a few things you can do, depending on who you are.

- If you are a cluster administrator, simply set **autoProvisionEnabled** to **false**. This will disable autoprovisioning across the cluster.
- If you are an unprivileged user, a Service must be created for OpenShift Container Platform to use. The service name must match the cluster configuration value of **serviceName** in the **jenkinsPipelineConfig**. The default value is **jenkins**. If you are disabling autoprovisioning because you are running a Jenkins server outside your project, it is recommended that you point this new service to your existing Jenkins server. See: [Integrating External Services](#)


The latter option could also be used to disable autoprovisioning in select projects only.

26.2. OPENSIFT JENKINS CLIENT PLUGIN

The OpenShift Jenkins Client Plugin is a Jenkins plugin which aims to provide a readable, concise, comprehensive, and fluent Jenkins Pipeline syntax for rich interactions with an OpenShift API Server. The plugin leverages the OpenShift command line tool (**oc**) which must be available on the nodes executing the script.

For more information about installing and configuring the plugin, use the links provided below that reference the official documentation.

- [Installing](#)
- [Configuring an OpenShift Cluster](#)
- [Setting up Credentials](#)
- [Setting up Jenkins Nodes](#)



NOTE

Are you a developer looking for information about using this plugin? If so, see [OpenShift Pipeline Overview](#).

26.3. OPENSIFT JENKINS SYNC PLUGIN

This Jenkins plugin keeps OpenShift BuildConfig and Build objects in sync with Jenkins Jobs and Builds.

The OpenShift jenkins Sync Plugin provides the following:

- Dynamic job/run creation in Jenkins.
- Dynamic creation of slave pod templates from ImageStreams, ImageStreamTags, or ConfigMaps.
- Injecting of environment variables.
- Pipeline visualization in the OpenShift web console.
- Integration with the Jenkins git plugin, which passes commit information from OpenShift builds to the Jenkins git plugin.

For more information about this plugin, see:

- [OpenShift Jenkins Sync Plug-in](#)

- [OpenShift Container Platform Sync Plug-in](#)

CHAPTER 27. CONFIGURING ROUTE TIMEOUTS

After installing OpenShift Container Platform and [deploying a router](#), you can configure the default timeouts for an existing route when you have services in need of a low timeout, as required for Service Level Availability (SLA) purposes, or a high timeout, for cases with a slow back end.

Using the **oc annotate** command, add the timeout to the route:

```
# oc annotate route <route_name> \
    --overwrite haproxy.router.openshift.io/timeout=<timeout><time_unit>
```

For example, to set a route named **myroute** to a timeout of two seconds:

```
# oc annotate route myroute --overwrite
haproxy.router.openshift.io/timeout=2s
```

Supported time units are microseconds (us), milliseconds (ms), seconds (s), minutes (m), hours (h), or days (d).


CHAPTER 28. CONFIGURING NATIVE CONTAINER ROUTING

28.1. NETWORK OVERVIEW

The following describes a general network setup:

- 11.11.0.0/16 is the container network.
- The 11.11.x.0/24 subnet is reserved for each node and assigned to the Docker Linux bridge.
- Each node has a route to the router for reaching anything in the 11.11.0.0/16 range, except the local subnet.
- The router has routes for each node, so it can be directed to the right node.
- Existing nodes do not need any changes when new nodes are added, unless the network topology is modified.
- IP forwarding is enabled on each node.

The following diagram shows the container networking setup described in this topic. It uses one Linux node with two network interface cards serving as a router, two switches, and three nodes connected to these switches.



28.2. CONFIGURE NATIVE CONTAINER ROUTING

You can set up container networking using existing switches and routers, and the kernel networking stack in Linux.

As a network administrator, you must modify, or create a script to modify, the router or routers when new nodes are added to the cluster.

You can adapt this process to use with any type of router.

28.3. SETTING UP A NODE FOR CONTAINER NETWORKING

1. Assign an unused 11.11.x.0/24 subnet IP address to the Linux bridge on the node:

```
# brctl addbr lbr0
# ip addr add 11.11.1.1/24 dev lbr0
# ip link set dev lbr0 up
```

2. Modify the Docker startup script to use the new bridge. By default, the startup script is the **/etc/sysconfig/docker** file:

```
# docker -d -b lbr0 --other-options
```

3. Add a route to the router for the 11.11.0.0/16 network:

```
# ip route add 11.11.0.0/16 via 192.168.2.2 dev p3p1
```

4. Enable IP forwarding on the node:

```
# sysctl -w net.ipv4.ip_forward=1
```

28.4. SETTING UP A ROUTER FOR CONTAINER NETWORKING

The following procedure assumes a Linux box with multiple NICs is used as a router. Modify the steps as required to use the syntax for a particular router:

1. Enable IP forwarding on the router:

```
# sysctl -w net.ipv4.ip_forward=1
```

2. Add a route for each node added to the cluster:

```
# ip route add <node_subnet> via <node_ip_address> dev <interface
through which node is L2 accessible>
# ip route add 11.11.1.0/24 via 192.168.2.1 dev p3p1
# ip route add 11.11.2.0/24 via 192.168.3.3 dev p3p2
# ip route add 11.11.3.0/24 via 192.168.3.4 dev p3p2
```

CHAPTER 29. ROUTING FROM EDGE LOAD BALANCERS

29.1. OVERVIEW

Pods inside of an OpenShift Container Platform cluster are only reachable via their IP addresses on the cluster network. An edge load balancer can be used to accept traffic from outside networks and proxy the traffic to pods inside the OpenShift Container Platform cluster. In cases where the load balancer is not part of the cluster network, routing becomes a hurdle as the internal cluster network is not accessible to the edge load balancer.

To solve this problem where the OpenShift Container Platform cluster is using [OpenShift Container Platform SDN](#) as the cluster networking solution, there are two ways to achieve network access to the pods.

29.2. INCLUDING THE LOAD BALANCER IN THE SDN

If possible, run an OpenShift Container Platform node instance on the load balancer itself that uses OpenShift SDN as the networking plug-in. This way, the edge machine gets its own Open vSwitch bridge that the SDN automatically configures to provide access to the pods and nodes that reside in the cluster. The *routing table* is dynamically configured by the SDN as pods are created and deleted, and thus the routing software is able to reach the pods.

Mark the load balancer machine as an [unschedulable node](#) so that no pods end up on the load balancer itself:

```
$ oc adm manage-node <load_balancer_hostname> --schedulable=false
```

If the load balancer comes packaged as a container, then it is even easier to integrate with OpenShift Container Platform: Simply run the load balancer as a pod with the host port exposed. The pre-packaged [HAProxy router](#) in OpenShift Container Platform runs in precisely this fashion.

29.3. ESTABLISHING A TUNNEL USING A RAMP NODE

In some cases, the previous solution is not possible. For example, an **F5 BIG-IP®** host cannot run an OpenShift Container Platform node instance or the OpenShift Container Platform SDN because **F5®** uses a custom, incompatible Linux kernel and distribution.

Instead, to enable **F5 BIG-IP®** to reach pods, you can choose an existing node within the cluster network as a *ramp node* and establish a tunnel between the **F5 BIG-IP®** host and the designated ramp node. Because it is otherwise an ordinary OpenShift Container Platform node, the ramp node has the necessary configuration to route traffic to any pod on any node in the cluster network. The ramp node thus assumes the role of a gateway through which the **F5 BIG-IP®** host has access to the entire cluster network.

Following is an example of establishing an **ipip** tunnel between an **F5 BIG-IP®** host and a designated ramp node.

On the F5 BIG-IP® host:

1. Set the following variables:

```
# F5_IP=10.3.89.66 1
# RAMP_IP=10.3.89.89 2
```

```
# TUNNEL_IP1=10.3.91.216 3
# CLUSTER_NETWORK=10.128.0.0/14 4
```

- 1** **2** The **F5_IP** and **RAMP_IP** variables refer to the **F5 BIG-IP®** host's and the ramp node's IP addresses, respectively, on a shared, internal network.
- 3** An arbitrary, non-conflicting IP address for the **F5®** host's end of the **ipip** tunnel.
- 4** The overlay network CIDR range that the OpenShift SDN uses to assign addresses to pods.

2. Delete any old route, self, tunnel and SNAT pool:

```
# tmsh delete net route $CLUSTER_NETWORK || true
# tmsh delete net self SDN || true
# tmsh delete net tunnels tunnel SDN || true
# tmsh delete ltm snatpool SDN_snatpool || true
```

3. Create the new tunnel, self, route and SNAT pool and use the SNAT pool in the virtual servers:

```
# tmsh create net tunnels tunnel SDN \
    \{ description "OpenShift SDN" local-address \
    $F5_IP profile ipip remote-address $RAMP_IP \}
# tmsh create net self SDN \{ address \
    ${TUNNEL_IP1}/24 allow-service all vlan SDN \}
# tmsh create net route $CLUSTER_NETWORK interface SDN
# tmsh create ltm snatpool SDN_snatpool members add { $TUNNEL_IP1 }
# tmsh modify ltm virtual ose-vserver source-address-translation {
    type snat pool SDN_snatpool }
# tmsh modify ltm virtual https-ose-vserver source-address-
translation { type snat pool SDN_snatpool }
```

On the ramp node:



NOTE

The following creates a configuration that is not persistent, meaning that when the ramp node or the **openvswitch** service is restarted, the settings disappear.

1. Set the following variables:

```
# F5_IP=10.3.89.66
# TUNNEL_IP1=10.3.91.216
# TUNNEL_IP2=10.3.91.217 1
# CLUSTER_NETWORK=10.128.0.0/14 2
```

- 1** A second, arbitrary IP address for the ramp node's end of the **ipip** tunnel.
- 2** The overlay network CIDR range that the OpenShift SDN uses to assign addresses to pods.

2. Delete any old tunnel:


```
# ip tunnel del tun1 || true
```

3. Create the **ipip** tunnel on the ramp node, using a suitable L2-connected interface (e.g., **eth0**):

```
# ip tunnel add tun1 mode ipip \
    remote $F5_IP dev eth0
# ip addr add $TUNNEL_IP2 dev tun1
# ip link set tun1 up
# ip route add $TUNNEL_IP1 dev tun1
# ping -c 5 $TUNNEL_IP1
```

4. SNAT the tunnel IP with an unused IP from the SDN subnet:

```
# source /run/openshift-sdn/config.env
# tap1=$(ip -o -4 addr list tun0 | awk '{print $4}' | cut -d/ -f1 |
head -n 1)
# subaddr=$(echo ${OPENSIFT_SDN_TAP1_ADDR:-"$tap1"} | cut -d "." -f
1,2,3)
# export RAMP_SDN_IP=${subaddr}.254
```

5. Assign this **RAMP_SDN_IP** as an additional address to **tun0** (the local SDN's gateway):

```
# ip addr add ${RAMP_SDN_IP} dev tun0
```

6. Modify the OVS rules for SNAT:


```
# ipflowopts="cookie=0x999,ip"
# arpflowopts="cookie=0x999, table=0, arp"
#
# ovs-ofctl -O OpenFlow13 add-flow br0 \

"${ipflowopts},nw_src=${TUNNEL_IP1},actions=mod_nw_src:${RAMP_SDN_IP
},resubmit(,0)"
# ovs-ofctl -O OpenFlow13 add-flow br0 \

"${ipflowopts},nw_dst=${RAMP_SDN_IP},actions=mod_nw_dst:${TUNNEL_IP1
},resubmit(,0)"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
    "${arpflowopts}, arp_tpa=${RAMP_SDN_IP}, actions=output:2"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
    "${arpflowopts}, priority=200, in_port=2,
arp_spa=${RAMP_SDN_IP}, arp_tpa=${CLUSTER_NETWORK},
actions=goto_table:30"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
    "arp, table=5, priority=300, arp_tpa=${RAMP_SDN_IP},
actions=output:2"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
    "ip, table=5, priority=300, nw_dst=${RAMP_SDN_IP}, actions=output:2"
# ovs-ofctl -O OpenFlow13 add-flow br0
"${ipflowopts},nw_dst=${TUNNEL_IP1},actions=output:2"
```

7. Optionally, if you do not plan on configuring the ramp node to be highly available, mark the ramp node as unschedulable. Skip this step if you do plan to follow the next section and plan on creating a highly available ramp node.

```
$ oc adm manage-node <ramp_node_hostname> --schedulable=false
```



NOTE

The [F5 router plug-in](#) integrates with F5 BIG-IP®.

29.3.1. Configuring a Highly-Available Ramp Node

You can use OpenShift Container Platform's **ipfailover** feature, which uses **keepalived** internally, to make the ramp node highly available from **F5 BIG-IP®**'s point of view. To do so, first bring up two nodes, for example called **ramp-node-1** and **ramp-node-2**, on the same L2 subnet.

Then, choose some unassigned IP address from within the same subnet to use for your virtual IP, or *VIP*. This will be set as the **RAMP_IP** variable with which you will configure your tunnel on **F5 BIG-IP®**.

For example, suppose you are using the **10.20.30.0/24** subnet for your ramp nodes, and you have assigned **10.20.30.2** to **ramp-node-1** and **10.20.30.3** to **ramp-node-2**. For your VIP, choose some unassigned address from the same **10.20.30.0/24** subnet, for example **10.20.30.4**. Then, to configure **ipfailover**, mark both nodes with a label, such as **f5ramptime**:

```
$ oc label node ramp-node-1 f5ramptime=true
$ oc label node ramp-node-2 f5ramptime=true
```

Similar to instructions from the [ipfailover documentation](#), you must now create a service account and add it to the **privileged** SCC. First, create the **f5ipfailover** service account:

```
$ oc create serviceaccount f5ipfailover -n default
```

Next, you can add the **f5ipfailover** service to the **privileged** SCC. To add the **f5ipfailover** in the **default** namespace to the **privileged** SCC, run:

```
$ oc adm policy add-scc-to-user privileged
system:serviceaccount:default:f5ipfailover
```

Finally, configure **ipfailover** using your chosen VIP (the **RAMP_IP** variable) and the **f5ipfailover** service account, assigning the VIP to your two nodes using the **f5ramptime** label you set earlier:

```
# RAMP_IP=10.20.30.4
# IFNAME=eth0 ❶
# oc adm ipfailover <name-tag> \
  --virtual-ips=$RAMP_IP \
  --interface=$IFNAME \
  --watch-port=0 \
  --replicas=2 \
  --service-account=f5ipfailover \
  --selector='f5ramptime=true'
```

❶ The interface where **RAMP_IP** should be configured.

With the above setup, the VIP (the **RAMP_IP** variable) is automatically re-assigned when the ramp node host that currently has it assigned fails.

CHAPTER 30. AGGREGATING CONTAINER LOGS

30.1. OVERVIEW

As an OpenShift Container Platform cluster administrator, you can deploy the EFK stack to aggregate logs for a range of OpenShift Container Platform services. Application developers can view the logs of the projects for which they have view access. The EFK stack aggregates logs from hosts and applications, whether coming from multiple containers or even deleted pods.

The EFK stack is a modified version of the [ELK stack](#) and is comprised of:


- [Elasticsearch \(ES\)](#): An object store where all logs are stored.
- [Fluentd](#): Gathers logs from nodes and feeds them to Elasticsearch.
- [Kibana](#): A web UI for Elasticsearch.

Once deployed in a cluster, the stack aggregates logs from all nodes and projects into Elasticsearch, and provides a Kibana UI to view any logs. Cluster administrators can view all logs, but application developers can only view logs for projects they have permission to view. The stack components communicate securely.

Aggregated logging is supported using the **json-file** or **journald** driver in Docker. The Docker log driver is set to **journald** as the default for all nodes. See [Updating Fluentd's Log Source After a Docker Log Driver Update](#) for more information about switching between **json-file** and **journald**. Fluentd automatically determines which log driver (**journald** or **json-file**) the container runtime is using.

When the log driver is set to **journald**, Fluentd reads journald logs. When set to **json-file** Fluentd reads from **/var/log/containers**.

See [Managing Docker Container Logs](#) for information on **json-file** logging driver options to manage container logs and prevent filling node disks.



IMPORTANT

If Docker log-driver is set to **journald**, there is no log rate throttling with the **journald** driver. As a result, there is a risk of denial-of-service attacks from rogue containers.

30.2. PRE-DEPLOYMENT CONFIGURATION

1. An Ansible playbook is available to deploy and upgrade aggregated logging. You should familiarize yourself with the [advanced installation and configuration](#) section. This provides information for preparing to use Ansible and includes information about configuration. Parameters are added to the Ansible inventory file to configure various areas of the EFK stack.
2. Review the [sizing guidelines](#) to determine how best to configure your deployment.
3. Ensure that you have deployed a router for the cluster.
4. Ensure that you have [the necessary storage](#) for Elasticsearch. Note that each Elasticsearch replica requires its own storage volume. See [Elasticsearch](#) for more information.
5. Choose a project. Once deployed, the EFK stack collects logs for every project within your OpenShift Container Platform cluster. The examples in this section use the default project

logging. The Ansible playbook creates the project for you if it does not already exist. You will only need to create a project if you want to specify a node-selector on it. Otherwise, the **openshift-logging** role will create a project.

```
$ oc adm new-project logging --node-selector=""
$ oc project logging
```



NOTE

Specifying an empty [node selector](#) on the project is recommended, as Fluentd should be deployed throughout the cluster and any selector would restrict where it is deployed. To control component placement, specify node selectors per component to be applied to their deployment configurations.

30.3. SPECIFYING LOGGING ANSIBLE VARIABLES

Parameters for the EFK deployment may be specified to the [inventory host file](#) to override the [defaults](#). Read the [Elasticsearch](#) and the [Fluentd](#) sections before choosing parameters:




NOTE

By default the Elasticsearch service uses port 9300 for TCP communication between nodes in a cluster.

Parameter	Description
openshift_logging_image_prefix	The prefix for logging component images. For example, setting the prefix to registry.access.redhat.com/openshift3/ creates registry.access.redhat.com/openshift3/logging-fluentd:latest .
openshift_logging_image_version	The version for logging component images. For example, setting the version to v3.7 creates registry.access.redhat.com/openshift3/logging-fluentd:v3.7 .
openshift_logging_use_ops	If set to true , configures a second Elasticsearch cluster and Kibana for operations logs. Fluentd splits logs between the main cluster and a cluster reserved for operations logs, which consists of the logs from the projects default , openshift , and openshift-infra , as well as Docker, OpenShift, and system logs from the journal. This means a second Elasticsearch cluster and Kibana are deployed. The deployments are distinguishable by the -ops suffix included in their names and have parallel deployment options listed below and described in Creating the Curator Configuration .
openshift_logging_master_url	The URL for the Kubernetes master, this does not need to be public facing but should be accessible from within the cluster. For example, https://<PRIVATE-MASTER-URL>:8443 .
openshift_logging_master_public_url	The public facing URL for the Kubernetes master. This is used for Authentication redirection by the Kibana proxy. For example, https://<CONSOLE-PUBLIC-URL-MASTER>:8443 .

Parameter	Description
openshift_logging_namespace	The namespace where Aggregated Logging is deployed.
openshift_logging_install_logging	Set to true to install logging. Set to false to uninstall logging.
openshift_logging_purge_logging	The common uninstall keeps PVC to prevent unwanted data loss during reinstalls. To ensure that the Ansible playbook completely and irreversibly removes all logging persistent data including PVC, set openshift_logging_install_logging to 'false' to trigger uninstallation and openshift_logging_purge_logging to 'true'. The default is set to 'false'.
openshift_logging_install_eventrouter	Coupled with openshift_logging_install_logging . When both are set to 'true', eventrouter will be installed. When both are 'false', eventrouter will be uninstalled.
openshift_logging_eventrouter_image_prefix	The prefix for the eventrouter logging image. The default is set to openshift_logging_image_prefix .
openshift_logging_eventrouter_image_version	The image version for the logging eventrouter. The default is set to 'latest'.
openshift_logging_eventrouter_sink	Select a sink for eventrouter, supported stdout and glog . The default is set to stdout .
openshift_logging_eventrouter_nodeselect	A map of labels, such as "node": "infra", "region": "west" , to select the nodes where the pod will land.
openshift_logging_eventrouter_replicas	The default is set to '1'.
openshift_logging_eventrouter_cpu_limit	The minimum amount of CPU to allocate to eventrouter. The default is set to '100m'.
openshift_logging_eventrouter_memory_limit	The memory limit for eventrouter pods. The default is set to '128Mi'.

Parameter	Description
openshift_logging_eventrouter_namespace	<p>The project where eventrouter is deployed. The default is set to 'default'.</p> <div>  <div> <p>IMPORTANT</p> <p>Do not set the project to anything other than default or openshift-*. If you specify a different project, event information from the other project can leak into indices that are not restricted to operations users. To use a non-default project, create the project as usual using oc new-project.</p> </div> </div>
openshift_logging_image_pull_secret	Specify the name of an existing pull secret to be used for pulling component images from an authenticated registry.
openshift_logging_curator_default_days	The default minimum age (in days) Curator uses for deleting log records.
openshift_logging_curator_run_hour	The hour of the day Curator will run.
openshift_logging_curator_run_minute	The minute of the hour Curator will run.
openshift_logging_curator_run_timezone	The timezone Curator uses for figuring out its run time. Provide a the timezone as a string in the tzselect(8) or timedatectl(1) "Region/Locality" format, for example America/New_York or UTC .
openshift_logging_curator_script_log_level	The script log level for Curator.
openshift_logging_curator_log_level	The log level for the Curator process.
openshift_logging_curator_cpu_limit	The amount of CPU to allocate to Curator.
openshift_logging_curator_memory_limit	The amount of memory to allocate to Curator.

Parameter	Description
openshift_logging_curator_nodeselector	A node selector that specifies which nodes are eligible targets for deploying Curator instances.
openshift_logging_curator_ops_cpu_limit	Equivalent to openshift_logging_curator_cpu_limit for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_curator_ops_memory_limit	Equivalent to openshift_logging_curator_memory_limit for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_kibana_hostname	The external host name for web clients to reach Kibana.
openshift_logging_kibana_cpu_limit	The amount of CPU to allocate to Kibana.
openshift_logging_kibana_memory_limit	The amount of memory to allocate to Kibana.
openshift_logging_kibana_proxy_debug	When true , set the Kibana Proxy log level to DEBUG.
openshift_logging_kibana_proxy_cpu_limit	The amount of CPU to allocate to Kibana proxy.
openshift_logging_kibana_proxy_memory_limit	The amount of memory to allocate to Kibana proxy.
openshift_logging_kibana_replica_count	The number of replicas to which Kibana should be scaled up.
openshift_logging_kibana_nodeselector	A node selector that specifies which nodes are eligible targets for deploying Kibana instances.
openshift_logging_kibana_env_vars	A map of environment variables to add to the Kibana deployment configuration. For example, {"ELASTICSEARCH_REQUESTTIMEOUT":"30000"}.
openshift_logging_kibana_key	The public facing key to use when creating the Kibana route.
openshift_logging_kibana_cert	The cert that matches the key when creating the Kibana route.
openshift_logging_kibana_ca	Optional. The CA to goes with the key and cert used when creating the Kibana route.

Parameter	Description
openshift_logging_kibana_ops_hostname	Equivalent to openshift_logging_kibana_hostname for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_kibana_ops_cpu_limit	Equivalent to openshift_logging_kibana_cpu_limit for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_kibana_ops_memory_limit	Equivalent to openshift_logging_kibana_memory_limit for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_kibana_ops_proxy_debug	Equivalent to openshift_logging_kibana_proxy_debug for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_kibana_ops_proxy_cpu_limit	Equivalent to openshift_logging_kibana_proxy_cpu_limit for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_kibana_ops_proxy_memory_limit	Equivalent to openshift_logging_kibana_proxy_memory_limit for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_kibana_ops_replica_count	Equivalent to openshift_logging_kibana_replica_count for Ops cluster when openshift_logging_use_ops is set to true .
openshift_logging_es_allow_external	Set to true to expose Elasticsearch as a reencrypt route. Set to false by default.
openshift_logging_es_hostname	<p>The external-facing hostname to use for the route and the TLS server certificate. The default is set to es.</p> <p>For example, if openshift_master_default_subdomain is set to =example.test, then the default value of openshift_logging_es_hostname will be es.example.test.</p>
openshift_logging_es_cert	The location of the certificate Elasticsearch uses for the external TLS server cert. The default is a generated cert.
openshift_logging_es_key	The location of the key Elasticsearch uses for the external TLS server cert. The default is a generated key.
openshift_logging_es_ca_ext	The location of the CA cert Elasticsearch uses for the external TLS server cert. The default is the internal CA.
openshift_logging_es_ops_allow_external	Set to true to expose Elasticsearch as a reencrypt route. Set to false by default.

Parameter	Description
openshift_logging_es_ops_hostname	<p>The external-facing hostname to use for the route and the TLS server certificate. The default is set to es-ops.</p> <p>For example, if openshift_master_default_subdomain is set to =example.test, then the default value of openshift_logging_es_ops_hostname will be es-ops.example.test.</p>
openshift_logging_es_ops_cert	The location of the certificate Elasticsearch uses for the external TLS server cert. The default is a generated cert.
openshift_logging_es_ops_key	The location of the key Elasticsearch uses for the external TLS server cert. The default is a generated key.
openshift_logging_es_ops_ca_ext	The location of the CA cert Elasticsearch uses for the external TLS server cert. The default is the internal CA.
openshift_logging_fluentd_nodeselector	<p>A node selector that specifies which nodes are eligible targets for deploying Fluentd instances. Any node where Fluentd should run (typically, all) must have this label before Fluentd is able to run and collect logs.</p> <p>When scaling up the Aggregated Logging cluster after installation, the openshift_logging role labels nodes provided by openshift_logging_fluentd_hosts with this node selector.</p> <p>As part of the installation, it is recommended that you add the Fluentd node selector label to the list of persisted node labels.</p>
openshift_logging_fluentd_cpu_limit	The CPU limit for Fluentd pods.
openshift_logging_fluentd_memory_limit	The memory limit for Fluentd pods.
openshift_logging_fluentd_journal_read_from_head	Set to true if Fluentd should read from the head of Journal when first starting up, using this may cause a delay in ES receiving current log records.
openshift_logging_fluentd_hosts	List of nodes that should be labeled for Fluentd to be deployed. The default is to label all nodes with <code>['--all']</code> . The null value is openshift_logging_fluentd_hosts={} . To spin up Fluentd pods update the daemonset's nodeSelector to a valid label. For example, <code>['host1.example.com', 'host2.example.com']</code> .

Parameter	Description
openshift_logging_fluentd_audit_container_engine	When openshift_logging_fluentd_audit_container_engine is set to true , the audit log of the container engine is collected and stored in ES. Enabling this variable allows the EFK to watch the specified audit log file or the default /var/log/audit.log file, collects audit information for the container engine for the platform, then puts it into Kibana.
openshift_logging_fluentd_audit_file	Location of audit log file. The default is /var/log/audit/audit.log . Enabling this variable allows the EFK to watch the specified audit log file or the default /var/log/audit.log file, collects audit information for the container engine for the platform, then puts it into Kibana.
openshift_logging_fluentd_audit_pos_file	Location of the Fluentd in_tail position file for the audit log file. The default is /var/log/audit/audit.log.pos . Enabling this variable allows the EFK to watch the specified audit log file or the default /var/log/audit.log file, collects audit information for the container engine for the platform, then puts it into Kibana.
openshift_logging_es_host	The name of the ES service where Fluentd should send logs.
openshift_logging_es_port	The port for the ES service where Fluentd should send logs.
openshift_logging_es_ca	The location of the CA Fluentd uses to communicate with openshift_logging_es_host .
openshift_logging_es_client_cert	The location of the client certificate Fluentd uses for openshift_logging_es_host .
openshift_logging_es_client_key	The location of the client key Fluentd uses for openshift_logging_es_host .
openshift_logging_es_cluster_size	Elasticsearch replicas to deploy. Redundancy requires at least three or more.
openshift_logging_es_cpu_limit	The amount of CPU limit for the ES cluster.
openshift_logging_es_memory_limit	Amount of RAM to reserve per Elasticsearch instance. It must be at least 512M. Possible suffixes are G,g,M,m.
openshift_logging_es_number_of_replicas	The number of replica shards per primary shard for every new index. Defaults to '0'. A minimum of 1 is advisable for production clusters.
openshift_logging_es_number_of_shards	The number of primary shards for every new index created in ES. Defaults to '1'.

Parameter	Description
openshift_logging_es_pv_selector	A key/value map added to a PVC in order to select specific PVs.
openshift_logging_es_pvc_dynamic	Set to true to have PVC claims annotated so that their backing storage is dynamically provisioned. When set to true the storage class is ignored and not set to the PVC.
openshift_logging_es_pvc_storage_class_name	To use a non-default storage class, set the variable with the storage class name. For example, set to one of the following, openshift_logging_es_pvc_storage_class_name=glusterprovisioner or openshift_logging_es_pvc_storage_class_name=cephrbdprovisioner .
openshift_logging_es_pvc_size	Size of the persistent volume claim to create per Elasticsearch instance. For example, 100G. If omitted, no PVCs are created and ephemeral volumes are used instead.
openshift_logging_es_pvc_prefix	<p>Prefix for the names of persistent volume claims to be used as storage for Elasticsearch instances. A number is appended per instance, such as logging-es-1. If they do not already exist, they are created with size es-pvc-size.</p> <p>When openshift_logging_es_pvc_prefix is set, and:</p> <ul style="list-style-type: none"> • openshift_logging_es_pvc_dynamic=true, the value for openshift_logging_es_pvc_size is optional. • openshift_logging_es_pvc_dynamic=false, the value for openshift_logging_es_pvc_size must be set.
openshift_logging_es_recover_after_time	The amount of time ES will wait before it tries to recover.
openshift_logging_es_storage_group	Number of a supplemental group ID for access to Elasticsearch storage volumes. Backing volumes should allow access by this group ID.
openshift_logging_es_nodeselector	A node selector specified as a map that determines which nodes are eligible targets for deploying Elasticsearch instances. This can be used to place these instances on nodes reserved or optimized for running them. For example, the selector could be {"node-type": "infrastructure"} . At least one active node must have this label before Elasticsearch will deploy.
openshift_logging_es_ops_host	Equivalent to openshift_logging_es_host for Ops cluster when openshift_logging_use_ops is set to true .

Parameter	Description
<code>openshift_logging_es_ops_port</code>	Equivalent to <code>openshift_logging_es_port</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_ca</code>	Equivalent to <code>openshift_logging_es_ca</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_client_cert</code>	Equivalent to <code>openshift_logging_es_client_cert</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_client_key</code>	Equivalent to <code>openshift_logging_es_client_key</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_cluster_size</code>	Equivalent to <code>openshift_logging_es_cluster_size</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_cpu_limit</code>	Equivalent to <code>openshift_logging_es_cpu_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_memory_limit</code>	Equivalent to <code>openshift_logging_es_memory_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_pv_selector</code>	Equivalent to <code>openshift_logging_es_pv_selector</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_pvc_dynamic</code>	Equivalent to <code>openshift_logging_es_pvc_dynamic</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_pvc_size</code>	Equivalent to <code>openshift_logging_es_pvc_size</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_pvc_prefix</code>	Equivalent to <code>openshift_logging_es_pvc_prefix</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_recover_after_time</code>	Equivalent to <code>openshift_logging_es_recover_after_time</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_storage_group</code>	Equivalent to <code>openshift_logging_es_storage_group</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to true .
<code>openshift_logging_es_ops_nodeselector</code>	A node selector that specifies which nodes are eligible targets for deploying Elasticsearch instances. This can be used to place these instances on nodes reserved or optimized for running them. For example, the selector could be node-type=infrastructure . At least one active node must have this label before Elasticsearch will deploy.

Parameter	Description
openshift_logging_elasticsearch_kibana_index_mode	<p>The default value, unique, allows users to each have their own Kibana index. In this mode, their saved queries, visualizations, and dashboards are not shared.</p> <p>You may also set the value shared_ops. In this mode, all operations users share a Kibana index which allows each operations user to see the the same queries, visualizations, and dashboards.</p>
openshift_logging_kibana_ops_nodeselector	A node selector that specifies which nodes are eligible targets for deploying Kibana instances.
openshift_logging_curator_ops_nodeselector	A node selector that specifies which nodes are eligible targets for deploying Curator instances.

Custom Certificates

You can specify custom certificates using the following inventory variables instead of relying on those generated during the deployment process. These certificates are used to encrypt and secure communication between a user's browser and Kibana. The security-related files will be generated if they are not supplied.

File Name	Description
openshift_logging_kibana_cert	A browser-facing certificate for the Kibana server.
openshift_logging_kibana_key	A key to be used with the browser-facing Kibana certificate.
openshift_logging_kibana_ca	The absolute path on the control node to the CA file to use for the browser facing Kibana certs.
openshift_logging_kibana_ops_cert	A browser-facing certificate for the Ops Kibana server.
openshift_logging_kibana_ops_key	A key to be used with the browser-facing Ops Kibana certificate.
openshift_logging_kibana_ops_ca	The absolute path on the control node to the CA file to use for the browser facing ops Kibana certs.

30.4. DEPLOYING THE EFK STACK

The EFK stack is deployed using an Ansible playbook to the EFK components. Run the playbook from the default OpenShift Ansible location using the default [inventory](#) file.

■

```
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/openshift-logging.yml
```

Running the playbook deploys all resources needed to support the stack; such as Secrets, ServiceAccounts, and DeploymentConfigs. The playbook waits to deploy the component pods until the stack is running. If the wait steps fail, the deployment could still be successful; it may be retrieving the component images from the registry which can take up to a few minutes. You can watch the process with:

```
$ oc get pods -w
```

They will eventually enter **Running** status. For additional details about the status of the pods during deployment by retrieving associated events:

```
$ oc describe pods/<pod_name>
```

Check the logs if the pods do not run successfully:

```
$ oc logs -f <pod_name>
```

30.5. UNDERSTANDING AND ADJUSTING THE DEPLOYMENT

This section describes adjustments that you can make to deployed components.

30.5.1. Ops Cluster



NOTE

The logs for the **default**, **openshift**, and **openshift-infra** projects are automatically aggregated and grouped into the **.operations** item in the Kibana interface.

The project where you have deployed the EFK stack (**logging**, as documented here) is *not* aggregated into **.operations** and is found under its ID.

If you set **openshift_logging_use_ops** to **true** in your inventory file, Fluentd is configured to split logs between the main Elasticsearch cluster and another cluster reserved for operations logs, which are defined as node system logs and the projects **default**, **openshift**, and **openshift-infra**. Therefore, a separate Elasticsearch cluster, a separate Kibana, and a separate Curator are deployed to index, access, and manage operations logs. These deployments are set apart with names that include **-ops**. Keep these separate deployments in mind if you enable this option. Most of the following discussion also applies to the operations cluster if present, just with the names changed to include **-ops**.

30.5.2. Elasticsearch

A highly-available environment requires at least three replicas of Elasticsearch; each on a different host. Elasticsearch replicas require their own storage, but an OpenShift Container Platform deployment configuration shares storage volumes between all its pods. So, when scaled up, the EFK deployer ensures each replica of Elasticsearch has its own deployment configuration.

It is possible to scale your cluster up after creation by modifying the **openshift_logging_es_cluser_size** in the inventory file and re-running the logging playbook.

Additional clustering parameters can be modified and are described in [Specifying Logging Ansible Variables](#).

Refer to [Elastic's documentation](#) for considerations involved in choosing storage and network location as directed below.

Viewing all Elasticsearch Deployments

To view all current Elasticsearch deployments:

```
$ oc get dc --selector logging-infra=elasticsearch
```

Node Selector

Because Elasticsearch can use a lot of resources, all members of a cluster should have low latency network connections to each other and to any remote storage. Ensure this by directing the instances to dedicated nodes, or a dedicated region within your cluster, using a [node selector](#).

To configure a node selector, specify the **openshift_logging_es_nodeselector** configuration option in the inventory file. This applies to all Elasticsearch deployments; if you need to individualize the node selectors, you must manually edit each deployment configuration after deployment. The node selector is specified as a python compatible dict. For example, **{"node-type": "infra", "region": "east"}**.

Persistent Elasticsearch Storage

By default, the **openshift_logging** Ansible role creates an ephemeral deployment in which all of a pod's data is lost upon restart. For production usage, specify a persistent storage volume for each Elasticsearch deployment configuration. You can create the necessary [persistent volume claims](#) before deploying or have them created for you. The PVCs must be named to match the **openshift_logging_es_pvc_prefix** setting, which defaults to **logging-es**; each PVC name will have a sequence number added to it: **logging-es-0**, **logging-es-1**, **logging-es-2**, and so on. If a PVC needed for the deployment exists already, it is used; if not, and **openshift_logging_es_pvc_size** has been specified, it is created with a request for that size.

**WARNING**

Using NFS storage as a volume or a persistent volume (or via NAS such as Gluster) is not supported for Elasticsearch storage, as Lucene relies on file system behavior that NFS does not supply. Data corruption and other problems can occur. If NFS storage is a requirement, you can allocate a large file on a volume to serve as a storage device and mount it locally on one host. For example, if your NFS storage volume is mounted at **/nfs/storage**:

```
$ truncate -s 1T /nfs/storage/elasticsearch-1
$ mkfs.xfs /nfs/storage/elasticsearch-1
$ mount -o loop /nfs/storage/elasticsearch-1 /usr/local/es-
storage
$ chown 1000:1000 /usr/local/es-storage
```

Then, use **/usr/local/es-storage** as a host-mount as described below. Use a different backing file as storage for each Elasticsearch replica.

This loopback must be maintained manually outside of OpenShift Container Platform, on the node. You must not maintain it from inside a container.

It is possible to use a local disk volume (if available) on each node host as storage for an Elasticsearch replica. Doing so requires some preparation as follows.

1. The relevant service account must be given the privilege to mount and edit a local volume:

```
$ oc adm policy add-scc-to-user privileged \
    system:serviceaccount:logging:aggregated-logging-
elasticsearch 1
```

- 1** Use the project you created earlier (for example, **logging**) when running the logging playbook.

2. Each Elasticsearch replica definition must be patched to claim that privilege, for example (change to **--selector component=es-ops** for Ops cluster):

```
$ for dc in $(oc get deploymentconfig --selector component=es -o
name); do
    oc scale $dc --replicas=0
    oc patch $dc \
        -p '{"spec":{"template":{"spec":{"containers":
[{"name":"elasticsearch","securityContext":{"privileged":
true}}]}}}}'
done
```

3. The Elasticsearch replicas must be located on the correct nodes to use the local storage, and should not move around even if those nodes are taken down for a period of time. This requires giving each Elasticsearch replica a node selector that is unique to a node where an administrator

has allocated storage for it. To configure a node selector, edit each Elasticsearch deployment configuration and add or edit the **nodeSelector** section to specify a unique label that you have applied for each desired node:

```
apiVersion: v1
kind: DeploymentConfig
spec:
  template:
    spec:
      nodeSelector:
        logging-es-node: "1" 1
```

- 1** This label should uniquely identify a replica with a single node that bears that label, in this case **logging-es-node=1**. Use the **oc label** command to apply labels to nodes as needed.

To automate applying the node selector you can instead use the **oc patch** command:

```
$ oc patch dc/logging-es-<suffix> \
  -p '{"spec":{"template":{"spec":{"nodeSelector":{"logging-es-
node":"1"}}}}}'
```

4. Once these steps are taken, a local host mount can be applied to each replica as in this example (where we assume storage is mounted at the same path on each node) (change to **--selector component=es-ops** for Ops cluster):

```
$ for dc in $(oc get deploymentconfig --selector component=es -o
name); do
  oc set volume $dc \
    --add --overwrite --name=elasticsearch-storage \
    --type=hostPath --path=/usr/local/es-storage
  oc rollout latest $dc
  oc scale $dc --replicas=1
done
```

Changing the Scale of Elasticsearch

If you need to scale up the number of Elasticsearch instances your cluster uses, it is not as simple as scaling up an Elasticsearch deployment configuration. This is due to the nature of persistent volumes and how Elasticsearch is configured to store its data and recover the cluster. Instead, scaling up requires creating a deployment configuration for each Elasticsearch cluster node.

The simplest way to change the scale of Elasticsearch is to modify the inventory host file and re-run the logging playbook as described previously. Assuming you have supplied persistent storage for the deployment, this should not be disruptive.



NOTE

Resizing an Elasticsearch cluster using the logging playbook is only possible when the new **openshift_logging_es_cluster_size** value is higher than the current number of Elasticsearch nodes (scaled up) in the cluster.

If you do not wish to reinstall, for instance because you have made customizations that you would like to preserve, then it is possible to add new Elasticsearch deployment configurations to the cluster using a template supplied by the deployer. This requires a more complicated procedure however.

Expose Elasticsearch as a Route

By default, Elasticsearch deployed with OpenShift aggregated logging is not accessible from outside the logging cluster. You can enable a route for external access to Elasticsearch for those tools that want to access its data.

You have access to Elasticsearch using your OpenShift token, and you can provide the external Elasticsearch and Elasticsearch Ops hostnames when creating the server certificate (similar to Kibana).

1. To access Elasticsearch as a reencrypt route, define the following variables:

```
openshift_logging_es_allow_external=True
openshift_logging_es_hostname=elasticsearch.example.com
```

2. Run the **openshift-logging.yml** Ansible playbook:

```
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
    cluster/openshift-logging.yml
```

3. To log in to Elasticsearch remotely, the request must contain three HTTP headers:

```
Authorization: Bearer $token
X-Proxy-Remote-User: $username
X-Forwarded-For: $ip_address
```

4. You must have access to the project in order to be able to access to the logs. For example:

```
$ oc login <user1>
$ oc new-project <user1project>
$ oc new-app <httpd-example>
```

5. You need to get the token of this ServiceAccount to be used in the request:

```
$ token=$(oc whoami -t)
```

6. Using the token previously configured, you should be able access Elasticsearch through the exposed route:

```
$ curl -k -H "Authorization: Bearer $token" -H "X-Proxy-Remote-User:
$(oc whoami)" -H "X-Forwarded-For: 127.0.0.1"
https://es.example.test/_cat/indices
```

30.5.3. Fluentd

Fluentd is deployed as a DaemonSet that deploys replicas according to a node label selector, which you can specify with the inventory parameter **openshift_logging_fluentd_nodeselector** and the default is **logging-infra-fluentd**. As part of the OpenShift cluster installation, it is recommended that you add the Fluentd node selector to the list of persisted [node labels](#).

Fluentd uses **journald** as the system log source. These are log messages from the operating system, Docker, and OpenShift. For container logs, Fluentd determines which log driver Docker is using, **json-file** or **journald**, and automatically reads the logs from that source.



NOTE

As of OpenShift Container Platform 3.3, Fluentd no longer reads historical log files when using the JSON file log driver. In situations where clusters have a large number of log files and are older than the EFK deployment, this avoids delays when pushing the most recent logs into Elasticsearch. Curator deleting logs are migrated soon after they are added to Elasticsearch.



NOTE

It may require several minutes, or hours, depending on the size of your journal, before any new log entries are available in Elasticsearch, when using **openshift_logging_journal_read_from_head=true**.



WARNING

It is highly recommended that you use the default value for **use-journal**. In scenarios where upgrading OpenShift Container Platform changes the Docker log driver, if **use-journal=False** is explicitly specified as part of installation, Fluentd still expects to read logs generated using the **json-file** log driver. This results in a lack of log ingestion. If this has happened within your logging cluster, [troubleshoot](#) it.

See [Updating Fluentd's Log Source After a Docker Log Driver Update](#) for more information.

Configuring Fluentd to Send Logs to an External Log Aggregator

You can configure Fluentd to send a copy of its logs to an external log aggregator, and not the default Elasticsearch, using the **secure-forward** plug-in. From there, you can further process log records after the locally hosted Fluentd has processed them.

The logging deployment provides a **secure-forward.conf** section in the Fluentd configmap for configuring the external aggregator:

```
<store>
@type secure_forward
self_hostname pod-${HOSTNAME}
shared_key thisisasharedkey
secure yes
enable_strict_verification yes
ca_cert_path /etc/fluent/keys/your_ca_cert
ca_private_key_path /etc/fluent/keys/your_private_key
ca_private_key_passphrase passphrase
<server>
  host ose1.example.com
```

```

    port 24284
  </server>
  <server>
    host ose2.example.com
    port 24284
    standby
  </server>
  <server>
    host ose3.example.com
    port 24284
    standby
  </server>
</store>

```

This can be updated using the **oc edit** command:

```
$ oc edit configmap/logging-fluentd
```

Certificates to be used in **secure-forward.conf** can be added to the existing secret that is mounted on the Fluentd pods. The **your_ca_cert** and **your_private_key** values must match what is specified in **secure-forward.conf** in **configmap/logging-fluentd**:

```

$ oc patch secrets/logging-fluentd --type=json \
  --patch "[{'op':'add','path':'/data/your_ca_cert','value':'$(base64
/path/to/your_ca_cert.pem)'}]"
$ oc patch secrets/logging-fluentd --type=json \
  --patch "[{'op':'add','path':'/data/your_private_key','value':'$(base64
/path/to/your_private_key.pem)'}]"

```



NOTE

Replace **your_private_key** with a generic name. This is a link to the JSON path, not a path on your host system

When configuring the external aggregator, it must be able to accept messages securely from Fluentd.

If the external aggregator is another Fluentd server, it must have the **fluent-plugin-secure-forward** plug-in installed and make use of the input plug-in it provides:

```

<source>
  @type secure_forward

  self_hostname ${HOSTNAME}
  bind 0.0.0.0
  port 24284

  shared_key thisisasharedkey

  secure yes
  cert_path      /path/for/certificate/cert.pem
  private_key_path /path/for/certificate/key.pem
  private_key_passphrase secret_foo_bar_baz
</source>

```

Further explanation of how to set up the **fluent-plugin-secure-forward** plug-in can be [found here](#).

Reducing the Number of Connections from Fluentd to the API Server

With **mux**, you can deploy **N** number of **mux** services, where **N** is fewer than the number of nodes. Each Fluentd is configured with **USE_MUX_CLIENT=1**. This tells Fluentd to send the raw logs to **mux** with no filtering and no Kubernetes metadata filtering, which involves connections to the API server. You can perform all of the processing and Kubernetes metadata filtering with **mux**.



IMPORTANT

The **mux** is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offerings/techpreview/>.

Parameter	Description
openshift_logging_use_mux	The default is set to False . If set to True , a service called mux is deployed. This service acts as a Fluentd secure_forward aggregator for the node agent Fluentd daemonsets running in the cluster. Use openshift_logging_use_mux to reduce the number of connections to the OpenShift API server, and configure each node in Fluentd to send raw logs to mux and turn off the Kubernetes metadata plug-in.
openshift_logging_mux_allow_external	The default is set to False . If set to True , the mux service is deployed, and it is configured to allow Fluentd clients running outside of the cluster to send logs using secure_forward . This allows OpenShift logging to be used as a central logging service for clients other than OpenShift, or other OpenShift clusters.
openshift_logging_use_mux_client	The default is set to False . If set to True , the node agent Fluentd services is configured to send logs to the mux service rather than directly to Elasticsearch, and their Kubernetes metadata filters is disabled, reducing the number of connections to the API server.
openshift_logging_mux_hostname	The default is mux plus openshift_master_default_subdomain . This is the hostname external_clients will use to connect to mux , and is used in the TLS server cert subject.
openshift_logging_mux_port	24284
openshift_logging_mux_cpu_limit	500M

Parameter	Description
openshift_logging_mux_memory_limit	1Gi
openshift_logging_mux_default_namespaces	The default is mux-undefined . The first value in the list is the namespace to use for undefined projects, followed by any additional namespaces to create by default. Usually, you do not need to set this value.
openshift_logging_mux_namespaces	The default value is empty, allowing for additional namespaces to create for external mux clients to associate with their logs. You will need to set this value.

Throttling logs in Fluentd

For projects that are especially verbose, an administrator can throttle down the rate at which the logs are read in by Fluentd before being processed.



WARNING

Throttling can contribute to log aggregation falling behind for the configured projects; log entries can be lost if a pod is deleted before Fluentd catches up.



NOTE

Throttling does not work when using the systemd journal as the log source. The throttling implementation depends on being able to throttle the reading of the individual log files for each project. When reading from the journal, there is only a single log source, no log files, so no file-based throttling is available. There is not a method of restricting the log entries that are read into the Fluentd process.

To tell Fluentd which projects it should be restricting, edit the throttle configuration in its ConfigMap after deployment:

```
$ oc edit configmap/logging-fluentd
```

The format of the **throttle-config.yaml** key is a YAML file that contains project names and the desired rate at which logs are read in on each node. The default is 1000 lines at a time per node. For example:

```
logging:
  read_lines_limit: 500

test-project:
  read_lines_limit: 10

operations:
  read_lines_limit: 100
```

When you make changes to any part of the EFK stack, specifically Elasticsearch or Fluentd, you should first scale Elasticsearch down to zero and scale Fluentd so it does not match any other nodes. Then, make the changes and scale Elasticsearch and Fluentd back.

To scale Elasticsearch to zero:

```
$ oc scale --replicas=0 dc/<ELASTICSEARCH_DC>
```

Change nodeSelector in the daemonset configuration to match zero:

Get the fluentd node selector:

```
$ oc get ds logging-fluentd -o yaml |grep -A 1 Selector
nodeSelector:
  logging-infra-fluentd: "true"
```

Use the `oc patch` command to modify the daemonset nodeSelector:

```
$ oc patch ds logging-fluentd -p '{"spec":{"template":{"spec":{"nodeSelector":{"nonexistlabel":"true"}}}}}'
```

Get the fluentd node selector:

```
$ oc get ds logging-fluentd -o yaml |grep -A 1 Selector
nodeSelector:
  "nonexistlabel: "true"
```

Scale Elasticsearch back up from zero:

```
$ oc scale --replicas=# dc/<ELASTICSEARCH_DC>
```

Change nodeSelector in the daemonset configuration back to logging-infra-fluentd: "true".

Use the **oc patch** command to modify the daemonset nodeSelector:

```
oc patch ds logging-fluentd -p '{"spec":{"template":{"spec":{"nodeSelector":{"logging-infra-fluentd":"true"}}}}}'
```

30.5.4. Kibana


To access the Kibana console from the OpenShift Container Platform web console, add the **loggingPublicURL** parameter in the */etc/origin/master/master-config.yaml* file, with the URL of the Kibana console (the **kibana-hostname** parameter). The value must be an HTTPS URL:

```
...
assetConfig:
  ...
  loggingPublicURL: "https://kibana.example.com"
...
```

Setting the **loggingPublicURL** parameter creates a **View Archive** button on the OpenShift Container Platform web console under the **Browse** → **Pods** → **<pod_name>** → **Logs** tab. This links to the Kibana console.

You can scale the Kibana deployment as usual for redundancy:

```
$ oc scale dc/logging-kibana --replicas=2
```



NOTE

To ensure the scale persists across multiple executions of the logging playbook, make sure to update the **openshift_logging_kibana_replica_count** in the inventory file.

You can see the user interface by visiting the site specified by the **openshift_logging_kibana_hostname** variable.

See the [Kibana documentation](#) for more information on Kibana.

Kibana Visualize

Kibana Visualize enables you to create visualizations and dashboards for monitoring container and pod logs allows administrator users (**cluster-admin** or **cluster-reader**) to view logs by deployment, namespace, pod, and container.

Kibana Visualize exists inside the Elasticsearch and ES-OPS pod, and must be run inside those pods. To load dashboards and other Kibana UI objects, you must first log into Kibana as the user you want to add the dashboards to, then log out. This will create the necessary per-user configuration that the next step relies on. Then, run:

```
$ oc exec <$espod> -- es_load_kibana_ui_objects <user-name>
```

Where **\$espod** is the name of any one of your Elasticsearch pods.

30.5.5. Curator

Curator allows administrators to configure scheduled Elasticsearch maintenance operations to be performed automatically on a per-project basis. It is scheduled to perform actions daily based on its configuration. Only one Curator pod is recommended per Elasticsearch cluster. Curator is configured via a YAML configuration file with the following structure:

```
$PROJECT_NAME:
  $ACTION:
    $UNIT: $VALUE

$PROJECT_NAME:
  $ACTION:
    $UNIT: $VALUE
...
```

The available parameters are:

Variable Name	Description
\$PROJECT_NAME	The actual name of a project, such as myapp-devel . For OpenShift Container Platform operations logs, use the name .operations as the project name.
\$ACTION	The action to take, currently only delete is allowed.
\$UNIT	One of days , weeks , or months .
\$VALUE	An integer for the number of units.
.defaults	Use .defaults as the \$PROJECT_NAME to set the defaults for projects that are not specified.
runhour	(Number) the hour of the day in 24-hour format at which to run the Curator jobs. For use with .defaults .
runminute	(Number) the minute of the hour at which to run the Curator jobs. For use with .defaults .

For example, to configure Curator to:

- delete indices in the **myapp-dev** project older than **1 day**
- delete indices in the **myapp-qe** project older than **1 week**
- delete **operations** logs older than **8 weeks**
- delete all other projects indices after they are **30 days** old
- run the Curator jobs at midnight every day

Use:

```
myapp-dev:
  delete:
    days: 1

myapp-qe:
  delete:
    weeks: 1

.operations:
  delete:
    weeks: 8

.defaults:
  delete:
    days: 30
  runhour: 0
  runminute: 0
```



IMPORTANT

When you use **month** as the **\$UNIT** for an operation, Curator starts counting at the first day of the current month, not the current day of the current month. For example, if today is April 15, and you want to delete indices that are 2 months older than today (**delete: months: 2**), Curator does not delete indices that are dated older than February 15; it deletes indices older than February 1. That is, it goes back to the first day of the current month, then goes back two whole months from that date. If you want to be exact with Curator, it is best to use days (for example, **delete: days: 30**).

30.5.5.1. Creating the Curator Configuration

The **openshift_logging** Ansible role provides a ConfigMap from which Curator reads its configuration. You may edit or replace this ConfigMap to reconfigure Curator. Currently the **logging-curator** ConfigMap is used to configure both your ops and non-ops Curator instances. Any **.operations** configurations are in the same location as your application logs configurations.

1. To edit the provided ConfigMap to configure your Curator instances:

```
$ oc edit configmap/logging-curator
```

2. To replace the provided ConfigMap instead:

```
$ create /path/to/mycuratorconfig.yaml
$ oc create configmap logging-curator -o yaml \
  --from-file=config.yaml=/path/to/mycuratorconfig.yaml | \
  oc replace -f -
```

3. After you make your changes, redeploy Curator:

```
$ oc rollout latest dc/logging-curator
$ oc rollout latest dc/logging-curator-ops
```

30.6. CLEANUP

Remove everything generated during the deployment.

```
$ ansible-playbook [-i </path/to/inventory>] \
  /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
  cluster/openshift-logging.yml \
```

30.7. TROUBLESHOOTING KIBANA

Using the Kibana console with OpenShift Container Platform can cause problems that are easily solved, but are not accompanied with useful error messages. Check the following troubleshooting sections if you are experiencing any problems when deploying Kibana on OpenShift Container Platform:

Login Loop

The OAuth2 proxy on the Kibana console must share a secret with the master host's OAuth2 server. If the secret is not identical on both servers, it can cause a login loop where you are continuously redirected back to the Kibana login page.

To fix this issue, delete the current OAuthClient, and use **openshift-ansible** to re-run the **openshift_logging** role:

```
$ oc delete oauthclient/kibana-proxy
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
cluster/openshift-logging.yml
```

Cryptic Error When Viewing the Console

When attempting to visit the Kibana console, you may receive a browser error instead:

```
{"error":"invalid_request","error_description":"The request is missing a
required parameter,
includes an invalid parameter value, includes a parameter more than once,
or is otherwise malformed."}
```

This can be caused by a mismatch between the OAuth2 client and server. The return address for the client must be in a whitelist so the server can securely redirect back after logging in.

Fix this issue by replacing the OAuthClient entry:

```
$ oc delete oauthclient/kibana-proxy
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
cluster/openshift-logging.yml
```

If the problem persists, check that you are accessing Kibana at a URL listed in the OAuth client. This issue can be caused by accessing the URL at a forwarded port, such as 1443 instead of the standard 443 HTTPS port. You can adjust the server whitelist by editing the OAuth client:

```
$ oc edit oauthclient/kibana-proxy
```

503 Error When Viewing the Console

If you receive a proxy error when viewing the Kibana console, it could be caused by one of two issues.

First, Kibana may not be recognizing pods. If Elasticsearch is slow in starting up, Kibana may timeout trying to reach it. Check whether the relevant service has any endpoints:

```
$ oc describe service logging-kibana
Name:                logging-kibana
[...]
Endpoints:           <none>
```

If any Kibana pods are live, endpoints are listed. If they are not, check the state of the Kibana pods and deployment. You may need to scale the deployment down and back up again.

The second possible issue may be caused if the route for accessing the Kibana service is masked. This can happen if you perform a test deployment in one project, then deploy in a different project without completely removing the first deployment. When multiple routes are sent to the same destination, the default router will only route to the first created. Check the problematic route to see if it is defined in multiple places:

```
$ oc get route --all-namespaces --selector logging-infra=support
```

F-5 Load Balancer and X-Forwarded-For Enabled

If you are attempting to use a F-5 load balancer in front of Kibana with **X-Forwarded-For** enabled, this can cause an issue in which the Elasticsearch **Searchguard** plug-in is unable to correctly accept connections from Kibana.

Example Kibana Error Message

```
Kibana: Unknown error while connecting to Elasticsearch
Error: Unknown error while connecting to Elasticsearch
Error: UnknownHostException[No trusted proxies]
```

To configure Searchguard to ignore the extra header:

1. Scale down all Fluentd pods.
2. Scale down Elasticsearch after the Fluentd pods have terminated.
3. Add **searchguard.http.xforwardedfor.header: DUMMY** to the Elasticsearch configuration section.

```
$ oc edit configmap/logging-elasticsearch 1
```

1 This approach requires that Elasticsearch's configurations are within a ConfigMap.

4. Scale Elasticsearch back up.
5. Scale up all Fluentd pods.

30.8. SENDING LOGS TO AN EXTERNAL ELASTICSEARCH INSTANCE

Fluentd sends logs to the value of the **ES_HOST**, **ES_PORT**, **OPS_HOST**, and **OPS_PORT** environment variables of the Elasticsearch deployment configuration. The application logs are directed to the **ES_HOST** destination, and operations logs to **OPS_HOST**.



NOTE

Sending logs directly to an AWS Elasticsearch instance is not supported. Use [Fluentd Secure Forward](#) to direct logs to an instance of Fluentd that you control and that is configured with the **fluent-plugin-aws-elasticsearch-service** plug-in.

To direct logs to a specific Elasticsearch instance, edit the deployment configuration and replace the value of the above variables with the desired instance:

```
$ oc edit dc/<deployment_configuration>
```

For an external Elasticsearch instance to contain both application and operations logs, you can set **ES_HOST** and **OPS_HOST** to the same destination, while ensuring that **ES_PORT** and **OPS_PORT** also have the same value.

If your externally hosted Elasticsearch instance does not use TLS, update the `_CLIENT_CERT`, `_CLIENT_KEY`, and `_CA` variables to be empty. If it does use TLS, but not mutual TLS, update the `_CLIENT_CERT` and `_CLIENT_KEY` variables to be empty and patch or recreate the **logging-fluentd** secret with the appropriate `_CA` value for communicating with your Elasticsearch instance. If it uses Mutual TLS as the provided Elasticsearch instance does, patch or recreate the **logging-fluentd** secret with your client key, client cert, and CA.



NOTE

If you are not using the provided Kibana and Elasticsearch images, you will not have the same multi-tenant capabilities and your data will not be restricted by user access to a particular project.

30.9. SENDING LOGS TO AN EXTERNAL SYSLOG SERVER

Use the **fluent-plugin-remote-syslog** plug-in on the host to send logs to an external syslog server.

Set environment variables in the **logging-fluentd** or **logging-mux** deployment configurations:

- name: REMOTE_SYSLOG_HOST 1
value: host1
- name: REMOTE_SYSLOG_HOST_BACKUP
value: host2
- name: REMOTE_SYSLOG_PORT_BACKUP
value: 5555

1 The desired remote syslog host. Required for each host.

This will build two destinations. The syslog server on **host1** will be receiving messages on the default port of **514**, while **host2** will be receiving the same messages on port **5555**.

Alternatively, you can configure your own custom **fluent.conf** in the **logging-fluentd** or **logging-mux** ConfigMaps.

Fluentd Environment Variables

Parameter	Description
USE_REMOTE_SYSLOG	Defaults to false . Set to true to enable use of the fluent-plugin-remote-syslog gem
REMOTE_SYSLOG_HOST	(Required) Hostname or IP address of the remote syslog server.
REMOTE_SYSLOG_PORT	Port number to connect on. Defaults to 514 .
REMOTE_SYSLOG_SEVERITY	Set the syslog severity level. Defaults to debug .

Parameter	Description
REMOTE_SYSLOG_FACILITY	Set the syslog facility. Defaults to local0 .
REMOTE_SYSLOG_USE_RECORD	Defaults to false . Set to true to use the record's severity and facility fields to set on the syslog message.
REMOTE_SYSLOG_REMOVE_TAG_PREFIX	Removes the prefix from the tag, defaults to ' ' (empty).
REMOTE_SYSLOG_TAG_KEY	If specified, uses this field as the key to look on the record, to set the tag on the syslog message.
REMOTE_SYSLOG_PAYLOAD_KEY	If specified, uses this field as the key to look on the record, to set the payload on the syslog message.

**WARNING**

This implementation is insecure, and should only be used in environments where you can guarantee no snooping on the connection.

Fluentd Logging Ansible Variables

Parameter	Description
openshift_logging_fluentd_remote_syslog	The default is set to false . Set to true to enable use of the fluent-plugin-remote-syslog gem.
openshift_logging_fluentd_remote_syslog_host	Hostname or IP address of the remote syslog server, this is mandatory.
openshift_logging_fluentd_remote_syslog_port	Port number to connect on, defaults to 514 .
openshift_logging_fluentd_remote_syslog_severity	Set the syslog severity level, defaults to debug .
openshift_logging_fluentd_remote_syslog_facility	Set the syslog facility, defaults to local0 .

Parameter	Description
<code>openshift_logging_fluentd_remote_syslog_use_record</code>	The default is set to false . Set to true to use the record's severity and facility fields to set on the syslog message.
<code>openshift_logging_fluentd_remote_syslog_remove_tag_prefix</code>	Removes the prefix from the tag, defaults to <code>' '</code> (empty).
<code>openshift_logging_fluentd_remote_syslog_tag_key</code>	If string is specified, uses this field as the key to look on the record, to set the tag on the syslog message.
<code>openshift_logging_fluentd_remote_syslog_payload_key</code>	If string is specified, uses this field as the key to look on the record, to set the payload on the syslog message.

Mux Logging Ansible Variables

Parameter	Description
<code>openshift_logging_mux_remote_syslog</code>	The default is set to false . Set to true to enable use of the fluent-plugin-remote-syslog gem.
<code>openshift_logging_mux_remote_syslog_host</code>	Hostname or IP address of the remote syslog server, this is mandatory.
<code>openshift_logging_mux_remote_syslog_port</code>	Port number to connect on, defaults to 514 .
<code>openshift_logging_mux_remote_syslog_severity</code>	Set the syslog severity level, defaults to debug .
<code>openshift_logging_mux_remote_syslog_facility</code>	Set the syslog facility, defaults to local0 .
<code>openshift_logging_mux_remote_syslog_use_record</code>	The default is set to false . Set to true to use the record's severity and facility fields to set on the syslog message.
<code>openshift_logging_mux_remote_syslog_remove_tag_prefix</code>	Removes the prefix from the tag, defaults to <code>' '</code> (empty).

Parameter	Description
<code>openshift_logging_mux_remote_syslog_tag_key</code>	If string is specified, uses this field as the key to look on the record, to set the tag on the syslog message.
<code>openshift_logging_mux_remote_syslog_payload_key</code>	If string is specified, uses this field as the key to look on the record, to set the payload on the syslog message.

30.10. PERFORMING ADMINISTRATIVE ELASTICSEARCH OPERATIONS

As of logging version 3.2.0, an administrator certificate, key, and CA that can be used to communicate with and perform administrative operations on Elasticsearch are provided within the **logging-elasticsearch** secret.



NOTE

To confirm whether or not your EFK installation provides these, run:

```
$ oc describe secret logging-elasticsearch
```

If they are not available, refer to [Manual Upgrades](#) to ensure you are on the latest version first.

1. Connect to an Elasticsearch pod that is in the cluster on which you are attempting to perform maintenance.
2. To find a pod in a cluster use either:

```
$ oc get pods -l component=es -o name | head -1
$ oc get pods -l component=es-ops -o name | head -1
```

3. Connect to a pod:

```
$ oc rsh <your_Elasticsearch_pod>
```

4. Once connected to an Elasticsearch container, you can use the certificates mounted from the secret to communicate with Elasticsearch per its [Indices APIs documentation](#).
Fluentd sends its logs to Elasticsearch using the index format **project.{project_name}.
{project_uuid}.YYYY.MM.DD** where YYYY.MM.DD is the date of the log record.

For example, to delete all logs for the **logging** project with uuid **3b3594fa-2ccd-11e6-acb7-0eb6b35eae3** from June 15, 2016, we can run:


```
$ curl --key /etc/elasticsearch/secret/admin-key \
--cert /etc/elasticsearch/secret/admin-cert \
--cacert /etc/elasticsearch/secret/admin-ca -XDELETE \
```



```
"https://localhost:9200/project.logging.3b3594fa-2ccd-11e6-acb7-0eb6b35eae3.2016.06.15"
```

30.11. CHANGING THE AGGREGATED LOGGING DRIVER

By default, aggregated logging uses the **journald** log driver [unless json-file was specified during installation](#). You can change the log driver between **journald** and **json-file** as needed.



IMPORTANT

When using the **json-file** driver, ensure that your Docker version is Docker version **docker-1.12.6-55.gitc4618fb.el7_4** now or later.

Fluentd determines the driver Docker is using by checking the **/etc/docker/daemon.json** and **/etc/sysconfig/docker** files.

You can determine which driver Docker is using with the **docker info** command:

```
# docker info | grep Logging
LoggingDriver: journald
```

To change between **json-file** and **journald** after installation:

1. Modify either the **/etc/sysconfig/docker** or **/etc/docker/daemon.json** files.

For example:

```
# cat /etc/sysconfig/docker
OPTIONS=' --selinux-enabled --log-driver=json-file --log-opt max-size=1M --log-opt max-file=3 --signature-verification=False'

cat /etc/docker/daemon.json
{
  "log-driver": "json-file",
  "log-opts": {
    "max-size": "1M",
    "max-file": "1"
  }
}
```

2. Restart the Docker service:

```
systemctl restart docker
```

3. Update the [Fluentd log source](#).

30.12. UPDATING FLUENTD'S LOG SOURCE AFTER A DOCKER LOG DRIVER UPDATE

If the Docker log driver has changed from **json-file** to **journald** and Fluentd was previously configured with **USE_JOURNAL=False**, then it will not be able to pick up any new logs that are created. When the Fluentd daemonset is configured with the default value for **USE_JOURNAL**, then it will detect

the Docker log driver upon pod start-up, and configure itself to pull from the appropriate source.

To update Fluentd to detect the correct source upon start-up:

1. Remove the label from nodes where Fluentd is deployed:

```
$ oc label node --all logging-infra-fluentd- 1
```

- 1 This example assumes use of the default Fluentd node selector and it being deployed on all nodes.

2. Update the **daemonset/logging-fluentd USE_JOURNAL** value to be empty:

```
$ oc patch daemonset/logging-fluentd \
  -p '{"spec":{"template":{"spec":{"containers":
[{"name":"fluentd-elasticsearch","env":[{"name":"USE_JOURNAL",
"value":""}]}}}}}'
```

3. Relabel your nodes to schedule Fluentd deployments:

```
$ oc label node --all logging-infra-fluentd=true 1
```

- 1 This example assumes use of the default Fluentd node selector and it being deployed on all nodes.

30.13. MANUAL ELASTICSEARCH ROLLOUTS

As of OpenShift Container Platform 3.7 the Aggregated Logging stack updated the Elasticsearch Deployment Config object so that it no longer has a Config Change Trigger, meaning any changes to the **dc** will not result in an automatic rollout. This was to prevent unintended restarts happening in the ES cluster, which could create excessive shard rebalancing as cluster members restart.

This section presents two restart procedures: [rolling-restart](#) and [full-restart](#). Where a rolling restart applies appropriate changes to the Elasticsearch cluster without down time (provided three masters are configured) and a full restart safely applies major changes without risk to existing data.

30.13.1. Performing an Elasticsearch Rolling Cluster Restart

A rolling restart is recommended, when any of the following changes are made:

- nodes on which Elasticsearch pods run require a reboot
- logging-elasticsearch configmap
- logging-es-* deployment configuration
- new image deployment, or upgrade

This will be the recommended restart policy going forward.

**NOTE**

Any action you do for an ES cluster will need to be repeated for the ops cluster if **openshift_logging_use_ops** was configured to be **True**.

1. Prevent shard balancing when purposely bringing down nodes:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
  curl -s
  --cacert /etc/elasticsearch/secret/admin-ca \
  --cert /etc/elasticsearch/secret/admin-cert \
  --key /etc/elasticsearch/secret/admin-key \
  -XPUT 'https://localhost:9200/_cluster/settings' \
  -d '{ "transient": { "cluster.routing.allocation.enable" :
    "none" } }'
```

2. Once complete, for each **dc** you have for an ES cluster, run **oc rollout latest** to deploy the latest version of the **dc** object:

```
$ oc rollout latest <dc_name>
```

You will see a new pod deployed. Once the pod has two ready containers, you can move on to the next **dc**.

3. Once all **dc**'s for the cluster have been rolled out, re-enable shard balancing:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
  curl -s
  --cacert /etc/elasticsearch/secret/admin-ca \
  --cert /etc/elasticsearch/secret/admin-cert \
  --key /etc/elasticsearch/secret/admin-key \
  -XPUT 'https://localhost:9200/_cluster/settings' \
  -d '{ "transient": { "cluster.routing.allocation.enable" :
    "all" } }'
```

30.13.2. Performing an Elasticsearch Full Cluster Restart

A full restart is recommended when changing major versions of Elasticsearch or other changes which might put data integrity a risk during the change process.

**NOTE**

Any action you do for an ES cluster will need to be repeated for the ops cluster if **openshift_logging_use_ops** was configured to be **True**.

**NOTE**

When making changes to the **logging-es-ops** service use components "es-ops-blocked" and "es-ops" instead in the patch

1. Disable all external communications to the ES cluster while it is down. Edit your non-cluster logging service (for example, **logging-es**, **logging-es-ops**) to no longer match the ES pods running:

```
$ oc patch svc/logging-es -p '{"spec":{"selector":{"component":"es-blocked"},"provider":"openshift"}}}'
```

2. Prevent shard balancing when purposely bringing down nodes:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
  curl -s
  --cacert /etc/elasticsearch/secret/admin-ca \
  --cert /etc/elasticsearch/secret/admin-cert \
  --key /etc/elasticsearch/secret/admin-key \
  -XPUT 'https://localhost:9200/_cluster/settings' \
  -d '{ "transient": { "cluster.routing.allocation.enable" :
    "none" } }'
```

3. Perform a shard synced flush to ensure there are no pending operations waiting to be written to disk prior to shutting down:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
  curl -s
  --cacert /etc/elasticsearch/secret/admin-ca \
  --cert /etc/elasticsearch/secret/admin-cert \
  --key /etc/elasticsearch/secret/admin-key \
  -XPUT 'https://localhost:9200/_flush/synced'
```

4. Once complete, for each **dc** you have for an ES cluster, run **oc rollout latest** to deploy the latest version of the **dc** object:

```
$ oc rollout latest <dc_name>
```

You will see a new pod deployed. Once the pod has two ready containers, you can move on to the next **dc**.

5. Once all DCs for the cluster have been rolled out, re-enable shard balancing:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
  curl -s
  --cacert /etc/elasticsearch/secret/admin-ca \
  --cert /etc/elasticsearch/secret/admin-cert \
  --key /etc/elasticsearch/secret/admin-key \
  -XPUT 'https://localhost:9200/_cluster/settings' \
  -d '{ "transient": { "cluster.routing.allocation.enable" :
    "all" } }'
```

6. Once the restart is complete, enable all external communications to the ES cluster. Edit your non-cluster logging service (for example, **logging-es**, **logging-es-ops**) to match the ES pods running again:

```
$ oc patch svc/logging-es -p '{"spec":{"selector":
  {"component":"es","provider":"openshift"}}}'
```

CHAPTER 31. AGGREGATE LOGGING SIZING GUIDELINES

31.1. OVERVIEW

The [Elasticsearch, Fluentd, and Kibana](#) (EFK) stack aggregates logs from nodes and applications running inside your OpenShift Container Platform installation. Once deployed it uses [Fluentd](#) to aggregate event logs from all nodes, projects, and pods into [Elasticsearch \(ES\)](#). It also provides a centralized [Kibana](#) web UI where users and administrators can create rich visualizations and dashboards with the aggregated data.

Fluentd [bulk uploads](#) logs to an index, in JSON format, then Elasticsearch routes your search requests to the appropriate shards.

31.2. INSTALLATION

The general procedure for installing an aggregate logging stack in OpenShift Container Platform is described in [Aggregating Container Logs](#). There are some important things to keep in mind while going through the installation guide:

In order for the logging pods to spread evenly across your cluster, an empty [node selector](#) should be used.

```
$ oc adm new-project logging --node-selector=""
```

In conjunction with node labeling, which is done later, this controls pod placement across the logging project. You can now create the logging project.

```
$ oc project logging
```

Elasticsearch (ES) should be deployed with a cluster size of at least three for resiliency to node failures. This is specified by setting the `openshift_logging_es_cluster_size` parameter in the inventory host file.

Refer to [Ansible Variables](#) for a full list of parameters.

If you do not have an existing Kibana installation, you can use `kibana.example.com` as a value to `openshift_logging_kibana_hostname`.

Installation can take some time depending on whether the images were already retrieved from the registry or not, and on the size of your cluster.

Inside the `logging` namespace, you can check your deployment with `oc get all`.

```
$ oc get all
```

NAME	REVISION	REPLICAS
TRIGGERED BY		
logging-curator	1	1
logging-es-6cvk237t	1	1
logging-es-e5x4t4ai	1	1
logging-es-xmwvnrsv	1	1
logging-kibana	1	1
NAME	DESIRED	CURRENT
AGE		

```

logging-curator-1          1          1          3d
logging-es-6cvk237t-1      1          1          3d
logging-es-e5x4t4ai-1     1          1          3d
logging-es-xmwvnrsv-1     1          1          3d
logging-kibana-1          1          1          3d
NAME                        HOST/PORT    PATH
SERVICE                    TERMINATION  LABELS
logging-kibana              kibana.example.com
logging-kibana              reencrypt   component=support,logging-
infra=support,provider=openshift
logging-kibana-ops         kibana-ops.example.com
logging-kibana-ops         reencrypt   component=support,logging-
infra=support,provider=openshift
NAME                        CLUSTER-IP    EXTERNAL-IP
PORT(S)                    AGE
logging-es                 172.24.155.177 <none>
9200/TCP                   3d
logging-es-cluster        None          <none>
9300/TCP                   3d
logging-es-ops            172.27.197.57 <none>
9200/TCP                   3d
logging-es-ops-cluster    None          <none>
9300/TCP                   3d
logging-kibana            172.27.224.55 <none>
443/TCP                    3d
logging-kibana-ops        172.25.117.77 <none>
443/TCP                    3d
NAME                        READY          STATUS
RESTARTS                    AGE
logging-curator-1-6s7wy     1/1           Running        0
3d
logging-deployer-un6ut      0/1           Completed      0
3d
logging-es-6cvk237t-1-cnvw3 1/1           Running        0
3d
logging-es-e5x4t4ai-1-v933h 1/1           Running        0
3d
logging-es-xmwvnrsv-1-adr5x 1/1           Running        0
3d
logging-fluentd-156xn       1/1           Running        0
3d
logging-fluentd-40biz       1/1           Running        0
3d
logging-fluentd-8k847       1/1           Running        0
3d

```

You should end up with a similar setup to the following.

```
$ oc get pods -o wide
```

```

NAME                        READY    STATUS    RESTARTS  AGE
NODE
logging-curator-1-6s7wy     1/1     Running   0          3d
ip-172-31-24-239.us-west-2.compute.internal
logging-deployer-un6ut      0/1     Completed 0          3d
ip-172-31-6-152.us-west-2.compute.internal

```

```

logging-es-6cvk237t-1-cnvw3    1/1      Running    0          3d
ip-172-31-24-238.us-west-2.compute.internal
logging-es-e5x4t4ai-1-v933h    1/1      Running    0          3d
ip-172-31-24-235.us-west-2.compute.internal
logging-es-xmwvnrsv-1-adr5x    1/1      Running    0          3d
ip-172-31-24-233.us-west-2.compute.internal
logging-fluentd-156xn          1/1      Running    0          3d
ip-172-31-24-241.us-west-2.compute.internal
logging-fluentd-40biz          1/1      Running    0          3d
ip-172-31-24-236.us-west-2.compute.internal
logging-fluentd-8k847          1/1      Running    0          3d
ip-172-31-24-237.us-west-2.compute.internal
logging-fluentd-9a3qx          1/1      Running    0          3d
ip-172-31-24-231.us-west-2.compute.internal
logging-fluentd-abvgj          1/1      Running    0          3d
ip-172-31-24-228.us-west-2.compute.internal
logging-fluentd-bh74n          1/1      Running    0          3d
ip-172-31-24-238.us-west-2.compute.internal
...
...

```

By default the amount of RAM allocated to each ES instance is 8GB.

openshift_logging_es_memory_limit is the parameter used in the **openshift-ansible** host inventory file. Keep in mind that **half** of this value will be passed to the individual elasticsearch pods java processes [heap size](#).

[Learn more about installing EFK.](#)

31.2.1. Large Clusters

At 100 nodes or more, it is recommended to first pre-pull the logging images from **docker pull registry.access.redhat.com/openshift3/logging-fluentd:v3.7**. After deploying the logging infrastructure pods (Elasticsearch, Kibana, and Curator), node labeling should be done in steps of 20 nodes at a time. For example:

Using a simple loop:

```

$ while read node; do oc label nodes $node logging-infra-fluentd=true;
done < 20_fluentd.lst

```

The following also works:

```

$ oc label nodes 10.10.0.{100..119} logging-infra-fluentd=true

```

Labeling nodes in groups paces the DaemonSets used by OpenShift logging, helping to avoid contention on shared resources such as the image registry.



NOTE

Check for the occurrence of any "CrashLoopBackOff | ImagePullFailed | Error" issues. **oc logs <pod>**, **oc describe pod <pod>** and **oc get event** are helpful diagnostic commands.

31.3. SYSTEMD-JOURNALD AND RSYSLOG

Rate-limiting

In Red Hat Enterprise Linux (RHEL) 7 the **systemd-journald.socket** unit creates **/dev/log** during the boot process, and then passes input to **systemd-journald.service**. Every **syslog()** call goes to the journal.

Rsyslog uses the **imjournal** module as a default input mode for journal files. Refer to [Interaction of rsyslog and journal](#) for detailed information about this topic.

A simple test harness was developed, which uses [logger](#) across the cluster nodes to make entries of different sizes at different rates in the system log. During testing simulations under a default Red Hat Enterprise Linux (RHEL) 7 installation with **systemd-219-19.el7.x86_64** at certain logging rates (approximately 40 log lines per second), we encountered the default rate limit of **rsyslogd**. After adjusting these limits, entries stopped being written to journald due to local journal file corruption. [This issue is resolved in later versions of systemd](#).

Scaling up

As you scale up your project, the default logging environment might need some adjustments. After updating to **systemd-219-22.el7.x86_64**, we added:

```
$IMUXSockRateLimitInterval 0
$IMJournalRateLimitInterval 0
```

to **/etc/rsyslog.conf** and:

```
# Disable rate limiting
RateLimitInterval=1s
RateLimitBurst=10000
Storage=volatile
Compress=no
MaxRetentionSec=30s
```

to **/etc/systemd/journald.conf**.

Now, restart the services.

```
$ systemctl restart systemd-journald.service
$ systemctl restart rsyslog.service
```

These settings account for the bursty nature of uploading in bulk.

After removing the rate limit, you may see increased CPU utilization on the system logging daemons as it processes any messages that would have previously been throttled.

Rsyslog is configured (see **ratelimit.interval**, **ratelimit.burst**) to rate-limit entries read from the journal at 10,000 messages in 300 seconds. A good rule of thumb is to ensure that the rsyslog rate-limits account for the systemd-journald rate-limits.

31.4. SCALING UP EFK LOGGING

If you do not indicate the desired scale at first deployment, the least disruptive way of adjusting your cluster is by re-running the Ansible logging playbook after updating the inventory file with an updated **openshift_logging_es_cluster_size** value. parameter. Refer to the [Performing Administrative Elasticsearch Operations](#) section for more in-depth information.

31.5. STORAGE CONSIDERATIONS

An Elasticsearch index is a collection of shards and its corresponding replica shards. This is how ES implements high availability internally, therefore there is little need to use hardware based mirroring RAID variants. RAID 0 can still be used to increase overall disk performance.

Every search request needs to hit a copy of every shard in the index. Each ES instance requires its own individual storage, but an OpenShift Container Platform deployment can only provide volumes shared by all of its pods, which again means that Elasticsearch shouldn't be implemented with a single node.

A [persistent volume](#) should be added to each Elasticsearch deployment configuration so that we have one volume per [replica shard](#). On OpenShift Container Platform this is often achieved through [Persistent Volume Claims](#)

- 1 volume per shard
- 1 volume per replica shard

The PVCs must be named based on the `openshift_logging_es_pvc_prefix` setting. Refer to [Persistent Elasticsearch Storage](#) for more details.

Below are capacity planning guidelines for OpenShift Container Platform aggregate logging. **Example scenario**

Assumptions:

1. Which application: Apache
2. Bytes per line: 256
3. Lines per second load on application: 1
4. Raw text data → JSON

Baseline (256 characters per minute → 15KB/min)

Logging Infra Pods	Storage Throughput
3 es 1 kibana 1 curator 1 fluentd	6 pods total: 90000 x 86400 = 7,7 GB/day
3 es 1 kibana 1 curator 11 fluentd	16 pods total: 225000 x 86400 = 24,0 GB/day
3 es 1 kibana 1 curator 20 fluentd	25 pods total: 225000 x 86400 = 32,4 GB/day

Calculating total logging throughput and disk space required for your logging environment requires knowledge of your application. For example, if one of your applications on average logs 10 lines-per-second, each 256 bytes-per-line, calculate per-application throughput and disk space as follows:

```
(bytes-per-line * (lines-per-second) = 2560 bytes per app per second
(2560) * (number-of-pods-per-node,100) = 256,000 bytes per second per node
256k * (number-of-nodes) = total logging throughput per cluster
```

Fluentd ships any logs from **systemd journal** and `/var/lib/docker/containers/` to Elasticsearch. [Learn more](#).

Local SSD drives are recommended in order to achieve the best performance. In Red Hat Enterprise Linux (RHEL) 7, the [deadline](#) IO scheduler is the default for all block devices except SATA disks. For SATA disks, the default IO scheduler is **cfq**.

Sizing storage for ES is greatly dependent on how you optimize your indices. Therefore, consider how much data you need in advance and that you are aggregating application log data. Some Elasticsearch users have found that it is necessary to [keep absolute storage consumption around 50% and below 70% at all times](#). This helps to avoid Elasticsearch becoming unresponsive during large merge operations.

CHAPTER 32. ENABLING CLUSTER METRICS

32.1. OVERVIEW

The [kubelet](#) exposes metrics that can be collected and stored in back-ends by [Heapster](#).

As an OpenShift Container Platform administrator, you can view a cluster's metrics from all containers and components in one user interface. These metrics are also used by [horizontal pod autoscalers](#) in order to determine when and how to scale.

This topic describes using [Hawkular Metrics](#) as a metrics engine which stores the data persistently in a [Cassandra](#) database. When this is configured, CPU, memory and network-based metrics are viewable from the OpenShift Container Platform web console and are available for use by [horizontal pod autoscalers](#).

Heapster retrieves a list of all nodes from the master server, then contacts each node individually through the `/stats` endpoint. From there, Heapster scrapes the metrics for CPU, memory and network usage, then exports them into Hawkular Metrics.

The storage volume metrics available on the kubelet are not available through the `/stats` endpoint, but are available through the `/metrics` endpoint. See OpenShift Container Platform via Prometheus for detailed information.

Browsing individual pods in the web console displays separate sparkline charts for memory and CPU. The time range displayed is selectable, and these charts automatically update every 30 seconds. If there are multiple containers on the pod, then you can select a specific container to display its metrics.

If [resource limits](#) are defined for your project, then you can also see a donut chart for each pod. The donut chart displays usage against the resource limit. For example: **145 Available of 200 MiB**, with the donut chart showing **55 MiB Used**.

32.2. BEFORE YOU BEGIN

An Ansible playbook is available to deploy and upgrade cluster metrics. You should familiarize yourself with the [Advanced Installation](#) section. This provides information for preparing to use Ansible and includes information about configuration. Parameters are added to the Ansible inventory file to configure various areas of cluster metrics.

The following describe the various areas and the parameters that can be added to the Ansible inventory file in order to modify the defaults:

- [Metrics Project](#)
- [Metrics Data Storage](#)

32.3. METRICS PROJECT

The components for cluster metrics must be deployed to the **openshift-infra** project in order for autoscaling to work. [Horizontal pod autoscalers](#) specifically use this project to discover the Heapster service and use it to retrieve metrics. The metrics project can be changed by adding **openshift_metrics_project** to the inventory file.

32.4. METRICS DATA STORAGE

You can store the metrics data to either [persistent storage](#) or to a temporary [pod volume](#).

32.4.1. Persistent Storage

Running OpenShift Container Platform cluster metrics with persistent storage means that your metrics are stored to a [persistent volume](#) and are able to survive a pod being restarted or recreated. This is ideal if you require your metrics data to be guarded from data loss. For production environments it is highly recommended to configure persistent storage for your metrics pods.

The size requirement of the Cassandra storage is dependent on the number of pods. It is the administrator's responsibility to ensure that the size requirements are sufficient for their setup and to monitor usage to ensure that the disk does not become full. The size of the persisted volume claim is specified with the `openshift_metrics_cassandra_pvc_size` [Ansible variable](#) which is set to 10 GB by default.

If you would like to use [dynamically provisioned persistent volumes](#) set the `openshift_metrics_cassandra_storage_type` [variable](#) to `dynamic` in the inventory file.

32.4.2. Capacity Planning for Cluster Metrics

After running the `openshift_metrics` Ansible role, the output of `oc get pods` should resemble the following:

```
# oc get pods -n openshift-infra
NAME                                READY   STATUS    RESTARTS   AGE
hawkular-cassandra-1-l5y4g         1/1     Running   0          17h
hawkular-metrics-1t9so             1/1     Running   0          17h
heapster-febru                     1/1     Running   0          17h
```

OpenShift Container Platform metrics are stored using the Cassandra database, which is deployed with settings of `openshift_metrics_cassandra_limits_memory: 2G`; this value could be adjusted further based upon the available memory as determined by the Cassandra start script. This value should cover most OpenShift Container Platform metrics installations, but using environment variables you can modify the `MAX_HEAP_SIZE` along with heap new generation size, `HEAP_NEWSIZE`, in the Cassandra Dockerfile prior to deploying cluster metrics.

By default, metrics data is stored for seven days. After seven days, Cassandra begins to purge the oldest metrics data. Metrics data for deleted pods and projects is not automatically purged; it is only removed once the data is more than seven days old.

Example 32.1. Data Accumulated by 10 Nodes and 1000 Pods

In a test scenario including 10 nodes and 1000 pods, a 24 hour period accumulated 2.5 GB of metrics data. Therefore, the capacity planning formula for metrics data in this scenario is:

$$(((2.5 \times 10^9) \div 1000) \div 24) \div 10^6 = \sim 0.125 \text{ MB/hour per pod.}$$

Example 32.2. Data Accumulated by 120 Nodes and 10000 Pods

In a test scenario including 120 nodes and 10000 pods, a 24 hour period accumulated 25 GB of metrics data. Therefore, the capacity planning formula for metrics data in this scenario is:

$$(((11.410 \times 10^9) \div 1000) \div 24) \div 10^6 = 0.475 \text{ MB/hour}$$

	1000 pods	10000 pods
Cassandra storage data accumulated over 24 hours (default metrics parameters)	2.5 GB	11.4 GB

If the default value of 7 days for **openshift_metrics_duration** and 30 seconds for **openshift_metrics_resolution** are preserved, then weekly storage requirements for the Cassandra pod would be:

	1000 pods	10000 pods
Cassandra storage data accumulated over seven days (default metrics parameters)	20 GB	90 GB

In the previous table, an additional 10 percent was added to the expected storage space as a buffer for unexpected monitored pod usage.



WARNING

If the Cassandra persisted volume runs out of sufficient space, then data loss occurs.

For cluster metrics to work with persistent storage, ensure that the persistent volume has the **ReadWriteOnce** access mode. If this mode is not active, then the persistent volume claim cannot locate the persistent volume, and Cassandra fails to start.

To use persistent storage with the metric components, ensure that a [persistent volume](#) of sufficient size is available. The creation of [persistent volume claims](#) is handled by the OpenShift Ansible **openshift_metrics** role.

OpenShift Container Platform metrics also supports dynamically-provisioned persistent volumes. To use this feature with OpenShift Container Platform metrics, it is necessary to set the value of **openshift_metrics_cassandra_storage_type** to **dynamic**. You can use EBS, GCE, and Cinder storage back-ends to [dynamically provision persistent volumes](#).

For information on configuring the performance and scaling the cluster metrics pods, see the [Scaling Cluster Metrics](#) topic.

Table 32.1. Cassandra Database storage requirements based on number of nodes/pods in the cluster

Number of Nodes	Number of Pods	Cassandra Storage growth speed	Cassandra storage growth per day	Cassandra storage growth per week
210	10500	500 MB per hour	15 GB	75 GB
990	11000	1 GB per hour	30 GB	210 GB

In the above calculation, approximately 20 percent of the expected size was added as overhead to ensure that the storage requirements do not exceed calculated value.

If the **METRICS_DURATION** and **METRICS_RESOLUTION** values are kept at the default (7 days and 30 seconds respectively), it is safe to plan Cassandra storage size requirements for week, as in the values above.



WARNING

Because OpenShift Container Platform metrics uses the Cassandra database as a datastore for metrics data, if **USE_PERSISTANT_STORAGE=true** is set during the metrics set up process, **PV** will be on top in the network storage, with NFS as the default. However, using network storage in combination with Cassandra is not recommended, as per the [Cassandra documentation](#).

Recommendations for OpenShift Container Platform Version 3.7

- Run metrics pods on dedicated OpenShift Container Platform [infrastructure nodes](#).
- Use persistent storage when configuring metrics. Set **USE_PERSISTENT_STORAGE=true**.
- Keep the **METRICS_RESOLUTION=30** parameter in OpenShift Container Platform metrics deployments. Using a value lower than the default value of **30** for **METRICS_RESOLUTION** is not recommended. When using the Ansible metrics installation procedure, this is the **openshift_metrics_resolution** parameter.
- Closely monitor OpenShift Container Platform nodes with host metrics pods to detect early capacity shortages (CPU and memory) on the host system. These capacity shortages can cause problems for metrics pods.
- In OpenShift Container Platform version 3.7 testing, test cases up to 25,000 pods were monitored in a OpenShift Container Platform cluster.

Known Issues and Limitations

Testing found that the **heapster** metrics component is capable of handling up to 25,000 pods. If the amount of pods exceed that number, Heapster begins to fall behind in metrics processing, resulting in the possibility of metrics graphs no longer appearing. Work is ongoing to increase the number of pods that Heapster can gather metrics on, as well as upstream development of alternate metrics-gathering solutions.

32.4.3. Non-Persistent Storage

Running OpenShift Container Platform cluster metrics with non-persistent storage means that any stored metrics are deleted when the pod is deleted. While it is much easier to run cluster metrics with non-persistent data, running with non-persistent data does come with the risk of permanent data loss. However, metrics can still survive a container being restarted.

In order to use non-persistent storage, you must set the `openshift_metrics_cassandra_storage_type` variable to `emptydir` in the inventory file.



NOTE

When using non-persistent storage, metrics data is written to `/var/lib/origin/openshift.local.volumes/pods` on the node where the Cassandra pod runs. Ensure `/var` has enough free space to accommodate metrics storage.

32.5. METRICS ANSIBLE ROLE

The OpenShift Container Platform Ansible `openshift_metrics` role configures and deploys all of the metrics components using the variables from the [Configuring Ansible](#) inventory file.

32.5.1. Specifying Metrics Ansible Variables

The `openshift_metrics` role included with OpenShift Ansible defines the tasks to deploy cluster metrics. The following is a list of role variables that can be added to your inventory file if it is necessary to override them.

Table 32.2. Ansible Variables

Variable	Description
<code>openshift_metrics_install_metrics</code>	Deploy metrics if <code>true</code> . Otherwise, undeploy.
<code>openshift_metrics_start_cluster</code>	Start the metrics cluster after deploying the components.
<code>openshift_metrics_image_prefix</code>	The prefix for the component images. With The prefix for the component images. With <code>openshift3/ose-metrics-cassandra:v3.7.9</code> , set prefix <code>openshift/ose-</code> .
<code>openshift_metrics_image_version</code>	The version for the component images. For example, with <code>openshift3/ose-metrics-cassandra:v3.7.9</code> , set version as <code>v3.7.9</code> , or to always get the latest 3.7 image, set <code>v3.7</code> .
<code>openshift_metrics_startup_timeout</code>	The time, in seconds, to wait until Hawkular Metrics and Heapster start up before attempting a restart.
<code>openshift_metrics_duration</code>	The number of days to store metrics before they are purged.

Variable	Description
openshift_metrics_resolution	The frequency that metrics are gathered. Defined as a number and time identifier: seconds (s), minutes (m), hours (h).
openshift_metrics_cassandra_pvc_prefix	The persistent volume claim prefix created for Cassandra. A serial number is appended to the prefix starting from 1.
openshift_metrics_cassandra_pvc_size	The persistent volume claim size for each of the Cassandra nodes.
openshift_metrics_cassandra_storage_class_name	If you want to explicitly set the storage class, you must not set openshift_metrics_cassandra_storage_type to emptydir or dynamic .
openshift_metrics_cassandra_storage_type	Use emptydir for ephemeral storage (for testing); pv for persistent volumes, which need to be created before the installation; or dynamic for dynamic persistent volumes.
openshift_metrics_cassandra_replicas	The number of Cassandra nodes for the metrics stack. This value dictates the number of Cassandra replication controllers.
openshift_metrics_cassandra_limits_memory	The memory limit for the Cassandra pod. For example, a value of 2Gi would limit Cassandra to 2 GB of memory. This value could be further adjusted by the start script based on available memory of the node on which it is scheduled.
openshift_metrics_cassandra_limits_cpu	The CPU limit for the Cassandra pod. For example, a value of 4000m (4000 millicores) would limit Cassandra to 4 CPUs.
openshift_metrics_cassandra_requests_memory	The amount of memory to request for Cassandra pod. For example, a value of 2Gi would request 2 GB of memory.
openshift_metrics_cassandra_requests_cpu	The CPU request for the Cassandra pod. For example, a value of 4000m (4000 millicores) would request 4 CPUs.
openshift_metrics_cassandra_storage_group	The supplemental storage group to use for Cassandra.

Variable	Description
openshift_metrics_cassandra_nodeselector	Set to the desired, existing node selector to ensure that pods are placed onto nodes with specific labels. For example, {"region": "infra"} .
openshift_metrics_hawkular_ca	An optional certificate authority (CA) file used to sign the Hawkular certificate.
openshift_metrics_hawkular_cert	The certificate file used for re-encrypting the route to Hawkular metrics. The certificate must contain the host name used by the route. If unspecified, the default router certificate is used.
openshift_metrics_hawkular_key	The key file used with the Hawkular certificate.
openshift_metrics_hawkular_limits_memory	The amount of memory to limit the Hawkular pod. For example, a value of 2Gi would limit the Hawkular pod to 2 GB of memory. This value could be further adjusted by the start script based on available memory of the node on which it is scheduled.
openshift_metrics_hawkular_limits_cpu	The CPU limit for the Hawkular pod. For example, a value of 4000m (4000 millicores) would limit the Hawkular pod to 4 CPUs.
openshift_metrics_hawkular_replicas	The number of replicas for Hawkular metrics.
openshift_metrics_hawkular_requests_memory	The amount of memory to request for the Hawkular pod. For example, a value of 2Gi would request 2 GB of memory.
openshift_metrics_hawkular_requests_cpu	The CPU request for the Hawkular pod. For example, a value of 4000m (4000 millicores) would request 4 CPUs.
openshift_metrics_hawkular_nodeselector	Set to the desired, existing node selector to ensure that pods are placed onto nodes with specific labels. For example, {"region": "infra"} .
openshift_metrics_heapster_allowed_users	A comma-separated list of CN to accept. By default, this is set to allow the OpenShift service proxy to connect. Add system:master-proxy to the list when overriding in order to allow horizontal pod autoscaling to function properly.
openshift_metrics_heapster_limits_memory	The amount of memory to limit the Heapster pod. For example, a value of 2Gi would limit the Heapster pod to 2 GB of memory.

Variable	Description
openshift_metrics_heapster_limits_cpu	The CPU limit for the Heapster pod. For example, a value of 4000m (4000 millicores) would limit the Heapster pod to 4 CPUs.
openshift_metrics_heapster_requests_memory	The amount of memory to request for Heapster pod. For example, a value of 2Gi would request 2 GB of memory.
openshift_metrics_heapster_requests_cpu	The CPU request for the Heapster pod. For example, a value of 4000m (4000 millicores) would request 4 CPUs.
openshift_metrics_heapster_standalone	Deploy only Heapster, without the Hawkular Metrics and Cassandra components.
openshift_metrics_heapster_nodeselector	Set to the desired, existing node selector to ensure that pods are placed onto nodes with specific labels. For example, {"region": "infra"} .
openshift_metrics_install_hawkular_agent	Set to true to install the Hawkular OpenShift Agent (HOSA). Set to false to remove the HOSA from an installation. HOSA can be used to collect custom metrics from your pods. This component is currently in Technology Preview and is not installed by default.
openshift_metrics_hawkular_hostname	Set when executing the openshift_metrics Ansible role, since it uses the host name for the Hawkular Metrics route . This value should correspond to a fully qualified domain name.



NOTE

The Hawkular OpenShift Container Platform Agent on OpenShift Container Platform is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offerings/techpreview/>.

See [Compute Resources](#) for further discussion on how to specify requests and limits.

If you are using [persistent storage](#) with Cassandra, it is the administrator's responsibility to set a sufficient disk size for the cluster using the **openshift_metrics_cassandra_pvc_size** variable. It is also the administrator's responsibility to monitor disk usage to make sure that it does not become full.

**WARNING**

Data loss results if the Cassandra persisted volume runs out of sufficient space.

All of the other variables are optional and allow for greater customization. For instance, if you have a custom install in which the Kubernetes master is not available under `https://kubernetes.default.svc:443` you can specify the value to use instead with the `openshift_metrics_master_url` parameter. To deploy a specific version of the metrics components, modify the `openshift_metrics_image_version` variable.

**WARNING**

It is highly recommended to not use **latest** for the `openshift_metrics_image_version`. The **latest** version corresponds to the very latest version available and can cause issues if it brings in a newer version not meant to function on the version of OpenShift Container Platform you are currently running.

32.5.2. Using Secrets

The OpenShift Container Platform Ansible `openshift_metrics` role auto-generates self-signed certificates for use between its components and generates a [re-encrypting route](#) to expose the Hawkular Metrics service. This route is what allows the web console to access the Hawkular Metrics service.

In order for the browser running the web console to trust the connection through this route, it must trust the route's certificate. This can be accomplished by [providing your own certificates](#) signed by a trusted Certificate Authority. The `openshift_metrics` role allows you to specify your own certificates, which it then uses when creating the route.

The router's default certificate are used if you do not provide your own.

32.5.2.1. Providing Your Own Certificates

To provide your own certificate, which is used by the [re-encrypting route](#), you can set the `openshift_metrics_hawkular_cert`, `openshift_metrics_hawkular_key`, and `openshift_metrics_hawkular_cavariab`les in your inventory file.


The `hawkular-metrics.pem` value needs to contain the certificate in its *.pem* format. You may also need to provide the certificate for the Certificate Authority which signed this *.pem* file via the `hawkular-metrics-ca.cert` secret.

For more information, see the [re-encryption route documentation](#).

32.6. DEPLOYING THE METRIC COMPONENTS

Because deploying and configuring all the metric components is handled with OpenShift Container Platform Ansible, you can deploy everything in one step.

The following examples show you how to deploy metrics with and without persistent storage using the default parameters.



IMPORTANT

In accordance with upstream Kubernetes rules, metrics can be collected only on the default interface of **eth0**.

Example 32.3. Deploying with Persistent Storage

The following command sets the Hawkular Metrics route to use **hawkular-metrics.example.com** and is deployed using persistent storage.

You must have a persistent volume of sufficient size available.

```
$ ansible-playbook [-i </path/to/inventory>]
<OPENSIFT_ANSIBLE_DIR>/byo/openshift-cluster/openshift-metrics.yml \
-e openshift_metrics_install_metrics=True \
-e openshift_metrics_hawkular_hostname=hawkular-metrics.example.com \
-e openshift_metrics_cassandra_storage_type=pv
```

Example 32.4. Deploying without Persistent Storage

The following command sets the Hawkular Metrics route to use **hawkular-metrics.example.com** and deploy without persistent storage.

```
$ ansible-playbook [-i </path/to/inventory>]
<OPENSIFT_ANSIBLE_DIR>/byo/openshift-cluster/openshift-metrics.yml \
-e openshift_metrics_install_metrics=True \
-e openshift_metrics_hawkular_hostname=hawkular-metrics.example.com
```



WARNING

Because this is being deployed without persistent storage, metric data loss can occur.

32.6.1. Metrics Diagnostics

There are some diagnostics for metrics to assist in evaluating the state of the metrics stack. To execute diagnostics for metrics:

```
$ oc adm diagnostics MetricsApiProxy
```

32.7. SETTING THE METRICS PUBLIC URL

The OpenShift Container Platform web console uses the data coming from the Hawkular Metrics service to display its graphs. The URL for accessing the Hawkular Metrics service must be configured with the **metricsPublicURL** option in the [master configuration file](#) (*/etc/origin/master/master-config.yaml*). This URL corresponds to the route created with the **openshift_metrics_hawkular_hostname** inventory variable used during the [deployment](#) of the metrics components.



NOTE

You must be able to resolve the **openshift_metrics_hawkular_hostname** from the browser accessing the console.

For example, if your **openshift_metrics_hawkular_hostname** corresponds to **hawkular-metrics.example.com**, then you must make the following change in the **master-config.yaml** file:

```
assetConfig:
  ...
  metricsPublicURL: "https://hawkular-
    metrics.example.com/hawkular/metrics"
```

Once you have updated and saved the **master-config.yaml** file, you must restart your OpenShift Container Platform instance.

When your OpenShift Container Platform server is back up and running, metrics are displayed on the pod overview pages.

CAUTION

If you are using self-signed certificates, remember that the Hawkular Metrics service is hosted under a different host name and uses different certificates than the console. You may need to explicitly open a browser tab to the value specified in **metricsPublicURL** and accept that certificate.

To avoid this issue, use certificates which are configured to be acceptable by your browser.

32.8. ACCESSING HAWKULAR METRICS DIRECTLY

To access and manage metrics more directly, use the [Hawkular Metrics API](#).



NOTE

When accessing Hawkular Metrics from the API, you are only able to perform reads. Writing metrics is disabled by default. If you want individual users to also be able to write metrics, you must set the **openshift_metrics_hawkular_user_write_access** [variable](#) to **true**.

However, it is recommended to use the default configuration and only have metrics enter the system via Heapster. If write access is enabled, any user can write metrics to the system, which can affect performance and cause Cassandra disk usage to unpredictably increase.

The [Hawkular Metrics documentation](#) covers how to use the API, but there are a few differences when dealing with the version of Hawkular Metrics configured for use on OpenShift Container Platform:

32.8.1. OpenShift Container Platform Projects and Hawkular Tenants

Hawkular Metrics is a multi-tenanted application. It is configured so that a project in OpenShift Container Platform corresponds to a tenant in Hawkular Metrics.

As such, when accessing metrics for a project named **MyProject** you must set the **Hawkular-Tenant** header to **MyProject**.

There is also a special tenant named **_system** which contains system level metrics. This requires either a **cluster-reader** or **cluster-admin** level privileges to access.

32.8.2. Authorization

The Hawkular Metrics service authenticates the user against OpenShift Container Platform to determine if the user has access to the project it is trying to access.

Hawkular Metrics accepts a bearer token from the client and verifies that token with the OpenShift Container Platform server using a **SubjectAccessReview**. If the user has proper read privileges for the project, they are allowed to read the metrics for that project. For the **_system** tenant, the user requesting to read from this tenant must have **cluster-reader** permission.

When accessing the Hawkular Metrics API, you must pass a bearer token in the **Authorization** header.

32.9. SCALING OPENSIFT CONTAINER PLATFORM CLUSTER METRICS PODS

Information about scaling cluster metrics capabilities is available in the [Scaling and Performance Guide](#).

32.10. INTEGRATION WITH AGGREGATED LOGGING

Hawkular Alerts must be connected to the Aggregated Logging's Elasticsearch to react on log events. By default, Hawkular tries to find Elasticsearch on its default place (namespace **logging**, pod **logging-es**) at every boot. If Aggregated Logging is installed after Hawkular, the Hawkular Metrics pod might need to be restarted in order to recognize the new Elasticsearch server. The Hawkular boot log provides a clear indication if the integration could not be properly configured, with messages like:

```
Failed to import the logging certificate into the store. Continuing, but
the
logging integration might fail.
```

or

```
Could not get the logging secret! Status code: 000. The Hawkular Alerts
integration with Logging might not work properly.
```

This feature is available from version 3.7.0. You can confirm if logging is available by checking the log for an entry like:

```
Retrieving the Logging's CA and adding to the trust store, if Logging is
available.
```

32.11. CLEANUP

You can remove everything deployed by the OpenShift Container Platform Ansible **openshift_metrics** role by performing the following steps:

```
$ ansible-playbook [-i </path/to/inventory>]
<OPENSIFT_ANSIBLE_DIR>/byo/openshift-cluster/openshift-metrics.yml \
    -e openshift_metrics_install_metrics=False
```

32.12. PROMETHEUS ON OPENSIFT CONTAINER PLATFORM

Prometheus is a stand-alone, open source systems monitoring and alerting toolkit. You can use Prometheus to visualize metrics and alerts for OpenShift Container Platform system resources.



IMPORTANT

Prometheus on OpenShift Container Platform is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offerings/techpreview/>.

32.12.1. Setting Prometheus Role Variables

The Prometheus role creates:

- The **openshift-metrics** namespace.
- Prometheus **clusterrolebinding** and service account.
- Prometheus pod with Prometheus behind OAuth proxy, Alertmanager, and Alert Buffer as a stateful set.
- Prometheus and **prometheus-alerts** ConfigMaps.
- Prometheus and Prometheus Alerts services and direct routes.

Prometheus deployment is disabled by default, enable it by setting **openshift_hosted_prometheus_deploy** to **true**. For example:

```
# openshift_hosted_prometheus_deploy=true
```

Set the following role variables to install and configure Prometheus.

Table 32.3. Prometheus Variables

Variable	Description
----------	-------------

Variable	Description
openshift_prometheus_namespace	Project namespace where the components are deployed. Default set to openshift-metrics . For example, openshift_prometheus_namespace=\${USER_PROJECT} .
openshift_prometheus_node_selector	Selector for the nodes on which Prometheus is deployed.
openshift_prometheus_storage_kind	Set to create PV for Prometheus. For example, openshift_prometheus_storage_kind=nfs .
openshift_prometheus_alertmanager_storage_kind	Set to create PV for Alertmanager. For example, openshift_prometheus_alertmanager_storage_kind=nfs .
openshift_prometheus_alertbuffer_storage_kind	Set to create PV for Alert Buffer. For example, openshift_prometheus_alertbuffer_storage_kind=nfs .
openshift_prometheus_storage_type	Set to create PVC for Prometheus. For example, openshift_prometheus_storage_type=pvc .
openshift_prometheus_alertmanager_storage_type	Set to create PVC for Alertmanager. For example, openshift_prometheus_alertmanager_storage_type=pvc .
openshift_prometheus_alertbuffer_storage_type	Set to create PVC for Alert Buffer. For example, openshift_prometheus_alertbuffer_storage_type=pvc .
openshift_prometheus_additional_rules_file	Additional Prometheus rules file. Set to null by default.

32.12.2. Deploying Prometheus Using Ansible Installer

The Ansible Installer is the default method of deploying Prometheus.

Add label to your node:

```
# Inventory file
openshift_prometheus_namespace=openshift-metrics

openshift_prometheus_node_selector={"region":"infra"}
```


Run the playbook:

```
$ ansible-playbook -vvv -i ${INVENTORY_FILE} playbooks/byo/openshift-cluster/openshift-prometheus.yml
```

32.12.2.1. Additional Methods for Deploying Prometheus

Deploy Using Node-Selector

Label the node on which you want to deploy Prometheus:

```
# oc adm label node/$NODE ${KEY}=${VALUE}
```

Deploy Prometheus with Ansible and container resources:

```
# Inventory file
openshift_prometheus_namespace=openshift-metrics

# Set node selector for prometheus
openshift_prometheus_node_selector={"${KEY}":"${VALUE}"}
```

Run the playbook:

```
$ ansible-playbook -vvv -i ${INVENTORY_FILE} playbooks/byo/openshift-cluster/openshift-prometheus.yml
```

Deploy Using a Non-default Namespace

Identify your namespace:

```
# Inventory file
openshift_prometheus_node_selector={"region":"infra"}

# Set non-default openshift_prometheus_namespace
openshift_prometheus_namespace=${USER_PROJECT}
```

Run the playbook:

```
$ ansible-playbook -vvv -i ${INVENTORY_FILE} playbooks/byo/openshift-cluster/openshift-prometheus.yml
```

32.12.2.2. Accessing the Prometheus Web UI

The Prometheus server automatically exposes a Web UI at **localhost:9090**. You can access the Prometheus Web UI with the **view** role.

32.12.2.3. Configuring Prometheus for OpenShift Container Platform

Prometheus Storage Related Variables

With each Prometheus component (including Prometheus, Alertmanager, Alert Buffer, and OAuth proxy) you can set the PV claim by setting corresponding role variable, for example:

```
openshift_prometheus_storage_type: pvc
openshift_prometheus_alertmanager_pvc_name: alertmanager
openshift_prometheus_alertbuffer_pvc_size: 10G
openshift_prometheus_pvc_access_modes: [ReadWriteOnce]
```

Prometheus Alert Rules File Variable

You can add an external file with alert rules by setting the path to an additional rules variable:

```
openshift_prometheus_additional_rules_file: <PATH>
```

The file must follow [the Prometheus Alert rules format](#). The following example sets a rule to send an alert when one of the cluster nodes is down:

```
groups:
- name: example-rules
  interval: 30s # defaults to global interval
  rules:
  - alert: Node Down
    expr: up{job="kubernetes-nodes"} == 0
    for: 10m 1
    annotations:
      miqTarget: "ContainerNode"
      severity: "HIGH"
      message: "{{{ '{' } } }{{ '$labels.instance' } }{{ '}' } } is down"
```


- 1** The optional **for** value specifies the amount of time Prometheus waits before it sends an alert for this element. For example, if you set **10m**, Prometheus waits 10 minutes after it encounters this issue before sending an alert.

Prometheus Variables to Control Resource Limits

With each Prometheus component (including Prometheus, Alertmanager, Alert Buffer, and OAuth proxy) you can specify CPU, memory limits, and requests by setting the corresponding role variable, for example:

```
openshift_prometheus_alertmanager_limits_memory: 1Gi
openshift_prometheus_oauth_proxy_cpu_requests: 100m
```

For more detailed information, see [OpenShift Prometheus](#).



NOTE

Once **openshift_metrics_project: openshift-infra** is installed, metrics can be gathered from the [http://\\${POD_IP}:7575/metrics](http://${POD_IP}:7575/metrics) endpoint.

32.12.3. OpenShift Container Platform Metrics via Prometheus

The state of a system can be gauged by the metrics that it emits. This section describes current and proposed metrics that identify the health of the storage subsystem and cluster.

32.12.3.1. Current Metrics

This section describes the metrics currently emitted from Kubernetes's storage subsystem.

Cloud Provider API Call Metrics

This metric reports the time and count of success and failures of all cloudprovider API calls. These metrics include **aws_attach_time** and **aws_detach_time**. The type of emitted metrics is a histogram, and hence, Prometheus also generates sum, count, and bucket metrics for these metrics.

Example summary of cloudprovider metrics from GCE:

```
cloudprovider_gce_api_request_duration_seconds { request =
"instance_list"}
cloudprovider_gce_api_request_duration_seconds { request = "disk_insert"}
cloudprovider_gce_api_request_duration_seconds { request = "disk_delete"}
cloudprovider_gce_api_request_duration_seconds { request = "attach_disk"}
cloudprovider_gce_api_request_duration_seconds { request = "detach_disk"}
cloudprovider_gce_api_request_duration_seconds { request = "list_disk"}
```

Example summary of cloudprovider metrics from AWS:

```
cloudprovider_aws_api_request_duration_seconds { request =
"attach_volume"}
cloudprovider_aws_api_request_duration_seconds { request =
"detach_volume"}
cloudprovider_aws_api_request_duration_seconds { request = "create_tags"}
cloudprovider_aws_api_request_duration_seconds { request =
"create_volume"}
cloudprovider_aws_api_request_duration_seconds { request =
"delete_volume"}
cloudprovider_aws_api_request_duration_seconds { request =
"describe_instance"}
cloudprovider_aws_api_request_duration_seconds { request =
"describe_volume"}
```

See [Cloud Provider \(specifically GCE and AWS\) metrics for Storage API calls](#) for more information.

Volume Operation Metrics

These metrics report time taken by a storage operation once started. These metrics keep track of operation time at the plug-in level, but do not include time taken by **goroutine** to run or operation to be picked up from the internal queue. These metrics are a type of histogram.

Example summary of available volume operation metrics

```
storage_operation_duration_seconds { volume_plugin = "aws-efs",
operation_name = "volume_attach" }
storage_operation_duration_seconds { volume_plugin = "aws-efs",
operation_name = "volume_detach" }
storage_operation_duration_seconds { volume_plugin = "glusterfs",
operation_name = "volume_provision" }
storage_operation_duration_seconds { volume_plugin = "gce-pd",
operation_name = "volume_delete" }
storage_operation_duration_seconds { volume_plugin = "vsphere",
operation_name = "volume_mount" }
storage_operation_duration_seconds { volume_plugin = "iscsi" ,
```

```

operation_name = "volume_unmount" }
storage_operation_duration_seconds { volume_plugin = "aws-ebs",
operation_name = "unmount_device" }
storage_operation_duration_seconds { volume_plugin = "cinder" ,
operation_name = "verify_volumes_are_attached" }
storage_operation_duration_seconds { volume_plugin = "<n/a>" ,
operation_name = "verify_volumes_are_attached_per_node" }

```

See [Volume operation metrics](#) for more information.

Volume Stats Metrics

These metrics typically report usage stats of PVC (such as used space versus available space). The type of metrics emitted is gauge.

Table 32.4. Volume Stats Metrics

Metric	Type	Labels/tags
volume_stats_capacityBytes	Gauge	namespace,persistentvolumeclaim,persistentvolume=
volume_stats_usedBytes	Gauge	namespace= <persistentvolumeclaim-namespace> persistentvolumeclaim= <persistentvolumeclaim-name> persistentvolume= <persistentvolume-name>
volume_stats_availableBytes	Gauge	namespace= <persistentvolumeclaim-namespace> persistentvolumeclaim= <persistentvolumeclaim-name> persistentvolume=
volume_stats_inodesFree	Gauge	namespace= <persistentvolumeclaim-namespace> persistentvolumeclaim= <persistentvolumeclaim-name> persistentvolume= <persistentvolume-name>
volume_stats_inodes	Gauge	namespace= <persistentvolumeclaim-namespace> persistentvolumeclaim= <persistentvolumeclaim-name> persistentvolume= <persistentvolume-name>

Metric	Type	Labels/tags
volume_stats_inodesUsed	Gauge	namespace= <persistentvolumeclaim- namespace> persistentvolumeclaim= <persistentvolumeclaim-name> persistentvolume= <persistentvolume-name>

32.12.4. Undeploying Prometheus

To undeploy Prometheus, run:

```
$ ansible-playbook -vvv -i ${INVENTORY_FILE} playbooks/byo/openshift-  
cluster/openshift-prometheus.yml -e openshift_prometheus_state=absent
```

CHAPTER 33. CUSTOMIZING THE WEB CONSOLE

33.1. OVERVIEW

Administrators can customize the [web console](#) using extensions, which let you run scripts and load custom stylesheets when the web console loads. Extension scripts allow you to override the default behavior of the web console and customize it for your needs.

For example, extension scripts can be used to add your own company's branding or to add company-specific capabilities. A common use case for this is rebranding or white-labelling for different environments. You can use the same extension code, but provide settings that change the web console. You can change the look and feel of nearly any aspect of the user interface in this way.

33.2. LOADING EXTENSION SCRIPTS AND STYLESHEETS

To add scripts and stylesheets, edit the [master configuration file](#). The scripts and stylesheet files must exist on the Asset Server and are added with the following options:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/script1.js
    - /path/to/script2.js
    - ...
  extensionStylesheets:
    - /path/to/stylesheet1.css
    - /path/to/stylesheet2.css
    - ...
```

NOTE

Wrap extension scripts in an Immediately Invoked Function Expression (IIFE). This ensures that you do not create global variables that conflict with the names used by the web console or by other extensions. For example:

```
(function() {
  // Put your extension code here...
})();
```

Relative paths are resolved relative to the master configuration file. To pick up configuration changes, restart the server.

Custom scripts and stylesheets are read once at server start time. To make developing extensions easier, you can reload scripts and stylesheets on every request by enabling development mode with the following setting:

```
assetConfig:
  ...
  extensionDevelopment: true
```

When set, the web console reloads any changes to existing extension script or stylesheet files when you refresh the page in your browser. You still must restart the server when adding new extension

stylesheets or scripts, however. This setting is only recommended for testing changes and not for production.

The examples in the following sections show common ways you can customize the web console.



NOTE

Additional extension examples are available in the [OpenShift Origin](#) repository on GitHub.

33.2.1. Setting Extension Properties

If you have a specific extension, but want to use different text in it for each of the environments, you can define the environment in the ***master-config.yaml*** file, and use the same extension script across environments. Pass settings from the ***master-config.yaml*** file to be used by the extension using the [extensionProperties](#) mechanism:

```
assetConfig:
  extensionDevelopment: true
  extensionProperties:
    doc_url: https://docs.openshift.com
    key1: value1
    key2: value2
  extensionScripts:
```

This results in a global variable that can be accessed by the extension, as if the following code was executed:

```
window.OPENSIFT_EXTENSION_PROPERTIES = {
  doc_url: "https://docs.openshift.com",
  key1: "value1",
  key2: "value2",
}
```

33.3. EXTENSION OPTION FOR EXTERNAL LOGGING SOLUTIONS

As of OpenShift Container Platform 3.6, there is an extension option to link to external logging solutions instead of using OpenShift Container Platform's EFK logging stack:

```
'use strict';
angular.module("mylinkextensions", ['openshiftConsole'])
  .run(function(extensionRegistry) {
    extensionRegistry.add('log-links', _.spread(function(resource,
options) {
    return {
      type: 'dom',
      node: '<span><a href="https://extension-
point.example.com">' + resource.metadata.name + '</a><span class="action-
divider">|</span></span>'
    };
  }));
  });
hawtioPluginLoader.addModule("mylinkextensions");
```

The URL to the logging stack you are wanting to access AD master configuration file. Then, restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

33.4. CUSTOMIZING AND DISABLING THE GUIDED TOUR

A guided tour will pop up the first time a user logs in on a particular browser. You can enable the **auto_launch** for new users:

```
window.OPENSIFT_CONSTANTS.GUIDED TOURS.landing_page_tour.auto_launch = true;
```

33.5. CUSTOMIZING DOCUMENTATION LINKS

Documentation links on the landing page are customizable.

window.OPENSIFT_CONSTANTS.CATALOG_HELP_RESOURCES is an array of objects containing a title and an **href**. These will be turned into links. You can completely override the array, push or pop additional links, or modify the attributes of existing links.

Example Link

```
{
  title: 'Blog',
  href: 'https://blog.openshift.com'
}
```

33.6. CUSTOMIZING THE LOGO

The following style changes the logo in the web console header:

```
#header-logo {
  background-image: url("https://www.example.com/images/logo.png");
  width: 190px;
  height: 20px;
}
```

1. Replace the **example.com** URL with a URL to an actual image, and adjust the width and height. The ideal height is **20px**.
2. Save the style to a file (for example, **logo.css**) and add it to the master configuration file:

```
assetConfig:
  ...
  extensionStylesheets:
    - /path/to/logo.css
```

3. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```


33.7. CHANGING LINKS TO DOCUMENTATION

Links to external documentation are shown in various sections of the web console. The following example changes the URL for two given links to the documentation:

```
window.OPENSIFT_CONSTANTS.HELP['get_started_cli'] =
  "https://example.com/doc1.html";
window.OPENSIFT_CONSTANTS.HELP['basic_cli_operations'] =
  "https://example.com/doc2.html";
```

Alternatively, you can change the base URL for all documentation links.

This example would result in the default help URL

`https://example.com/docs/welcome/index.html`:

```
window.OPENSIFT_CONSTANTS.HELP_BASE_URL = "https://example.com/docs/"; ❶
```

❶ The path must end in a `/`.

Save this script to a file (for example, **`help-links.js`**) and add it to the master configuration file:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/help-links.js
```

Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
```

33.8. ADDING OR CHANGING LINKS TO DOWNLOAD THE CLI

The **About** page in the web console provides download links for the [command line interface \(CLI\)](#) tools. These links can be configured by providing both the link text and URL, so that you can choose to point them directly to file packages, or to an external page that points to the actual packages.

For example, to point directly to packages that can be downloaded, where the link text is the package platform:

```
window.OPENSIFT_CONSTANTS.CLI = {
  "Linux (32 bits)": "https://<cdn>/openshift-client-tools-linux-
32bit.tar.gz",
  "Linux (64 bits)": "https://<cdn>/openshift-client-tools-linux-
64bit.tar.gz",
  "Windows":        "https://<cdn>/openshift-client-tools-windows.zip",
  "Mac OS X":       "https://<cdn>/openshift-client-tools-mac.zip"
};
```

Alternatively, to point to a page that links the actual download packages, with the **Latest Release** link text:

```
window.OPENSIFT_CONSTANTS.CLI = {
  "Latest Release": "https://<cdn>/openshift-client-tools/latest.html"
};
```

Save this script to a file (for example, **cli-links.js**) and add it to the master configuration file:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/cli-links.js
```

Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

33.8.1. Customizing the About Page

To provide a custom **About** page for the web console:

1. Write an extension that looks like:

```
angular
  .module('aboutPageExtension', ['openshiftConsole'])
  .config(function($routeProvider) {
    $routeProvider
      .when('/about', {
        templateUrl: 'extensions/about/about.html',
        controller: 'AboutController'
      });
  })
  );

hawtioPluginLoader.addModule('aboutPageExtension');
```

2. Save the script to a file (for example, **about/about.js**).
3. Write a customized template.
 - a. Start from the version of **about.html** from the OpenShift Container Platform [release](#) you are using. Within the template, there are two angular scope variables available: **version.master.openshift** and **version.master.kubernetes**.
 - b. Save the custom template to a file (for example, **about/about.html**).
 - c. Modify the master configuration file:

```
assetConfig:
  ...
  extensionScripts:
    - about/about.js
```

```
...
extensions:
  - name: about
    sourceDirectory: /path/to/about
```

d. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

33.9. CONFIGURING NAVIGATION MENUS


33.9.1. Top Navigation Dropdown Menus

The top navigation bar of the web console contains the help icon and the user dropdown menus. You can add additional menu items to these using the [angular-extension-registry](#).

The available extension points are:

- **nav-help-dropdown** - the help icon dropdown menu, visible at desktop screen widths
- **nav-user-dropdown** - the user dropdown menu, visible at desktop screen widths
- **nav-dropdown-mobile** - the single menu for top navigation items at mobile screen widths

The following example extends the **nav-help-dropdown** menu, with a name of **<myExtensionModule>**:



NOTE

<myExtensionModule> is a placeholder name. Each dropdown menu extension must be unique enough so that it does not clash with any future angular modules.

```
angular
  .module('<myExtensionModule>', ['openshiftConsole'])
  .run([
    'extensionRegistry',
    function(extensionRegistry) {
      extensionRegistry
        .add('nav-help-dropdown', function() {
          return [
            {
              type: 'dom',
              node: '<li><a href="http://www.example.com/report"
target="_blank">Report a Bug</a></li>'
            }, {
              type: 'dom',
              node: '<li class="divider"></li>' // If you want a
horizontal divider to appear in the menu
            }, {
              type: 'dom',
              node: '<li><a href="http://www.example.com/status"
target="_blank">System Status</a></li>'
            }
          ]
        })
    }
  ])
```

```

    }
  ];
});
}
]);

```

```
hawtioPluginLoader.addModule('<myExtensionModule>');
```

33.9.2. Application Launcher

The top navigation bar also contains an optional application launcher for linking to other web applications. This dropdown menu is empty by default, but when links are added, appears to the left of the help menu in the masthead.

1. Create the configuration scripts within a file (for example, **applicationLauncher.js**):

```

// Add items to the application launcher dropdown menu.
window.OPENSIFT_CONSTANTS.APP_LAUNCHER_NAVIGATION = [{
  title: "Dashboard",                // The text label
  iconClass: "fa fa-dashboard",      // The icon you want to
  appear                             // Where to go when this
  href: "http://example.com/dashboard", // Optional tooltip to
  tooltip: 'View dashboard'          display on hover
}, {
  title: "Manage Account",
  iconClass: "pficon pficon-user",
  href: "http://example.com/account",
  tooltip: "Update email address or password."
}];

```

2. Save the file and add it to the master configuration at **/etc/origin/master/master-config.yaml**:

```

assetConfig:
  ...
  extensionScripts:
    - /path/to/applicationLauncher.js

```

3. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

33.9.3. System Status Badge

The top navigation bar can also include an optional system status badge in order to notify users of system-wide events such as maintenance windows. To make use of the existing styles using a yellow warning icon for the badge, follow the example below.

1. Create the configuration scripts within a file (for example, **systemStatusBadge.js**):

```
'use strict';
```

```

angular
  .module('mysystemstatusbadgeextension', ['openshiftConsole'])
  .run([
    'extensionRegistry',
    function(extensionRegistry) {
      // Replace http://status.example.com/ with your domain
      var system_status_elem = $('<a
href="http://status.example.com/"' +
      'target="_blank" class="nav-item-iconic system-status"><span
title="' +
      'System Status" class="fa status-icon pficon-warning-triangle-
o">' +
      '</span></a>');

      // Add the extension point to the registry so the badge
      appears
      // To disable the badge, comment this block out
      extensionRegistry
        .add('nav-system-status', function() {
          return [{
            type: 'dom',
            node: system_status_elem
          }];
        });
    }
  ]);

hawtioPluginLoader.addModule('mysystemstatusbadgeextension');

```

2. Save the file and add it to the master configuration at **/etc/origin/master/master-config.yaml**:

```

assetConfig:
  ...
  extensionScripts:
    - /path/to/systemStatusBadge.js

```

3. Restart the master host:

```

# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers

```

33.9.4. Project Left Navigation

When navigating within a project, a menu appears on the left with primary and secondary navigation. This menu structure is defined as a constant and can be overridden or modified.



NOTE

Significant customizations to the project navigation may affect the user experience and should be done with careful consideration. You may need to update this customization in future upgrades if you modify existing navigation items.

1. Create the configuration scripts within a file (for example, **navigation.js**):

```

// Append a new primary nav item. This is a simple direct
navigation item
// with no secondary menu.
window.OPENSIFT_CONSTANTS.PROJECT_NAVIGATION.push({
  label: "Dashboard",           // The text label
  iconClass: "fa fa-dashboard", // The icon you want to appear
  href: "/dashboard"           // Where to go when this nav item
is clicked.

                                // Relative URLs are pre-pended
with the path

                                // '/project/<project-name>'
});

// Splice a primary nav item to a specific spot in the list. This
primary item has
// a secondary menu.
window.OPENSIFT_CONSTANTS.PROJECT_NAVIGATION.splice(2, 0, { //
Insert at the third spot
  label: "Git",
  iconClass: "fa fa-code",
  secondaryNavSections: [      // Instead of an href, a sub-menu
can be defined
    {
      items: [
        {
          label: "Branches",
          href: "/git/branches",
          prefixes: [
            "/git/branches/" // Defines prefix URL patterns
that will cause

                                // this nav item to show the
active state, so

                                // tertiary or lower pages show
the right context
          ]
        }
      ]
    },
    {
      header: "Collaboration", // Sections within a sub-menu can
have an optional header
      items: [
        {
          label: "Pull Requests",
          href: "/git/pull-requests",
          prefixes: [
            "/git/pull-requests/"
          ]
        }
      ]
    }
  ]
});

// Add a primary item to the top of the list. This primary item is
shown conditionally.

```

```

window.OPENSIFT_CONSTANTS.PROJECT_NAVIGATION.unshift({
  label: "Getting Started",
  iconClass: "pficon pficon-screen",
  href: "/getting-started",
  prefixes: [                                // Primary nav items can also
    specify prefixes to trigger              // active state
    "/getting-started/"
  ],
  isValid: function() {                     // Primary or secondary items can
    define an isValid                       // function. If present it will be
    return isNewUser;                      // called to test whether
    should return a boolean                // the item should be shown, it
  }
});

// Modify an existing menu item
var applicationsMenu =
_.find(window.OPENSIFT_CONSTANTS.PROJECT_NAVIGATION, { label:
'Applications' });
applicationsMenu.secondaryNavSections.push({ // Add a new secondary
nav section to the Applications menu
  // my secondary nav section
});

```

2. Save the file and add it to the master configuration at `/etc/origin/master/master-config.yaml`:

```

assetConfig:
  ...
  extensionScripts:
    - /path/to/navigation.js

```

3. Restart the master host:


```

# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers

```

33.10. CONFIGURING FEATURED APPLICATIONS

The web console has an optional list of featured application links in its landing page catalog. These appear near the top of the page and can have an icon, a title, a short description, and a link.



1. Create the following configuration scripts within a file (for example, ***featured-applications.js***):

```
// Add featured applications to the top of the catalog.
window.OPENSIFT_CONSTANTS.SAAS_OFFERINGS = [{
  title: "Dashboard",           // The text label
  icon: "fa fa-dashboard",      // The icon you want
  to appear
  url: "http://example.com/dashboard", // Where to go when
  this item is clicked
  description: "Open application dashboard." // Short description
}, {
  title: "System Status",
  icon: "fa fa-heartbeat",
  url: "http://example.com/status",
  description: "View system alerts and outages."
}, {
  title: "Manage Account",
  icon: "pficon pficon-user",
  url: "http://example.com/account",
  description: "Update email address or password."
}];
```

2. Save the file and add it to the master configuration at ***/etc/origin/master/master-config.yaml***:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/featured-applications.js
```

3. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

33.11. CONFIGURING CATALOG CATEGORIES

Catalog categories organize the display of items in the web console catalog landing page. Each category has one or more subcategories. A builder image, template, or service is grouped in a subcategory if it includes a tag listed in the matching subcategory tags, and an item can appear in more than one subcategory. Categories and subcategories only display if they contain at least one item.



NOTE

Significant customizations to the catalog categories may affect the user experience and should be done with careful consideration. You may need to update this customization in future upgrades if you modify existing category items.

1. Create the following configuration scripts within a file (for example, ***catalog-categories.js***):

```
// Find the Languages category.
var category =
_.find(window.OPENSIFT_CONSTANTS.SERVICE_CATALOG_CATEGORIES,
      { id: 'languages' });
```



```

// Add Go as a new subcategory under Languages.
category.subCategories.splice(2,0,{ // Insert at the third spot.
  // Required. Must be unique.
  id: "go",
  // Required.
  label: "Go",
  // Optional. If specified, defines a unique icon for this item.
  icon: "icon-go-gopher",
  // Required. Items matching any tag will appear in this
subcategory.
  tags: [
    "go",
    "golang"
  ]
});

// Add a Featured category as the first category tab.
window.OPENSIFT_CONSTANTS.SERVICE_CATALOG_CATEGORIES.unshift({
  // Required. Must be unique.
  id: "featured",
  // Required
  label: "Featured",
  subCategories: [
    {
      // Required. Must be unique.
      id: "go",
      // Required.
      label: "Go",
      // Optional. If specified, defines a unique icon for this
item.
      icon: "icon-go-gopher",
      // Required. Items matching any tag will appear in this
subcategory.
      tags: [
        "go",
        "golang"
      ]
    },
    {
      // Required. Must be unique.
      id: "jenkins",
      // Required.
      label: "Jenkins",
      // Optional. If specified, defines a unique icon for this
item.
      icon: "icon-jenkins",
      // Required. Items matching any tag will appear in this
subcategory.
      tags: [
        "jenkins"
      ]
    }
  ]
});

```

2. Save the file and add it to the master configuration at `/etc/origin/master/master-config.yaml`.

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/catalog-categories.js
```

3. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

33.12. CONFIGURING QUOTA NOTIFICATION MESSAGES

Whenever a user reaches a quota, a quota notification is put into the notification drawer. A custom quota notification message, per [quota resource type](#), can be added to the notification. For example: **Your project is over quota. It is using 200% of 2 cores CPU (Limit). Upgrade to <a href='http://www.openshift.com' → OpenShift Pro</a → if you need additional resources.** The "Upgrade to..." part of the notification is the custom message and may contain HTML such as links to additional resources.

1. Create the following configuration scripts within a file (for example, *quota-messages.js*):

```
// Set custom notification messages per quota type/key
window.OPENSIFT_CONSTANTS.QUOTA_NOTIFICATION_MESSAGE = {
  "pods": 'Upgrade to <a href="http://www.openshift.com">OpenShift
Pro</a> if you need additional resources.',
  "limits.memory": 'Upgrade to <a
href="http://www.openshift.com">OpenShift Online Pro</a> if you need
additional resources.'
}
```

2. Save the file and add it to the master configuration at */etc/origin/master/master-config.yaml*:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/quota-messages.js
```

3. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

33.13. CONFIGURING THE CREATE FROM URL NAMESPACE WHITELIST

[Create from URL](#) only works with image streams or templates from namespaces that have been explicitly specified in `OPENSIFT_CONSTANTS.CREATE_FROM_URL_WHITELIST`. To add namespaces to the whitelist, follow these steps:



NOTE

openshift is included in the whitelist by default. Do not remove it.

1. Create the following configuration scripts within a file (for example, ***create-from-url-whitelist.js***):

```
// Add a namespace containing the image streams and/or templates
window.OPENSIFT_CONSTANTS.CREATE_FROM_URL_WHITELIST.push(
  'shared-stuff'
);
```

2. Save the file and add it to the master configuration file at ***/etc/origin/master/master-config.yaml***:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/create-from-url-whitelist.js
```

3. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

33.14. DISABLING THE COPY LOGIN COMMAND

The web console allows users to copy a login command, including the current access token, to the clipboard from the user menu and the Command Line Tools page. This function can be changed so that the user's access token is not included in the copied command.

1. Create the following configuration scripts within a file (for example, ***disable-copy-login.js***):

```
// Do not copy the user's access token in the copy login command.
window.OPENSIFT_CONSTANTS.DISABLE_COPY_LOGIN_COMMAND = true;
```

2. Save the file and add it to the master configuration file at ***/etc/origin/master/master-config.yaml***:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/disable-copy-login.js
```

3. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

33.14.1. Enabling Wildcard Routes

If you enabled wildcard routes for a router, you can also enable wildcard routes in the web console. This lets users enter hostnames starting with an asterisk like ****.example.com*** when creating a route. To enable wildcard routes:

1. Save this script to a file (for example, ***enable-wildcard-routes.js***):

■

```
window.OPENSIFT_CONSTANTS.DISABLE_WILDCARD_ROUTES = false;
```

2. Add it to the master configuration file:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/enable-wildcard-routes.js
```

[Learn how to configure HAProxy routers to allow wildcard routes.](#)

If you enabled wildcard routes for a router, you can also enable wildcard routes in the web console. This lets users enter hostnames starting with an asterisk like ***.example.com** when creating a route. To enable wildcard routes:

1. Save this script to a file (for example, **enable-wildcard-routes.js**):

```
window.OPENSIFT_CONSTANTS.DISABLE_WILDCARD_ROUTES = false;
```

2. Add it to the master configuration file:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/enable-wildcard-routes.js
```

3. Restart the master host:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

[Learn how to configure HAProxy routers to allow wildcard routes.](#)

33.15. ENABLING FEATURES IN TECHNOLOGY PREVIEW

Sometimes features are available in Technology Preview. By default, these features are disabled and hidden in the web console.

To enable a Technology Preview feature:

1. Save this script to a file (for example, **tech-preview.js**):

```
window.OPENSIFT_CONSTANTS.ENABLE_TECH_PREVIEW_FEATURE.
<feature_name> = true;
```

2. Add it to the master configuration file:

```
assetConfig:
  ...
  extensionScripts:
    - /path/to/tech-preview.js
```

3. Restart the master host:

```
# systemctl restart origin-master-api origin-master-controllers
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

33.16. SERVING STATIC FILES

You can serve other files from the Asset Server as well. For example, you might want to make the CLI executable available for download from the web console or add images to use in a custom stylesheet.

Add the directory with the files you want using the following configuration option:

```
assetConfig:
  ...
  extensions:
    - name: images
      sourceDirectory: /path/to/my_images
```

The files under the **/path/to/my_images** directory will be available under the URL **/<context>/extensions/images** in the web console.

To reference these files from a stylesheet, you should generally use a relative path. For example:

```
#header-logo {
  background-image: url("../extensions/images/my-logo.png");
}
```

33.16.1. Enabling HTML5 Mode

The web console has a special mode for supporting certain static web applications that use the HTML5 history API:

```
assetConfig:
  ...
  extensions:
    - name: my_extension
      sourceDirectory: /path/to/myExtension
      html5Mode: true
```

Setting **html5Mode** to **true** enables two behaviors:

1. Any request for a non-existent file under **/<context>/extensions/my_extension/** instead serves **/path/to/myExtension/index.html** rather than a "404 Not Found" page.
2. The element **<base href="/">** will be rewritten in **/path/to/myExtension/index.html** to use the actual base depending on the asset configuration; only this exact string is rewritten.

This is needed for JavaScript frameworks such as AngularJS that require **base** to be set in **index.html**.

33.17. CUSTOMIZING THE LOGIN PAGE

You can also change the login page, and the login provider selection page for the web console. Run the following commands to create templates you can modify:

■

```
$ oc adm create-login-template > login-template.html
$ oc adm create-provider-selection-template > provider-selection-template.html
```

Edit the file to change the styles or add content, but be careful not to remove any required parameters inside the curly brackets.

To use your custom login page or provider selection page, set the following options in the master configuration file:

```
oauthConfig:
  ...
  templates:
    login: /path/to/login-template.html
    providerSelection: /path/to/provider-selection-template.html
```

Relative paths are resolved relative to the master configuration file. You must restart the server after changing this configuration.

When there are multiple login providers configured or when the [alwaysShowProviderSelection](#) option in the *master-config.yaml* file is set to **true**, each time a user's token to OpenShift Container Platform expires, the user is presented with this custom page before they can proceed with other tasks.

33.17.1. Example Usage

Custom login pages can be used to create Terms of Service information. They can also be helpful if you use a third-party login provider, like GitHub or Google, to show users a branded page that they trust and expect before being redirected to the authentication provider.

33.18. CUSTOMIZING THE OAUTH ERROR PAGE

When errors occur during authentication, you can change the page shown.

1. Run the following command to create a template you can modify:

```
$ oc adm create-error-template > error-template.html
```

2. Edit the file to change the styles or add content.
You can use the **Error** and **ErrorCode** variables in the template. To use your custom error page, set the following option in the master configuration file:

```
oauthConfig:
  ...
  templates:
    error: /path/to/error-template.html
```

Relative paths are resolved relative to the master configuration file.

3. You must restart the server after changing this configuration.

33.19. CHANGING THE LOGOUT URL

You can change the location a console user is sent to when logging out of the console by modifying the **logoutURL** parameter in the `/etc/origin/master/master-config.yaml` file:

```
...
assetConfig:
  logoutURL: "http://www.example.com"
...
```

This can be useful when authenticating with [Request Header](#) and OAuth or [OpenID](#) identity providers, which require visiting an external URL to destroy single sign-on sessions.

33.20. CONFIGURING WEB CONSOLE CUSTOMIZATIONS WITH ANSIBLE

During [advanced installations](#), many modifications to the web console can be configured using [the following parameters](#), which are configurable in the inventory file:

- [openshift_master_logout_url](#)
- [openshift_master_extension_scripts](#)
- [openshift_master_extension_stylesheets](#)
- [openshift_master_extensions](#)
- [openshift_master_oauth_template](#)
- [openshift_master_metrics_public_url](#)
- [openshift_master_logging_public_url](#)

Example Web Console Customization with Ansible

```
# Configure logoutURL in the master config for console customization
# See:
https://docs.openshift.com/enterprise/latest/install_config/web_console_customization.html#changing-the-logout-url
#openshift_master_logout_url=http://example.com

# Configure extensionScripts in the master config for console customization
# See:
https://docs.openshift.com/enterprise/latest/install_config/web_console_customization.html#loading-custom-scripts-and-stylesheets
#openshift_master_extension_scripts=
['/path/on/host/to/script1.js', '/path/on/host/to/script2.js']

# Configure extensionStylesheets in the master config for console customization
# See:
https://docs.openshift.com/enterprise/latest/install_config/web_console_customization.html#loading-custom-scripts-and-stylesheets
#openshift_master_extension_stylesheets=
['/path/on/host/to/styleSheet1.css', '/path/on/host/to/styleSheet2.css']
```

```
# Configure extensions in the master config for console customization
# See:
https://docs.openshift.com/enterprise/latest/install\_config/web\_console\_customization.html#serving-static-files
#openshift_master_extensions=[{'name': 'images', 'sourceDirectory':
'/path/to/my_images'}]


# Configure extensions in the master config for console customization
# See:
https://docs.openshift.com/enterprise/latest/install\_config/web\_console\_customization.html#serving-static-files
#openshift_master_oauth_template=/path/on/host/to/login-template.html

# Configure metricsPublicURL in the master config for cluster metrics.
Ansible is also able to configure metrics for you.
# See:
https://docs.openshift.com/enterprise/latest/install\_config/cluster\_metrics.html
#openshift_master_metrics_public_url=https://hawkular-
metrics.example.com/hawkular/metrics

# Configure loggingPublicURL in the master config for aggregate logging.
Ansible is also able to install logging for you.
# See:
https://docs.openshift.com/enterprise/latest/install\_config/aggregate\_logging.html
#openshift_master_logging_public_url=https://kibana.example.com
```


CHAPTER 34. DEPLOYING EXTERNAL PERSISTENT VOLUME PROVISIONERS

34.1. OVERVIEW



IMPORTANT

The external provisioner for AWS EFS on OpenShift Container Platform is a Technology Preview feature. Technology Preview features are not supported with Red Hat production service-level agreements (SLAs) and might not be functionally complete, and Red Hat does not recommend using them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process. For more information, see [Red Hat Technology Preview Features Support Scope](#).

An external provisioner is an application that enables dynamic provisioning for a particular storage provider. External provisioners can run alongside the provisioner plug-ins provided by OpenShift Container Platform and are configured in a similar way as the **StorageClass** objects are configured, as described in the [Dynamic Provisioning and Creating Storage Classes](#) section. Since these provisioners are external, you can deploy and update them independently of OpenShift Container Platform.

34.2. BEFORE YOU BEGIN



NOTE

Before proceeding, familiarize yourself with the [Configuring Cluster Metrics](#) and the [Configuring Cluster Logging](#) sections.

34.2.1. External Provisioners Ansible Role

The OpenShift Ansible **openshift_provisioners** role configures and deploys external provisioners using the variables from the [Ansible](#) inventory file. You must specify which provisioners to install by overriding their respective **install** variables to **true**.

34.2.2. External Provisioners Ansible Variables

Following is a list of role variables that apply to all provisioners for which the **install** variable is **true**.

Table 34.1. Ansible Variables

Variable	Description
openshift_provisioners_install_provisioners	If true , deploy all provisioners that have their respective install variables set as true , otherwise, remove them.
openshift_provisioners_image_prefix	The prefix for the component images. Defaults to registry.access.redhat.com/openshift3/ , set it to a different value if you are using an alternative registry.

Variable	Description
<code>openshift_provisioners_image_version</code>	The version for the component images. Defaults to latest .
<code>openshift_provisioners_project</code>	The project to deploy provisioners in. Defaults to openshift-infra .

34.2.3. AWS EFS Provisioner Ansible Variables

The AWS EFS provisioner dynamically provisions [NFS PVs](#) backed by dynamically created directories in a given EFS file system's directory. You must satisfy the following requirements before the AWS EFS Provisioner Ansible variables can be configured:

- An IAM user assigned with the ***AmazonElasticFileSystemReadOnlyAccess*** policy (or better).
- An EFS file system in your cluster's region.
- [Mount targets](#) and [security groups](#) such that any node (in any zone in the cluster's region) can mount the EFS file system by its [File system DNS name](#).

Table 34.2. Required EFS Ansible Variables

Variable	Description
<code>openshift_provisioners_efs_fs_id</code>	The File system ID of the EFS file system, for example: fs-47a2c22e
<code>openshift_provisioners_efs_region</code>	The Amazon EC2 region for the EFS file system.
<code>openshift_provisioners_efs_aws_access_key_id</code>	The AWS access key of the IAM user (to check that the specified EFS file system exists).
<code>openshift_provisioners_efs_aws_secret_access_key</code>	The AWS secret access key of the IAM user (to check that the specified EFS file system exists).

Table 34.3. Optional EFS Ansible Variables

Variable	Description
<code>openshift_provisioners_efs</code>	If true , the AWS EFS provisioner is installed or uninstalled according to whether <code>openshift_provisioners_install_provisioners</code> is true or false , respectively. Defaults to false .

Variable	Description
openshift_provisioners_efs_path	The path of the directory in the EFS file system, in which the EFS provisioner will create a directory to back each PV it creates. It must exist and be mountable by the EFS provisioner. Defaults to /persistentvolumes .
openshift_provisioners_efs_name	The provisioner name that StorageClasses specify. Defaults to openshift.org/aws-efs .
openshift_provisioners_efs_node_selector	A map of labels to select the nodes where the pod will land. For example: {"node": "infra", "region": "west"} .
openshift_provisioners_efs_supplementalgroup	The supplemental group to give the pod, in case it is needed for permission to write to the EFS file system. Defaults to 65534 .

34.3. DEPLOYING THE PROVISIONERS

You can deploy all provisioners at once or one provisioner at a time according to the configuration specified in the OpenShift Ansible variables. The following example shows you how to deploy a given provisioner and then create and configure a corresponding [StorageClass](#).

34.3.1. Deploying the AWS EFS Provisioner

The following command sets the directory in the EFS volume to **/data/persistentvolumes**. This directory must exist in the file system and must be mountable and writeable by the provisioner pod.

```
$ ansible-playbook -v -i <inventory_file> \
  /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
cluster/openshift-provisioners.yml \
  -e openshift_provisioners_install_provisioners=True \
  -e openshift_provisioners_efs=True \
  -e openshift_provisioners_efs_fs_id=fs-47a2c22e \
  -e openshift_provisioners_efs_region=us-west-2 \
  -e openshift_provisioners_efs_aws_access_key_id=AKIAIOSFODNN7EXAMPLE \
  -e
openshift_provisioners_efs_aws_secret_access_key=wJalrXUtnFEMI/K7MDENG/bPx
RfiCYEXAMPLEKEY \
  -e openshift_provisioners_efs_path=/data/persistentvolumes
  -e openshift_provisioners_image_version=<image_version> ❶
```

❶ Replace with the desired image version.

34.3.1.1. AWS EFS Object Definition

aws-efs-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1beta1
metadata:
  name: slow
provisioner: openshift.org/aws-efs 1
parameters:
  gidMin: "40000" 2
  gidMax: "50000" 3
```

- 1** Set this value same as the value of **openshift_provisioners_efs_name** variable, which defaults to **openshift.org/aws-efs**.
- 2** The minimum value of GID range for the **StorageClass**. (Optional)
- 3** The maximum value of GID range for the **StorageClass**. (Optional)

Each dynamically provisioned volume's corresponding NFS directory is assigned a unique GID owner from the range **gidMin-gidMax**. If it is not specified, **gidMin** defaults to **2000** and **gidMax** defaults to **2147483647**. Any pod that consumes a provisioned volume via a claim automatically runs with the needed GID as a supplemental group and is able to read & write to the volume. Other mounters that do not have the supplemental group (and are not running as root) will not be able to read or write to the volume. For more information on using the supplemental groups to manage NFS access, see the [Group IDs](#) section of NFS Volume Security topic.

34.4. CLEANUP

You can remove everything deployed by the OpenShift Ansible **openshift_provisioners** role by running the following command:

```
$ ansible-playbook -v -i <inventory_file> \
  /usr/share/ansible/openshift-ansible/playbooks/byo/openshift-
  cluster/openshift-provisioners.yml \
  -e openshift_provisioners_install_provisioners=False
  -e openshift_provisioners_image_version=<image_version> 1
```

- 1** Replace with the desired (or up-to-date) image version.

CHAPTER 35. REVISION HISTORY: INSTALLATION AND CONFIGURATION

35.1. MON MAR 12 2018

Affected Topic	Description of Change
Advanced Installation	Updated recommended storage for logging and metrics to use dynamic provisioning the Configuring Metrics Storage and Configuring Logging Storage sections.
Aggregating Container Logs	Updated the <code>openshift_logging_es_pvc_dynamic</code> variable in the Specifying Logging Ansible Variables section.

35.2. WED MAR 07 2018

Affected Topic	Description of Change
Aggregating Container Logs	Added to instructions to scale EFK pods when changes are made in the Understanding and Adjusting the Deployment section.

35.3. MON FEB 26 2018

Affected Topic	Description of Change
Installation and Configuration	Added information in multiple locations to use <code>oc adm ca</code> commands from the first master only.
Getting Started → Install OpenShift Container Platform	Added information to use <code>oc adm ca</code> commands from the first master only to Interact with OpenShift Container Platform section.
Getting Started → Configure OpenShift Container Platform	Added information to use <code>oc adm ca</code> commands from the first master only to the Create User Accounts section.
Performing Manual In-place Cluster Upgrades	Added information to use <code>oc adm ca</code> commands from the first master only to the Updating the Default Image Streams and Templates section.

35.4. FRI FEB 23 2018

Affected Topic	Description of Change
Aggregating Container Logs	Added information on changing the Docker log driver .

35.5. MON FEB 19 2018

Affected Topic	Description of Change
Aggregating Container Logs	Added the Expose Elasticsearch as a Route section, and updated related variables in the Specifying Logging Ansible Variables section.

35.6. FRI FEB 16 2018

Affected Topic	Description of Change
Installing a Cluster → Advanced Installation	Added information on using a Cockpit registry console image other than the default .
Configuring Custom Certificates	Clarified that, for the master API or web console, wildcard names are accepted.

35.7. TUE FEB 06 2018

Affected Topic	Description of Change
Aggregating Container Logs	Added the Manual Elasticsearch Rollouts section.
Installing a Cluster → Advanced Installation	Added the Configuring the OpenShift Ansible Broker for Local APB Development section.
Installing a Cluster → Prerequisites	Added that setting NM_CONTROLLED is required for DNS to work properly.
Using the Default HAProxy Router	Modified some information in the Router Environment Variables section.
Aggregating Container Logs	Added URL examples to the variable descriptions for openshift_logging_master_url and openshift_logging_master_public_url in the Specifying Logging Ansible Variables section.
Installation → Using the F5 Router Plug-in	Added a note that the F5 user needs Advanced Shell permission to use the F5 Router Plug-in .

Affected Topic	Description of Change
OpenShift Ansible Broker Configuration	New topic describing the OAB broker configuration file and how to update it.

35.8. THU JAN 25 2018

Affected Topic	Description of Change
Installing a Cluster → Disconnected Installation	Updated the example in the Editing the Image Stream Definitions section.
Customizing the Web Console	Added a new section on System Status Badge , which can notify users of system-wide events such as maintenance windows.
Customizing the Web Console	Updated the Configuring Catalog Categories section to reflect the latest web console categories.
Advanced Installation	Corrected logging variable and updated default installation status in the Configuring Cluster Logging section.

35.9. FRI DEC 22 2017

Affected Topic	Description of Change
Installing a Cluster → Advanced Installation	Added the openshift_master_admission_plugin_config parameter to the Cluster Variables table.
Configuring the SDN	Added section on configuring the SDN for multiple CIDR ranges to the Configuring the Pod Network on Masters section.
Setting up the Registry → Securing and Exposing the Registry	Added default registry to the example in the Manually Securing the Registry section.
Configuring Global Build Defaults and Overrides	Changed the units from m to Mi in the Example Build Defaults Configuration .
Installing a Cluster → Prerequisites	Added more information about port 1936 to the Required Ports section.

35.10. MON DEC 11 2017

Affected Topic	Description of Change
Configuring the SDN	Fixed command error in the Migrating from ovs-multitenant to ovs-networkpolicy section.

35.11. WED NOV 29 2017

OpenShift Container Platform 3.7 Initial Release