



Red Hat CloudForms 4.1

Installing Red Hat CloudForms on Red Hat OpenStack Platform

How to install and configure Red Hat CloudForms on a Red Hat OpenStack Platform environment

Red Hat CloudForms 4.1 Installing Red Hat CloudForms on Red Hat OpenStack Platform

How to install and configure Red Hat CloudForms on a Red Hat OpenStack Platform environment

Red Hat CloudForms Documentation Team
cloudforms-docs@redhat.com

Legal Notice

Copyright © 2018 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This guide provides instructions on how to install and configure Red Hat CloudForms on a Red Hat OpenStack Platform environment. If you have a suggestion for improving this guide or have found an error, please submit a Bugzilla report at <http://bugzilla.redhat.com> against Red Hat CloudForms Management Engine for the Documentation component. Please provide specific details, such as the section number, guide name, and CloudForms version so we can easily locate the content.

Table of Contents

| | |
|----------------------------------------------------------------|-----------|
| 1. INSTALLING RED HAT CLOUDFORMS | 2 |
| 1.1. Obtaining the Appliance | 2 |
| 1.2. Uploading the Appliance on OpenStack | 2 |
| 1.3. Adding a Rule to a Security Group | 3 |
| 1.4. Creating a Custom Flavor | 4 |
| 1.5. Launching the Instance | 5 |
| 1.6. Adding a Floating IP Address | 6 |
| 2. CONFIGURING RED HAT CLOUDFORMS | 7 |
| 2.1. Changing Configuration Settings | 7 |
| 2.2. Advanced Configuration Settings | 8 |
| 2.3. Configuring a Database for Red Hat CloudForms | 9 |
| 2.3.1. Configuring an Internal Database | 9 |
| 2.3.2. Configuring an External Database | 10 |
| 2.4. Configuring a Worker Appliance | 11 |
| 3. ADDITIONAL REQUIREMENTS | 12 |
| 3.1. Installing VMware VDDK on Red Hat CloudForms | 12 |
| 4. LOGGING IN AFTER INSTALLING RED HAT CLOUDFORMS | 13 |
| 4.1. Changing the Default Login Password | 13 |

1. INSTALLING RED HAT CLOUDFORMS

Red Hat CloudForms is able to be installed and ready to configure in a few quick steps. After downloading Red Hat CloudForms as a virtual machine image template from the Red Hat Customer Portal, the installation process takes you through the steps of uploading the appliance to a supported virtualization or cloud provider.



IMPORTANT

After installing the Red Hat CloudForms appliance, you must configure the database for Red Hat CloudForms. See [Section 2.3, “Configuring a Database for Red Hat CloudForms”](#).

1.1. Obtaining the Appliance

1. Go to access.redhat.com and log in to the Red Hat Customer Portal using your customer account details.
2. Click **Downloads** in the menu bar.
3. Click **A-Z** to sort the product downloads alphabetically.
4. Click **Red Hat CloudForms** to access the product download page. The latest version of each download displays by default.
5. From the list of installers and images under **Product Software**, select **CFME OpenStack Virtual Appliance** and click **Download Now**.

1.2. Uploading the Appliance on OpenStack

Log in to your OpenStack dashboard to upload your Red Hat CloudForms appliance.

1. Log in to the OpenStack dashboard.
2. In the **Project** tab, navigate to **Compute** → **Images**.
3. Click **Create Image**.
4. In **Name**, enter a name for the image.
5. From **Image Source** list, select **Image Location**. Note that currently only images available via an HTTP URL are supported.
6. In **Image Location**, add an external (HTTP) URL to load the image from. For example, <http://example.com/image.iso>.
7. From the **Format** list, select the image format. For example, **ISO - Optical Disk Image**.
8. Specify the **Architecture**. For example, **i386** for a 32-bit architecture or **x86-64** for a 64-bit architecture.
9. Leave the **Minimum Disk (GB)** and **Minimum RAM (MB)** fields empty.

10. Check the **Public** box to make the appliance available to all users.
11. Check the **Protected** box to protect the image from being accidentally deleted.
12. Click **Create Image**.

You have successfully uploaded the Red Hat CloudForms appliance.

The appliance image is placed in a queue to be uploaded. It may take some time before the Status of the image changes from Queued to Active.

1.3. Adding a Rule to a Security Group

Security groups specify what IP traffic is allowed to reach an instance on its public IP address. Security group rules are processed before network traffic reaches firewall rules defined within the guest itself.



NOTE

In the default configuration, the default security group accepts all connections from the default source; all instances within the default group can talk to each other on any port.

1. From the OpenStack dashboard, navigate to **Project** → **Compute** → **Access & Security**.
2. Navigate to **Security Groups** → **Manage Rules** on the row for the default security group.

Manage Security Group Rules: default

Security Group Rules + Add Rule ✖ Delete Rules

| <input type="checkbox"/> | Direction | Ether Type | IP Protocol | Port Range | Remote | Actions |
|--------------------------|-----------|------------|-------------|------------|------------------|----------------------------------------------|
| <input type="checkbox"/> | Egress | IPv4 | Any | - | 0.0.0.0/0 (CIDR) | Delete Rule |
| <input type="checkbox"/> | Ingress | IPv6 | Any | - | default | Delete Rule |
| <input type="checkbox"/> | Ingress | IPv4 | Any | - | default | Delete Rule |
| <input type="checkbox"/> | Egress | IPv6 | Any | - | :::0 (CIDR) | Delete Rule |

3. Click **Add Rule**.

Add Rule

Rule *

Custom TCP Rule

Direction

Ingress

Open Port *

Port

Port

Remote *

CIDR

CIDR

0.0.0.0/0

Description:

Rules define which traffic is allowed to instances assigned to the security group. A security group rule consists of three main parts:

Rule: You can specify the desired rule template or use custom rules, the options are Custom TCP Rule, Custom UDP Rule, or Custom ICMP Rule.

Open Port/Port Range: For TCP and UDP rules you may choose to open either a single port or a range of ports. Selecting the "Port Range" option will provide you with space to provide both the starting and ending ports for the range. For ICMP rules you instead specify an ICMP type and code in the spaces provided.

Remote: You must specify the source of the traffic to be allowed via this rule. You may do so either in the form of an IP address block (CIDR) or via a source group (Security Group). Selecting a security group as the source will allow any other instance in that security group access to any other instance via this rule.

Cancel Add

4. Configure the rule.

- a. Select **Rule** → **Custom TCP Rule**.
- b. Select **Direction** → **Ingress**.
- c. Select **Port** from the **Open Port** list.
- d. Specify **443** in the **Port** field.
- e. Select **CIDR** from the **Remote** list.
- f. Specify **0 . 0 . 0 . 0 / 0** in the **CIDR** field.
- g. Click **Add**.

1.4. Creating a Custom Flavor

A flavor is a resource allocation profile that specifies, for example, how many virtual CPUs and how much RAM can be allocated to an instance. You can, for example, run Red Hat CloudForms on a Red Hat OpenStack m1.large flavor, which specifies a virtual machine with 4 cores, 8GB RAM, and 80GB disk space. Creating a flavor to run Red Hat CloudForms is optional.

The following procedure demonstrates creating a flavor with the minimum requirements (4 cores, 8GB RAM, 44GB disk space) for Red Hat CloudForms. For more information about flavors, see the Red Hat OpenStack Platform Administration User Guide.

1. Log in to the OpenStack dashboard as admin.
2. In the **Admin** tab, navigate to **System** → **Flavors**.
3. Click **Create Flavor** to display the **Create Flavor** dialog.
4. Configure the settings to define a flavor that meets Red Hat CloudForms system requirements.
 - a. Enter a name for the flavor.
 - b. Enter the following settings:
 - **VCPUs:** 4
 - **RAM MB:** 8192
 - **Root Disk GB:** 45
 - **Ephemeral Disk GB:** 0
 - **Swap Disk MB:** 0
5. Click **Create Flavor**.

A new flavor specific to Red Hat CloudForms is created.

1.5. Launching the Instance

1. From the OpenStack dashboard, navigate to **Project** → **Compute** → **Instances**.
2. Click **Launch Instance**.
3. Enter a name for the instance.
4. Select the custom flavor for your instance. The flavor selection determines the computing resources available to your instance. The resources used by the flavor are displayed in the **Flavor Details** pane.
5. Enter **1** in the **Instance Count** field.
6. Select a boot option from the **Instance Boot Source** list:
 - **Boot from image** - displays a new field for **Image Name**. Select the image from the drop-down list.
 - **Boot from snapshot** - displays a new field for **Instance Snapshot**. Select the snapshot from the drop-down list.
 - **Boot from volume** - displays a new field for **Volume**. Select the volume from the drop-down list.
 - **Boot from image (creates a new volume)** - boot from an image and create a volume by choosing **Device Size** and **Device Name** for your volume. Some volumes can be persistent. To ensure the volume is deleted when the instance is deleted, select **Delete on Terminate**.
 - **Boot from volume snapshot (creates a new volume)** - boot from volume snapshot and create a new volume by choosing **Volume Snapshot** from the drop-down list and adding a **Device Name** for your volume. Some volumes can be persistent. To ensure the volume is deleted when the instance is deleted, select **Delete on Terminate**.

- Click **Networking** and select a network for the instance by clicking the + (plus) button for the network from **Available Networks**.
- Click **Launch**.

1.6. Adding a Floating IP Address

When you create an instance, Red Hat OpenStack Platform automatically assigns it a fixed IP address in the network to which the instance belongs. This IP address is permanently associated with the instance until the instance is terminated.

In addition to the fixed address, you can also assign a floating IP address to an instance. Unlike fixed IP addresses, you can modify floating IP addresses associations at any time, regardless of the state of the instances involved.

- At the command-line on your RHEL OpenStack Platform host, create a pool of floating IP addresses using the **nova-manage floating create** command. Replace **IP_BLOCK** with the desired block of IP addresses expressed in CIDR notation.

```
$ nova-manage floating create IP_BLOCK
```

- In the **Project** tab, navigate to **Compute** → **Access & Security**.
- Click **Floating IPs** → **Allocate IP To Project**. The **Allocate Floating IP** window is displayed.

Allocate Floating IP ×

Pool *

public


Description:

Allocate a floating IP from a given floating IP pool.

Project Quotas

Floating IP (0)

50 Available



Cancel

Allocate IP

- Click **Allocate IP** to allocate a floating IP from the pool. The allocated IP address appears in the **Floating IPs** table.

- Select the newly allocated IP address from the **Floating IPs** table. Click **Associate** to assign the IP address to a specific instance.

Manage Floating IP Associations ×

IP Address *

IP Address *

172.24.4.231 +

Port to be associated *

Select a port ▼

Select the IP address you wish to associate with the selected instance.

Cancel
Associate

- Select an instance with which to associate the floating IP Address.
- Click **Associate** to associate the IP address with the selected instance.



NOTE

To disassociate a floating IP address from an instance when it is no longer required, click **Release Floating IPs**.

2. CONFIGURING RED HAT CLOUDFORMS

Although the Red Hat CloudForms appliance comes configured to be integrated immediately into your environment, you can make some changes to its configuration.



NOTE

The Red Hat CloudForms appliance is intended to have minimal configuration options.

2.1. Changing Configuration Settings

The procedure describes how to make changes to the configuration settings on the Red Hat CloudForms appliance.

- After starting the appliance, log in with a user name of **root** and the default password of **smartvm**. This displays the Bash prompt for the **root** user.
- Enter the **appliance_console** command. The Red Hat CloudForms appliance summary screen displays.
- Press **Enter** to manually configure settings.
- Press the number for the item you want to change, and press **Enter**. The options for your selection are displayed.
- Follow the prompts to make the changes.

6. Press **Enter** to accept a setting where applicable.



NOTE

The Red Hat CloudForms appliance console automatically logs out after five minutes of inactivity.

2.2. Advanced Configuration Settings

After logging in, you can use the following menu items for advanced configuration of the appliance:

- Use **Set DHCP Network Configuration** to use DHCP to obtain the IP address and network configuration for your Red Hat CloudForms appliance. The appliance is initially configured as a DHCP client with bridged networking.
- Use **Set Static Network Configuration** if you have a specific IP address and network settings you need to use for the Red Hat CloudForms appliance.
- Use **Test Network Configuration** to check that name resolution is working correctly.
- Use **Set Hostname** to specify a hostname for the Red Hat CloudForms appliance.



IMPORTANT

A valid fully qualified hostname for the Red Hat CloudForms appliance is required for SmartState analysis to work correctly,

- Use **Set Timezone, Date, and Time** to configure the time zone, date, and time for the Red Hat CloudForms appliance.
- Use **Restore Database from Backup** to restore the VMDB database from a previous backup.
- Use **Setup Database Region** to create regions for VMDB replication.
- Use **Configure Database** to configure the VMDB database. Use this option to configure the database for the appliance after installing and running it for the first time.
- Use **Extend Temporary Storage** to add temporary storage to the appliance. The appliance formats an unpartitioned disk attached to the appliance host and mounts it at `/var/www/miq_tmp`. The appliance uses this temporary storage directory to perform certain image download functions.
- Use **Configure External Authentication (httpd)** to configure authentication through an IPA server.
- Use **Generate Custom Encryption Key** to regenerate the encryption key used to encode plain text password.
- Use **Harden Appliance Using SCAP Configuration** to apply Security Content Automation Protocol (SCAP) standards to the appliance. You can view these SCAP rules in the `/var/www/miq/lib/appliance_console/config/scap_rules.yml` file.
- Use **Stop Server Processes** to stop all server processes. You may need to do this to perform maintenance.
- Use **Start Server Processes** to start the server. You may need to do this after performing maintenance.

- Use **Restart Appliance** to restart the Red Hat CloudForms appliance. You can either restart the appliance and clear the logs or just restart the appliance.
- Use **Shut Down Appliance** to power down the appliance and exit all processes.
- Use **Summary Information** to go back to the network summary screen for the Red Hat CloudForms appliance.
- Use **Quit** to leave the Red Hat CloudForms appliance console.

2.3. Configuring a Database for Red Hat CloudForms

Before using Red Hat CloudForms, configure the database options for it. Red Hat CloudForms provides two options for database configuration:

- Install an internal PostgreSQL database to the appliance
- Configure the appliance to use an external PostgreSQL database

2.3.1. Configuring an Internal Database



IMPORTANT

Before installing an internal database, add a disk to the infrastructure hosting your appliance. See the documentation specific to your infrastructure for instructions on how to add a disk. As a storage disk usually cannot be added while a virtual machine is running, Red Hat recommends adding the disk before starting the appliance. Red Hat CloudForms only supports installing of an internal VMDB on blank disks. The installation will fail if the disks are not blank.

1. Start the appliance and open a terminal from your virtualization or cloud provider.
2. After starting the appliance, log in with a user name of **root** and the default password of **smartvm**. This displays the Bash prompt for the **root** user.
3. Enter the **appliance_console** command. The Red Hat CloudForms appliance summary screen displays.
4. Press **Enter** to manually configure settings.
5. Select **8) Configure Database** from the menu.
6. You are prompted to create or fetch an encryption key.
 - If this is the first Red Hat CloudForms appliance, choose **1) Create key**.
 - If this is not the first Red Hat CloudForms appliance, choose **2) Fetch key** from remote machine to fetch the key from the first Red Hat CloudForms appliance. All Red Hat CloudForms appliances in a multi-region deployment must use the same key.
7. Choose **1) Internal** for the database location.
8. Choose a disk for the database. For example:

1) /dev/vdb: 20480

Choose disk:

Enter **1** to choose **/dev/vdb** for the database location.

- When prompted, enter a unique three digit region ID to create a new region.



IMPORTANT

Creating a new region destroys any existing data on the chosen database.

- Confirm the configuration when prompted.

Red Hat CloudForms configures the internal database.

2.3.2. Configuring an External Database

Based on your setup, you will choose to configure the appliance to use an external PostgreSQL database. For example, we can only have one database in a single region. However, a region can be segmented into multiple zones, such as database zone, user interface zone, and reporting zone, where each zone provides a specific function. The appliances in these zones must be configured to use an external database.

The **postgresql.conf** file used with Red Hat CloudForms databases requires specific settings for correct operation. For example, it must correctly reclaim table space, control session timeouts, and format the PostgreSQL server log for improved system support. Due to these requirements, Red Hat recommends that external Red Hat CloudForms databases use a **postgresql.conf** file based on the standard file used by the Red Hat CloudForms appliance.

Ensure you configure the settings in the **postgresql.conf** to suit your system. For example, customize the **shared_buffers** setting according to the amount of real storage available in the external system hosting the PostgreSQL instance. In addition, depending on the aggregate number of appliances expected to connect to the PostgreSQL instance, it may be necessary to alter the **max_connections** setting.



NOTE

- Red Hat CloudForms 4.x requires PostgreSQL version 9.4.
- Because the **postgresql.conf** file controls the operation of all databases managed by a single instance of PostgreSQL, do not mix Red Hat CloudForms databases with other types of databases in a single PostgreSQL instance.

- Start the appliance and open a terminal console from your virtualization or cloud provider.
- After starting the appliance, log in with a user name of **root** and the default password of **smartvm**. This displays the Bash prompt for the **root** user.
- Enter the **appliance_console** command. The Red Hat CloudForms appliance summary screen displays.
- Press **Enter** to manually configure settings.
- Select **8) Configure Database** from the menu.

6. You are prompted to create or fetch a security key.
 - If this is the first Red Hat CloudForms appliance, select the option to create a key.
 - If this is not the first Red Hat CloudForms appliance, select the option to fetch the key from the first Red Hat CloudForms appliance. All Red Hat CloudForms appliances in a multi-region deployment must use the same key.
7. Choose **2) External** for the database location.
8. Enter the database hostname or IP address when prompted.
9. Enter the database name or leave blank for the default (**vldb_production**).
10. Enter the database username or leave blank for the default (**root**).
11. Enter the chosen database user's password.
12. Confirm the configuration if prompted.

Red Hat CloudForms will then configure the external database.

2.4. Configuring a Worker Appliance

You can use multiple appliances to facilitate horizontal scaling, as well as for dividing up work by roles. Accordingly, configure an appliance to handle work for one or many roles, with workers within the appliance carrying out the duties for which they are configured. You can configure a worker appliance through the terminal. The following steps demonstrate how to join a worker appliance to an appliance that already has a region configured with a database.

1. Start the appliance and open a terminal from your virtualization or cloud provider.
2. After starting the appliance, log in with a user name of **root** and the default password of **smar tvn**. This displays the Bash prompt for the **root** user.
3. Enter the **appliance_console** command. The Red Hat CloudForms appliance summary screen displays.
4. Press **Enter** to manually configure settings.
5. Select **8) Configure Database** from the menu.
6. You are prompted to create or fetch a security key. Select the option to fetch the key from the first Red Hat CloudForms appliance. All Red Hat CloudForms appliances in a multi-region deployment must use the same key.
7. Choose **2) External** for the database location.
8. Enter the database hostname or IP address when prompted.
9. Enter the database name or leave blank for the default (**vldb_production**).
10. Enter the database username or leave blank for the default (**root**).
11. Enter the chosen database user's password.
12. Confirm the configuration if prompted.

3. ADDITIONAL REQUIREMENTS

3.1. Installing VMware VDDK on Red Hat CloudForms

Execution of SmartState Analysis on virtual machines within a VMware environment requires the Virtual Disk Development Kit (VDDK). Red Hat CloudForms supports **VDDK 5.5**.

1. Download **VDDK 5.5** (**VMware-vix-disklib-5.5.0-1284542.x86_64.tar.gz** at the time of this writing) from the VMware website.



NOTE

If you do not already have a login ID to VMware, then you will need to create one. At the time of this writing, the file can be found by navigating to **Downloads** → **All Downloads** → **Drivers & Tools** → **VMware vSphere** → **Drivers & Tools**. Expand **Automation Tools and SDKs**, and select **vSphere Virtual Disk Development Kit 5.5**. Alternatively, find the file by searching for it using the **Search** on the VMware site.

2. Download and copy the **VMware-vix-disklib-5.5.0-1284542.x86_64.tar.gz** file to the **/root** directory of the appliance.
3. Start an **SSH** session into the appliance.
4. Extract and install **VDDK 5.5** using the following commands:

```
# cd /root
# tar -xvf VMware-vix-disklib-5.5.0-1284542.x86_64.tar.gz
# cd vmware-vix-disklib-distrib
# /vmware-install.pl
```

5. Accept the defaults during the installation

```
Installing VMware VIX DiskLib API. You must read and accept the VMware
VIX DiskLib API End User License Agreement to continue. Press enter to
display it. Do you accept? (yes/no) yes
```

```
Thank you. What prefix do you want to use to install VMware VIX DiskLib
API? The prefix is the root directory where the other folders such as
man, bin, doc, lib, etc. will be placed. [/usr] (Press Enter)
```

```
The installation of VMware VIX DiskLib API 5.5.0 build-1284542 for Linux
completed successfully. You can decide to remove this software from your
system at any time by invoking the following command:
"/usr/bin/vmware-uninstall-vix-disklib.pl". Enjoy, --the VMware team
```

6. Run **ldconfig** in order for Red Hat CloudForms to find the newly installed **VDDK** library.

**NOTE**

Use the following command to verify the VDDK files are listed and accessible to the appliance:

```
# lsconfig -p | grep vix
```

7. Restart the Red Hat CloudForms appliance.

The **VDDK** is now installed on the Red Hat CloudForms appliance. This enables use of the **SmartState Analysis Server Role** on the appliance.

4. LOGGING IN AFTER INSTALLING RED HAT CLOUDFORMS

Once Red Hat CloudForms is installed, you can log in and perform administration tasks.

Log in to Red Hat CloudForms for the first time after installing by:

1. Navigate to the URL for the login screen. (<https://xx.xx.xx.xx> on the virtual machine instance)
2. Enter the default credentials (Username: **admin** | Password: **smartvm**) for the initial login.
3. Click **Login**.

4.1. Changing the Default Login Password

Change your password to ensure more private and secure access to Red Hat CloudForms.

1. Navigate to the URL for the login screen. (<https://xx.xx.xx.xx> on the virtual machine instance)
2. Click **Update Password** beneath the **Username** and **Password** text fields.
3. Enter your current **Username** and **Password** in the text fields.
4. Input a new password in the **New Password** field.
5. Repeat your new password in the **Verify Password** field.
6. Click **Login**.