

# Red Hat OpenShift Data Foundation 4.15

# Scaling storage

Instructions for scaling operations in OpenShift Data Foundation

Last Updated: 2024-03-25

Instructions for scaling operations in OpenShift Data Foundation

# Legal Notice

Copyright © 2024 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux <sup>®</sup> is the registered trademark of Linus Torvalds in the United States and other countries.

Java <sup>®</sup> is a registered trademark of Oracle and/or its affiliates.

XFS <sup>®</sup> is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL <sup>®</sup> is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js <sup>®</sup> is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack <sup>®</sup> Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## Abstract

This document explains scaling options for Red Hat OpenShift Data Foundation.

# Table of Contents

MAKING OPEN SOURCE MORE INCLUSIVE	4
PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	5
CHAPTER 1. INTRODUCTION TO SCALING STORAGE	<b>6</b> 6
CHAPTER 2. REQUIREMENTS FOR SCALING STORAGE	8
<ul> <li>CHAPTER 3. SCALING STORAGE CAPACITY OF AWS OPENSHIFT DATA FOUNDATION CLUSTER</li> <li>3.1. SCALING UP STORAGE CAPACITY ON A CLUSTER</li> <li>3.2. SCALING OUT STORAGE CAPACITY ON A AWS CLUSTER</li> <li>3.2.1. Adding a node</li> <li>3.2.1.1. Adding a node to an installer-provisioned infrastructure</li> <li>3.2.1.2. Adding a node to an user-provisioned infrastructure</li> <li>3.2.2. Scaling up storage capacity</li> </ul>	9 11 12 12 14
<ul> <li>CHAPTER 4. SCALING STORAGE OF BARE METAL OPENSHIFT DATA FOUNDATION CLUSTER</li> <li>4.1. SCALING UP A CLUSTER CREATED USING LOCAL STORAGE DEVICES</li> <li>4.2. SCALING OUT STORAGE CAPACITY ON A BARE METAL CLUSTER</li> <li>4.2.1. Adding a node</li> <li>4.2.1.1. Adding a node to an installer-provisioned infrastructure</li> <li>4.2.1.2. Adding a node using a local storage device</li> <li>4.2.2. Scaling up storage capacity</li> </ul>	<b>15</b> 17 18 18 19 21
<ul> <li>5.1. SCALING UP STORAGE ON A VMWARE CLUSTER</li> <li>5.2. SCALING UP A CLUSTER CREATED USING LOCAL STORAGE DEVICES</li> <li>5.3. SCALING OUT STORAGE CAPACITY ON A VMWARE CLUSTER</li> <li>5.3.1. Adding a node to an installer-provisioned infrastructure</li> <li>5.3.2. Adding a node to an user-provisioned infrastructure</li> </ul>	<ul> <li>22</li> <li>24</li> <li>26</li> <li>26</li> <li>27</li> <li>28</li> <li>31</li> </ul>
<ul><li>6.1. SCALING UP STORAGE CAPACITY ON A CLUSTER</li><li>6.2. SCALING OUT STORAGE CAPACITY ON A MICROSOFT AZURE CLUSTER</li><li>6.2.1. Adding a node to an installer-provisioned infrastructure</li></ul>	<b>32</b> 32 34 34 35
<ul> <li>7.1. SCALING UP STORAGE CAPACITY ON A CLUSTER</li> <li>7.2. SCALING OUT STORAGE CAPACITY ON A RED HAT VIRTUALIZATION CLUSTER</li> <li>7.2.1. Adding a node to an installer-provisioned infrastructure</li> <li>7.2.2. Adding a node using a local storage device</li> <li>7.2.3. Scaling up storage capacity</li> </ul>	<ul> <li>36</li> <li>38</li> <li>38</li> <li>39</li> <li>41</li> <li>42</li> </ul>
<ul> <li>8.2. SCALING OUT STORAGE CAPACITY ON A GCP CLUSTER</li> <li>8.2.1. Adding a node</li> <li>8.2.1.1. Adding a node to an installer-provisioned infrastructure</li> </ul>	42 44 44 45 45

CHAPTER 9. SCALING STORAGE OF IBM Z OR IBM LINUXONE OPENSHIFT DATA FOUNDATION CLUS	TER
	46
9.1. SCALING UP STORAGE BY ADDING CAPACITY TO YOUR OPENSHIFT DATA FOUNDATION NODES	ON
IBM Z OR IBM LINUXONE INFRASTRUCTURE	46
9.2. SCALING OUT STORAGE CAPACITY ON A IBM Z OR IBM LINUXONE CLUSTER	49
9.2.1. Adding a node using a local storage device	49
9.2.2. Scaling up storage capacity	51
CHAPTER 10. SCALING STORAGE OF IBM POWER OPENSHIFT DATA FOUNDATION CLUSTER	. 52
10.1. SCALING UP STORAGE BY ADDING CAPACITY TO YOUR OPENSHIFT DATA FOUNDATION NODES	SON
IBM POWER INFRASTRUCTURE USING LOCAL STORAGE DEVICES	52
10.2. SCALING OUT STORAGE CAPACITY ON A IBM POWER CLUSTER	55
10.2.1. Adding a node using a local storage device on IBM Power	56
10.2.2. Scaling up storage capacity	58

# MAKING OPEN SOURCE MORE INCLUSIVE

Red Hat is committed to replacing problematic language in our code, documentation, and web properties. We are beginning with these four terms: master, slave, blacklist, and whitelist. Because of the enormity of this endeavor, these changes will be implemented gradually over several upcoming releases. For more details, see our CTO Chris Wright's message.

# PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your input on our documentation. Do let us know how we can make it better.

To give feedback, create a Bugzilla ticket:

- 1. Go to the Bugzilla website.
- 2. In the **Component** section, choose **documentation**.
- 3. Fill in the **Description** field with your suggestion for improvement. Include a link to the relevant part(s) of documentation.
- 4. Click Submit Bug.

# CHAPTER 1. INTRODUCTION TO SCALING STORAGE

Red Hat OpenShift Data Foundation is a highly scalable storage system. OpenShift Data Foundation allows you to scale by adding the disks in the multiple of three, or three or any number depending upon the deployment type.

- For internal (dynamic provisioning) deployment mode, you can increase the capacity by adding 3 disks at a time.
- For internal-attached (Local Storage Operator based) mode, you can deploy with less than 3 failure domains.

With flexible scale deployment enabled, you can scale up by adding any number of disks. For deployment with 3 failure domains, you will be able to scale up by adding disks in the multiple of 3.

For scaling your storage in external mode, see Red Hat Ceph Storage documentation .



## NOTE

You can use a maximum of nine storage devices per node. The high number of storage devices will lead to a higher recovery time during the loss of a node. This recommendation ensures that nodes stay below the cloud provider dynamic storage device attachment limits, and limits the recovery time after node failure with local storage devices.

While scaling, you must ensure that there are enough CPU and Memory resources as per scaling requirement.

#### Supported storage classes by default

- gp2-csi on AWS
- thin on VMware
- managed\_premium on Microsoft Azure

# 1.1. SUPPORTED DEPLOYMENTS FOR RED HAT OPENSHIFT DATA FOUNDATION

- User-provisioned infrastructure:
  - Amazon Web Services (AWS)
  - VMware
  - Bare metal
  - IBM Power
  - IBM Z or IBM<sup>®</sup> LinuxONE
- Installer-provisioned infrastructure:
  - Amazon Web Services (AWS)

- Microsoft Azure
- VMware
- Bare metal

# CHAPTER 2. REQUIREMENTS FOR SCALING STORAGE

Before you proceed to scale the storage nodes, refer to the following sections to understand the node requirements for your specific Red Hat OpenShift Data Foundation instance:

- Platform requirements
- Resource requirements
- Storage device requirements
  - Dynamic storage devices
  - Local storage devices
  - Capacity planning



#### IMPORTANT

Always ensure that you have plenty of storage capacity.

If storage ever fills completely, it is not possible to add capacity or delete or migrate content away from the storage to free up space completely. Full storage is very difficult to recover.

Capacity alerts are issued when cluster storage capacity reaches 75% (near-full) and 85% (full) of total capacity. Always address capacity warnings promptly, and review your storage regularly to ensure that you do not run out of storage space.

If you do run out of storage space completely, contact Red Hat Customer Support.

# CHAPTER 3. SCALING STORAGE CAPACITY OF AWS OPENSHIFT DATA FOUNDATION CLUSTER

To scale the storage capacity of your configured Red Hat OpenShift Data Foundation worker nodes on AWS cluster, you can increase the capacity by adding three disks at a time. Three disks are needed since OpenShift Data Foundation uses a replica count of 3 to maintain the high availability. So the amount of storage consumed is three times the usable space.



# NOTE

Usable space might vary when encryption is enabled or replica 2 pools are being used.

# **3.1. SCALING UP STORAGE CAPACITY ON A CLUSTER**

To increase the storage capacity in a dynamically created storage cluster on an user-provisioned infrastructure, you can add storage capacity and performance to your configured Red Hat OpenShift Data Foundation worker nodes.

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.
- The disk should be of the same size and type as used during initial deployment.

#### Procedure

- 1. Log in to the OpenShift Web Console.
- 2. Click **Operators** → **Installed Operators**.
- 3. Click OpenShift Data Foundation Operator.
- 4. Click the Storage Systems tab.
  - a. Click the **Action Menu ( : )** on the far right of the storage system name to extend the options menu.
  - b. Select Add Capacity from the options menu.
  - c. Select the **Storage Class**. Choose the storage class which you wish to use to provision new storage devices.
  - d. Click Add.
- 5. To check the status, navigate to **Storage** → **Data Foundation** and verify that the **Storage System** in the Status card has a green tick.

#### Verification steps

- Verify the **Raw Capacity** card.
  - a. In the OpenShift Web Console, click **Storage**  $\rightarrow$  **Data Foundation**.

- b. In the **Status** card of the **Overview** tab, click **Storage System** and then click the storage system link from the pop up that appears.
- c. In the **Block and File** tab, check the **Raw Capacity** card. Note that the capacity increases based on your selections.



#### NOTE

The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:
    - a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
    - b. Select **openshift-storage** from the **Project** drop-down list.



#### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- To view the state of the PVCs:
  - a. Click **Storage** → **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select **openshift-storage** from the **Project** drop-down list.



#### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/<*OSD*-pod-name>

#### <OSD-pod-name>

Is the name of the OSD pod. For example:

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rook-ceph-osd-0-544db49d7f-qrgqm

Example output:



- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected hosts.



\$ oc debug node/<node-name>

#### <node-name>

Is the name of the node.



ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.

\$ Isblk



#### IMPORTANT

Cluster reduction is supported only with the Red Hat Support Team's assistance.

# 3.2. SCALING OUT STORAGE CAPACITY ON A AWS CLUSTER

OpenShift Data Foundation is highly scalable. It can be scaled out by adding new nodes with required storage and enough hardware resources in terms of CPU and RAM. Practically there is no limit on the number of nodes which can be added but from the support perspective 2000 nodes is the limit for OpenShift Data Foundation.

Scaling out storage capacity can be broken down into two steps

- Adding new node
- Scaling up the storage capacity



#### NOTE

OpenShift Data Foundation does not support heterogeneous OSD/Disk sizes.

## 3.2.1. Adding a node

You can add nodes to increase the storage capacity when existing worker nodes are already running at their maximum supported OSDs or there are not enough resources to add new OSDs on the existing nodes. It is always recommended to add nodes in the multiple of three, each of them in different failure domains.

While we recommend adding nodes in the multiple of three, you still get the flexibility of adding one node at a time in the flexible scaling deployment. Refer to the Knowledgebase article Verify if flexible scaling is enabled.



## NOTE

OpenShift Data Foundation does not support heterogeneous disk size and types. The new nodes to be added should have the disk of the same type and size which was used during OpenShift Data Foundation deployment.

#### 3.2.1.1. Adding a node to an installer-provisioned infrastructure

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

#### Procedure

- 1. Navigate to **Compute** → **Machine Sets**.
- 2. On the machine set where you want to add nodes, select Edit Machine Count
  - a. Add the amount of nodes, and click **Save**.
  - b. Click **Compute**  $\rightarrow$  **Nodes** and confirm if the new node is in **Ready** state.
- 3. Apply the OpenShift Data Foundation label to the new node.
  - a. For the new node, click Action menu ( : )  $\rightarrow$  Edit Labels.
  - b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.



#### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them. In case of bare metal installer-provisioned infrastructure deployment, you must expand the cluster first. For instructions, see Expanding the cluster.

#### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

#### 3.2.1.2. Adding a node to an user-provisioned infrastructure

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

#### Procedure

- 1. Depending on the type of infrastructure, perform the following steps:
  - a. Get a new machine with the required infrastructure. See Platform requirements.
  - b. Create a new OpenShift Container Platform worker node using the new machine.
- 2. Check for certificate signing requests (CSRs) that are in **Pending** state.

\$ oc get csr

3. Approve all the required CSRs for the new node.

\$ oc adm certificate approve < Certificate\_Name>

#### <Certificate\_Name>

Is the name of the CSR.

- 4. Click **Compute**  $\rightarrow$  **Nodes**, confirm if the new node is in **Ready** state.
- 5. Apply the OpenShift Data Foundation label to the new node using any one of the following:

#### From User interface

- a. For the new node, click Action Menu ( : )  $\rightarrow$  Edit Labels.
- b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.

#### From Command line interface

• Apply the OpenShift Data Foundation label to the new node.

\$ oc label node <new\_node\_name> cluster.ocs.openshift.io/openshift-storage=""

#### <new\_node\_name>

Is the name of the new node.

#### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*

• csi-rbdplugin-\*

# 3.2.2. Scaling up storage capacity

To scale up storage capacity, see Scaling up a cluster.

# CHAPTER 4. SCALING STORAGE OF BARE METAL OPENSHIFT DATA FOUNDATION CLUSTER

To scale the storage capacity of your configured Red Hat OpenShift Data Foundation worker nodes on your bare metal cluster, you can increase the capacity by adding three disks at a time. Three disks are needed since OpenShift Data Foundation uses a replica count of 3 to maintain the high availability. So the amount of storage consumed is three times the usable space.



# NOTE

Usable space might vary when encryption is enabled or replica 2 pools are being used.

# 4.1. SCALING UP A CLUSTER CREATED USING LOCAL STORAGE DEVICES

In order to scale up an OpenShift Data Foundation cluster which was created using local storage devices, a new disk needs to be added to the storage node. It is recommended to have the new disks of the same size as used earlier during the deployment as OpenShift Data Foundation does not support heterogeneous disks/OSD's.

For deployments having three failure domains, you can scale up the storage by adding disks in the multiple of three, with the same number of disks coming from nodes in each of the failure domains. For example, if we scale by adding six disks, two disks are taken from nodes in each of the three failure domains. If the number of disks is not in multiples of three, it will only consume the disk to the maximum in the multiple of three while the remaining disks remain unused.

For deployments having less than three failure domains, there is flexibility in adding the number of disks. In this case, you can add any number of disks. In order to check if flexible scaling is enabled or not, refer to the Knowledgebase article Verify if flexible scaling is enabled.



## NOTE

Flexible scaling features get enabled at the time of deployment and can not be enabled or disabled later on.

## Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.
- Disks to be used for scaling are already attached to the storage node
- LocalVolumeDiscovery and LocalVolumeSet objects are already created.

## Procedure

To add capacity, you can either use a storage class that you provisioned during the deployment or any other storage class that matches the filter.

- 1. In the OpenShift Web Console, click **Operators**  $\rightarrow$  **Installed Operators**.
- 2. Click OpenShift Data Foundation Operator.

- 3. Click the **Storage Systems** tab.
  - a. Click the Action menu (:) next to the visible list to extend the options menu.
  - b. Select Add Capacity from the options menu.
  - c. Select the **Storage Class** for which you added disks or the new storage class depending on your requirement. Available Capacity displayed is based on the local disks available in storage class.
  - d. Click Add.
- To check the status, navigate to Storage → Data Foundation and verify that the Storage System in the Status card has a green tick.

#### Verification steps

- Verify the Raw Capacity card.
  - a. In the OpenShift Web Console, click **Storage**  $\rightarrow$  **Data Foundation**.
  - b. In the **Status** card of the **Overview** tab, click **Storage System** and then click the storage system link from the pop up that appears.
  - c. In the **Block and File** tab, check the **Raw Capacity** card. Note that the capacity increases based on your selections.



#### NOTE

The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:
    - a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
    - b. Select **openshift-storage** from the **Project** drop-down list.



#### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- To view the state of the PVCs:
  - a. Click **Storage**  $\rightarrow$  **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select **openshift-storage** from the **Project** drop-down list.



#### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/<OSDpod-name>

#### <OSD-pod-name>

Is the name of the OSD pod. For example:

\$ c

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rookceph-osd-0-544db49d7f-qrgqm

Example output:



- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected host(s).



#### <node-name>

Is the name of the node.



ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.





#### IMPORTANT

Cluster reduction is supported only with the Red Hat Support Team's assistance.

# 4.2. SCALING OUT STORAGE CAPACITY ON A BARE METAL CLUSTER

OpenShift Data Foundation is highly scalable. It can be scaled out by adding new nodes with required storage and enough hardware resources in terms of CPU and RAM. There is no limit on the number of nodes which can be added. Howerver, from the technical support perspective, 2000 nodes is the limit for OpenShift Data Foundation.

Scaling out storage capacity can be broken down into two steps

- Adding new node
- Scaling up the storage capacity



## NOTE

OpenShift Data Foundation does not support heterogeneous OSD/Disk sizes.

## 4.2.1. Adding a node

You can add nodes to increase the storage capacity when existing worker nodes are already running at their maximum supported OSDs or there are not enough resources to add new OSDs on the existing nodes. It is always recommended to add nodes in the multiple of three, each of them in different failure domains.

While we recommend adding nodes in the multiple of three, you still get the flexibility of adding one node at a time in the flexible scaling deployment. Refer to the Knowledgebase article Verify if flexible scaling is enabled.



#### NOTE

OpenShift Data Foundation does not support heterogeneous disk size and types. The new nodes to be added should have the disk of the same type and size which was used during OpenShift Data Foundation deployment.

#### 4.2.1.1. Adding a node to an installer-provisioned infrastructure

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

#### Procedure

- 1. Navigate to **Compute → Machine Sets**.
- 2. On the machine set where you want to add nodes, select Edit Machine Count
  - a. Add the amount of nodes, and click **Save**.
  - b. Click **Compute**  $\rightarrow$  **Nodes** and confirm if the new node is in **Ready** state.
- 3. Apply the OpenShift Data Foundation label to the new node.
  - a. For the new node, click Action menu (:)  $\rightarrow$  Edit Labels.
  - b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.



#### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them. In case of bare metal installer-provisioned infrastructure deployment, you must expand the cluster first. For instructions, see Expanding the cluster.

#### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

#### 4.2.1.2. Adding a node using a local storage device

You can add nodes to increase the storage capacity when existing worker nodes are already running at their maximum supported OSDs or when there are not enough resources to add new OSDs on the existing nodes.

Add nodes in the multiple of 3, each of them in different failure domains. Though it is recommended to add nodes in multiples of 3 nodes, you have the flexibility to add one node at a time in flexible scaling deployment. See Knowledgebase article Verify if flexible scaling is enabled



#### NOTE

OpenShift Data Foundation does not support heterogeneous disk size and types. The new nodes to be added should have the disk of the same type and size which was used during initial OpenShift Data Foundation deployment.

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

#### Procedure

- 1. Depending on the type of infrastructure, perform the following steps:
  - a. Get a new machine with the required infrastructure. See Platform requirements.
  - b. Create a new OpenShift Container Platform worker node using the new machine.
- 2. Check for certificate signing requests (CSRs) that are in **Pending** state.

#### \$ oc get csr

3. Approve all the required CSRs for the new node.

\$ oc adm certificate approve < Certificate\_Name>

#### <Certificate\_Name>

Is the name of the CSR.

4. Click **Compute**  $\rightarrow$  **Nodes**, confirm if the new node is in **Ready** state.

5. Apply the OpenShift Data Foundation label to the new node using any one of the following:

#### From User interface

- a. For the new node, click Action Menu ( : )  $\rightarrow$  Edit Labels.
- b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.

#### From Command line interface


• Apply the OpenShift Data Foundation label to the new node.

\$ oc label node <new\_node\_name> cluster.ocs.openshift.io/openshift-storage=""

#### <new\_node\_name>

Is the name of the new node.

- Click Operators → Installed Operators from the OpenShift Web Console. From the Project drop-down list, make sure to select the project where the Local Storage Operator is installed.
- 7. Click Local Storage.
- 8. Click the Local Volume Discovery tab.
  - a. Beside the **LocalVolumeDiscovery**, click Action menu (:) → Edit Local Volume Discovery.
  - b. In the YAML, add the hostname of the new node in the **values** field under the node selector.
  - c. Click Save.
- 9. Click the Local Volume Sets tab.
  - a. Beside the **LocalVolumeSet**, click Action menu (:) → Edit Local Volume Set
  - b. In the YAML, add the hostname of the new node in the **values** field under the **node selector**.



c. Click Save.



#### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them.

#### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

#### 4.2.2. Scaling up storage capacity

To scale up storage capacity, see Scaling up storage by adding capacity.

# CHAPTER 5. SCALING STORAGE OF VMWARE OPENSHIFT DATA FOUNDATION CLUSTER

# 5.1. SCALING UP STORAGE ON A VMWARE CLUSTER

To increase the storage capacity in a dynamically created storage cluster on a VMware user-provisioned infrastructure, you can add storage capacity and performance to your configured Red Hat OpenShift Data Foundation worker nodes.

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.
- The disk should be of the same size and type as used during initial deployment.

#### Procedure

- 1. Log in to the OpenShift Web Console.
- 2. Click Operators → Installed Operators
- 3. Click OpenShift Data Foundation Operator.
- 4. Click the Storage Systems tab.
  - a. Click the **Action Menu ( : )** on the far right of the storage system name to extend the options menu.
  - b. Select Add Capacity from the options menu.
  - c. Select the **Storage Class**. Choose the storage class which you wish to use to provision new storage devices.
  - d. Click Add.
- 5. To check the status, navigate to **Storage** → **Data Foundation** and verify that **Storage System** in the Status card has a green tick.

#### Verification steps

- Verify the **Raw Capacity** card.
  - a. In the OpenShift Web Console, click **Storage**  $\rightarrow$  **Data Foundation**.
  - b. In the **Status** card of the **Overview** tab, click **Storage System** and then click the storage system link from the pop up that appears.
  - c. In the **Block and File** tab, check the **Raw Capacity** card. Note that the capacity increases based on your selections.



## NOTE

The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:
    - a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
    - b. Select **openshift-storage** from the **Project** drop-down list.



#### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.


- To view the state of the PVCs:
  - a. Click **Storage** → **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select **openshift-storage** from the **Project** drop-down list.



#### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.



#### <OSD-pod-name>

Is the name of the OSD pod. For example:



\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rook-ceph-osd-0-544db49d7f-qrgqm

Example output:




- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected hosts.

\$ oc debug node/<node-name>

#### <node-name>

Is the name of the node.



ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.





## IMPORTANT

Cluster reduction is supported only with the Red Hat Support Team's assistance.

# 5.2. SCALING UP A CLUSTER CREATED USING LOCAL STORAGE DEVICES

In order to scale up an OpenShift Data Foundation cluster which was created using local storage devices, a new disk needs to be added to the storage node. It is recommended to have the new disks of the same size as used earlier during the deployment as OpenShift Data Foundation does not support heterogeneous disks/OSD's.

For deployments having three failure domains, you can scale up the storage by adding disks in the multiple of three, with the same number of disks coming from nodes in each of the failure domains. For example, if we scale by adding six disks, two disks are taken from nodes in each of the three failure domains. If the number of disks is not in multiples of three, it will only consume the disk to the maximum in the multiple of three while the remaining disks remain unused.

For deployments having less than three failure domains, there is flexibility in adding the number of disks. In this case, you can add any number of disks. In order to check if flexible scaling is enabled or not, refer to the Knowledgebase article Verify if flexible scaling is enabled.



#### NOTE

Flexible scaling features get enabled at the time of deployment and can not be enabled or disabled later on.

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.
- Disks to be used for scaling are already attached to the storage node
- LocalVolumeDiscovery and LocalVolumeSet objects are already created.

#### Procedure

To add capacity, you can either use a storage class that you provisioned during the deployment or any other storage class that matches the filter.

- 1. In the OpenShift Web Console, click **Operators**  $\rightarrow$  **Installed Operators**.
- 2. Click **OpenShift Data Foundation** Operator.
- 3. Click the **Storage Systems** tab.
  - a. Click the Action menu (:) next to the visible list to extend the options menu.
  - b. Select Add Capacity from the options menu.
  - c. Select the **Storage Class** for which you added disks or the new storage class depending on your requirement. Available Capacity displayed is based on the local disks available in storage class.
  - d. Click Add.
- To check the status, navigate to Storage → Data Foundation and verify that the Storage System in the Status card has a green tick.

#### Verification steps

- Verify the Raw Capacity card.
  - a. In the OpenShift Web Console, click **Storage**  $\rightarrow$  **Data Foundation**.
  - b. In the **Status** card of the **Overview** tab, click **Storage System** and then click the storage system link from the pop up that appears.
  - c. In the **Block and File** tab, check the **Raw Capacity** card. Note that the capacity increases based on your selections.



#### NOTE

The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:
    - a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
    - b. Select **openshift-storage** from the **Project** drop-down list.



#### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- To view the state of the PVCs:
  - a. Click **Storage**  $\rightarrow$  **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select **openshift-storage** from the **Project** drop-down list.



## NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/<*OSD*pod-name>

#### <OSD-pod-name>

Is the name of the OSD pod. For example:



\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rook-ceph-osd-0-544db49d7f-qrgqm

Example output:



- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected host(s).

\$ oc debug node/<node-name>

#### <node-name>

Is the name of the node.



ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.



#### IMPORTANT

\$ lsblk

Cluster reduction is supported only with the Red Hat Support Team's assistance.

# 5.3. SCALING OUT STORAGE CAPACITY ON A VMWARE CLUSTER

#### 5.3.1. Adding a node to an installer-provisioned infrastructure

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

#### Procedure

- 1. Navigate to **Compute** → **Machine Sets**.
- 2. On the machine set where you want to add nodes, select Edit Machine Count
  - a. Add the amount of nodes, and click Save.
  - b. Click **Compute**  $\rightarrow$  **Nodes** and confirm if the new node is in **Ready** state.
- 3. Apply the OpenShift Data Foundation label to the new node.
  - a. For the new node, click Action menu ( : )  $\rightarrow$  Edit Labels.
  - b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.



#### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them. In case of bare metal installer-provisioned infrastructure deployment, you must expand the cluster first. For instructions, see Expanding the cluster.

#### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

#### 5.3.2. Adding a node to an user-provisioned infrastructure

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

#### Procedure

- 1. Depending on the type of infrastructure, perform the following steps:
  - a. Get a new machine with the required infrastructure. See Platform requirements.

- b. Create a new OpenShift Container Platform worker node using the new machine.
- 2. Check for certificate signing requests (CSRs) that are in **Pending** state.

\$ oc get csr

3. Approve all the required CSRs for the new node.

\$ oc adm certificate approve < Certificate\_Name>

#### <Certificate\_Name>

Is the name of the CSR.

- 4. Click **Compute**  $\rightarrow$  **Nodes**, confirm if the new node is in **Ready** state.
- 5. Apply the OpenShift Data Foundation label to the new node using any one of the following:

#### From User interface

- a. For the new node, click Action Menu (:)  $\rightarrow$  Edit Labels.
- b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.

#### From Command line interface

• Apply the OpenShift Data Foundation label to the new node.

\$ oc label node <new\_node\_name> cluster.ocs.openshift.io/openshift-storage=""

#### <new\_node\_name>

Is the name of the new node.

#### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

#### 5.3.3. Adding a node using a local storage device

You can add nodes to increase the storage capacity when existing worker nodes are already running at their maximum supported OSDs or when there are not enough resources to add new OSDs on the existing nodes.

Add nodes in the multiple of 3, each of them in different failure domains. Though it is recommended to add nodes in multiples of 3 nodes, you have the flexibility to add one node at a time in flexible scaling deployment. See Knowledgebase article Verify if flexible scaling is enabled



#### NOTE

OpenShift Data Foundation does not support heterogeneous disk size and types. The new nodes to be added should have the disk of the same type and size which was used during initial OpenShift Data Foundation deployment.

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

#### Procedure

- 1. Depending on the type of infrastructure, perform the following steps:
  - a. Get a new machine with the required infrastructure. See Platform requirements.
  - b. Create a new OpenShift Container Platform worker node using the new machine.
- 2. Check for certificate signing requests (CSRs) that are in **Pending** state.

\$ oc get csr

3. Approve all the required CSRs for the new node.

\$ oc adm certificate approve < Certificate\_Name>

#### <Certificate\_Name>

Is the name of the CSR.

- 4. Click **Compute**  $\rightarrow$  **Nodes**, confirm if the new node is in **Ready** state.
- 5. Apply the OpenShift Data Foundation label to the new node using any one of the following:

#### From User interface

- a. For the new node, click Action Menu ( : )  $\rightarrow$  Edit Labels.
- b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.

#### From Command line interface

• Apply the OpenShift Data Foundation label to the new node.

\$ oc label node <new\_node\_name> cluster.ocs.openshift.io/openshift-storage=""

#### <new\_node\_name>

Is the name of the new node.

- Click Operators → Installed Operators from the OpenShift Web Console. From the Project drop-down list, make sure to select the project where the Local Storage Operator is installed.
- 7. Click Local Storage.
- 8. Click the Local Volume Discovery tab.
  - a. Beside the **LocalVolumeDiscovery**, click Action menu (:) → Edit Local Volume Discovery.
  - b. In the YAML, add the hostname of the new node in the **values** field under the node selector.
  - c. Click Save.
- 9. Click the Local Volume Sets tab.

Details YAML

Resources Events

- a. Beside the **LocalVolumeSet**, click Action menu (:) → Edit Local Volume Set
- b. In the YAML, add the hostname of the new node in the **values** field under the **node selector**.

42	spec:	View shortcuts        View side
43	deviceInclusionSpec:	A Construction of the second second
44	deviceMechanicalProperties:	
45	- NonRotational	- Carl The Alerent server
46	deviceTypes:	
47	- disk	A STATE OF
48	- part	and the second sec
49	minSize: 100Gi	
50	nodeSelector:	Section and the section of the secti
51	nodeSelectorTerms:	
52	- matchExpressions:	
53	- key: kubernetes.io/hostname	
54	operator: In	
55	Values:	
56	- worker1.example.com	
57	- worker2.example.com	
58	- worker3.example.com	
59	- worker4.example.com	
50	- worker5.example.com	
51	- worker6.example.com	
52	storageClassName: localblock	
53	volumeMode: Block	
54	status:	
65	conditions:	
56	- lastTransitionTime: '2020-12-01T19:46:15Z'	
57	message: 'DiskMaker: Available, LocalProvisioner: Available'	
58	status: 'True'	
59	type: DaemonSetsAvailable	
_		
ave	Reload Cancel	🕹 Downle

c. Click Save.



#### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them.

#### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

### 5.3.4. Scaling up storage capacity

To scale up storage capacity:

- For dynamic storage devices, see Scaling up storage capacity on a cluster .
- For local storage devices, see Scaling up a cluster created using local storage devices

# CHAPTER 6. SCALING STORAGE OF MICROSOFT AZURE OPENSHIFT DATA FOUNDATION CLUSTER

To scale the storage capacity of your configured Red Hat OpenShift Data Foundation worker nodes on Microsoft Azure cluster, you can increase the capacity by adding three disks at a time. Three disks are needed since OpenShift Data Foundation uses a replica count of 3 to maintain the high availability. So the amount of storage consumed is three times the usable space.



# NOTE

Usable space might vary when encryption is enabled or replica 2 pools are being used.

# 6.1. SCALING UP STORAGE CAPACITY ON A CLUSTER

To increase the storage capacity in a dynamically created storage cluster on an user-provisioned infrastructure, you can add storage capacity and performance to your configured Red Hat OpenShift Data Foundation worker nodes.

#### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.
- The disk should be of the same size and type as used during initial deployment.

#### Procedure

- 1. Log in to the OpenShift Web Console.
- 2. Click **Operators** → **Installed Operators**.
- 3. Click OpenShift Data Foundation Operator.
- 4. Click the Storage Systems tab.
  - a. Click the **Action Menu ( : )** on the far right of the storage system name to extend the options menu.
  - b. Select Add Capacity from the options menu.
  - c. Select the **Storage Class**. Choose the storage class which you wish to use to provision new storage devices.
  - d. Click Add.
- 5. To check the status, navigate to **Storage** → **Data Foundation** and verify that the **Storage System** in the Status card has a green tick.

#### Verification steps

- Verify the **Raw Capacity** card.
  - a. In the OpenShift Web Console, click **Storage**  $\rightarrow$  **Data Foundation**.

- b. In the **Status** card of the **Overview** tab, click **Storage System** and then click the storage system link from the pop up that appears.
- c. In the **Block and File** tab, check the **Raw Capacity** card. Note that the capacity increases based on your selections.



The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:
    - a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
    - b. Select **openshift-storage** from the **Project** drop-down list.



### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- To view the state of the PVCs:
  - a. Click **Storage** → **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select **openshift-storage** from the **Project** drop-down list.



### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/<*OSD*-pod-name>

### <OSD-pod-name>

Is the name of the OSD pod. For example:

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rook-ceph-osd-0-544db49d7f-qrgqm

Example output:



- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected hosts.



\$ oc debug node/<node-name>

### <node-name>

Is the name of the node.



ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.

\$ Isblk



### IMPORTANT

Cluster reduction is supported only with the Red Hat Support Team's assistance.

# 6.2. SCALING OUT STORAGE CAPACITY ON A MICROSOFT AZURE CLUSTER

OpenShift Data Foundation is highly scalable. It can be scaled out by adding new nodes with required storage and enough hardware resources in terms of CPU and RAM. Practically there is no limit on the number of nodes which can be added but from the support perspective 2000 nodes is the limit for OpenShift Data Foundation.

Scaling out storage capacity can be broken down into two steps

- Adding new node
- Scaling up the storage capacity



### NOTE

OpenShift Data Foundation does not support heterogeneous OSD/Disk sizes.

### 6.2.1. Adding a node to an installer-provisioned infrastructure

### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

### Procedure

- 1. Navigate to **Compute**  $\rightarrow$  **Machine Sets**.
- 2. On the machine set where you want to add nodes, select Edit Machine Count
  - a. Add the amount of nodes, and click **Save**.
  - b. Click **Compute**  $\rightarrow$  **Nodes** and confirm if the new node is in **Ready** state.
- 3. Apply the OpenShift Data Foundation label to the new node.
  - a. For the new node, click Action menu ( :)  $\rightarrow$  Edit Labels.
  - b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.



It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them. In case of bare metal installer-provisioned infrastructure deployment, you must expand the cluster first. For instructions, see Expanding the cluster.

### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

### 6.2.2. Scaling up storage capacity

To scale up storage capacity, see Scaling up storage capacity on a cluster .

### CHAPTER 7. SCALING STORAGE OF RED HAT VIRTUALIZATION OPENSHIFT DATA FOUNDATION CLUSTER

To scale the storage capacity of your configured Red Hat OpenShift Data Foundation worker nodes on Red Hat Virtualization cluster, you can increase the capacity by adding three disks at a time. Three disks are needed since OpenShift Data Foundation uses a replica count of 3 to maintain the high availability. So the amount of storage consumed is three times the usable space.



### NOTE

Usable space might vary when encryption is enabled or replica 2 pools are being used.

### 7.1. SCALING UP STORAGE CAPACITY ON A CLUSTER

To increase the storage capacity in a dynamically created storage cluster on an user-provisioned infrastructure, you can add storage capacity and performance to your configured Red Hat OpenShift Data Foundation worker nodes.

### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.
- The disk should be of the same size and type as used during initial deployment.

### Procedure

- 1. Log in to the OpenShift Web Console.
- 2. Click **Operators** → **Installed Operators**.
- 3. Click OpenShift Data Foundation Operator.
- 4. Click the Storage Systems tab.
  - a. Click the **Action Menu ( : )** on the far right of the storage system name to extend the options menu.
  - b. Select Add Capacity from the options menu.
  - c. Select the **Storage Class**. Choose the storage class which you wish to use to provision new storage devices.
  - d. Click Add.
- 5. To check the status, navigate to **Storage** → **Data Foundation** and verify that the **Storage System** in the Status card has a green tick.

### Verification steps

- Verify the **Raw Capacity** card.
  - a. In the OpenShift Web Console, click **Storage**  $\rightarrow$  **Data Foundation**.

- b. In the **Status** card of the **Overview** tab, click **Storage System** and then click the storage system link from the pop up that appears.
- c. In the **Block and File** tab, check the **Raw Capacity** card. Note that the capacity increases based on your selections.



The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:
    - a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
    - b. Select openshift-storage from the Project drop-down list.



#### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- To view the state of the PVCs:
  - a. Click **Storage** → **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select **openshift-storage** from the **Project** drop-down list.



### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/<OSDpod-name>

### <OSD-pod-name>

Is the name of the OSD pod. For example:

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rook-ceph-osd-0-544db49d7f-qrgqm

Example output:



- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected hosts.



\$ oc debug node/<node-name>

### <node-name>

Is the name of the node.



ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.





### IMPORTANT

Cluster reduction is supported only with the Red Hat Support Team's assistance.

# 7.2. SCALING OUT STORAGE CAPACITY ON A RED HAT VIRTUALIZATION CLUSTER

OpenShift Data Foundation is highly scalable. It can be scaled out by adding new nodes with required storage and enough hardware resources in terms of CPU and RAM. Practically there is no limit on the number of nodes which can be added but from the support perspective 2000 nodes is the limit for OpenShift Data Foundation.

Scaling out storage capacity can be broken down into two steps

- Adding new node
- Scaling up the storage capacity



### NOTE

OpenShift Data Foundation does not support heterogeneous OSD/Disk sizes.

### 7.2.1. Adding a node to an installer-provisioned infrastructure

### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

### Procedure

- 1. Navigate to **Compute**  $\rightarrow$  **Machine Sets**.
- 2. On the machine set where you want to add nodes, select Edit Machine Count
  - a. Add the amount of nodes, and click **Save**.
  - b. Click **Compute**  $\rightarrow$  **Nodes** and confirm if the new node is in **Ready** state.
- 3. Apply the OpenShift Data Foundation label to the new node.
  - a. For the new node, click Action menu ( : )  $\rightarrow$  Edit Labels.
  - b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.



It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them. In case of bare metal installer-provisioned infrastructure deployment, you must expand the cluster first. For instructions, see Expanding the cluster.

### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

### 7.2.2. Adding a node using a local storage device

You can add nodes to increase the storage capacity when existing worker nodes are already running at their maximum supported OSDs or when there are not enough resources to add new OSDs on the existing nodes.

Add nodes in the multiple of 3, each of them in different failure domains. Though it is recommended to add nodes in multiples of 3 nodes, you have the flexibility to add one node at a time in flexible scaling deployment. See Knowledgebase article Verify if flexible scaling is enabled



### NOTE

OpenShift Data Foundation does not support heterogeneous disk size and types. The new nodes to be added should have the disk of the same type and size which was used during initial OpenShift Data Foundation deployment.

### Prerequisites

• You have administrative privilege to the OpenShift Container Platform Console.

• You have a running OpenShift Data Foundation Storage Cluster.

### Procedure

- 1. Depending on the type of infrastructure, perform the following steps:
  - a. Get a new machine with the required infrastructure. See Platform requirements.
  - b. Create a new OpenShift Container Platform worker node using the new machine.
- 2. Check for certificate signing requests (CSRs) that are in **Pending** state.

\$ oc get csr

3. Approve all the required CSRs for the new node.

\$ oc adm certificate approve < Certificate\_Name>

### <Certificate\_Name>

Is the name of the CSR.

- 4. Click **Compute**  $\rightarrow$  **Nodes**, confirm if the new node is in **Ready** state.
- 5. Apply the OpenShift Data Foundation label to the new node using any one of the following:

### From User interface

- a. For the new node, click Action Menu (:)  $\rightarrow$  Edit Labels.
- b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.

### From Command line interface

• Apply the OpenShift Data Foundation label to the new node.

\$ oc label node <new\_node\_name> cluster.ocs.openshift.io/openshift-storage=""

#### <new\_node\_name>

Is the name of the new node.

- Click Operators → Installed Operators from the OpenShift Web Console.
   From the Project drop-down list, make sure to select the project where the Local Storage Operator is installed.
- 7. Click Local Storage.
- 8. Click the Local Volume Discovery tab.
  - a. Beside the **LocalVolumeDiscovery**, click Action menu (:) → Edit Local Volume Discovery.
  - b. In the YAML, add the hostname of the new node in the **values** field under the node selector.
  - c. Click Save.

- 9. Click the Local Volume Sets tab.
  - a. Beside the **LocalVolumeSet**, click Action menu (:) → Edit Local Volume Set
  - b. In the YAML, add the hostname of the new node in the **values** field under the **node selector**.

Details	YAML Resources Events	
		<b>?</b> View shortcuts   <b>1</b> View sidebar
42	spec:	
43 44	deviceInclusionSpec: deviceMechanicalProperties:	1225
	- NonRotational	
45 46	deviceTypes:	and the second sec
40	- disk	Party and a second seco
47	- orsk	H.
40	minSize: 100Gi	
50	nodeSelector:	South and the second
50	nodeSelectorTerms:	- <b>1977</b>
52	- matchExpressions:	
53	key: kubernetes.io/hostname	
54	operator: In	
55	values:	
56	- worker1.example.com	
57	- worker2.example.com	
58	- worker3.example.com	
59	worker4.example.com	
60	worker5.example.com	
61	- worker6.example.com	
62	storageClassName: localblock	
63	volumeMode: Block	
64	status:	
65	conditions:	
66	- lastTransitionTime: '2020-12-01T19:46:15Z'	
67	message: 'DiskMaker: Available, LocalProvisioner: Available'	
68	status: 'True'	
69	type: DaemonSetsAvailable	
Save	Reload Cancel	🛓 Download

c. Click Save.



### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them.

### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

### 7.2.3. Scaling up storage capacity

To scale up storage capacity:

- For dynamic storage devices, see Scaling up storage capacity on a cluster .
- For local storage devices, see Scaling up a cluster created using local storage devices

## CHAPTER 8. SCALING STORAGE CAPACITY OF GCP OPENSHIFT DATA FOUNDATION CLUSTER

To scale the storage capacity of your configured Red Hat OpenShift Data Foundation worker nodes on GCP cluster, you can increase the capacity by adding three disks at a time. Three disks are needed since OpenShift Data Foundation uses a replica count of 3 to maintain the high availability. So the amount of storage consumed is three times the usable space.



### NOTE

Usable space might vary when encryption is enabled or replica 2 pools are being used.

### 8.1. SCALING UP STORAGE CAPACITY ON A CLUSTER

To increase the storage capacity in a dynamically created storage cluster on an user-provisioned infrastructure, you can add storage capacity and performance to your configured Red Hat OpenShift Data Foundation worker nodes.

### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.
- The disk should be of the same size and type as used during initial deployment.

### Procedure

- 1. Log in to the OpenShift Web Console.
- 2. Click **Operators** → **Installed Operators**.
- 3. Click OpenShift Data Foundation Operator.
- 4. Click the Storage Systems tab.
  - a. Click the **Action Menu ( : )** on the far right of the storage system name to extend the options menu.
  - b. Select Add Capacity from the options menu.
  - c. Select the **Storage Class**. Choose the storage class which you wish to use to provision new storage devices.
  - d. Click Add.
- 5. To check the status, navigate to **Storage** → **Data Foundation** and verify that the **Storage System** in the Status card has a green tick.

### Verification steps

- Verify the **Raw Capacity** card.
  - a. In the OpenShift Web Console, click **Storage**  $\rightarrow$  **Data Foundation**.

- b. In the **Status** card of the **Overview** tab, click **Storage System** and then click the storage system link from the pop up that appears.
- c. In the **Block and File** tab, check the **Raw Capacity** card. Note that the capacity increases based on your selections.



The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:
    - a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
    - b. Select **openshift-storage** from the **Project** drop-down list.



### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- To view the state of the PVCs:
  - a. Click **Storage** → **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select **openshift-storage** from the **Project** drop-down list.



### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/<*OSD*-pod-name>

### <OSD-pod-name>

Is the name of the OSD pod. For example:

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rook-ceph-osd-0-544db49d7f-qrgqm

Example output:



- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected hosts.



\$ oc debug node/<node-name>

### <node-name>

Is the name of the node.



ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.

\$ lsblk



### IMPORTANT

Cluster reduction is supported only with the Red Hat Support Team's assistance.

### 8.2. SCALING OUT STORAGE CAPACITY ON A GCP CLUSTER

OpenShift Data Foundation is highly scalable. It can be scaled out by adding new nodes with required storage and enough hardware resources in terms of CPU and RAM. Practically there is no limit on the number of nodes which can be added but from the support perspective 2000 nodes is the limit for OpenShift Data Foundation.

Scaling out storage capacity can be broken down into two steps

- Adding new node
- Scaling up the storage capacity



### NOTE

OpenShift Data Foundation does not support heterogeneous OSD/Disk sizes.

### 8.2.1. Adding a node

You can add nodes to increase the storage capacity when existing worker nodes are already running at their maximum supported OSDs or there are not enough resources to add new OSDs on the existing nodes. It is always recommended to add nodes in the multiple of three, each of them in different failure domains.

While we recommend adding nodes in the multiple of three, you still get the flexibility of adding one node at a time in the flexible scaling deployment. Refer to the Knowledgebase article Verify if flexible scaling is enabled.



OpenShift Data Foundation does not support heterogeneous disk size and types. The new nodes to be added should have the disk of the same type and size which was used during OpenShift Data Foundation deployment.

### 8.2.1.1. Adding a node to an installer-provisioned infrastructure

### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

### Procedure

- 1. Navigate to **Compute** → **Machine Sets**.
- 2. On the machine set where you want to add nodes, select Edit Machine Count
  - a. Add the amount of nodes, and click **Save**.
  - b. Click **Compute**  $\rightarrow$  **Nodes** and confirm if the new node is in **Ready** state.
- 3. Apply the OpenShift Data Foundation label to the new node.
  - a. For the new node, click Action menu ( : )  $\rightarrow$  Edit Labels.
  - b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.



### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them. In case of bare metal installer-provisioned infrastructure deployment, you must expand the cluster first. For instructions, see Expanding the cluster.

### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

### 8.2.2. Scaling up storage capacity

To scale up storage capacity, see Scaling up storage capacity on a cluster .

### CHAPTER 9. SCALING STORAGE OF IBM Z OR IBM LINUXONE OPENSHIFT DATA FOUNDATION CLUSTER

### 9.1. SCALING UP STORAGE BY ADDING CAPACITY TO YOUR OPENSHIFT DATA FOUNDATION NODES ON IBM Z OR IBM LINUXONE INFRASTRUCTURE

You can add storage capacity and performance to your configured Red Hat OpenShift Data Foundation worker nodes.



### NOTE

Flexible scaling features get enabled at the time of deployment and can not be enabled or disabled later on.

### Prerequisites

- A running OpenShift Data Foundation Platform.
- Administrative privileges on the OpenShift Web Console.
- To scale using a storage class other than the one provisioned during deployment, first define an additional storage class. See Creating storage classes and pools for details.

### Procedure

- 1. Add additional hardware resources with zFCP disks.
  - a. List all the disks.

### \$ lszdev

Example output:

 TYPE
 ID
 ON
 PERS
 NAMES

 zfcp-host
 0.0.8204
 yes
 yes

 zfcp-lun
 0.0.8204:0x102107630b1b5060:0x4001402900000000 yes no
 sda sg0

 zfcp-lun
 0.0.8204:0x500407630c0b50a4:0x3002b0300000000 yes yes
 sdb sg1

 qeth
 0.0.bdd0:0.0.bdd1:0.0.bdd2
 yes no
 encbdd0

 generic-ccw
 0.0.0009
 yes no
 yes no

A SCSI disk is represented as a **zfcp-lun** with the structure **<device-id>:<wwpn>:<lun-id>** in the ID section. The first disk is used for the operating system. The device id for the new disk can be the same.

b. Append a new SCSI disk.

\$ chzdev -e 0.0.8204:0x400506630b1b50a4:0x3001301a0000000



The device ID for the new disk must be the same as the disk to be replaced. The new disk is identified with its WWPN and LUN ID.

c. List all the FCP devices to verify the new disk is configured.

 \$ Iszdev zfcp-lun
 ON
 PERS
 NAMES

 TYPE
 ID
 ON
 PERS
 NAMES

 zfcp-lun
 0.0.8204:0x102107630b1b5060:0x4001402900000000 yes no
 sda sg0

 zfcp-lun
 0.0.8204:0x500507630b1b50a4:0x4001302a00000000 yes yes
 sdb sg1

 zfcp-lun
 0.0.8204:0x400506630b1b50a4:0x3001301a00000000 yes yes
 sdb sg2

- 2. Navigate to the OpenShift Web Console.
- 3. Click **Operators** on the left navigation bar.
- 4. Select Installed Operators.
- 5. In the window, click **OpenShift Data Foundation** Operator.
- 6. In the top navigation bar, scroll right and click **Storage Systems** tab.
  - a. Click the Action menu (:) next to the visible list to extend the options menu.
  - b. Select Add Capacity from the options menu.
     The Raw Capacity field shows the size set during storage class creation. The total amount of storage consumed is three times this amount, because OpenShift Data Foundation uses a replica count of 3.
  - c. Click Add.
- 7. To check the status, navigate to **Storage** → **Data Foundation** and verify that **Storage System** in the **Status** card has a green tick.

### Verification steps

- Verify the **Raw Capacity** card.
  - a. In the OpenShift Web Console, click **Storage**  $\rightarrow$  **Data Foundation**.
  - b. In the **Status** card of the **Overview** tab, click **Storage System** and then click the storage system link from the pop up that appears.
  - c. In the **Block and File** tab, check the **Raw Capacity** card. Note that the capacity increases based on your selections.



### NOTE

The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:

- a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
- b. Select openshift-storage from the Project drop-down list.



If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- To view the state of the PVCs:
  - a. Click **Storage**  $\rightarrow$  **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select openshift-storage from the Project drop-down list.



### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/<OSDpod-name>

#### <OSD-pod-name>

Is the name of the OSD pod. For example:

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rook-ceph-osd-0-544db49d7f-qrgqm

Example output:

NODE compute-1

- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected host(s).



\$ oc debug node/<node-name>

#### <node-name>

Is the name of the node.

\$ chroot /host

ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.

\$ Isblk



### IMPORTANT

Cluster reduction is supported only with the Red Hat Support Team's assistance.

# 9.2. SCALING OUT STORAGE CAPACITY ON A IBM Z OR IBM LINUXONE CLUSTER

### 9.2.1. Adding a node using a local storage device

You can add nodes to increase the storage capacity when existing worker nodes are already running at their maximum supported OSDs or when there are not enough resources to add new OSDs on the existing nodes.

Add nodes in the multiple of 3, each of them in different failure domains. Though it is recommended to add nodes in multiples of 3 nodes, you have the flexibility to add one node at a time in flexible scaling deployment. See Knowledgebase article Verify if flexible scaling is enabled



### NOTE

OpenShift Data Foundation does not support heterogeneous disk size and types. The new nodes to be added should have the disk of the same type and size which was used during initial OpenShift Data Foundation deployment.

### Prerequisites

- You have administrative privilege to the OpenShift Container Platform Console.
- You have a running OpenShift Data Foundation Storage Cluster.

### Procedure

- 1. Depending on the type of infrastructure, perform the following steps:
  - a. Get a new machine with the required infrastructure. See Platform requirements.
  - b. Create a new OpenShift Container Platform worker node using the new machine.
- 2. Check for certificate signing requests (CSRs) that are in **Pending** state.

\$ oc get csr

3. Approve all the required CSRs for the new node.

\$ oc adm certificate approve < Certificate\_Name>

### <Certificate\_Name>

Is the name of the CSR.

- 4. Click **Compute**  $\rightarrow$  **Nodes**, confirm if the new node is in **Ready** state.
- 5. Apply the OpenShift Data Foundation label to the new node using any one of the following:

### From User interface

- a. For the new node, click Action Menu (:)  $\rightarrow$  Edit Labels.
- b. Add cluster.ocs.openshift.io/openshift-storage, and click Save.

#### From Command line interface


• Apply the OpenShift Data Foundation label to the new node.

\$ oc label node <new\_node\_name> cluster.ocs.openshift.io/openshift-storage=""

#### <new\_node\_name>

Is the name of the new node.

- Click Operators → Installed Operators from the OpenShift Web Console.
   From the Project drop-down list, make sure to select the project where the Local Storage Operator is installed.
- 7. Click Local Storage.
- 8. Click the Local Volume Discovery tab.
  - a. Beside the LocalVolumeDiscovery, click Action menu (:) → Edit Local Volume Discovery.
  - b. In the YAML, add the hostname of the new node in the **values** field under the node selector.
  - c. Click Save.
- 9. Click the Local Volume Sets tab.
  - a. Beside the **LocalVolumeSet**, click Action menu (:) → Edit Local Volume Set
  - b. In the YAML, add the hostname of the new node in the **values** field under the **node selector**.



c. Click Save.



### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them.

### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

### 9.2.2. Scaling up storage capacity

To scale up storage capacity, see Scaling up storage capacity on a cluster .

## CHAPTER 10. SCALING STORAGE OF IBM POWER OPENSHIFT DATA FOUNDATION CLUSTER

To scale the storage capacity of your configured Red Hat OpenShift Data Foundation worker nodes on IBM Power cluster, you can increase the capacity by adding three disks at a time. Three disks are needed since OpenShift Data Foundation uses a replica count of 3 to maintain the high availability. So the amount of storage consumed is three times the usable space.



### NOTE

Usable space might vary when encryption is enabled or replica 2 pools are being used.

### 10.1. SCALING UP STORAGE BY ADDING CAPACITY TO YOUR OPENSHIFT DATA FOUNDATION NODES ON IBM POWER INFRASTRUCTURE USING LOCAL STORAGE DEVICES

In order to scale up an OpenShift Data Foundation cluster which was created using local storage devices, a new disk needs to be added to the storage node. It is recommended to have the new disks of the same size as used earlier during the deployment as OpenShift Data Foundation does not support heterogeneous disks/OSD's.

You can add storage capacity (additional storage devices) to your configured local storage based OpenShift Data Foundation worker nodes on IBM Power infrastructures.



### NOTE

Flexible scaling features get enabled at the time of deployment and can not be enabled or disabled later on.

### Prerequisites

- You must be logged into the OpenShift Container Platform cluster.
- You must have installed the local storage operator. Use the following procedure:
  - Installing Local Storage Operator on IBM Power
- You must have three OpenShift Container Platform worker nodes with the same storage type and size attached to each node (for example, 0.5TB SSD) as the original OpenShift Data Foundation StorageCluster was created with.

### Procedure

- 1. To add storage capacity to OpenShift Container Platform nodes with OpenShift Data Foundation installed, you need to
  - a. Find the available devices that you want to add, that is, a minimum of one device per worker node. You can follow the procedure for finding available storage devices in the respective deployment guide.




Make sure you perform this process for all the existing nodes (minimum of 3) for which you want to add storage.

b. Add the additional disks to the **LocalVolume** custom resource (CR).

\$ oc edit -n openshift-local-storage localvolume localblock

Example output:



Make sure to save the changes after editing the CR.

Example output:

localvolume.local.storage.openshift.io/localblock edited

You can see in this CR that new devices are added.

• sdx

2. Display the newly created Persistent Volumes (PVs) with the **storageclass** name used in the **localVolume** CR.

\$ oc get pv | grep localblock | grep Available

Example output:

local-pv-a04ffd8	500Gi	RWO	Delete	Available	localblock	24s
local-pv-a0ca996b	500Gi	RWO	Delete	Available	localblock	23s
local-pv-c171754a	500Gi	RWO	Delete	Available	localblock	23s

- 3. Navigate to the OpenShift Web Console.
- 4. Click **Operators** on the left navigation bar.

- 5. Select Installed Operators.
- 6. In the window, click **OpenShift Data Foundation** Operator.
- 7. In the top navigation bar, scroll right and click **Storage System** tab.
  - a. Click the Action menu (:) next to the visible list to extend the options menu.
  - b. Select Add Capacity from the options menu.
     From this dialog box, set the Storage Class name to the name used in the localVolume CR.
     Available Capacity displayed is based on the local disks available in storage class.
  - c. Click Add.
- 8. To check the status, navigate to **Storage** → **Data Foundation** and verify that the **Storage System** in the **Status** card has a green tick.

#### Verification steps

- Verify the available Capacity.
  - In the OpenShift Web Console, click **Storage** → **Data Foundation**.
  - Click the **Storage Systems** tab and then click on **ocs-storagecluster-storagesystem**.
  - Navigate to **Overview** → **Block and File** tab, then check the **Raw Capacity** card. Note that the capacity increases based on your selections.



### NOTE

The raw capacity does not take replication into account and shows the full capacity.

- Verify that the new OSDs and their corresponding new Persistent Volume Claims (PVCs) are created.
  - To view the state of the newly created OSDs:
    - a. Click **Workloads**  $\rightarrow$  **Pods** from the OpenShift Web Console.
    - b. Select openshift-storage from the Project drop-down list.



### NOTE

If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- To view the state of the PVCs:
  - a. Click **Storage** → **Persistent Volume Claims** from the OpenShift Web Console.
  - b. Select **openshift-storage** from the **Project** drop-down list.



If the **Show default projects** option is disabled, use the toggle button to list all the default projects.

- Optional: If cluster-wide encryption is enabled on the cluster, verify that the new OSD devices are encrypted.
  - a. Identify the nodes where the new OSD pods are running.

\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/<*OSD*pod-name>

### <OSD-pod-name>

Is the name of the OSD pod. For example:



\$ oc get -n openshift-storage -o=custom-columns=NODE:.spec.nodeName pod/rook-ceph-osd-0-544db49d7f-qrgqm

Example output:



- b. For each of the nodes identified in the previous step, do the following:
  - i. Create a debug pod and open a chroot environment for the selected host(s).

\$ oc debug node/<node-name>

### <node-name>

Is the name of the node.

\$ chroot /host

ii. Check for the **crypt** keyword beside the **ocs-deviceset** names.



### IMPORTANT

\$ Isblk

Cluster reduction is supported only with the Red Hat Support Team's assistance.

### 10.2. SCALING OUT STORAGE CAPACITY ON A IBM POWER CLUSTER

OpenShift Data Foundation is highly scalable. It can be scaled out by adding new nodes with required storage and enough hardware resources in terms of CPU and RAM. Practically there is no limit on the number of nodes which can be added but from the support perspective 2000 nodes is the limit for OpenShift Data Foundation.

Scaling out storage capacity can be broken down into two steps:

- Adding new node
- Scaling up the storage capacity



### NOTE

OpenShift Data Foundation does not support heterogeneous OSD/Disk sizes.

### 10.2.1. Adding a node using a local storage device on IBM Power

You can add nodes to increase the storage capacity when existing worker nodes are already running at their maximum supported OSDs or when there are not enough resources to add new OSDs on the existing nodes.

Add nodes in the multiple of 3, each of them in different failure domains. Though it is recommended to add nodes in multiples of 3 nodes, you have the flexibility to add one node at a time in flexible scaling deployment. See Knowledgebase article Verify if flexible scaling is enabled



### NOTE

OpenShift Data Foundation does not support heterogeneous disk size and types. The new nodes to be added should have the disk of the same type and size which was used during initial OpenShift Data Foundation deployment.

### Prerequisites

- You must be logged into the OpenShift Container Platform cluster.
- You must have three OpenShift Container Platform worker nodes with the same storage type and size attached to each node (for example, 2TB SSD drive) as the original OpenShift Data Foundation StorageCluster was created with.

### Procedure

- 1. Get a new IBM Power machine with the required infrastructure. See Platform requirements.
- 2. Create a new OpenShift Container Platform node using the new IBM Power machine.
  - a. Check for certificate signing requests (CSRs) that are in **Pending** state.



b. Approve all the required CSRs for the new node.



\$ oc adm certificate approve <Certificate\_Name>

### <Certificate\_Name>

Is the name of the CSR.

- c. Click **Compute**  $\rightarrow$  **Nodes**, confirm if the new node is in **Ready** state.
- d. Apply the OpenShift Data Foundation label to the new node using any one of the following:

### From User interface

- i. For the new node, click Action Menu (:)  $\rightarrow$  Edit Labels.
- ii. Add cluster.ocs.openshift.io/openshift-storage and click Save.

### From Command line interface

• Apply the OpenShift Data Foundation label to the new node.

\$ oc label node <new\_node\_name> cluster.ocs.openshift.io/openshift-storage=""

### <new\_node\_name>

Is the name of the new node.

- e. Click Operators → Installed Operators from the OpenShift Web Console.
   From the Project drop-down list, make sure to select the project where the Local Storage Operator is installed.
- f. Click Local Storage.
- g. Click the Local Volume tab.
  - i. Beside the **LocalVolume**, click Action menu (:) → Edit Local Volume.
  - ii. In the YAML, add the hostname of the new node in the **values** field under the **node selector**.

### Figure 10.1. YAML showing the addition of new hostnames

-							
1	apiVersion: local.storage.openshift.io/vl						
2	kind: LocalVolume						
3	metadata:						
4	creationTimestamp: '2021-07-09T08:12:56Z'						
5	finalizers:…						
7	generation: 2						
8	managedFields:…						
47	name: localblock						
48	namespace: openshift-local-storage						
49	resourceVersion: '1988620'						
50	uid: 89d78619-a76b-4b97-af9d-6760c57ab531						
51	spec:						
52	logLevel: Normal						
53	managementState: Managed						
54	nodeSelector:						
55	nodeSelectorTerms:						
56	- matchExpressions:						
57	key: kubernetes.io/hostname						
58	operator: In						
59	values:						
60	- vorker-0						
61	- worker-1						
62	- worker-2						
63	- worker-3						
64	storageClassDevices:						

iii. Click Save.

### NOTE

It is recommended to add 3 nodes, one each in different zones. You must add 3 nodes and perform this procedure for all of them.

### Verification steps

1. Execute the following command the terminal and verify that the new node is present in the output:

\$ oc get nodes --show-labels | grep cluster.ocs.openshift.io/openshift-storage= |cut -d' ' -f1

- 2. On the OpenShift web console, click **Workloads** → **Pods**, confirm that at least the following pods on the new node are in **Running** state:
  - csi-cephfsplugin-\*
  - csi-rbdplugin-\*

### 10.2.2. Scaling up storage capacity

To scale up storage capacity, see Scaling up storage capacity on a cluster .