



Red Hat OpenStack Platform 16.2

Block Storage Backup Guide

Understanding, using, and managing the Block Storage backup service in Red Hat OpenStack Platform

Red Hat OpenStack Platform 16.2 Block Storage Backup Guide

Understanding, using, and managing the Block Storage backup service in Red Hat OpenStack Platform

OpenStack Team
rhos-docs@redhat.com

Legal Notice

Copyright © 2021 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document describes how to deploy the Red Hat OpenStack Platform Block Storage (cinder) backup service. Red Hat OpenStack Platform director can configure Red Hat Ceph Storage, NFS, and Object Storage (swift) as back ends. You can also configure Google Cloud Storage as a backup back end.

Table of Contents

MAKING OPEN SOURCE MORE INCLUSIVE	3
PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	4
CHAPTER 1. OVERVIEW OF THE RED HAT OPENSTACK PLATFORM BLOCK STORAGE BACKUP SERVICE	5
1.1. BACKUPS AND SNAPSHOTS	5
1.2. VOLUME BACKUP WORKFLOW	5
1.3. VOLUME RESTORE WORKFLOW	7
1.4. CLOUD STORAGE VERSUS LOCAL STORAGE	8
CHAPTER 2. BLOCK STORAGE BACKUP SERVICE DEPLOYMENT	10
2.1. CONFIGURING BACK END STORAGE OPTIONS FOR THE BACKUP SERVICE	10
2.2. DEPLOYING THE OVERCLOUD WITH YOUR GOOGLE CLOUD CONFIGURATION	11
CHAPTER 3. USING THE BLOCK STORAGE BACKUP SERVICE	12
3.1. FULL BACKUPS	12
3.1.1. Creating a full volume backup	12
3.1.2. Creating a volume backup as an admin	13
3.1.3. Exporting the metadata of a volume backup	13
3.1.4. Backing up an in-use volume	14
3.1.5. Backing up a snapshot	14
3.1.6. Backing up and restoring across edge sites	14
3.2. INCREMENTAL BACKUPS	15
3.2.1. Performance considerations	16
3.2.2. Impact of backing up from a snapshot	16
3.2.3. Performing incremental backups	16
3.3. CANCELING A BACKUP	16
3.4. VIEWING AND MODIFYING TENANT BACKUP QUOTA	17
3.5. RESTORING FROM BACKUPS	17
3.5.1. Restoring a volume from a backup	18
3.5.2. Restoring a volume after a Block Storage database loss	18
3.5.3. Canceling a backup restore	19
CHAPTER 4. TROUBLESHOOTING THE BLOCK STORAGE BACKUP SERVICE	20
4.1. VERIFYING SERVICES	20
4.2. QUERYING THE STATUS OF A FAILED BACKUP	21
4.3. USING PACEMAKER TO MANAGE RESOURCES	21
APPENDIX A. GOOGLE CLOUD STORAGE CONFIGURATION	22
A.1. CREATING THE GCS CREDENTIALS FILE	22
A.2. CREATING CINDER-BACKUP-GCS.YAML	23
A.3. CREATING THE ENVIRONMENT FILE WITH YOUR GOOGLE CLOUD SETTINGS	24
A.4. DEPLOYING THE OVERCLOUD	27
APPENDIX B. ADVANCED BLOCK STORAGE CONFIGURATION	28
B.1. ADVANCED CONFIGURATION OPTIONS	28

MAKING OPEN SOURCE MORE INCLUSIVE

Red Hat is committed to replacing problematic language in our code, documentation, and web properties. We are beginning with these four terms: master, slave, blacklist, and whitelist. Because of the enormity of this endeavor, these changes will be implemented gradually over several upcoming releases. For more details, see [our CTO Chris Wright's message](#).

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your input on our documentation. Tell us how we can make it better.

Using the Direct Documentation Feedback (DDF) function

Use the **Add Feedback** DDF function for direct comments on specific sentences, paragraphs, or code blocks.

1. View the documentation in the *Multi-page HTML* format.
2. Ensure that you see the **Feedback** button in the upper right corner of the document.
3. Highlight the part of text that you want to comment on.
4. Click **Add Feedback**.
5. Complete the **Add Feedback** field with your comments.
6. Optional: Add your email address so that the documentation team can contact you for clarification on your issue.
7. Click **Submit**.

CHAPTER 1. OVERVIEW OF THE RED HAT OPENSTACK PLATFORM BLOCK STORAGE BACKUP SERVICE

Red Hat OpenStack Platform (RHOSP) provides the foundation to build a private or public Infrastructure-as-a-Service (IaaS) cloud on top of Red Hat Enterprise Linux. It is a scalable, fault-tolerant platform for the development of cloud-enabled workloads.

You can manage most features of the backup service by using either the RHOSP dashboard or the command-line client methods, however you must use the command line to execute some of the more advanced procedures.



NOTE

For the complete suite of documentation for Red Hat OpenStack Platform, see [Red Hat OpenStack Platform Documentation](#).

The Block Storage service (cinder) includes a horizontally scalable backup service that you can use to back up cinder volumes to diverse storage back ends. You can use the Block Storage backup service to create and restore full or incremental backups. The service is volume-array independent.

The Red Hat OpenStack Platform (RHOSP) director is a toolset to install and manage a complete RHOSP environment called the overcloud. For more information about director, see the [Director Installation and Usage](#) guide. The overcloud contains the components that provide services to end users, including Block Storage. The Block Storage backup service is an optional service that you deploy on Controller nodes.

1.1. BACKUPS AND SNAPSHOTS

A volume backup is a persistent copy of the contents of a volume. Volume backups are typically created as object stores, and are managed through the OpenStack Object Storage service (swift) by default. You can use Red Hat Ceph and NFS as alternative back ends for backups.

When you create a volume backup, all of the backup metadata is stored in the Block Storage service database. The cinder-backup service uses this metadata when it restores a volume from the backup. This means that when you perform a recovery from a catastrophic database loss, you must restore the Block Storage service database first before you restore any volumes from backups, provided that the original volume backup metadata of the Block Storage service database is intact. If you want to configure only a subset of volume backups to survive a catastrophic database loss, you can also export the backup metadata. You can then re-import the metadata to the Block Storage database by using the REST API or the cinder client, and restore the volume backup as normal.

Volume backups are different from snapshots. Backups preserve the data contained in the volume, and snapshots preserve the state of a volume at a specific point in time. You cannot delete a volume if it has existing snapshots. Volume backups prevent data loss, whereas snapshots facilitate cloning. For this reason, snapshot back ends are typically colocated with volume back ends in order to minimize latency during cloning. By contrast, the backup repository is typically located separately from the back ends, either on a different node or different physical storage. This protects the backup repository from any damage that might occur to the volume back end.


For more information about volume snapshots, see [Create, Use, or Delete Volume Snapshots](#) in the *Storage Guide*.

1.2. VOLUME BACKUP WORKFLOW

When the Block Storage backup service performs a back up, it receives a request from the cinder API to back up a targeted volume. The backup service completes the request and stores the content on the back end.

The following diagram illustrates how the request interacts with the Block Storage (cinder) services to perform the backup.

Figure 1.1. Creating a backup with the Block Storage service



OPENSTACK_483337_1218


1. The client issues a request to back up a Block Storage volume by invoking the cinder API.
2. The cinder API service receives the request from HAProxy and validates the request, the user credentials, and other information.
3. Creates the backup record in the SQL database.
4. Makes an asynchronous RPC call to the **cinder-backup** service via AMQP to back up the volume.
5. Returns current backup record, with an ID, to the API caller.
6. An RPC create message arrives on one of the backup services.
7. The **cinder-backup** service performs a synchronous RPC call to **get_backup_device**.
8. The **cinder-volume** service ensures that the correct device is returned to the caller. Normally, it is the same volume, but if the volume is in use, the service returns a temporary cloned volume or a temporary snapshot, depending on the configuration.
9. The **cinder-backup** service issues another synchronous RPC to **cinder-volume** to expose the source device.
10. The **cinder-volume** service exports and maps the source device (volume or snapshot) and returns the appropriate connection information.

11. The **cinder-backup** service attaches source volume by using connection information.
12. The **cinder-backup** service calls the backup driver, with the device already attached, which begins the data transfer to the backup destination.
13. The volume is detached from the Backup host.
14. The **cinder-backup** service issues a synchronous RPC to **cinder-volume** to disconnect the source device.
15. The **cinder-volume** service unmaps and removes the export for the device.
16. If a temporary volume or temporary snapshot was created, **cinder-backup** calls **cinder-volume** to remove it.
17. The **cinder-volume** service removes the temporary volume.
18. When the backup is completed, the backup record is updated in the database.

1.3. VOLUME RESTORE WORKFLOW

The following diagram illustrates the steps that occur when a user requests to restore a Block Storage service (cinder) backup.

Figure 1.2. Restoring a Block Storage backup



1. The client issues a request to restore a Block Storage backup by invoking the CinderREST API.
2. The cinder API receives the request from HAProxy and validates the request, the user credentials, and other information.

3. If the request does not contain an existing volume as the destination, the API makes an asynchronous RPC call to create a new volume and polls the status of the volume until it becomes available.
4. The **cinder-scheduler** selects a volume service and makes the RPC call to create the volume.
5. Selected **cinder-volume** service creates the volume.
6. When **cinder-api** detects that the volume is available, the backup record is created in the database.
7. Makes an asynchronous RPC call to the backup service via AMQP to restore the backup.
8. Returns the current volume ID, backup ID, and volume name to the API caller.
9. An RPC create message arrives on one of the backup services.
10. The **cinder-backup** service performs a synchronous RPC call to **cinder-volume** to expose the destination volume.
11. The **cinder-volume** service exports and maps the Destination Volume returning the appropriate connection information.
12. The **cinder-backup** service attaches source volume using connection information.
13. The **cinder-backup** service calls the driver with the device already attached, which begins the data restoration to the volume destination.
14. The volume is detached from the backup host.
15. The **cinder-backup** service issues a synchronous RPC to **cinder-volume** to disconnect the source device.
16. The **cinder-volume** service unmaps and removes the export for the device.
17. When the backup is completed, the Backup record is updated in the database.

1.4. CLOUD STORAGE VERSUS LOCAL STORAGE

The Google Cloud Storage driver is the only cloud driver that is supported by the Block Storage backup service. By default, the Google Cloud Storage driver uses the least expensive storage solution, Nearline, for this type of backup.

Configure the backup service to optimize performance. For example, if you create backups from Europe, change the backup region to Europe. If you do not change the backup region from the default, US, the performance might be slower due to the geographical distance between the two regions.



NOTE

Google Cloud Storage requires special configuration that is explained in section [Appendix A, Google Cloud Storage configuration](#).

The following table lists the benefits and limitations of cloud storage and local storage based on the situation.

Situation	Cloud storage	Local storage
Offsite backup	Cloud storage is in the data center of another company and is therefore automatically offsite. You can access data from many locations. Remote copy is available for disaster recovery.	Requires additional planning and expense.
Hardware control	Relies on the availability and expertise of another service.	You have complete control over storage hardware. Requires management and expertise.
Cost considerations	Different pricing policies or tiers depending upon the services you use from the vendor.	Adding additional hardware as needed is a known cost.
Network speed and data access	Overall data access is slower and requires Internet access. Speed and latency depend on multiple factors.	Access to data is fast and immediate. No internet access is required.

CHAPTER 2. BLOCK STORAGE BACKUP SERVICE DEPLOYMENT

The Block Storage backup service is optional. It is not installed by default so you must add it to your overcloud deployment

Prerequisites

- An existing Red Hat OpenStack Platform (RHOSP) installation.
- An available storage source with a compatible backup driver: Object Storage (swift; default), Ceph, NFS, or Google Cloud storage.



NOTE

Google Cloud Storage requires additional configuration. For more information, see [Appendix A, Google Cloud Storage configuration](#).

2.1. CONFIGURING BACK END STORAGE OPTIONS FOR THE BACKUP SERVICE

You can configure the backup service to use a different back end from the default. This procedure describes how to make a copy of the **cinder-backup.yaml** file and how to modify parameter defaults.

Procedure

1. Create a copy of the **cinder-backup.yaml** file, which is located in the **/usr/share/openstack-tripleo-heat-templates/environments/** directory, and store it in the same location as your other custom templates.

```
cp /usr/share/openstack-tripleo-heat-templates/environments/cinder-backup.yaml
/home/stack/templates/cinder-backup-settings.yaml
```

2. Your copy of the **cinder-backup.yaml** file contains default settings that configure an OpenStack Object Storage (swift) back end for the Block Storage backup service with Pacemaker. If this is the back end you are using for your backup then you do not need to make changes to this file. If you are using an alternative back end, configure **parameter_defaults** depending on the backup back end:
 - If you are using Red Hat Ceph Storage, configure **parameter_defaults** in the following way:
 - **CinderBackupBackend:** (Required) **ceph**
 - **CinderBackupRbdPoolName:** (Optional) Set to a custom RBD pool name. Default: **backups**
 - If you are using NFS, configure **parameter_defaults** in the following way:
 - **CinderBackupBackend:** (Required) **nfs**
 - **CinderBackupNfsShare:** (Required) Set to the NFS share that you want to mount. The default value is empty.
 - **CinderBackupNfsMountOptions:** (Optional) Set to your required mount option.

3. Save the changes to the file.
4. To enable the backup service and apply this configuration, add your backup settings environment file to the stack with your other environment files and deploy the overcloud:

```
(undercloud) [stack@undercloud ~]$ openstack overcloud deploy --templates \
-e [your environment files]
-e /home/stack/templates/cinder-backup-settings.yaml
```

For more information and additional configuration options, see [Appendix A, Google Cloud Storage configuration](#).

2.2. DEPLOYING THE OVERCLOUD WITH YOUR GOOGLE CLOUD CONFIGURATION

After you create the environment file in `~/home/stack/templates/`, deploy the overcloud then restart the `cinder-backup` service.



IMPORTANT

Cinder backup with Google Cloud Storage is being deprecated and support will be removed in the next major release.

Procedure

1. Log in as the **stack** user.
2. Deploy the configuration:

```
$ openstack overcloud deploy --templates \
-e /home/stack/templates/cinder-backup-settings.yaml
```



IMPORTANT

If you passed any extra environment files when you created the overcloud, pass them again here using the **-e** option to avoid making undesired changes to the overcloud.

3. Restart the **cinder-backup** service after the deployment finishes.

For more information, see the [Including environment files in an overcloud deployment](#) in the *Director Installation and Usage* guide and [Environment Files](#) in the *Advanced Overcloud Customization* guide.

CHAPTER 3. USING THE BLOCK STORAGE BACKUP SERVICE

You can use the Block Storage backup service to perform full or incremental backups, and to restore a backup to a volume.

3.1. FULL BACKUPS

The **cinder backup-create** command creates a full backup of the volume by default. You can create backups of volumes you have access to. This means that users with administrative privileges can back up any volume, regardless of owner.

3.1.1. Creating a full volume backup

To back up a volume, use the cinder **backup-create** command. By default, this command creates a full backup of the volume. If the volume has existing backups, you can choose to create an incremental backup instead. For more information, see [Section 3.2.3, "Performing incremental backups"](#).



NOTE

Before Red Hat OpenStack Platform (RHOSP) version 16, the **cinder backup-create** command created incremental backups after the first full Ceph volume backup to a Ceph Storage back end. In RHOSP version 16 and later, you must use the **--incremental** option to create incremental volume backups. If you do not use the **--incremental** option with the **cinder backup-create** command, the default setting creates full backups. For more information, see [Section 3.2.3, "Performing incremental backups"](#).

You can create backups of volumes you have access to. This means that users with administrative privileges can back up any volume, regardless of owner. For more information, see [Section 3.1.2, "Creating a volume backup as an admin"](#).

Procedure

1. View the ID or Display Name of the volume you want to back up:

```
# cinder list
```

2. Back up the volume:

```
# cinder backup-create _VOLUME_
```

Replace *VOLUME* with the **ID** or **Display Name** of the volume you want to back up. For example:

```
+-----+-----+
| Property |          Value          |
+-----+-----+
|  id    | e9d15fc7-eeae-4ca4-aa72-d52536dc551d |
|  name  |          None           |
| volume_id | 5f75430a-abff-4cc7-b74e-f808234fa6c5 |
+-----+-----+
```

The **volume_id** of the resulting backup is identical to the ID of the source volume.

3. Verify that the volume backup creation is complete:

```
# cinder backup-list
```

4. The volume backup creation is complete when the **Status** of the backup entry is available.

3.1.2. Creating a volume backup as an admin

Users with administrative privileges can back up any volume managed by Red Hat OpenStack Platform. When an admin user backs up a volume that is owned by a non-admin user, the backup is hidden from the volume owner by default.

Procedure

- As an admin user, you can use the following command to back up a volume and make the backup available to a specific tenant:

```
# cinder --os-auth-url <KEYSTONEURL> --os-tenant-name <TENANTNAME> --os-username <USERNAME> --os-password <PASSWD> backup-create <VOLUME>
```

Replace the following variables according to your environment requirements:

- <TENANTNAME> is the name of the tenant where you want to make the backup available.
- <USERNAME> and <PASSWD> are the username and password credentials of a user within <TENANTNAME>.
- <VOLUME> is the name or ID of the volume that you want to back up.
- <KEYSTONEURL> is the URL endpoint of the Identity service, which is typically `http://IP:5000/v2`, where *IP* is the IP address of the Identity service host. When you perform this operation, the size of the resulting backup counts against the quota of **TENANTNAME** rather than the quota of the tenant admin.

3.1.3. Exporting the metadata of a volume backup

You can export and store the metadata of a volume backup so that you can restore the volume backup even if the Block Storage database suffers a catastrophic loss.

Procedure

- Run the following command:

```
# cinder backup-export _BACKUPID_
```


Replace <BACKUPID> with the ID or name of the volume backup:

```
+-----+-----+
| Property | Value |
+-----+-----+
| backup_service | cinder.backup.drivers.swift |
| backup_url | eyJzdGF0dXMiOiAiYXZhaWxhYmxlliwglm9iam...|
| | ...4NS02ZmY4MzBhZWYwNWUiLCAic2I6ZSI6IDF9 |
+-----+-----+
```

The volume backup metadata consists of the **backup_service** and **backup_url** values.

3.1.4. Backing up an in-use volume

You can create a backup of an in-use volume with the **--force** option when the Block Storage back end snapshot is supported.



NOTE

To use the **--force** option, the Block Storage back end snapshot must be supported. You can verify snapshot support by checking the documentation for the back end that you are using.

By using the **--force** option, you acknowledge that you are not quiescing the drive before performing the backup. Using this method creates a crash-consistent, but not application-consistent, backup. This means that the backup does not have an awareness of which applications were running when the backup was performed. However, the data is intact.

Procedure

- To create a backup of an in-use volume, run:

```
# cinder backup-create _VOLUME_ --incremental --force
```

3.1.5. Backing up a snapshot

You can create a full backup from a snapshot by using the volume ID that is associated with the snapshot.

Procedure

1. Locate the snapshot ID of the snapshot to backup using **cinder snapshot list**.


```
# cinder snapshot-list --volume-id _VOLUME_ID_
```

2. If the snapshot is named, then you can use the following example to locate the **ID**:

```
# cinder snapshot-show _SNAPSHOT_NAME_
```

3. Create the backup of a snapshot:

```
# cinder backup-create _VOLUME_ --snapshot-id=_SNAPSHOT_ID_
```



NOTE

Snapshot-based backups of NFS volumes fail when you use the **--snapshot-id** option. This is a known issue.

3.1.6. Backing up and restoring across edge sites

You can back up and restore Block Storage service (cinder) volumes across distributed compute node (DCN) architectures in edge site and availability zones. The **cinder-backup** service runs in the central

availability zone (AZ), and backups are stored in the central AZ. The Block Storage service does not store backups at DCN sites.

Prerequisites

- The central site is deployed with the **cinder-backup.yaml** environment file located in `/usr/share/openstack-tripleo-heat-templates/environments`. For more information, see [Block Storage backup service deployment](#).
- The Block Storage service (cinder) CLI is available.
- All sites must use a common **openstack** cephx client name. For more information, see [Creating a Ceph key for external access](#).

Procedure

1. Create a backup of a volume in the first DCN site:

```
$ cinder --os-volume-api-version 3.51 backup-create --name <volume_backup> --availability-zone <az_central> <edge_volume>
```

- Replace **<volume_backup>** with a name for the volume backup.
- Replace **<az_central>** with the name of the central availability zone that hosts the **cinder-backup** service.
- Replace **<edge_volume>** with the name of the volume that you want to back up.



NOTE

If you experience issues with Ceph keyrings, you might need to restart the **cinder-backup** container so that the keyrings copy from the host to the container successfully.

2. Restore the backup to a new volume in the second DCN site:

```
$ cinder --os-volume-api-version 3.51 create --availability-zone <az_2> --name <new_volume> --backup-id <volume_backup> <volume_size>
```

- Replace **<az_2>** with the name of the availability zone where you want to restore the backup.
- Replace **<new_volume>** with a name for the new volume.
- Replace **<volume_backup>** with the name of the volume backup that you created in the previous step.
- Replace **<volume_size>** with a value in GB equal to or greater than the size of the original volume.

3.2. INCREMENTAL BACKUPS

If a volume has existing backups, you can use the Block Storage backup service to create an incremental backup instead.

3.2.1. Performance considerations

Some backup features like incremental and data compression can impact performance. Incremental backups have a performance impact because all of the data in a volume must be read and checksummed for both the full and each incremental backup.

You can use data compression with non-Ceph backends. Enabling data compression requires additional CPU power but uses less network bandwidth and storage space overall.

The multipathing configuration also impacts performance. If you attach multiple volumes without enabling multipathing, you might not be able to connect or have full network capabilities, which impacts performance.

You can use the advanced configuration options to enable or disable compression, define the number of processes, and add additional CPU resources. For more information, see [Section B.1, “Advanced configuration options”](#).

3.2.2. Impact of backing up from a snapshot

Some back ends support creating a backup from a snapshot. A driver that supports this feature can directly attach a snapshot, which is faster than cloning the snapshot into a volume to be able to attach to it. In general, this feature can affect performance because of the extra step of creating the volume from a snapshot.

3.2.3. Performing incremental backups

By default, the **cinder backup-create** command creates a full backup of a volume. However, if the volume has existing backups, you can create an incremental backup.

Incremental backups are fully supported on NFS, Object Storage (swift), and Red Hat Ceph Storage backup repositories.


An incremental backup captures any changes to the volume since the last full or incremental backup. Performing numerous, regular, full backups of a volume can become resource intensive because the size of the volume increases over time. With incremental backups, you can capture periodic changes to volumes and minimize resource usage.

Procedure

- To create an incremental volume backup, use the **--incremental** option with the following command:

```
# cinder backup-create _VOLUME_ --incremental
```

Replace *VOLUME* with the **ID** or **Display Name** of the volume you want to back up.



NOTE

You cannot delete a full backup if it already has an incremental backup. If a full backup has multiple incremental backups, you can only delete the latest one.

3.3. CANCELING A BACKUP

To cancel a backup, an administrator must request a force delete on the backup.

**IMPORTANT**

This operation is not supported if you use the Ceph or RBD back ends.

Procedure

- Run the following command:

```
# openstack volume backup delete --force <backup>
```

After you complete the cancellation and the backup no longer appears in the backup listings, there can be a slight delay for the backup to be successfully canceled. To verify that the backup is successfully canceled, the backing-up status in the source resource stops.

**NOTE**

Before Red Hat OpenStack version 12, the **backing-up** status was stored in the volume, even when backing up a snapshot. Therefore, when backing up a snapshot, any delete operation on the snapshot that followed a cancellation could result in an error if the snapshot was still mapped. In Red Hat OpenStack Platform version 13 and later, ongoing restoration operations can be canceled on any of the supported backup drivers.

3.4. VIEWING AND MODIFYING TENANT BACKUP QUOTA

Normally, you can use the dashboard to modify tenant storage quotas, for example, the number of volumes, volume storage, snapshots, or other operational limits that a tenant can have. However, the functionality to modify backup quotas with the dashboard is not yet available.

You must use the command-line interface to modify backup quotas.

Procedure

1. To view the storage quotas of a specific tenant (*TENANT_ID*), run the following command:

```
# cinder quota-show TENANT_ID
```

2. To update the maximum number of backups (*MAXNUM*) that can be created in a specific tenant, run the following command:

```
# cinder quota-update --backups MAXNUM TENANT_ID
```

3. To update the maximum total size of all backups (*MAXGB*) within a specific tenant, run the following command:

```
# cinder quota-update --backup-gigabytes MAXGB TENANT_ID
```

4. To view the storage quota usage of a specific tenant, run the following command:

```
# cinder quota-usage TENANT_ID
```

3.5. RESTORING FROM BACKUPS

After a database failure or another type of event that results in data loss, use the backups you created to restore data.



IMPORTANT

If you configure the **cinder-backup** service to use the Ceph RBD driver, you can restore backup volumes only to an RBD-based Block Storage (cinder) back end.

3.5.1. Restoring a volume from a backup

To create a new volume from a backup, complete the following steps.

Procedure

1. Find the ID of the volume backup you want to use:

```
# cinder backup-list
```

Ensure that the Volume ID matches the ID of the volume that you want to restore.

2. Restore the volume backup:

```
# cinder backup-restore _BACKUP_ID_
```

Replace *BACKUP_ID* with the ID of the volume backup you want to use.

3. If you no longer need the backup, delete it:

```
# cinder backup-delete _BACKUP_ID_
```

4. If you need to restore a backed up volume to a volume of a particular type, use the **--volume** option to restore a backup to a specific volume:

```
# cinder backup-restore _BACKUP_ID_ --volume VOLUME_ID_
```



NOTE

If you restore a volume from an encrypted backup, then the destination volume type must also be encrypted.

3.5.2. Restoring a volume after a Block Storage database loss

When a Block Storage database loss occurs, you cannot restore a volume backup because the database contains metadata that the volume backup service requires. However, after you create the volume backup, you can export and store the metadata, which consists of **backup_service** and **backup_url** values, so that when a database loss occurs, you can restore the volume backup. For more information see [Section 3.1.1, "Creating a full volume backup"](#)).

If you exported and stored this metadata, then you can import it to a new Block Storage database, which allows you to restore the volume backup.

**NOTE**

For incremental backups, you must import all exported data before you can restore one of the incremental backups.

Procedure

1. As a user with administrative privileges, run the following command:

```
# cinder backup-import _backup_service _backup_url_
```

Replace **backup_service** and **backup_url** with the metadata you exported. For example, using the exported metadata from [Section 3.1.1, "Creating a full volume backup"](#) :

```
# cinder backup-import cinder.backup.drivers.swift eyJzdGF0dXMi...c2l6ZSI6IDF9
+-----+-----+
| Property |          Value          |
+-----+-----+
| id      | 77951e2f-4aff-4365-8c64-f833802eaa43 |
| name    |          None           |
+-----+-----+
```

2. After you import the metadata into the Block Storage service database, you can restore the volume as normal, see [Section 3.5.1, "Restoring a volume from a backup"](#) .

3.5.3. Canceling a backup restore

To cancel a backup restore operation, alter the status of the backup to anything other than **restoring**. You can use the **error** state to minimize confusion regarding whether the restore was successful or not. Alternatively, you can change the value to **available**.

```
$ openstack volume backup set --state error BACKUP_ID
```

**NOTE**

Backup cancellation is an asynchronous action, because the backup driver must detect the status change before it cancels the backup. When the status changes to **available** in the destination volume, the cancellation is complete.

**NOTE**

This feature is not currently available on RBD backups.

**WARNING**

If a restore operation is canceled after it starts, the destination volume is useless, because there is no way of knowing how much data, if any, was actually restored.

CHAPTER 4. TROUBLESHOOTING THE BLOCK STORAGE BACKUP SERVICE

There are two common scenarios that cause many of the issues that occur with the backup service:

- When the **cinder-backup** service starts, it connects to its configured backend and uses this as a target for backups. Problems with this connection can cause services to fail.
- When backups are requested, the backup service connects to the volume service and attaches the requested volume. Problems with this connection are evident only during backup time.

In either case, the logs contain messages that describe the error.

For more information about log files and services, see [Location of log files for OpenStack services](#) in the *Logging, Monitoring and Troubleshooting Guide*.

For more information about log locations and troubleshooting suggestions, see [Block Storage \(cinder\) Log Files](#) in the *Logging, Monitoring and Troubleshooting Guide*.

4.1. VERIFYING SERVICES

You can diagnose many issues by verifying that services are available and by checking log files for error messages.

After you verify the status of the services, check the **cinder-backup.log** file. The Block Storage Backup service log is located in **/var/log/containers/cinder/cinder-backup.log**.

Procedure

1. Run the **cinder show** command on the volume to see if it is stored by the host:

```
# cinder show
```

2. Run the **cinder service-list** command to view running services:

```
# cinder service-list
+-----+-----+-----+-----+-----+-----+-----+
---+
| Binary      | Host      | Zone | Status | State | Updated_at           | Disabled Reason |
+-----+-----+-----+-----+-----+-----+-----+
---+
| cinder-backup | hostgroup | nova | enabled | up   | 2017-05-15T02:42:25.000000 | -
|
| cinder-scheduler | hostgroup | nova | enabled | up   | 2017-05-15T02:42:25.000000 | -
|
| cinder-volume  | hostgroup@sas-pool | nova | enabled | down | 2017-05-14T03:04:01.000000 | -
|
| cinder-volume  | hostgroup@ssd-pool | nova | enabled | down | 2017-05-14T03:04:01.000000 | -
+-----+-----+-----+-----+-----+-----+-----+
---+
```

3. Verify that the expected services are available.

4.2. QUERYING THE STATUS OF A FAILED BACKUP

Backups are asynchronous. The Block Storage backup service performs a small number of static checks upon receiving an API request, such as checking for an invalid volume reference (**missing**) or a volume that is **in-use** or attached to an instance. The **in-use** case requires you to use the **--force** option.



NOTE

Using the **--force** option means that I/O is not be quiesced and the resulting volume image may be corrupt.

If the API accepts the request, the backup occurs in the background. Usually, the CLI returns immediately even if the backup fails or is approaching failure. You can query the status of a backup by using the cinder backup API. If an error occurs, review the logs to discover the cause.

4.3. USING PACEMAKER TO MANAGE RESOURCES

By default, Pacemaker deploys the Block Storage backup service. Pacemaker configures virtual IP addresses, containers, services, and other features as resources in a cluster to ensure that the defined set of Red Hat OpenStack Platform cluster resources are running and available. When a service or an entire node in a cluster fails, Pacemaker can restart the resource, take the node out of the cluster, or reboot the node. Requests to most services are through HAProxy.

For information about how to use Pacemaker for troubleshooting, see [Managing high availability services with Pacemaker](#) in the *High Availability Deployment and Usage* guide.

APPENDIX A. GOOGLE CLOUD STORAGE CONFIGURATION

To configure the Block Storage service (cinder) to use Google Cloud Storage as a backup back end, complete the following procedures:

1. Create and download the service account credentials of your Google account:
 - [Section A.1, "Creating the GCS credentials file"](#)
 - [Section A.2, "Creating `cinder-backup-gcs.yaml`"](#)
2. Create an environment file to map the Block Storage settings that you require:
 - [Section A.3, "Creating the environment file with your Google Cloud settings"](#)
3. Re-deploy the overcloud with the environment file that you created:
 - [Section A.4, "Deploying the overcloud"](#)



IMPORTANT

Cinder backup with Google Cloud Storage is being deprecated and support will be removed in the next major release.

Prerequisites

- You have the username and password of an account with elevated privileges. You can use the **stack** user account that is created to deploy the overcloud. For more information, see the [Director Installation and Usage](#) guide.
- You have a Google account with access to Google Cloud Platform. The Block Storage service uses this account to access and use Google Cloud to store backups.

A.1. CREATING THE GCS CREDENTIALS FILE

The Block Storage service (cinder) requires your Google credentials to access and use Google Cloud for backups. You can provide these credentials to the Block Storage service by creating a service account key.

Procedure

1. Log in to the Google developer console (<http://console.developers.google.com>) with your Google account.
2. Click the **Credentials** tab and select **Service account key** from the **Create credentials** drop-down menu.
3. In the **Create service account key** screen, select the service account that you want the Block Storage service to use from the **Service account** drop-down menu.
4. In the same screen, select **JSON** from the **Key type** section and click **Create**. The browser will then download the key to its default download location.
5. Open the file and note the value of the **project_id** parameter:

```

{

```

```
"type": "service_account",
"project_id": "*cloud-backup-1370*",
...
```

6. Save a copy of the GCS JSON credentials to **/home/stack/templates/Cloud-Backup.json**.

Important

Name the file **Cloud-Backup.json** and do not change the file name. This JSON file must be in the same directory location as the **cinder-backup-gcs.yaml** file that you create as part of the procedure in [Section A.2, "Creating cinder-backup-gcs.yaml"](#).

A.2. CREATING CINDER-BACKUP-GCS.YAML

Using the example file provided, create the **cinder-backup-gcs.yaml** file.



NOTE

The white space and format used in this the example (and in your file) are critical. If the white space is changed, then the file might not function as expected.

Procedure

1. Copy the text below, paste it into the new file. Do not make any modifications to the file contents.

```
heat_template_version: rocky

description: >
  Post-deployment for configuration cinder-backup to GCS

parameters:
  servers:
    type: json
  DeployIdentifier:
    type: string

resources:
  CinderBackupGcsExtraConfig:
    type: OS::Heat::SoftwareConfig
    properties:
      group: script
      config:
        str_replace:
          template: |
            #!/bin/bash
            GCS_FILE=/var/lib/config-data/puppet-generated/cinder/etc/cinder/Cloud-
            Backup.json
            HOSTNAME=$(hostname -s)
            for NODE in $(hiera -c /etc/puppet/hiera.yaml cinder_backup_short_node_names | tr
            -d '[]','); do
              if [ $NODE == $HOSTNAME ]; then
                cat <<EOF > $GCS_FILE
                GCS_JSON_DATA
                EOF
```

```

    chmod 0640 $GCS_FILE
    chown root:42407 $GCS_FILE
  fi
done
params:
  GCS_JSON_DATA: {get_file: Cloud-Backup.json}

```

```

CinderBackupGcsDeployment:
  type: OS::Heat::SoftwareDeploymentGroup
  properties:
    servers: {get_param: servers}
    config: {get_resource: CinderBackupGcsExtraConfig}
    actions: ['CREATE','UPDATE']
  input_values:
    deploy_identifier: {get_param: DeployIdentifier}

```

2. Save the file as **/home/stack/templates/cinder-backup-gcs.yaml**.

A.3. CREATING THE ENVIRONMENT FILE WITH YOUR GOOGLE CLOUD SETTINGS

Create the environment file to contain the settings that you want to apply to the Block Storage service (cinder). In this case, the environment file configures the Block Storage service to store volume backups to Google Cloud. For more information about environment files, see the [Director Installation and Usage](#) guide.

Use the following example environment file and update the **backup_gcs_project_id** with the project ID that is listed in the **Cloud-Backup.json** file. You can also change the **backup_gcs_bucket_location** location from US to location that is closer to your location.

For a list of configuration options for the Google Cloud Backup Storage backup back end, see [Table A.1, "Google Cloud Storage backup back end configuration options"](#).

Procedure

1. Copy the environment file example below. Retain the white space usage.
2. Paste the content into a new file: **/home/stack/templates/cinder-backup-settings.yaml**.
3. Change the value for **backup_gcs_project_id** from **cloud-backup-1370** to the project ID listed in the **Cloud-Backup.json** file.
4. Save the file.

Environment file example

Define each setting in the environment file. Use [Table A.1, "Google Cloud Storage backup back end configuration options"](#) to select the available configuration options.

```

resource_registry:
  OS::TripleO::Services::CinderBackup: /usr/share/openstack-tripleo-heat-
  templates/deployment/cinder/cinder-backup-pacemaker-puppet.yaml
  # For non-pcmk managed implementation
  # OS::TripleO::Services::CinderBackup: /usr/share/openstack-tripleo-heat-
  templates/deployment/cinder/cinder-backup-container-puppet.yaml

```

```
OS::TripleO::NodeExtraConfigPost: /home/stack/templates/cinder-backup-gcs.yaml
```

```
parameter_defaults:
```

```
  CinderBackupBackend: swift
```

```
  ExtraConfig:
```

```
    cinder::backup::swift::backup_driver: cinder.backup.drivers.gcs.GoogleBackupDriver
```

```
    cinder::config::cinder_config:
```

```
      DEFAULT/backup_gcs_credential_file:
```

```
        value: /etc/cinder/Cloud-Backup.json
```

```
      DEFAULT/backup_gcs_project_id:
```

```
        value: cloud-backup-1370
```

```
      DEFAULT/backup_gcs_bucket:
```

```
        value: cinder-backup-gcs
```

```
      DEFAULT/backup_gcs_bucket_location:
```

```
        value: us
```

Table A.1. Google Cloud Storage backup back end configuration options

<i>PARAM</i>	Default	<i>CONFIG</i> Description
backup_gcs_project_id		Required. The project ID of the service account that you are using and that is included in the project_id of the service account key from Section A.1, "Creating the GCS credentials file" .
backup_gcs_credential_file		The absolute path to the service account key file that you created in Section A.1, "Creating the GCS credentials file" .
backup_gcs_bucket		The GCS bucket, or object storage repository, that you want to use, which might or might not exist. If you specify a non-existent bucket, the Google Cloud Storage backup driver creates one and assigns it the name that you specify here. For more information, see Buckets and Bucket name requirements .
backup_gcs_bucket_location	us	The location of the GCS bucket. This value is used only if you specify a non-existent bucket in backup_gcs_bucket ; in which case, the Google Cloud Storage backup driver specifies this as the GCS bucket location.

<i>PARAM</i>	Default	<i>CONFIG</i> Description
backup_gcs_object_size	52428800	The size, in bytes, of GCS backup objects.
backup_gcs_block_size	32768	The size, in bytes, that changes are tracked for incremental backups. This value must be a multiple of the backup_gcs_object_size value.
backup_gcs_user_agent	gcscinder	The HTTP user-agent string for the GCS API.
backup_gcs_reader_chunk_size	2097152	GCS objects are downloaded in chunks of this size, in bytes.
backup_gcs_writer_chunk_size	2097152	GCS objects are uploaded in chunks of this size, in bytes. To upload files as a single chunk instead, use the value -1.
backup_gcs_num_retries	3	Number of retries to attempt.
backup_gcs_storage_class	NEARLINE	Storage class of the GCS bucket. This value is used only if you specify a non-existent bucket in backup_gcs_bucket ; in which case, the Google Cloud Storage backup driver specifies this as the GCS bucket storage class. For more information, see Storage Classes .
backup_gcs_retry_error_codes	429	List of GCS error codes.
backup_gcs_enable_progress_timer	True	Boolean to enable or disable the timer for sending periodic progress notifications to the Telemetry service (ceilometer) during volume backups. This is enabled by default (True).

**WARNING**

When you create new buckets, Google Cloud Storage charges based on the storage class that you choose (**backup_gcs_storage_class**). The default **NEARLINE** class is appropriate for backup services.

**WARNING**

You cannot edit the location or class of a bucket after you create it. For more information, see [Managing a bucket's storage class or location](#).


A.4. DEPLOYING THE OVERCLOUD

When you have created the environment file file in **/home/stack/templates/**, deploy the overcloud then restart the cinder-backup service:

Procedure

1. Log in as the **stack** user.
2. Deploy the configuration:

```
$ openstack overcloud deploy --templates \
-e /home/stack/templates/cinder-backup-settings.yaml
```

**IMPORTANT**

If you passed any extra environment files when you created the overcloud, pass them again here using the **-e** option to avoid making undesired changes to the overcloud.

3. Restart the **cinder-backup** service after the deployment finishes.

For more information, see the [Including Environment Files in Overcloud Creation](#) in the *Director Installation and Usage Guide* and the [Environment Files](#) section of the *Advanced Overcloud Customization Guide*.

APPENDIX B. ADVANCED BLOCK STORAGE CONFIGURATION

Before director-deployed installations, the **cinder.conf** file configured the Block Storage service and the backup service. When a value from **cinder.conf** does not have an orchestration (heat) template equivalent, you can use a custom environment file to pass values to the director. Add the values to an **ExtraConfig** section in the **parameter_defaults** section of a custom environment file, for example, the **cinder-backup-settings.yaml** file.

B.1. ADVANCED CONFIGURATION OPTIONS

With **ExtraConfig**, you can add additional hiera configuration to the cluster on all nodes. These settings are included on a dedicated backup node. However, if you used **ControllerExtraConfig** instead of **ExtraConfig**, your settings are installed on Controller nodes and not on a dedicated backup node.

You can substitute **DEFAULT/[cinder.conf setting]** for the setting from the **DEFAULT** section of the **cinder.conf** file. The following example shows how the **ExtraConfig** entries appear in a YAML file:

```
parameter_defaults:
  ExtraConfig:
    cinder::config::cinder_config:
      DEFAULT/backup_compression_algorithm:
        value: None
```

Table B.1 lists backup-related sample options.

Table B.1. Block Storage backup service configuration options

Option	Type	Default value	Description
backup_service_inithost_offload	Optional	True	Offload pending backup delete during backup service startup. If false, the backup service remains down until all pending backups are deleted.
use_multipath_for_image_xfer	Optional	False	Attach volumes using multipath, if available, during backup and restore procedures. This affects all cinder attach operations, such as create volume from image, generic cold migrations, and other operations.
num_volume_device_scan_tries	Optional	3	The maximum number of times to rescan targets to find volumes during attach.

Option	Type	Default value	Description
backup_workers	Optional	1	Number of backup processes to run. Running multiple concurrent backups or restores with compression results in significant performance gains.
backup_native_threads_pool_size	Optional	60	Size of the native threads pool for the backups. Most backup drivers rely heavily on this. You can decrease the value for specific drivers that do not rely on this option.
backup_share	Required		Set to <code>HOST:_EXPORT_PATH_</code> .
backup_container	Optional	None	(String) Custom directory to use for backups.
backup_enable_progress_timer	Optional	True	Enable (true) or disable (false) the timer to send the periodic progress notifications to the Telemetry service (ceilometer) when backing up the volume to the backend storage.
backup_mount_options	Optional		Comma-separated list of options that you can specify when you mount the NFS export that is specified in <code>backup_share</code> .
backup_mount_point_base	Optional	<code>\$state_path/backup_mount</code>	(String) Base directory that contains mount point for NFS share.

Option	Type	Default value	Description
backup_compression_algorithm	Optional	zlib	The compression algorithm that you want to use when you send backup data to the repository. Valid values are zlib , bz2 , and None .
backup_file_size	Optional	1999994880	Data from cinder volumes that are larger than this value are stored as multiple files in the backup repository. This option must be a multiple of backup_sha_block_size_bytes.
backup_sha_block_size_bytes	Optional	32768	Size of cinder volume blocks for digital signature calculation