



Red Hat Fuse 7.8

Connecting Fuse Online to Applications and Services

Instructions for using provided connectors

Red Hat Fuse 7.8 Connecting Fuse Online to Applications and Services

Instructions for using provided connectors

Legal Notice

Copyright © 2023 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

Follow step-by-step instructions for creating connections and adding them to integrations.

Table of Contents

PREFACE	6
CHAPTER 1. CONNECTORS THAT ARE SUPPORTED BY FUSE ONLINE	7
CHAPTER 2. CONNECTING TO AMAZON WEB SERVICES	10
2.1. OBTAINING AWS CREDENTIALS FOR CREATING CONNECTIONS TO AMAZON SERVICES	10
2.2. CONNECTING TO AMAZON DYNAMODB	11
2.2.1. Creating Amazon DynamoDB connections	11
2.2.2. Obtaining data from an Amazon DynamoDB table	12
2.2.3. Adding data to an Amazon DynamoDB table	13
2.2.4. Removing data from an Amazon DynamoDB table	14
2.3. CONNECTING TO AMAZON SIMPLE NOTIFICATION SERVICE (SNS)	15
2.3.1. Creating Amazon SNS connections	15
2.3.2. Sending messages to Amazon SNS	16
2.4. CONNECTING TO AMAZON SIMPLE QUEUE SERVICE (SQS)	17
2.4.1. Creating Amazon SQS connections	17
2.4.2. Obtaining messages from Amazon SQS to trigger integration execution	18
2.4.3. Sending messages to an Amazon SQS queue	19
2.5. CONNECTING TO AMAZON SIMPLE STORAGE SERVICE (S3)	20
2.5.1. Creating Amazon S3 connections	21
2.5.2. Obtaining data from Amazon S3 to trigger integration execution	22
2.5.3. Adding data to Amazon S3 to finish an integration	23
2.5.4. Adding data to Amazon S3 in the middle of an integration	24
CHAPTER 3. CONNECTING TO AMQ	27
3.1. CREATING AN AMQ CONNECTION	27
3.2. ADDING AN AMQ CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES	28
3.3. PUBLISHING AMQ MESSAGES TO FINISH AN INTEGRATION	30
3.4. PUBLISHING AMQ MESSAGES IN THE MIDDLE OF AN INTEGRATION	31
CHAPTER 4. CONNECTING TO AMQP	34
4.1. CREATING AN AMQP CONNECTION	34
4.2. ADDING AN AMQP CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES	35
4.3. PUBLISHING MESSAGES TO AMQP IN THE MIDDLE OF A FLOW OR TO FINISH AN INTEGRATION	37
CHAPTER 5. CONNECTING TO API CLIENTS	40
5.1. REGISTERING FUSE ONLINE AS A REST API CLIENT	40
5.2. CREATING A REST API CLIENT CONNECTION	41
5.3. CREATING A SOAP API CLIENT CONNECTION	42
5.4. ADDING AN API CLIENT CONNECTION TO AN INTEGRATION	43
CHAPTER 6. CONNECTING TO BOX	44
6.1. REGISTERING FUSE ONLINE AS A BOX CLIENT	44
6.2. CREATING A BOX CONNECTION	45
6.3. DOWNLOADING OR UPLOADING A BOX FILE IN THE MIDDLE OF AN INTEGRATION	46
6.4. UPLOADING FILES TO BOX TO FINISH AN INTEGRATION	47
CHAPTER 7. CONNECTING TO DROPBOX	49
7.1. REGISTERING FUSE ONLINE AS A DROPBOX CLIENT	49
7.2. CREATING A DROPBOX CONNECTION	50
7.3. OBTAINING FILES FROM DROPBOX TO TRIGGER INTEGRATION EXECUTION	51

7.4. ADDING FILES TO DROPBOX TO FINISH AN INTEGRATION	52
7.5. ACCESSING DROPBOX IN THE MIDDLE OF AN INTEGRATION	53
CHAPTER 8. CONNECTING TO EMAIL SERVERS (IMAP, POP3, SMTP)	56
8.1. CREATING A CONNECTION TO AN IMAP OR POP3 EMAIL SERVER	56
8.2. CREATING A CONNECTION TO AN SMTP EMAIL SERVER	57
8.3. OBTAINING EMAIL TO TRIGGER INTEGRATION EXECUTION	58
8.4. SENDING EMAIL FROM AN INTEGRATION	60
CHAPTER 9. CONNECTING TO FHIR	62
9.1. CREATING A CONNECTION TO A FHIR SERVER	62
9.2. OBTAINING A RESOURCE FROM A FHIR SERVER	63
9.3. QUERYING A FHIR SERVER FOR RESOURCES	64
9.4. CREATING A RESOURCE ON A FHIR SERVER	65
9.5. UPDATING ALL FIELDS IN A RESOURCE ON A FHIR SERVER	66
9.6. UPDATING SPECIFIED FIELDS IN A RESOURCE ON A FHIR SERVER	67
9.7. CREATING RESOURCES OF DIFFERENT TYPES ON A FHIR SERVER	69
9.8. DELETING A RESOURCE FROM A FHIR SERVER	69
CHAPTER 10. CONNECTING TO AN FTP OR SFTP SERVER	71
10.1. CREATING AN FTP OR SFTP CONNECTION	71
10.2. OBTAINING FILES FROM AN FTP OR SFTP SERVER	72
10.3. UPLOADING FILES TO AN FTP OR SFTP SERVER	74
CHAPTER 11. CONNECTING TO GOOGLE APPLICATIONS	76
11.1. REGISTERING FUSE ONLINE AS A GOOGLE CLIENT APPLICATION	76
11.2. CONNECTING TO GMAIL	78
11.2.1. Creating a Gmail connection	79
11.2.2. Alternatives for populating email to send	80
11.2.3. Triggering an integration when polling returns a Gmail message	81
11.2.4. Sending an email from a Gmail account	82
11.3. CONNECTING TO GOOGLE CALENDAR	83
11.3.1. Creating a Google Calendar connection	83
11.3.2. Triggering an integration when polling returns an event from a Google Calendar	84
11.3.3. Obtaining a particular event from a Google Calendar	85
11.3.4. Adding an event to a Google Calendar	86
11.3.5. Updating an event in a Google Calendar	87
11.4. CONNECTING TO GOOGLE SHEETS	88
11.4.1. Creating a Google Sheets connection	89
11.4.2. Obtaining spreadsheet data to trigger an integration or in the middle of a flow	89
11.4.3. Triggering an integration when polling returns spreadsheet properties	92
11.4.4. Creating a spreadsheet	93
11.4.5. Updating data in a sheet	94
11.4.6. Appending data to a sheet	95
11.4.7. Updating spreadsheet properties	97
11.4.8. Adding a chart to a sheet	98
11.4.9. Adding a pivot table to a sheet	101
CHAPTER 12. CONNECTING TO HTTP AND HTTPS ENDPOINTS	105
12.1. CREATING A CONNECTION TO AN HTTP OR HTTPS ENDPOINT	105
12.2. ADDING AN HTTP OR HTTPS CONNECTION TO AN INTEGRATION	105
CHAPTER 13. CONNECTING TO IRC	108
13.1. CREATING AN IRC CONNECTION	108
13.2. ADDING AN IRC CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES	

	109
13.3. ADDING AN IRC CONNECTION TO SEND A MESSAGE	110
CHAPTER 14. CONNECTING TO JIRA	112
14.1. REGISTERING FUSE ONLINE WITH A JIRA SERVER THAT USES OAUTH	112
14.2. CREATING A JIRA CONNECTION	116
14.3. OBTAINING JIRA ISSUES OR COMMENTS TO TRIGGER INTEGRATION EXECUTION	117
14.4. ADDING AN ISSUE TO A JIRA SERVER	118
14.5. ADDING A COMMENT TO A JIRA ISSUE	119
14.6. ATTACHING A FILE TO A JIRA ISSUE	120
14.7. ADDING AND REMOVING JIRA ISSUE WATCHERS	120
14.8. UPDATING AN ISSUE ON A JIRA SERVER	121
14.9. TRANSITIONING A JIRA ISSUE TO A NEW STATUS	122
CHAPTER 15. CONNECTING TO KAFKA	124
15.1. CREATING A CONNECTION TO A KAFKA BROKER	124
15.2. OBTAINING DATA FROM A KAFKA BROKER TO TRIGGER INTEGRATION EXECUTION	125
15.3. PUBLISHING DATA TO A KAFKA BROKER	126
CHAPTER 16. CONNECTING TO APACHE KUDU	128
16.1. CREATING A CONNECTION TO AN APACHE KUDU DATA STORE	128
16.2. TRIGGERING AN INTEGRATION WHEN SCANNING RETURNS RECORDS FROM A KUDU TABLE	128
16.3. INSERTING RECORDS INTO A KUDU TABLE	129
CHAPTER 17. CONNECTING TO MONGODB	131
17.1. CREATING A CONNECTION TO A MONGODB DATABASE	131
17.2. TRIGGERING AN INTEGRATION WHEN A MONGODB COLLECTION IS UPDATED	132
17.3. OPERATING ON DOCUMENTS IN A MONGODB COLLECTION	134
CHAPTER 18. CONNECTING TO MQTT	139
18.1. CREATING A CONNECTION TO AN MQTT BROKER	139
18.2. OBTAINING A MESSAGE FROM AN MQTT BROKER TO TRIGGER INTEGRATION EXECUTION	140
18.3. PUBLISHING A MESSAGE TO AN MQTT BROKER	141
CHAPTER 19. CONNECTING TO ODATA	143
19.1. CREATING A CONNECTION TO AN ODATA SERVICE	143
19.2. TRIGGERING AN INTEGRATION WHEN POLLING RETURNS DATA FROM AN ODATA SERVICE	144
19.3. UPDATING, CREATING, AND DELETING DATA THAT IS MANAGED BY AN ODATA SERVICE	146
CHAPTER 20. CONNECTING TO SALESFORCE	148
20.1. REGISTERING FUSE ONLINE AS A SALESFORCE CLIENT APPLICATION	148
20.2. CREATING A SALESFORCE CONNECTION	149
20.3. ADDING A SALESFORCE CONNECTION TO AN INTEGRATION	150
CHAPTER 21. CONNECTING TO SAP CONCUR	152
21.1. USER ROLES FOR CONNECTING TO SAP CONCUR	152
21.2. HOW TO OBTAIN SAP CONCUR IMPLEMENTATION SITE OAUTH CREDENTIALS	152
21.3. HOW TO OBTAIN SAP CONCUR PRODUCTION SITE OAUTH CREDENTIALS	153
21.4. CONFIGURING THE SAP CONCUR CONNECTOR	153
21.5. CREATING A SAP CONCUR CONNECTION	154
21.6. ADDING A SAP CONCUR CONNECTION TO AN INTEGRATION	155
21.7. EXAMPLE OF MAPPING INTEGRATION DATA FIELDS TO SAP CONCUR FIELDS	155
CHAPTER 22. CONNECTING TO SERVICENOW	157
22.1. CREATING A SERVICENOW CONNECTION	157
22.2. OBTAINING RECORDS FROM SERVICENOW TO TRIGGER INTEGRATION EXECUTION	158

22.3. CREATING AN IMPORT SET IN SERVICENOW	159
22.4. COPYING RECORDS TO SERVICENOW DURING OR TO FINISH AN INTEGRATION	160
22.5. EXAMPLE SALESFORCE TO SERVICENOW INTEGRATIONS	161
CHAPTER 23. CONNECTING TO SLACK	163
23.1. CREATING A SLACK CONNECTION	163
23.2. ADDING A SLACK CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES	164
23.3. ADDING A SLACK CONNECTION TO SEND A MESSAGE TO A SLACK CHANNEL OR USER	165
CHAPTER 24. CONNECTING TO SQL DATABASES	166
24.1. CREATING A DATABASE CONNECTION	166
24.2. HOW TO SPECIFY THE SCHEMA IN A DATABASE CONNECTION	167
24.3. OBTAINING DATABASE RECORDS TO TRIGGER INTEGRATION EXECUTION	168
24.4. ABOUT PARAMETER PLACEHOLDERS AND VALUES IN SQL STATEMENTS THAT UPDATE DATA	169
24.5. ACCESSING A DATABASE IN THE MIDDLE OR TO COMPLETE AN INTEGRATION	170
24.6. CONNECTING TO PROPRIETARY DATABASES	172
CHAPTER 25. CONNECTING TO TELEGRAM	173
25.1. CREATING A TELEGRAM CONNECTION	173
25.2. ADDING A TELEGRAM CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES	174
25.3. ADDING A TELEGRAM CONNECTION TO SEND A MESSAGE TO A TELEGRAM CHAT	174
CHAPTER 26. CONNECTING TO TWITTER	176
26.1. REGISTERING FUSE ONLINE AS A TWITTER CLIENT APPLICATION	176
26.2. CREATING A TWITTER CONNECTION	177
26.3. ADDING A TWITTER CONNECTION TO TRIGGER INTEGRATION EXECUTION	178
26.4. ADDING A TWITTER CONNECTION THAT SENDS A DIRECT MESSAGE	180

PREFACE

To integrate applications, you create a connection to each application or service that you want to integrate. You then create an integration and add a connection to it for each integration or service that you want to integrate.

Fuse Online [supports numerous connectors](#) that serve as templates for creating connections. The following topics provide details for creating connections and adding them to integrations:

- [Chapter 2, Connecting to Amazon Web Services](#)
- [Chapter 3, Connecting to AMQ](#)
- [Chapter 4, Connecting to AMQP](#)
- [Chapter 5, Connecting to API clients](#)
- [Chapter 6, Connecting to Box](#)
- [Chapter 7, Connecting to Dropbox](#)
- [Chapter 8, Connecting to Email Servers \(IMAP, POP3, SMTP\)](#)
- [Chapter 9, Connecting to FHIR](#)
- [Chapter 10, Connecting to an FTP or SFTP server](#)
- [Chapter 11, Connecting to Google applications](#)
- [Chapter 12, Connecting to HTTP and HTTPS endpoints](#)
- [Chapter 13, Connecting to IRC](#)
- [Chapter 14, Connecting to Jira](#)
- [Chapter 15, Connecting to Kafka](#)
- [Chapter 16, Connecting to Apache Kudu](#)
- [Chapter 17, Connecting to MongoDB](#)
- [Chapter 18, Connecting to MQTT](#)
- [Chapter 19, Connecting to OData](#)
- [Chapter 20, Connecting to Salesforce](#)
- [Chapter 21, Connecting to SAP Concur](#)
- [Chapter 22, Connecting to ServiceNow](#)
- [Chapter 23, Connecting to Slack](#)
- [Chapter 24, Connecting to SQL databases](#)
- [Chapter 25, Connecting to Telegram](#)
- [Chapter 26, Connecting to Twitter](#)

CHAPTER 1. CONNECTORS THAT ARE SUPPORTED BY FUSE ONLINE

Fuse Online supports the following connectors.

Name	Description
Amazon DynamoDB	Obtain, add, update, or delete data in an Amazon DynamoDB table.
Amazon Simple Notification Service (SNS)	Send messages to an Amazon SNS topic.
Amazon Simple Queue Service (SQS)	Retrieve messages from or send messages to an Amazon SQS queue.
Amazon Simple Storage Service (S3)	Retrieve data from an Amazon S3 bucket or copy data into a bucket.
AMQ	Obtain messages from a Red Hat AMQ (Apache ActiveMQ) broker or publish messages to a Red Hat AMQ (Apache ActiveMQ) broker.
AMQP	Obtain messages from an Advanced Message Queue Protocol broker or publish messages to an AMQP broker.
Box	Download files from Box or upload files to Box.
Dropbox	Download files from Dropbox or upload files to Dropbox.
Email Servers	Retrieve email from an IMAP or POP3 email server or connect to an SMTP email server to send email.
FHIR	Obtain resources from a FHIR server or update resources on a FHIR server.
FTP/SFTP	Download files from an FTP or SFTP server or upload files to an FTP or SFTP server.
Gmail	Obtain messages sent to a particular Gmail account and send messages from a particular Gmail account.
Google Calendar	Obtain events from a Google Calendar that you specify or add/update events in a Google Calendar that you specify.
Google Sheets	Obtain data from a Google Sheets spreadsheet that you specify, add/update spreadsheet data, create charts, or create pivot tables in a spreadsheet that you specify.
HTTP/HTTPS	Connect to an HTTP or HTTPS endpoint and execute the GET, PUT, POST, DELETE, HEAD, OPTIONS, TRACE, OR PATCH method.

Name	Description
IRC	Receive messages that are sent to an IRC nickname or channel, or send messages to an IRC nickname on a particular channel.
Jira	Obtain, create, or update issues on a Jira server.
Kudu	Obtain records from a table in an Apache Kudu data store or add records to a table in a Kudu data store.
MongoDB	Obtain data from a MongoDB database or update data in a MongoDB database.
MQTT	Obtain messages from an MQ Telemetry Transport broker or publish messages to an MQTT broker.
OData	Obtain entities from an OData service or update, create, or delete entities that are managed by an OData service.
REST APIs	<p>Create a custom REST API client connector by uploading an OpenAPI document. You can then create a connection to that REST API.</p> <p>Create a REST API provider integration by uploading an OpenAPI document that defines operations that trigger integration execution. See Creating an integration that is triggered by a REST API call in Integrating Applications with Fuse Online.</p>
Salesforce	Create, update, fetch, or delete a Salesforce record.
SAP Concur	Perform any one of a large variety of SAP Concur actions.
ServiceNow	Obtain records from or copy records to your ServiceNow instance.
Slack	Obtain messages from a channel or send a message to a Slack channel or user.
SOAP API clients	Create a custom SOAP API client connector by uploading a WSDL file. You can then create a connection to that SOAP API client.
SQL databases	Invoke a SQL statement or a SQL stored procedure on an Apache Derby, MySQL, or PostgreSQL database. To connect to other types of SQL databases, you upload a Fuse Online library extension that contains a JDBC driver for that database.
Telegram	Obtain messages from a chat or send messages to a chat by using a Telegram chat bot.
Twitter	Trigger execution of a simple integration upon tweets that mention you or that contain data that you specify.
Webhook	Trigger execution of simple integrations with HTTP GET or POST requests.

If Fuse Online does not provide a connector that you need, an experienced developer can create an extension that defines a custom connector. For information about coding the extension and creating its **.jar** file, which you upload to Fuse Online, see:

- [Tooling User Guide, how to use Fuse tooling to develop extensions](#)
- [Integrating Applications with Fuse Online, how to code extensions](#)

CHAPTER 2. CONNECTING TO AMAZON WEB SERVICES

A Fuse Online integration can connect to the following Amazon web services:

- DynamoDB
- Simple Notification Service (SNS)
- Simple Queue Service (SQS)
- Simple Storage Service (S3)

You must obtain AWS credentials before you can create a connection to an Amazon web service. For details, see:

- [Section 2.1, "Obtaining AWS credentials for creating connections to Amazon services"](#)
- [Section 2.2, "Connecting to Amazon DynamoDB"](#)
- [Section 2.3, "Connecting to Amazon Simple Notification Service \(SNS\)"](#)
- [Section 2.4, "Connecting to Amazon Simple Queue Service \(SQS\)"](#)
- [Section 2.5, "Connecting to Amazon Simple Storage Service \(S3\)"](#)

2.1. OBTAINING AWS CREDENTIALS FOR CREATING CONNECTIONS TO AMAZON SERVICES

To create a connection to an Amazon service, you must have an access key that is associated with an AWS account. This is the AWS account that created, or will create, the resource that you want the Fuse Online connection to access. The resource can be an S3 bucket, an SNS topic, or an SQS queue.

An AWS access key has two parts:

- Amazon access key ID
- Amazon secret access key

AWS uses access keys to authenticate requests from a Fuse Online connection. There is plenty of AWS documentation about creating and managing access keys. If you already created an AWS Identity and Access Management (IAM) user and captured the access key associated with that user, you can specify those values to create a Fuse Online connection to S3, SNS, or SQS.

If you need to obtain an access key, the procedure below is one way to do it.

Prerequisites

- Login credentials for the AWS account that created the resource that you want a connection to access.
- Or, login credentials for the AWS account that you want the connection to use to create a new resource.

Procedure

1. Go to <https://aws.amazon.com/> and sign in to the console.

2. In the console, in the upper right, click the down arrow next to the user name and click **My Security Credentials**.
3. In the popup dialog, click **Get Started with IAM Users**
If a popup with this button does not appear, then on the left, click **Users**.
4. Add a user:
 - a. Click **Add User**
 - b. Enter a user name and select **Programmatic Access**.
 - c. Click **Next: Permissions**.
 - d. Respond to the prompts for adding the new user to a group.
 - e. Click **Next: Tags**.
 - f. Skip adding tags and click **Next: Review**.
 - g. Click **Create User**.
5. Click **Download .csv** to obtain a local copy of the access key. The downloaded file contains the access key ID and the secret access key, which you must specify to create a connection to an Amazon service.
6. Click **Close**.

Additional resources

- [Managing Access Keys for IAM Users](#)
- [IAM Best Practices](#)

2.2. CONNECTING TO AMAZON DYNAMODB

An integration can retrieve data from an Amazon DynamoDB table, add data to a DynamoDB table, or remove data from a DynamoDB table. To do this, create an Amazon DynamoDB connection and then add that connection to an integration flow.

For details, see:

- [Section 2.2.1, "Creating Amazon DynamoDB connections"](#)
- [Section 2.2.2, "Obtaining data from an Amazon DynamoDB table"](#)
- [Section 2.2.3, "Adding data to an Amazon DynamoDB table"](#)
- [Section 2.2.4, "Removing data from an Amazon DynamoDB table"](#)

2.2.1. Creating Amazon DynamoDB connections

You must create an Amazon DynamoDB connection before you can connect to Amazon DynamoDB in an integration.

Prerequisites

- You must have an AWS access key. See [Obtaining AWS credentials for creating connections to Amazon services](#).
- You must know which AWS region contains the DynamoDB table that you want the connection to access.
- You must know the name of the DynamoDB table that you want the connection to access. This table must exist when an integration connects to DynamoDB.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **Amazon DynamoDB** connector.
4. In the **Access Key** field, enter an Amazon access key ID that is part of a user access key in the AWS account that manages the DynamoDB table that you want the connection to access.
5. In the **Secret Key** field, enter the Amazon secret access key for the Amazon access key ID that you specified.
6. In the **Region** field, select the AWS region in which the DynamoDB table resides.
7. In the **Table Name** field, enter the name of the DynamoDB table that you want this connection to access.
8. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether or not validation is successful. If validation fails, revise the configuration details as needed and try again.
9. When validation is successful, click **Next**.
10. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **DynamoDB West**.
11. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample DynamoDB connection that accesses sales data in the western region**.
12. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **DynamoDB West** appears as a connection that you can choose to add to an integration.

Results

When Fuse Online is prompting you to add to an integration, it displays the DynamoDB connection that you just created. This connection always and only accesses the DynamoDB table that you specified when you created the connection.

2.2.2. Obtaining data from an Amazon DynamoDB table

In an integration flow, to obtain an item from an Amazon DynamoDB table, add an Amazon DynamoDB connection to the middle of the flow.

A DynamoDB connection cannot start a simple integration. If you want to periodically obtain data from a DynamoDB table, start a simple integration with a timer followed by a DynamoDB connection that queries a table.

Prerequisites

- You created an Amazon DynamoDB connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration.

Procedure

1. In the flow visualization, click the plus sign where you want to add an Amazon DynamoDB connection.
2. On the **Choose a connection** page, click the Amazon DynamoDB connection that is configured to access that table that you want to obtain data from.
3. On the **Choose an action** page, select the **Query** action.
4. In the **Filter** field, specify JSON notation that identifies the key attribute(s) for the item that the connection should return. You can specify input parameters with **:#**. For example, to obtain an item that has two key attributes, the specification might be something like this:

```
 {"key1":":#PARAM1", "key2":":#PARAM2"}
```

5. Optional. In the **Attributes to query** field, enter a comma-separated list of the attribute names that contain the data that you want the connection to return. For example:

```
 key1,key2,attribute3,attribute4,attribute5
```

If you do not specify attributes, the query returns the key attribute(s).

6. Click **Next**.

Result

The integration now has a DynamoDB connection that obtains data. At runtime, the connection returns a JSON instance document that contains the result of the query.

Next step

If you specified placeholder parameters in the **Filter** field, add a data mapper step before this connection. In the data mapper step, map source fields to the target placeholder fields in the DynamoDB connection.

2.2.3. Adding data to an Amazon DynamoDB table

In the middle of a flow, or to finish a simple integration, a DynamoDB connection can add an item to a DynamoDB table. To do this, add a DynamoDB connection to the middle of a flow or as a simple integration's finish connection.



NOTE

In this release, a DynamoDB connection cannot update an item in a DynamoDB table. This is expected to change in a future release.

Prerequisites

- You created an Amazon DynamoDB connection.
- You are creating or editing a simple integration and Fuse Online is prompting you to add to the integration or to choose the finish connection.

Procedure

1. On the **Choose a connection** page, click the Amazon DynamoDB connection that is configured to access the table that you want to add to.
2. On the **Choose an action** page, select **Put Item**.
3. In the **JSON definition of the element** field, enter JSON notation that defines the table item to be added. You must specify the item's key attribute(s). Input parameter placeholders prefixed with **:#** are allowed. Be sure to specify all attributes/values that you want to store. In the following example, **userID** is the key:

```

{"userID":"aslan","attr1":"some-value","attr2":"another-value"}

```

4. Click **Next**.

Result

The connection appears in the integration visualization at the location you added it. During execution, the connection adds the defined JSON item to the DynamoDB table that the connection is configured to access.

Next step

If you specified placeholder parameters in the JSON definition of the item, add a data mapper step before this connection. In the data mapper step, map source fields to the target placeholder fields in the DynamoDB connection.

2.2.4. Removing data from an Amazon DynamoDB table

In the middle of a flow, or to finish a simple integration, a DynamoDB connection can remove an item from a DynamoDB table. To do this, add a DynamoDB connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created an Amazon DynamoDB connection.
- You are creating or editing a simple integration and Fuse Online is prompting you to add to the integration or to choose the finish connection.

Procedure

1. On the **Choose a connection** page, click the Amazon DynamoDB connection that is configured to access the table that contains the item that you want to remove.
2. On the **Choose an action** page, select **Remove Item**.

3. In the **JSON filter of the element** field, enter JSON notation that identifies the item that you want to remove. You must specify the item's key attribute(s). Input parameters prefixed with **:#** are allowed. In the following example input, **userID** is a key attribute:

```
 {"userID": "aslan" }
```

4. Click **Next**.

Result

The connection appears in the flow visualization where you added it.

Next step

If you specified placeholder parameters in the **JSON filter of the element** field, add a data mapper step before this connection. In the data mapper step, map a source field to each target placeholder field in the DynamoDB connection.

2.3. CONNECTING TO AMAZON SIMPLE NOTIFICATION SERVICE (SNS)

An integration can send a message to an AWS Simple Notification Service topic. To do this, create an AWS SNS connection and then add that connection to an integration flow or as the finish connection for a simple integration. For details, see:

- [Section 2.3.1, "Creating Amazon SNS connections"](#)
- [Section 2.3.2, "Sending messages to Amazon SNS"](#)

2.3.1. Creating Amazon SNS connections

You must create an Amazon SNS connection before you can add an Amazon SNS connection to an integration.

Prerequisites

- AWS access key. See [Obtaining AWS credentials](#).
- You must know the region in which the SNS topic is located. This is the topic that you want the SNS connection that you are creating to send a message to.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **Amazon SNS** connector.
4. In the **Access Key** field, enter an Amazon access key ID that is part of a user access key in the AWS account that manages the topic that you want the connection to send a message to. If the topic that you want the connection to access does not already exist then when Fuse Online tries to start running the integration, it uses the AWS account associated with this access key to create the topic. However, if the topic already exists in some other AWS account, then the connection cannot create the topic and the integration cannot start.

5. In the **Secret Key** field, enter the Amazon secret access key for the Amazon access key ID that you specified.
6. In the **Region** field, select the AWS region in which the topic resides. If the connection creates the topic, then it creates it in the selected region.
7. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether or not validation is successful. If validation fails, revise the configuration details as needed and try again.
8. When validation is successful, click **Next**.
9. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **SNS North**.
10. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample SNS connection that sends messages to our north region topic**.
11. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **SNS North** appears as a connection that you can choose to add to an integration.

2.3.2. Sending messages to Amazon SNS

To send a message to an Amazon SNS topic, add an Amazon SNS connection to the middle of a flow or as the finish connection in a simple integration.

Prerequisites

- You created an Amazon SNS connection.
- Fuse Online is prompting you to add to the integration, or to add the finish connection to a simple integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the Amazon SNS connection that you want to use to send a message.
3. Click the **Send Object** action.
4. In the **Topic Name or Amazon Resource Name** field, enter the name of the SNS topic to send a message to or enter the topic's Amazon Resource Name (ARN).
If the SNS topic does not already exist in either the AWS account that the connection is authorized to access, or in any other AWS account, the connection creates the topic in the AWS account that the connection is configured to access.
5. Click **Next** to add the connection to the integration.

Result

The connection appears in the integration flow where you added it.

2.4. CONNECTING TO AMAZON SIMPLE QUEUE SERVICE (SQS)

An integration can retrieve messages from an Amazon SQS queue or send messages to an Amazon SQS queue. To do this, create an Amazon SQS connection and then add that connection to an integration flow. For details, see:

- [Section 2.4.1, “Creating Amazon SQS connections”](#)
- [Section 2.4.2, “Obtaining messages from Amazon SQS to trigger integration execution”](#)
- [Section 2.4.3, “Sending messages to an Amazon SQS queue”](#)

2.4.1. Creating Amazon SQS connections

You must create an Amazon SQS connection before you can add an Amazon SQS connection to an integration.

Prerequisites

- AWS access key. See [Obtaining AWS credentials](#).
- You must know the region in which the SQS queue is located. This is the queue that you want the SQS connection that you are creating to send messages to or retrieve messages from.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **Amazon SQS** connector.
4. In the **Access Key** field, enter an Amazon access key ID that is part of a user access key in the AWS account that manages the queue that you want the connection to access.
If the queue that you want the connection to access does not already exist then when Fuse Online tries to start running the integration, it uses the AWS account associated with this access key to create the queue. However, if the queue already exists in some other AWS account, then the connection cannot create the queue and the integration cannot start.
5. In the **Secret Key** field, enter the Amazon secret access key for the Amazon access key ID that you specified.
6. In the **Region** field, select the AWS region in which the queue resides. If the connection creates the queue, then it creates it in the selected region.
7. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether or not validation is successful. If validation fails, revise the configuration details as needed and try again.
8. When validation is successful, click **Next**.
9. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **SQS South**.

10. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample SQS connection that sends messages to our southern region queue**.
11. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **SQS South** appears as a connection that you can choose to add to an integration.

2.4.2. Obtaining messages from Amazon SQS to trigger integration execution

To start an integration by obtaining messages from an Amazon SQS queue, add an Amazon SQS connection as a simple integration's start connection.

Prerequisites

- You created an Amazon SQS connection that is configured to access the queue that you want to obtain messages from.
- You know the name of the SQS queue that you want the connection to obtain messages from.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Amazon SQS connection that you want to use to start the integration.
4. On the **Choose an action** page, select **Poll an Amazon SQS Queue** to periodically retrieve messages from an SQS queue.
5. Configure this action:
 - a. In the **Delay** field, accept the default of 500 milliseconds as the time that elapses between polls. Or, to specify a different polling interval, enter a number and select its time unit.
 - b. In the **Maximum Objects to Retrieve** field, enter the largest number of messages that one poll operation can obtain. The default is 10.
To have no limit on the number of messages that can be obtained, specify **0** or a negative integer. When **Maximum Objects to Retrieve** is unlimited, the poll action obtains all messages in the SQS queue.
 - c. In the **Queue Name or Amazon Resource Name** field, specify the name of the SQS queue to retrieve messages from, or the queue's ARN. If a queue with this name does not exist, the connection creates it. This is the only required field.
 - d. Indicate whether you want to **Obtain messages and then delete them from the queue**. Obtaining messages and then deleting them from the queue is the default behavior. Unselect this option only if you want the connection to retrieve messages and also leave them on the queue, which means that the messages will be retrieved again.
 - e. Indicate whether you want to **Obtain messages and delete the message if it does make it through a Camel filter**. This option is selected by default. Leave it selected when you want to pass a retrieved message through a filter to determine whether to delete it from the

queue. You do not need to unselect **Obtain messages and then delete from the queue**. Fuse Online ensures the correct behavior when you select **Obtain messages and delete the message if it does make it through a Camel filter**.

6. Click **Next**.

Result

The connection appears at the beginning of the integration flow.

Next steps

If you selected **Obtain messages and delete the message if it does make it through a Camel filter** then you need to add a filter step after this SQS connection. The filter step does not need to be immediately after the SQS connection. Add all connections to the integration, and then add the filter step. During execution, if there are messages that pass the filter, Fuse Online uses the same connection, the SQS start connection, to delete those messages from the queue.

2.4.3. Sending messages to an Amazon SQS queue

In the middle of a flow, or to finish a simple integration, you can send messages to an Amazon SQS queue.

Prerequisites

- You created an Amazon SQS connection that is configured to access the queue that you want to send messages to.
- You know the name of the SQS queue that you want the connection to send messages to.
- Fuse Online is prompting you to add to the integration, or to choose the finish connection for a simple integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the Amazon SQS connection that you want to use to send messages.
3. Select the action that you want the connection to perform:
 - **Send Object** sends one message to the queue.
 - **Send Batch Object** sends a batch of messages to the queue.
4. In the **Message group ID strategy** field, for a first-in, first-out (FIFO) queue, accept **ConstantMessageGroupIDStrategy** or click in the field and select a different strategy. The setting of this parameter has no effect on simple queues. The message group ID identifies the group that a message belongs to. Messages that belong to the same message group are always processed one by one, in a strict order relative to the message group. The message group ID strategy determines how the connection assigns a group ID to a message. The options are:
 - **ConstantMessageGroupIDStrategy** – The connection uses a constant to group messages.

- **ExchangeIdMessageGroupIdStrategy** – The connection uses the exchange ID, which is in each message, to group messages.
- **PropertyValueMessageGroupIdStrategy** – The connection uses the value of an internal property to group messages.

FIFO queues are designed to ensure that the order in which messages are sent and received is strictly preserved and that each message is processed exactly once. A FIFO queue name has **.fifo** as a suffix.

5. In the **Message deduplication ID strategy** field, for a FIFO queue, accept **NullMessageDeduplicationIdStrategy** or click in the field to select **ExchangeIdMessageDeduplicationIdStrategy**.

The setting of this parameter has no effect on simple queues. For a FIFO queue, the connection uses the selected strategy to ensure that it does not send duplicate messages to the queue.

- **NullMessageDeduplicationIdStrategy** uses the message body as the deduplication element. In other words, the connection compares message bodies to identify duplicate messages.
 - **ExchangeIdMessageDeduplicationIdStrategy** uses the message's exchange ID as the deduplication element. In other words, the connection compares exchange IDs to identify duplicate messages.
6. In the **Queue Name or Amazon Resource Name** field, enter the name of the queue to send messages to. If the queue does not exist, the connection creates it.
 7. In the **Delay** field, accept the default, which is 0 for no delay. Or, to add a delay, specify a number. The integration waits this number of seconds before sending messages. This is useful when the message consumers might not be immediately ready for the messages that the connection is sending.
 8. Click **Next**.

Result

The connection appears in the integration flow where you added it.

Additional resources

- [Using the Amazon Message Deduplication ID](#)
- [Using the Amazon SQS Message Group ID](#)

2.5. CONNECTING TO AMAZON SIMPLE STORAGE SERVICE (S3)

An integration can retrieve data from an Amazon S3 bucket or copy data into an Amazon S3 bucket. To do this, create an Amazon S3 connection and then add that connection to an integration flow. For details, see:

- [Section 2.5.1, "Creating Amazon S3 connections"](#)
- [Section 2.5.2, "Obtaining data from Amazon S3 to trigger integration execution"](#)
- [Section 2.5.3, "Adding data to Amazon S3 to finish an integration"](#)
- [Section 2.5.4, "Adding data to Amazon S3 in the middle of an integration"](#)

2.5.1. Creating Amazon S3 connections

You must create an Amazon S3 connection before you can add an Amazon S3 connection to an integration.

Prerequisites

- AWS access key. See [Obtaining AWS credentials](#).
- If the bucket that you want the connection to access already exists, you must know:
 - The region that the bucket is in.
 - The bucket's name or Amazon Resource Name (ARN).

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **Amazon S3** connector.
4. In the **Access Key** field, enter an Amazon access key ID that is part of a user access key in the AWS account that manages the bucket that you want the connection to access.
If the bucket that you want the connection to access does not already exist then when Fuse Online tries to start running the integration, it uses the AWS account associated with this access key to create the bucket. However, if the bucket already exists in some other AWS account, then the connection cannot create the bucket and the integration cannot start.
5. In the **Secret Key** field, enter the Amazon secret access key for the Amazon access key ID that you specified.
6. In the **Region** field, select the AWS region in which the bucket resides. If the connection creates the bucket, then it creates it in the selected region.
7. In the **Bucket Name or Amazon Resource Name** field, enter the name of the bucket that you want this connection to access or enter the bucket's ARN.
If the bucket you specify does not yet exist then the connection tries to create a bucket with the name that you specify. Because S3 allows a bucket to be used as a URL that can be accessed publicly, the bucket name that you specify must be globally unique. Also, it must meet [S3 bucket naming requirements](#).
8. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether or not validation is successful. If validation fails, revise the configuration details as needed and try again.
9. When validation is successful, click **Next**.
10. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Obtain S3 Data**.
11. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample S3 connection that obtains data from a northeast bucket**.

12. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Obtain S3 Data** appears as a connection that you can choose to add to an integration.

2.5.2. Obtaining data from Amazon S3 to trigger integration execution

To start an integration by obtaining data from an Amazon S3 bucket, add an Amazon S3 connection as a simple integration's start connection.

Prerequisite

You created an Amazon S3 connection.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Amazon S3 connection that you want to use to start the integration.
4. On the **Choose an action** page, select the action that you want the connection to perform:
 - **Get Object** obtains a file from the bucket that the connection accesses. In the **File Name** field, enter the name of the file that you want to obtain. If the specified file is not in the bucket, it is a runtime error.
 - **Poll an Amazon S3 Bucket** periodically obtains files from the bucket that the connection accesses. To configure this action:
 - a. In the **Delay** field, accept the default of 500 milliseconds as the time that elapses between polls. Or, to specify a different polling interval, enter a number and select its time unit.
 - b. In the **Maximum Objects to Retrieve** field, enter the largest number of files that one poll operation can obtain. The default is 10.
To have no limit on the number of files that can be obtained, specify **0** or a negative integer. When **Maximum Objects to Retrieve** is unlimited, the poll action obtains all files in the bucket.

If the bucket contains more than the specified maximum number of files then the action obtains the files that were most recently modified or created.
 - c. In the **Prefix** field, optionally specify a regular expression that evaluates to a string. If you specify a prefix then this action retrieves a file only when its name starts with that string.
 - d. Indicate whether you want to **Obtain files and then delete them from the bucket**
5. After you configure the action, click **Next** to specify the action's output type.
6. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
7. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 8. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 9. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 10. Click **Next**.

Result

The integration now has a start connection and Fuse Online is prompting you to choose the finish connection.

2.5.3. Adding data to Amazon S3 to finish an integration

To finish an integration by copying data to Amazon S3, add an Amazon S3 connection as a simple integration's finish connection.

Prerequisites

- You created an Amazon S3 connection.
- You are creating or editing a simple integration and Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Choose a connection** page, click the Amazon S3 connection that you want to use to finish the integration.
2. Select the action that you want the connection to perform:
 - **Copy Object** adds one or more objects to the bucket.
To add one file to the bucket, you can enter its name in the **File Name** field.

To add multiple files to the bucket, do not specify a file name. In this case, the action adds all objects that it obtains from the previous integration step(s).

If you used the poll action to obtain multiple files and you specify a file name then the **Copy Object** action adds only the last file that was received from the poll action.

- **Delete Object** deletes an object from the bucket. In the **File Name** field, specify the name of the object that you want to delete. If the specified file is not in the bucket, the integration continues with no error.
3. After you configure the chosen action, click **Next** to specify the action's input type.
 4. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
5. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 6. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name. You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 7. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 8. Click **Next**.

Result

The connection appears at the end of the integration visualization.

2.5.4. Adding data to Amazon S3 in the middle of an integration

In the middle of an integration, to add data to Amazon S3, add an Amazon S3 connection to the middle of a flow.

Prerequisite

- You created an Amazon S3 connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration.

Procedure

1. In the flow visualization, click the plus sign where you want to add an Amazon S3 connection.
2. Click the Amazon S3 connection that you want to use in the middle of a flow.
3. Select the action that you want the connection to perform:
 - **Copy Object** adds one or more objects to the bucket.
To add one file to the bucket, you can enter its name in the **File Name** field.

To add multiple files to the bucket, do not specify a file name. In this case, the action adds all objects that it obtains from the previous integration step(s).

If you used the poll action to obtain multiple files and you specify a file name then the **Copy Object** action adds only the last file that was received from the poll action.
 - **Delete Object** deletes an object from the bucket. In the **File Name** field, specify the name of the object that you want to delete. If the specified file is not in the bucket, the integration continues with no error.
4. After you configure the chosen action, click **Next** to specify the action's input type.
5. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
6. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 7. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.

You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.

8. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
9. Click **Next**.

Result

The connection appears in the flow visualization where you added it.

CHAPTER 3. CONNECTING TO AMQ

In an integration, you can obtain messages from a Red Hat AMQ broker or publish messages to a Red Hat AMQ broker. Red Hat AMQ uses the OpenWire protocol for communication between clients and message brokers. To communicate with the following broker types, use the Red Hat AMQ connector to create a connection to the broker of interest:

- Apache ActiveMQ broker that does not support AMQP
- AMQ 6 broker

To communicate with one of the following broker types, [use the AMQP connector](#) to create a connection to the broker of interest:

- Apache ActiveMQ broker that supports AMQP
- Apache ActiveMQ Artemis
- AMQ 7 broker
- EnMasse, which is an open source messaging platform

To use the Red Hat AMQ connector, see:

- [Section 3.1, "Creating an AMQ connection"](#)
- [Section 3.2, "Adding an AMQ connection to trigger integration execution upon receiving messages"](#)
- [Section 3.3, "Publishing AMQ messages to finish an integration"](#)
- [Section 3.4, "Publishing AMQ messages in the middle of an integration"](#)

3.1. CREATING AN AMQ CONNECTION

In an integration, to obtain messages from or to publish messages to:

- An Apache ActiveMQ broker that does not support AMQP
- An AMQ 6 broker

Create a Red Hat AMQ connection, which you can add to an integration.

Prerequisites

For the Red Hat AMQ broker that you want to connect to, you have the following:

- Broker URL
- User account credentials
- Broker's PEM certificate text

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.

2. Click **Create Connection** to display connectors.
3. Click the **Red Hat AMQ** connector.
4. Configure the connection:
 - a. In the **Broker URL** field, enter the location that you want to send data to or obtain data from, for example, **tcp://localhost:61616**.
 - b. In the **User name** field, enter the user name for the account that you want to use to access this broker.
 - c. In the **Password** field, enter the password for the account that you want to use to access this broker.
 - d. In the **Client ID** field, enter the ID that allows connections to close and reopen without missing messages. The destination type must be a topic.
 - e. If this connection will be used in a development environment, you can save some time by disabling **Check certificates**. Disabling the checking of certificates is a convenience for development environments. For secure production environments, always enable **Check certificates**.
 - f. In the **Broker certificate** field, paste the Red Hat AMQ broker's PEM certificate text. This is required except when you disable checking the certificates.
 - g. In the **Client certificate** field, paste the Red Hat client's PEM certificate text. Content in this field is always optional.
5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the configuration details as needed and try again.
6. If validation is successful, click **Next**.
7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, you might enter **Red Hat AMQ 1**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Red Hat AMQ connection that uses a provided broker**.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Red Hat AMQ 1** appears as a connection that you can choose to add to an integration.

3.2. ADDING AN AMQ CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES

To trigger execution of an integration upon receiving a message from a Red Hat AMQ broker, add a Red Hat AMQ connection as the start connection.

Prerequisite

You created a Red Hat AMQ connection to the Red Hat AMQ broker that you want to obtain messages from.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Red Hat AMQ connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Subscribe for messages** action to receive messages from the queue or topic that you specify.
5. Configure the action:
 - a. In the **Destination name** field, enter the name of the queue or topic to receive data from.
 - b. For the **Destination type**, accept **Queue** or select **Topic**.
 - c. In the **Durable subscription ID** field, to allow connections to close and reopen without missing messages, enter the durable subscription ID. The destination type must be a topic.
 - d. In the **Message selector** field, if you want to receive only data that satisfies a particular condition, enter a filter expression.
A message selector is a string that contains an expression. The syntax of the expression is based on a subset of the SQL92 conditional expression syntax. The message selector in the following example selects any message that has a **NewsType** property whose value is set to **Sports** or **Opinion**:

NewsType = 'Sports' OR NewsType = 'Opinion'

The message consumer receives only those messages whose headers and properties match the message selector expression. A message selector cannot select messages on the basis of the content of the message body.

6. Click **Next** to specify the action's output type.
7. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
- **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
- **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
- **XML instance** is a document that contains XML data. The document's file extension is **.xml**.

8. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
9. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
10. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
11. Click **Next**.

Result

The connection appears at the beginning of the integration flow.

3.3. PUBLISHING AMQ MESSAGES TO FINISH AN INTEGRATION

To finish a simple integration by publishing messages to a Red Hat AMQ broker, add a Red Hat AMQ connection as the simple integration's finish connection.

Prerequisites

- You created a connection to the Red Hat AMQ broker that you want to publish messages to.
- You are creating an integration and Fuse Online is prompting you to choose the finish connection, or you are editing an integration to change the finish connection.

Procedure

1. On the **Choose a connection** page, click the Red Hat AMQ connection that you want to use to finish the integration.
2. On the **Choose an action** page, select the **Publish messages** action to publish messages to the queue or topic that you specify.
3. In the **Destination name** field, enter the name of the queue or topic to send messages to.
4. For the **Destination type**, accept **Queue** or select **Topic**.
5. Select **Persistent** to guarantee message delivery even if a connection fails.
6. Click **Next** to specify the action's input/output type.
7. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input/output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
8. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 9. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 10. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 11. Click **Next**.

Result

The connection appears at the end of the integration visualization.

3.4. PUBLISHING AMQ MESSAGES IN THE MIDDLE OF AN INTEGRATION

In the middle of an integration, to publish messages to a Red Hat AMQ broker, add a Red Hat AMQ connection to the middle of a flow.

Prerequisites

- You created a connection to the Red Hat AMQ broker that you want to publish messages to.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the Red Hat AMQ connection that you want in the middle of the flow.
3. On the **Choose an action** page, select one of the following actions:
 - **Publish messages** to publish messages to the queue or topic that you specify. To configure this action:

- a. In the **Destination name** field, enter the name of the queue or topic to send messages to.
- b. For the **Destination type**, accept **Queue** or select **Topic**.
- c. Select **Persistent** to guarantee message delivery even if a connection fails.
- **Request response using messages** to send messages to the JMS destination that you specify and receive a response. To configure this action:
 - a. In the **Destination name** field, enter the name of the queue or topic to send messages to.
 - b. For the **Destination type**, accept **Queue** or select **Topic**.
 - c. In the **Message selector** field, if you want to receive only responses that satisfy a particular condition, enter a filter expression.

A message selector is a string that contains an expression. The syntax of the expression is based on a subset of the SQL92 conditional expression syntax. The message selector in the following example selects any message that has a **NewsType** property whose value is set to **Sports** or **Opinion**:

NewsType = 'Sports' OR NewsType = 'Opinion'

The message consumer receives only those messages whose headers and properties match the message selector expression. A message selector cannot select messages on the basis of the content of the message body.
 - d. In the **Named reply to** field, enter the name of a queue or topic. The destination sends its response to this queue or topic.
 - e. Select **Persistent** to guarantee message delivery even if a connection fails.
 - f. In the **Response time out** field, specify the number of milliseconds that this connection waits for a response message before throwing a runtime exception. The default is 5000 milliseconds (5 seconds).
4. Click **Next** to specify the action's input type and then the action's output type.
5. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input/output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
- **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
- **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
- **XML instance** is a document that contains XML data. The document's file extension is **.xml**.

6. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
7. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
8. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
9. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

CHAPTER 4. CONNECTING TO AMQP

In an integration, you can obtain messages from or publish messages to an Advanced Message Queue Protocol (AMQP) broker. AMQP defines communication between clients and message brokers. To communicate with the following broker types, use the AMQP connector to create a connection to the broker of interest:

- Apache ActiveMQ broker that supports AMQP
- Apache ActiveMQ Artemis
- AMQ 7 broker
- EnMasse, which is an open source messaging platform

To communicate with one of the following broker types, [use the Red Hat AMQ connector](#) to create a connection to the broker of interest:

- Apache ActiveMQ broker that does not support AMQP
- AMQ 6 broker



NOTE

It is possible to use the AMQP connector to create a connection to an Apache ActiveMQ broker that does not support AMQP or to an AMQ 6 broker. Doing this requires transport configuration in the broker. For information about configuring the broker, see [Red Hat JBoss A-MQ Managing and Monitoring Brokers, Adding Client Connection Points](#). For information about the configuration values to specify, see [Red Hat JBoss A-MQ Connection Reference, Advanced Message Queuing Protocol \(AMQP\)](#).

To use the AMQP connector, see:

- [Section 4.1, "Creating an AMQP connection"](#)
- [Section 4.2, "Adding an AMQP connection to trigger integration execution upon receiving messages"](#)
- [Section 4.3, "Publishing messages to AMQP in the middle of a flow or to finish an integration"](#)

4.1. CREATING AN AMQP CONNECTION

In an integration, to obtain messages from or publish messages to an AMQP broker, create an AMQP connection, which you can add to an integration.

Prerequisites

For the AMQP broker that you want to connect to, you have the following:

- Its URI
- User account credentials
- Its PEM certificate text

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display connectors.
3. Click the **AMQP Message Broker** connector.
4. Configure the connection:
 - a. In the **Connection URI** field, enter the location you want to send data to or obtain data from.
 - b. In the **User name** field, enter the user name for the account that you want to use to access this broker.
 - c. In the **Password** field, enter the password for the account that you want to use to access this broker.
 - d. In the **Client ID** field, enter the ID that allows connections to close and reopen without missing messages. The destination type must be a topic.
 - e. If this connection will be used in a development environment, you can save some time by disabling **Check certificates**. Disabling the checking of certificates is a convenience for development environments. For secure production environments, always enable **Check certificates**.
 - f. In the **Broker certificate** field, paste the broker's PEM certificate text. This is required except when you disable the checking of certificates.
 - g. In the **Client certificate** field, paste the client's PEM certificate text. Content in this field is always optional.
5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the configuration details as needed and try again.
6. If validation is successful, click **Next**.
7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, you might enter **AMQP 1**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample AMQP connection**.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **AMQP 1** appears as a connection that you can choose to add to an integration.

4.2. ADDING AN AMQP CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES

To trigger execution of an integration upon receiving messages from an AMQP broker, add an AMQP connection as the integration's start connection.

Prerequisites

- You created a connection to the AMQP broker that you want to receive messages from.
- You are creating an integration and Fuse Online is prompting you to choose the start connection.

Procedure

1. On the **Choose a connection** page, click the AMQP connection that you want to use to start the integration.
2. On the **Choose an action** page, select the **Subscribe for messages** action to receive messages from the queue or topic that you specify.
3. Configure the action:
 - a. In the **Destination name** field, enter the name of the queue or topic to receive data from.
 - b. For the **Destination type**, accept **Queue** or select **Topic**.
 - c. In the **Durable subscription ID** field, to allow connections to close and reopen without missing messages, enter the durable subscription ID. The destination type must be a topic.
 - d. In the **Message selector** field, if you want to receive only data that satisfies a particular condition, enter a filter expression.

A message selector is a string that contains an expression. The syntax of the expression is based on a subset of the SQL92 conditional expression syntax. The message selector in the following example selects any message that has a **NewsType** property whose value is set to **Sports** or **Opinion**:

NewsType = 'Sports' OR NewsType = 'Opinion'

The message consumer receives only those messages whose headers and properties match the message selector expression. A message selector cannot select messages on the basis of the content of the message body.

4. Click **Next** to specify the action's output type.
5. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
- **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
- **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
- **XML instance** is a document that contains XML data. The document's file extension is **.xml**.

6. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
7. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
8. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
9. Click **Next**.

Result

The connection appears at the beginning of the integration flow.

4.3. PUBLISHING MESSAGES TO AMQP IN THE MIDDLE OF A FLOW OR TO FINISH AN INTEGRATION

You can publish messages to an AMQP broker in the middle of a flow or to finish a simple integration. To do this, add an AMQP connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a connection to the AMQP broker that you want to publish messages to.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a simple integration's finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the AMQP connection that you want to use to publish messages.
3. On the **Choose an action** page, select one of the following actions:
 - **Publish messages** to publish messages to the queue or topic that you specify without receiving a response. To configure this action:
 - a. In the **Destination name** field, enter the name of the queue or topic to send messages to.
 - b. For the **Destination type**, accept **Queue** or select **Topic**.
 - c. Select **Persistent** to guarantee message delivery even if a connection fails.
 - **Request response using messages** to publish messages to the queue or topic that you specify and receive a response.



NOTE

When the finish connection in a simple integration is an AMQP connection that performs the **Request response using messages** action, the connection publishes the messages but the response is discarded. To avoid losing the response, add an AMQP connection as a middle connection that performs the **Request response using messages** action and finish the simple integration with a log step.

To configure this action:

- a. In the **Destination name** field, enter the name of the queue or topic to send messages to.
- b. For the **Destination type**, accept **Queue** or select **Topic**.
- c. In the **Durable subscription ID** field, to allow connections to close and reopen without missing messages, enter the durable subscription ID. The destination type must be a topic.
- d. In the **Message selector** field, if you want to receive only responses that satisfy a particular condition, enter a filter expression.

A message selector is a string that contains an expression. The syntax of the expression is based on a subset of the SQL92 conditional expression syntax. The message selector in the following example selects any message that has a **NewsType** property whose value is set to **Sports** or **Opinion**:

NewsType = 'Sports' OR NewsType = 'Opinion'

The message consumer receives only those messages whose headers and properties match the message selector expression. A message selector cannot select messages on the basis of the content of the message body.

4. Click **Next** to specify the action's input and output type.
5. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input/output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
- **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
- **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
- **XML instance** is a document that contains XML data. The document's file extension is **.xml**.

6. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
7. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
8. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
9. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

CHAPTER 5. CONNECTING TO API CLIENTS

In an integration, to connect to a REST or a SOAP API, you must have created a connector for that API. See [Integrating Applications with Fuse Online, Adding and managing API client connectors](#) .

When a connector for the API that you want to connect to is available in Fuse Online, the steps for connecting to that API are:

- [Section 5.1, "Registering Fuse Online as a REST API client"](#) if required
- [Section 5.2, "Creating a REST API client connection"](#)
- [Section 5.3, "Creating a SOAP API client connection"](#)
- [Section 5.4, "Adding an API client connection to an integration"](#)

5.1. REGISTERING FUSE ONLINE AS A REST API CLIENT


Before Fuse Online creates a REST API client connector, it prompts you to indicate the API's security requirements. For APIs that use the OAuth protocol, when Fuse Online creates the connector it also adds an entry for the API to the Fuse Online **Settings** page. This is where you provide the API client ID and the API client secret that authorize Fuse Online to access the API.

If the API you want to connect to does not use OAuth, skip this section and see [Creating a REST API client connection](#).

Prerequisite

You must know the URL for the OAuth custom application setting page for the REST API that you want to connect to.

Procedure

1. In Fuse Online:
 - a. On the **Settings** page, near the top, to the right of the callback URL, click  to copy the callback URL for your Fuse Online environment to the clipboard. You will need this URL later in this procedure.
 - b. Look for the name of the API you want to connect to and click it to display its client ID and client secret fields.
2. In another browser window, you must register Fuse Online as an OAuth client of the API you want to connect to. The exact steps for doing this vary for each API service. Typically, the API service provides an OAuth custom application setting page. Go to that page and do the following:
 - a. Provide the Fuse Online callback URL, which you copied at the beginning of this procedure.
 - b. Respond to any other prompts that require your input.
 - c. Obtain the client ID and client secret that the API service assigns to your Fuse Online environment.
3. Return to the Fuse Online **Settings** page entry for the API service you are registering with and do the following:

- a. Paste the assigned client ID.
- b. Paste the assigned client secret.
- c. Click **Save**.

5.2. CREATING A REST API CLIENT CONNECTION

In an integration, to connect to a REST API, create a connection to that REST API, which you can then add to any number of integrations.

Prerequisites

- You created a connector for the REST API that you want to connect to.
- If the REST API uses the OAuth protocol then you registered your Fuse Online environment as a client application that can access that REST API.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display available connectors.
3. Click the connector for the API that you want to create a connection for.
4. On the configuration page, provide the requested information. The definition of the API determines what Fuse Online prompts for.

Typically, an API service has security requirements and Fuse Online prompts for security input according to the particular security type that the OpenAPI document defines. The security type can be one of the following:


Security type	Fuse Online displays
HTTP Basic Authentication	Input fields for user name and password.
OAuth 2.0	A button for you to click so that Fuse Online can verify its registration credentials for connecting to the API. These credentials were provided when the connector was created.
API Key	Input field for an API key, which you must obtain from the API service.

5. Click **Validate**. Fuse Online validates connection parameters. For example, it checks for valid host/address URLs.
6. Click **Next**.
7. On the **Name connection** page:
 - a. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections.

- b. In the **Description** field, optionally enter any information that is helpful to know about this connection.
- c. Click **Save**. You can now choose the connection that you created and add it to an integration.

5.3. CREATING A SOAP API CLIENT CONNECTION

In an integration, to connect to a SOAP API, create a connection to that SOAP API, which you can then add to any number of integrations.



IMPORTANT

The SOAP API client connection is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process. For more information about the support scope of Red Hat Technology Preview features, see <https://access.redhat.com/support/offerings/techpreview/>

Prerequisite

- You created a connector for the SOAP API that you want to connect to.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display available connectors.
3. Click the connector for the API that you want to create a connection for.
4. On the configuration page, provide the requested information. The definition of the API determines what Fuse Online prompts for.
5. On the connection configuration page:
 - a. Accept or edit the SOAP Endpoint address.
 - b. Select an Authentication type (None, Basic, or WS-Security Username Token) to use when invoking the WSDL endpoint. Typically, an API service has security requirements and Fuse Online prompts for security input according to the particular security type that the WSDL file defines.
 - c. Select a WS-Security Password Type (**None**, **Text**, or **Digest**).
 - d. Specify **username** and **password**.
 - e. Select **Timestamp** if you want Fuse Online to add a timestamp to the WS-Security header.
 - f. Select **Username Token Nonce** if you want Fuse Online to add a Nonce element to the WS-Security Username Token header.
For more information about how to use the UsernameToken with the Web Services Security (WSS) specification, see [this OASIS document](#).

- g. Select **Username Token Created** if you want Fuse Online to add a timestamp element to the WS-Security Username Token header.

Note: Due to a lack of an OASIS/W3C standard for verifying connections to SOAP endpoints, SOAP connectors do not support validation.

6. Click **Next**.
7. On the **Name connection** page:
 - a. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections.
 - b. In the **Description** field, optionally enter any information that is helpful to know about this connection.
 - c. Click **Save**. You can now choose the connection that you created and add it to an integration.

5.4. ADDING AN API CLIENT CONNECTION TO AN INTEGRATION

In an integration, to connect to a REST or SOAP API, add a step that connects to that API.

In this release, a connection to a REST or SOAP API can be a step that is in the middle of a flow or it can be the finish connection in a simple integration. In other words, a connection to a REST or SOAP API cannot be a start connection.

Prerequisites

- You created a connection to the REST or SOAP API.
- You are creating or editing a flow.
- The flow already has its start connection.
- Fuse Online is prompting you to select a finish connection or to add to the integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. On the page that displays available steps, click the API connection that you want to add to the flow.
3. Select the action that you want the connection to perform. The actions that are available are based on the resource operations specified in the OpenAPI document or WSDL file that was uploaded to Fuse Online and that describes the API that you are connecting to.
4. Depending on the action you select, enter any parameters that Fuse Online prompts for.
5. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

CHAPTER 6. CONNECTING TO BOX

In an integration, you can download files from Box or upload files to Box.

A connection to Box cannot start a simple integration. In other words, you cannot use a Box connection to trigger integration execution.

The following topics provide the details:

- [Section 6.1, "Registering Fuse Online as a Box client"](#)
- [Section 6.2, "Creating a Box connection"](#)
- [Section 6.3, "Downloading or uploading a Box file in the middle of an integration"](#)
- [Section 6.4, "Uploading files to Box to finish an integration"](#)

6.1. REGISTERING FUSE ONLINE AS A BOX CLIENT


You must register your Fuse Online environment as a client application that can access Box. This lets you create any number of integrations that connect to Box. In other words, you need to register a particular Fuse Online environment with Box only once.

In each Fuse Online environment, there can be only one registration of Fuse Online as a Box client application. However, while each Box connection uses the same registration, it can use different user credentials.

Prerequisites

- You have a Box developer account, which you can obtain at <https://app.box.com/developers/console>.

Procedure

1. In Fuse Online:
 - a. In the left panel, click **Settings**.
 - b. On the **Settings** page, near the top, to the right of the callback URL, click  to copy the callback URL for your Fuse Online environment to the clipboard. You will need this URL toward the end of this procedure.
2. In another browser tab, go to the Box developer portal at <https://app.box.com/developers/console> and do the following:
 - a. Sign in.
 - b. Click **Create New App**.
 - c. Click **Custom App** and then **Next**.
 - d. For **Authentication Method**, click **Standard OAuth 2.0 (User Authentication)** and then **Next**.
 - e. Enter an app name, for example, **Fuse Online Client** and click **Create App**.

- f. Click **View Your App**.
- g. Optional. In the **OAuth 2.0 Credentials** section, copy the client ID and the client secret to a safe location. These values are needed to create a connection to Box.
- h. Click **Save Changes**.

Result

Your Fuse Online environment is now registered as a Box client, which means that Fuse Online can access content in the Box account that you signed into.

6.2. CREATING A BOX CONNECTION

In an integration, to download or upload Box files, create a Box connection, which you can add to an integration. You can add the same connection to any number of integrations.

Prerequisites

- There is a Box client application that registers your Fuse Online environment as an application that can access Box.
- You can log in to the Box developer account that created that application, or you have the Box client ID and Box client secret for that application.
- You know the user name and password for the Box account that you want this connection to use to access Box.

Procedure

1. If you already have the Box client ID and the client secret, skip to the next step. Otherwise, to obtain those values, in a new browser tab, go to <https://app.box.com/developers/console> and do the following:
 - a. Sign in to the Box account in which you created the app that registers access to Box from your Fuse Online environment.
 - b. On the **My Apps** page, click the Fuse Online app to display its settings.
 - c. On the left, click **Configuration**.
 - d. In the **OAuth 2.0 Credentials** section, copy the client ID to the clipboard.
2. In a different browser tab, in Fuse Online:
 - a. Click **Connections**.
 - b. Click **Create Connection**.
 - c. Click the Box connector.
 - d. In the **User name** field, enter the user name for the Box account that you want this connection to use to download or upload Box files.
 - e. In the **User password** field, enter the password for that account.
 - f. In the **Client ID** field, paste the Box client ID.

3. Optional. If you need to, go back to the **OAuth 2.0 Credentials** for the Box app, copy the client secret to the clipboard and then return to Fuse Online.
4. In the **Client secret** field, paste the Box client secret string.
5. Click **Validate**. Fuse Online displays a message that indicates whether it can validate this connection. If validation fails, try again and be sure to enter the correct values.
6. When validation is successful, click **Next**.
7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Box Sales Account**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Box connection that can access content in our company sales Box account**.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Box Sales Account** appears as a connection that you can choose to add to an integration.

6.3. DOWNLOADING OR UPLOADING A BOX FILE IN THE MIDDLE OF AN INTEGRATION

To download a file from Box, or upload a file to Box in the middle of a flow, add a Box connection to the middle of the flow.

Prerequisites

- You created a Box connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection.
2. Click the Box connection that you want the integration to use.
3. On the **Choose an action** page, select one of the following:
 - **Download** to obtain a file from the Box account that this connection accesses.
 - **Upload** to upload a file to the Box account that this connection accesses.
4. Configure the action you selected.

To **download** a file:

 - a. In the **File encoding** field, accept **UTF-8** or specify the encoding for the file that you want the connection to obtain.
 - b. Optional. In the **File ID** field, specify the Box ID for the file that you want to obtain. The file ID is at the end of the URL when you are viewing the file in Box. For example, in this URL: **https://app.box.com/file/537364588548**, the file ID is **537364588548**.
Alternatively, you can add a data mapper step before this connection and map the file ID from a previous step to this connection.

In this release, you can download only a single file. However, mapping the file ID from a previous step can make identification of the file dynamic, for example, the ID can come from a database table. This means each execution might download a different file.

To **upload** a file:

- a. In the **Parent folder ID** field, enter the ID of the Box folder to upload the file to. Box folder IDs are at the end of the URL when you view the content of a folder in Box. In this example: **https://app.box.com/folder/89490291417**, the folder ID is **89490291417**. In this release, you can upload only a single file.
- b. Optional. In the **File name** field, enter the name for a new file. If you specify the name of a file that is already in the specified Box folder, the connection overwrites the file that is in the folder.
The input to the connection must be a file that you want to upload to Box. If you do not specify a file name, the connection uploads a file that has the same name as the input file to the connection as long as a file with that name is not already present.
- c. Click **Next** to specify the upload action's input type.
- d. In the **Select Type** field, accept **Type specification not required** and click **Next**.

Result

The connection appears in the integration flow where you added it.

6.4. UPLOADING FILES TO BOX TO FINISH AN INTEGRATION

To finish an integration by uploading files to Box, add a Box connection as the integration's finish connection.

Prerequisites

- You created a Box connection.
- You are creating or editing a simple integration and Fuse Online is prompting you to choose the finish connection.

Procedure

1. On the **Choose a connection** page, click the Box connection that you want to use to finish the integration.
2. On the **Choose an action** page, select the **Upload** action to upload a file to the Box account that this connection accesses.
3. In the **Parent folder ID** field, enter the ID of the Box folder to upload the file to. Box folder IDs are at the end of the URL when you select a folder in Box. In this example: **https://app.box.com/folder/89490291417**, the folder ID is **89490291417**. In this release, you can upload only a single file.
4. Optional. In the **File name** field, enter the name for a new file or an existing file. If you specify the name of a file that is already in the specified Box folder, the connection overwrites the file that is in the folder.

The input to the connection must be a file that you want to upload to Box. If you do not specify a file name, the connection uploads a file that has the same name as the input file to the connection.

5. Click **Next**.
6. In the **Select Type** field, accept **Type specification not required** and click **Next**.

Result

The connection appears at the end of the integration visualization.

CHAPTER 7. CONNECTING TO DROPBOX

In an integration, you can download files from Dropbox or upload files to Dropbox. The following topics provide the details:

- [Section 7.1, “Registering Fuse Online as a Dropbox client”](#)
- [Section 7.2, “Creating a Dropbox connection”](#)
- [Section 7.3, “Obtaining files from Dropbox to trigger integration execution”](#)
- [Section 7.4, “Adding files to Dropbox to finish an integration”](#)
- [Section 7.5, “Accessing Dropbox in the middle of an integration”](#)

7.1. REGISTERING FUSE ONLINE AS A DROPBOX CLIENT


You must register your Fuse Online environment as a client application that can access Dropbox. This lets you create any number of integrations that connect to Dropbox. In other words, you need to register a particular Fuse Online environment with Dropbox only once.

In each Fuse Online environment, there can be only one registration of Fuse Online as a Dropbox client application. However, while each Dropbox connection uses the same registration, it can use different user credentials.

Prerequisite

You can sign in to the Dropbox account that you want an integration to use to download or upload files.

Procedure

1. In Fuse Online:
 - a. In the left panel, click **Settings**.
 - b. On the **Settings** page, near the top, to the right of the callback URL, click  to copy the callback URL for your Fuse Online environment to the clipboard. You will need this URL toward the end of this procedure.
2. In another browser tab, go to <https://www.dropbox.com> and do the following:
 - a. Sign in to the Dropbox account that has the data that you want to access in an integration.
 - b. After signing in, go to <https://www.dropbox.com/developers/apps>.
 - c. Click **Create App**.
 - d. Select **Dropbox API**.
 - e. Near the top of the page, in the sentence that starts with **During registration, enter this callback URL:**, paste the URL that you copied to the clipboard at the beginning of this procedure. For example, the URL that you paste is something like this: **`https://app-proj9128.7b63.fuse-ignite.openshiftapps.com/api/v1/credentials/callback`**.
 - f. Choose whether Fuse Online can access a single folder or all of the folders and files.

- g. Specify a name for your Dropbox app. For example, you might specify **Fuse Online Access From Aslan LLC**. The name you specify must be unique in the set of Dropbox app names.
- h. Check the box to indicate that you agree to Dropbox API terms and conditions.
- i. Click **Create App**.
- j. In the Dropbox **Settings** page for your new app, in the input field for **OAuth2 Redirect URIs**, paste your Fuse Online URL, which you copied to the clipboard at the beginning of this procedure.
- k. Click **Add**.

Result

Your Fuse Online environment is now registered as a Dropbox client, which means that Fuse Online can access content in the Dropbox account that you signed into.

7.2. CREATING A DROPBOX CONNECTION

In an integration, to download or upload Dropbox files, create a Dropbox connection, which you can add to an integration. You can add the same connection to any number of integrations.

Prerequisite

You registered your Fuse Online environment as an application that can access Dropbox.

Procedure

1. In a new browser tab, go to <https://www.dropbox.com> and do the following:
 - a. Sign in to the Dropbox account in which you created the app that registers access from your Fuse Online environment.
 - b. Go to <https://www.dropbox.com/developers/apps>.
 - c. Click the Fuse Online app to display its settings.
2. In another browser tab, in Fuse Online, do the following:
 - a. In the left panel, click **Connections** to display any available connections.
 - b. Click **Create Connection** to display the available connectors.
 - c. Click the **Dropbox** connector.
3. Go back to the Dropbox settings display for your app and do the following:
 - a. Scroll down to see **Generated Access Token**.
 - b. Click **Generate**.
 - c. Copy the generated access token to the clipboard.
4. Back in Fuse Online, in the **Configure Connection** page, in the **Access Token** field, paste the generated access token.

5. In the **Client Identifier** field, enter the name that you specified when you created the Dropbox app.
6. Click **Validate**. Fuse Online displays a message that indicates whether it can validate this connection. If validation fails, try again and be sure to enter the correct values.
7. When validation is successful, click **Next**.
8. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Dropbox Connect 1**.
9. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Dropbox connection that can access all content in our company Dropbox account**.
10. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Dropbox Connect 1** appears as a connection that you can choose to add to an integration.

7.3. OBTAINING FILES FROM DROPBOX TO TRIGGER INTEGRATION EXECUTION

To start an integration by downloading files from Dropbox, add a Dropbox connection as the start connection.

Prerequisite

You created a Dropbox connection.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Dropbox connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Download** action to obtain one or more files from the Dropbox account that this connection accesses.
5. To configure the action, in the **Folder or file name path to download** field, specify the filename path for the content that you want the integration to obtain. In this release, you can download only a single file.
6. Click **Next** to specify the action's output type.
7. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
8. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 9. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 10. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 11. Click **Next**.

Result

The connection starts the simple integration and Fuse Online prompts you to choose the finish connection.

7.4. ADDING FILES TO DROPBOX TO FINISH AN INTEGRATION

To finish an integration by uploading files to Dropbox, add a Dropbox connection as the integration's finish connection.

Prerequisites

- You created a Dropbox connection.
- You are creating or editing an integration and Fuse Online is prompting you to choose the finish connection.

Procedure

1. On the **Choose a connection** page, click the Dropbox connection that you want to use to finish the integration.
2. On the **Choose an action** page, select the **Upload** action to add the current integration data to the Dropbox account that this connection accesses.
3. In the **Remote Path** field, enter the local filename path for file that you want to upload. Dropbox stores the file with the same path and name. In this release, you can upload only a single file.
4. For the **Upload mode**:

- Select **Add** to upload a file only when a file with the same name is not already in the same Dropbox folder. If a file with the same name is already in the same Dropbox folder, then the file is not uploaded and the integration continues. This is the behavior regardless of whether the content in the file you are trying to upload has been updated.
 - Select **Force** to ensure that the file is uploaded even if a file with the same name is present in the same Dropbox folder. Dropbox overwrites the file that it already has with the file that you are uploading.
5. Click **Next** to specify the action's input type.
 6. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
7. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 8. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors you might specify **Vendor** as the data type name. You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 9. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 10. Click **Next**.

Result

The connection appears at the end of the integration visualization.

7.5. ACCESSING DROPBOX IN THE MIDDLE OF AN INTEGRATION

To upload a file to Dropbox in the middle of a flow, add a Dropbox connection to the middle of the flow.

Prerequisites

- You created a Dropbox connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the Dropbox connection that you want the integration to use.
3. On the **Choose an action** page, select **Upload** to add the current integration data to the Dropbox account that this connection accesses.
4. Configure this action:
 - a. In the **Remote Path** field, specify the local path and file name of the file that you want to upload. Dropbox stores the file with the same path and name. In this release, you can upload only a single file.
 - b. For the **Upload mode**:
 - Select **Add** to upload a file only when a file with the same name is not already in the same Dropbox folder. If a file with the same name is already in the same Dropbox folder, then the file is not uploaded and the integration continues. This is the behavior regardless of whether the content in the file you are trying to upload has been updated.
 - Select **Force** to ensure that the file is uploaded even if a file with the same name is present in the same Dropbox folder. Dropbox overwrites the file that it already has with the file that you are uploading.
5. Click **Next** to specify the action's input and output type.
6. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input/output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
7. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.

8. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
9. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
10. Click **Next**.

Result

The connection appears in the integration flow where you added it.

CHAPTER 8. CONNECTING TO EMAIL SERVERS (IMAP, POP3, SMTP)

An integration can connect to an IMAP or POP3 email server to retrieve email messages or connect to an SMTP email server to send email messages. To trigger integration execution upon retrieving email, create a connection to an IMAP or POP3 email server and then add that connection as a simple integration's start connection. To send an email from a flow, create a connection to an SMTP email server and then add that connection to the middle of a flow or to finish a simple integration.

For details, see:

- [Section 8.1, "Creating a connection to an IMAP or POP3 email server"](#)
- [Section 8.2, "Creating a connection to an SMTP email server"](#)
- [Section 8.3, "Obtaining email to trigger integration execution"](#)
- [Section 8.4, "Sending email from an integration"](#)

8.1. CREATING A CONNECTION TO AN IMAP OR POP3 EMAIL SERVER

You must create a connection to an IMAP or POP3 email server before you can create a simple integration whose execution is triggered by received email.

Prerequisites

You must be familiar with the email server that this connection accesses. Specifically, you must know:

- Whether the email server uses the IMAP or POP3 protocol.
- Whether authentication credentials are required. If they are, you must have a user name and password.
- Whether a security method is implemented. If one is, you must know which method.
- Whether a server certificate is required. If it is, you must be able to specify it.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **Receive Email** connector.
4. Configure the connection:
 - a. In the **Protocol** field, accept **imap** or select **pop3**.
 - b. In the **Email Host Name** field, enter the email server host name, virtual host name, or IP address.
 - c. In the **Email Server Port Number** field, enter the port number that the email server listens on.

- d. In the **User Name** field, specify the user name for the email account that this connection is authorized to access. During execution of an integration, this connection polls this email account for messages.
Rarely, an email server does not authenticate access. In that case, specification of user name and password is not required.
 - e. In the **Password** field, specify the password for the email account that this connection is authorized to access.
 - f. Optional. In the **Security Method** field, if the email server implements a security method, select **StartTLS** or **SSL/TLS**.
 - g. Optional. In the **Server Certificate** field, if the email server is not public, that is, it is on an internal network, and if you selected **StartTLS** or **SSL/TLS** as the security method, paste the self-signed email server certificate in this field. Fuse Online cannot verify this connection if a server certificate is required and you do not specify it.
5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether or not validation is successful. If validation fails, revise the configuration details as needed and try again.
 6. When validation is successful, click **Next**.
 7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Obtain Info Emails**.
 8. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Connect to our company email server to obtain messages sent to info@ourcompany.com**.
 9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Obtain Info Emails** appears as a connection that you can choose to add to an integration.

8.2. CREATING A CONNECTION TO AN SMTP EMAIL SERVER

You must create a connection to an SMTP email server before you can edit an integration flow so that it connects to an SMTP email server to send email.

Prerequisites

You must be familiar with the email server that this connection accesses. Specifically, you must know:

- Whether authentication credentials are required. If they are, you must have a user name and password.
- Whether a security method is implemented. If one is, you must know which method.
- Whether a server certificate is required. If it is, you must be able to specify it.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **Send Email** connector.

4. Configure the connection:
 - a. In the **Email Host Name** field, enter the email server host name, virtual host name, or IP address.
 - b. In the **Email Server Port Number** field, enter the port number that the email server listens on.
 - c. In the **User Name** field, specify the user name for the email account that this connection is authorized to access. During execution of an integration, this connection uses this email account to send messages.
Rarely, an email server does not authenticate access. In that case, specification of user name and password is not required.
 - d. In the **Password** field, specify the password for the email account that this connection is authorized to access.
 - e. Optional. In the **Security Method** field, if the email server implements a security method, select **StartTLS** or **SSL/TLS**.
 - f. Optional. In the **Server Certificate** field, if the email server is not public, that is, it is on an internal network, and if you selected **StartTLS** or **SSL/TLS** as the security method, paste the self-signed email server certificate in this field. Fuse Online cannot verify this connection if a server certificate is required and you do not specify it.
5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether or not validation is successful. If validation fails, revise the configuration details as needed and try again.
6. When validation is successful, click **Next**.
7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Send Emails to Leads**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Connect to our company email server to send messages from info@ourcompany.com**.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Send Emails to Leads** appears as a connection that you can choose to add to an integration.

8.3. OBTAINING EMAIL TO TRIGGER INTEGRATION EXECUTION

To trigger execution of an integration upon receiving email, add an IMAP or POP3 email server connection as a simple integration's start connection.

Prerequisites

- You created an IMAP or POP3 email server connection that is configured to access the account that you want to obtain email from.
- You know the name of the folder to retrieve messages from.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the email server connection that you want to use to start the integration.
4. On the **Choose an action** page, select **Receive Email** to periodically retrieve messages from the email account that the connection is authorized to access.
5. Configure the action:
 - a. Leave the **Folder** field blank to obtain email from the inbox. Or, to obtain messages from a particular folder, enter the name of that folder.
If this connection accesses a POP3 email server, only standard folders, such as **Inbox** or **Sent** are supported.
 - b. Select the **Unseen Only** checkbox to obtain only messages that are marked as unread on the email server.
 - c. In the **Delay** field, accept the default of 5 seconds as the time that elapses between polls for messages. Or, to specify a different polling interval, enter a number and select its time unit.
 - d. In the **Maximum Emails** field, enter the largest number of messages that one poll operation can return. The default is 5. If the inbox or folder contains more than the maximum number of messages that can be returned, the connection returns the oldest messages up to the number set for **Maximum Emails**.
Set **Maximum Emails** to **-1** if you want each poll to obtain:
 - All new messages in the specified folder when **Unseen Only** is selected.
 - All messages in the specified folder when **Unseen Only** is NOT selected.
6. Click **Next**.

Result

The connection appears at the beginning of the integration flow. During execution, if a poll returns email, the connection passes the messages to the next step in the integration. If a poll does not return any email, the integration continues to run but Fuse Online does not trigger the rest of the integration steps.

Example

Consider a **Receive Email** action that is configured as follows:

- The **Folder** field is blank so the connection polls the inbox.
- **Unseen Only** is selected.
- The defaults for **Delay** (5 seconds) and **Maximum Emails** (5) are accepted.

Suppose that 10 messages arrive in the inbox during the delay before the next poll. The connection returns the 5 oldest messages. At the next poll, 5 seconds later, the connection returns the other 5 messages. Even if new messages arrived, this is the case because the connection returns the oldest messages if there are more messages than the number set for **Maximum Emails**.

8.4. SENDING EMAIL FROM AN INTEGRATION

In the middle of a flow, or to finish a simple integration, you can add an email server connection that sends messages.

Prerequisites

- You created an SMTP email server connection that is configured to access the account that you want to send messages from.
- Fuse Online is prompting you to add to the integration, or to choose the finish connection for a simple integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the email server connection that you want to use to send messages.
3. Select the **Send Email** action.
4. In the **Email from** field, enter the email address that sends the messages. This is required even if you plan to add a data mapper step that maps an email address from a previous integration step to this connection.
5. Recommended: Specify a value in each of the following fields. Separate multiple email addresses with a comma.
 - a. **Email to**
 - b. **Email subject**
 - c. **Email text**
 - d. **Email cc**
 - e. **Email bcc**
6. In the **Parameter Priority** field, accept **Input Values** or select **Consumed Data**. This determines which of the following has precedence:
 - Input values in this action configuration
 - Data values that you map to this connection

The recommendation is to select **Consumed Data**. This means that the values that you specify in the email fields here serve as default values.
7. Click **Next** to add the connection to the flow.

Result

The connection appears in the integration flow where you added it.

Next steps

Add all other needed to connections to the flow. Then add a data mapper step before the connection that sends email. In the data mapper step, map source fields to the target fields for sending emails.

CHAPTER 9. CONNECTING TO FHIR

Fast Healthcare Interoperability Resources (FHIR) is a standard for exchanging healthcare data. In an integration, you can obtain one or more FHIR resources, create or update a resource, update one or more fields in a resource, or use a transaction to create multiple resources. To do this, add a FHIR connection to the middle of a flow or as a simple integration's finish connection.

Fuse Online connections to FHIR:

- Can communicate with FHIR servers that use basic or bearer token (OAuth) authentication.
- Can operate on all FHIR resources that comply with FHIR DSTU3.
- Cannot operate on extensions, which allow for storing custom data in a resource. If an extension is in data that is received from a FHIR server, the integration silently ignores it.

In an integration that connects to FHIR, in a data mapper step, you can map only one level of depth for a FHIR list field. In other words, if a FHIR list contains a list then you cannot map the fields in the nested list. To mitigate this limitation, Fuse Online converts some FHIR resource list fields to single-value fields, for example, an address that is in a list field might be displayed in the data mapper as a single field.

Details for connecting to FHIR are in the following topics:

- [Section 9.1, "Creating a connection to a FHIR server"](#)
- [Section 9.2, "Obtaining a resource from a FHIR server"](#)
- [Section 9.3, "Querying a FHIR server for resources"](#)
- [Section 9.4, "Creating a resource on a FHIR server"](#)
- [Section 9.5, "Updating all fields in a resource on a FHIR server"](#)
- [Section 9.6, "Updating specified fields in a resource on a FHIR server"](#)
- [Section 9.7, "Creating resources of different types on a FHIR server"](#)
- [Section 9.8, "Deleting a resource from a FHIR server"](#)

9.1. CREATING A CONNECTION TO A FHIR SERVER

In an integration, to operate on FHIR resources, create a connection to a FHIR server and then add that connection to the middle of a flow or as a simple integration's finish connection.

A FHIR connection cannot be the start connection of a simple integration. However, you can start a simple integration with a timer that periodically triggers a FHIR connection.

Prerequisites

- You must know the URL for the FHIR server that you want to connect to.
- You must have authorization credentials for accessing the FHIR server. You should obtain these from the FHIR server administrator. Rarely, a FHIR server does not require authentication and you can create a connection without specifying credentials. For example, a public FHIR server or a FHIR server in a private network might not require authentication.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display connectors.
3. Click the **FHIR** connector and configure the connection as follows:
 - a. In the **FHIR version** field, accept **DSTU3**, which is required.
 - b. In the **FHIR server URL** field, enter the URL for the FHIR server that you want to access. While creating an integration, you might accept the default test server **http://fhirtest.uhn.ca/baseDstu3**.
 - c. In the **FHIR server username** field, enter your username. This is required by FHIR servers that use basic authentication.
 - d. In the **FHIR server password** field, enter your password, which is also required by FHIR servers that use basic authentication.
 - e. In the **FHIR server bearer token** field, enter your token. This is required by FHIR servers that use OAuth authentication.
4. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the input parameters and try again.
5. If validation is successful, click **Next**.
6. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, you might enter **FHIR West**.
7. In the **Description** field, optionally enter any information that is helpful to know about this connection.
8. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **FHIR West** appears as a connection that you can choose to add to an integration.

9.2. OBTAINING A RESOURCE FROM A FHIR SERVER

In an integration, you can obtain one resource that is of the type that you specify. To do this, add a FHIR connection to the middle of a flow.

Prerequisites

- You created a connection to the FHIR server that has the resource that you want to obtain.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection.
2. Click the FHIR connection that can access the resource that you want to obtain.
3. On the **Choose an action** page, select **Read**.

4. Click in the **Resource Type** field to display a list of FHIR resource types. Select or enter the type of resource that you want to obtain.
5. In the **Contained Resource Types** field, if the resource type that you want contains other resource types, select them. Use the **Ctrl** key if you need to select more than one. Identifying contained resource types lets the data mapper display the fields that are in the contained resources. If you do not specify a contained resource type then you cannot map from any fields that are in the contained resource. There is no harm in selecting a resource that is not actually contained.
6. In the **Resource Id** field, enter the ID of the resource that you want. Or, leave this field blank if you plan to map it from an earlier step that is in the flow.
7. In the **Resource version** field, optionally specify a version ID for the resource. Leave this field blank to obtain the most recent version of the resource or to map the version ID of the resource that you want to obtain from a previous step.
8. Click **Next** to add this connection to the flow.

Result

The connection appears in the integration visualization where you added it. During execution, this connection returns one resource.

Next steps

To map a value to the **Resource Id** field or the **Resource version** field, add a data mapper step before this connection.

9.3. QUERYING A FHIR SERVER FOR RESOURCES

In an integration, you can query a FHIR server to obtain instances of a particular FHIR resource that satisfy a query that you specify. For example, suppose you want to ensure that all patients who are 65 and older received a pneumonia vaccination. Specify a query that obtains the resources for patients who were born before 1955. To do this, add a FHIR connection to the middle of a flow.

Prerequisites

- You created a connection to the FHIR server that has the resources that you want to obtain.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection.
2. Click the FHIR connection that has the resources that you want to obtain.
3. On the **Choose an action** page, select **Search**.
4. Click in the **Resource Type** field to display a list of FHIR resource types. Select or enter the type of resource that you want to obtain.
5. In the **Query** field, specify a FHIR query or leave this field blank to map the query from a previous step. For details about forming a FHIR query, see [FHIR Release 3 Search](#).
6. Click **Next** to add this connection to the flow.

Result

The connection appears in the integration visualization where you added it. During execution, this connection returns a list of resources that satisfy the query that you specified. Fuse Online treats this list as a collection.

Next steps

If you did not specify a query, then add a data mapper step before this connection and map the query to this connection. To operate on individual returned resources, rather than on the returned list collection, after this connection, add a split step to the flow.

9.4. CREATING A RESOURCE ON A FHIR SERVER

In an integration, you can create and add a resource to a FHIR server. When you configure the connection's **Create** action, you specify the type of the resource that you want to create. For example, you might want to add a new patient resource to a FHIR server. To create a resource, add a FHIR connection to the middle of a flow, or as a simple integration's finish connection.

To populate the values in the new resource, add a data mapper step to the flow just before the FHIR connection that you are adding in this procedure. It is expected that the previous steps in the flow provide the data that you want the new resource to contain. Map fields in the previous steps to fields in the target resource that this FHIR connection is creating. The new resource contains only the fields that you map to.

When a connection performs the **Create** action to create a new resource on a FHIR server, the new resource has an automatically-generated FHIR resource ID. If you want to specify the resource ID for a new resource, instead of selecting the **Create** action choose the **Update action** for the connection to perform.

Prerequisites

- You created a connection to the FHIR server that you want to add a resource to.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to add a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the FHIR connection to the server that you want to add a resource to.
3. On the **Choose an action** page, select **Create**.
4. Click in the **Resource Type** field to display a list of FHIR resource types. Select or enter the type of resource that you want to create.
5. In the **Contained Resource Types** field, if the resource type that you want to create contains other resource types, select them. Use the **Ctrl** key if you need to select more than one. Identifying contained resource types lets the data mapper display the fields that are in the contained resources. If you do not specify a contained resource type then you cannot map to or from any fields that are in the contained resource. There is no harm in selecting a resource that is not actually contained.

6. Click **Next** to add this connection to the flow.

Result

The connection appears in the integration visualization where you added it. During execution, the connection creates a new resource on the FHIR server. The connection returns a **MethodOutcome** resource that includes an **id.idPart** field. This field contains the new resource's resource ID, which you might want to map to a subsequent step in the flow.

Next steps

If this flow needs additional steps to obtain the data that you want the new resource to contain, add them before this FHIR connection. After those steps are in place, add a data mapper step to the flow just before the FHIR connection that creates a new resource. In the data mapper step, map to the fields in the resource to be created.

CAUTION

Without a data mapper step just before a FHIR connection that creates a new resource, the connection tries to create an empty resource. Depending on the FHIR server configuration, this might or might not work.

9.5. UPDATING ALL FIELDS IN A RESOURCE ON A FHIR SERVER

In an integration, you can update a resource that is on a FHIR server. To provide the updated values, add a data mapper step to the flow just before a FHIR connection that updates a resource. It is expected that previous steps in the flow provide the data that you want the updated resource to contain. Map fields in the previous steps to fields in the target resource that this FHIR connection updates.

CAUTION

The updated resource contains only the fields that you map to. In other words, in addition to mapping the fields whose values are changing, you must map the fields that you want to be in the resource and whose values are not changing. If you do not map a particular resource field then the connection deletes that field from the updated resource.

Be sure to map the resource ID from a previous step to the resource ID in this connection. This is the only resource field that the connection does not change. If the FHIR server does not already have a resource that has the resource ID for the resource to be updated, then the connection creates a new resource with that resource ID. This is the only way to add a new resource that has a resource ID that you choose.

To update or create a resource, add a FHIR connection to the middle of a flow, or as a simple integration's finish connection.

Prerequisites

- You created a connection to the FHIR server on which you want to update or create a resource.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to add a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the FHIR connection that you want to use to update a resource on a FHIR server.
3. On the **Choose an action** page, select **Update**.
4. Click in the **Resource Type** field to display a list of FHIR resource types. Select or enter the type of resource that you want to update or create.
5. In the **Contained Resource Types** field, if the resource type that you want to update or create contains other resource types, select them. Use the **Ctrl** key if you need to select more than one.
Identifying contained resource types lets the data mapper display the fields that are in the contained resources. If you do not specify a contained resource type then you cannot map to or from any fields that are in the contained resource. There is no harm in selecting a resource that is not actually contained.
6. Click **Next** to add this connection to the flow.
7. If this flow needs additional steps to obtain the data that you want the updated resource to contain, add them before this FHIR connection.
8. In the integration visualization, click the plus sign that is before the FHIR connection that updates a resource.
9. Click **Data Mapper**.
10. In the data mapper:
 - a. Map a resource ID to the target resource ID. This is the only way to specify the resource ID for a new resource.
 - b. Map to each resource field that you want the updated or new resource to contain. Be sure to map fields whose values are not changing, as well as fields whose values need to be updated.
 - c. Click **Done** to add the data mapper step to the flow.

Result

The connection appears in the integration visualization where you added it. During execution, the connection updates or creates a resource on the FHIR server and returns a **MethodOutcome** resource that includes an **id.idPart** field. This field contains the updated/created resource's ID, which you might want to map to a subsequent step in the flow.

9.6. UPDATING SPECIFIED FIELDS IN A RESOURCE ON A FHIR SERVER

In an integration, you can update individual fields in a resource that is on a FHIR server. To do this, add a FHIR connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a connection to the FHIR server that has the resource that you want to update.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the FHIR connection that you want to use to update the resource.
3. On the **Choose an action** page, select **Patch**.
4. Click in the **Resource Type** field to display a list of FHIR resource types. Select or enter the type of the resource whose fields you want to update.
5. In the **Number of Operations** field, specify the number of fields that you want to update.
6. Leave the **Resource id** field blank if you want to map the value from a previous step in the flow, which is typically what you want to do. Otherwise, specify the resource ID of the resource whose fields you want to update.
Note: For the current release, the JSON patch option does not work. Instead, use the Data Mapper to update the fields as described in the following steps.
7. Click **Next** to add this connection to the flow.
8. Add a data mapper step:
 - a. In the flow visualization, click the plus sign that is before the FHIR connection that you just added.
 - b. Click **Data Mapper**.
The **Target** panel displays a numbered folder for each field that you want to update. When you configured the **Patch** action, you specified how many fields to update. The data mapper displays this number of folders in the **Target** panel. For example, if you specified 3 as the number of fields to update, you would see three target folders with the labels **1**, **2**, and **3**.
 - c. For each field that you want to update, map to the fields in one target folder:
 - i. In the **Target** panel, expand a folder to display three fields for **op**, **path**, and **value**.
 - ii. Map a source field, constant, or property to the target **path** field. The path identifies the resource field that you want to update. In a path value, a number indicates the index of a list field, and a slash leads to a child field. For example, map this path **/name/1/given/1/value** to update the value of the given name field.
 - iii. Accept the default update operation, which replaces the current value of the field, or map a source field, constant, or property to the **op** field to indicate how you want to update the field. For details about possible operations, see [JSON patch operations](#).
 - iv. If you are updating a field to have a new value, then map a source field, constant, or property to the target **value**. This is the new value that you want the field to contain.
 - d. If you did not specify a resource ID when you configured the **Patch** action, then map the resource ID to the target **id** field.
 - e. Click **Done** to add the data mapper step to the flow.

Result

The connection appears in the integration visualization where you added it. During execution, the connection updates the specified resource field(s) and returns a **MethodOutcome** resource that includes an **id.idPart** field. This field contains the ID of the resource that was updated.

9.7. CREATING RESOURCES OF DIFFERENT TYPES ON A FHIR SERVER

In an integration, you can create two or more resources on a FHIR server and each resource can be of a different type. For example, you can add a new patient resource and a new provider resource in one connection to a FHIR server. To do this, add a FHIR connection to the middle of a flow, or as a simple integration's finish connection.

Prerequisites

- You created a connection to the FHIR server that you want to add resources to.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the FHIR connection that you want to use to create and add new resources to a FHIR server.
3. On the **Choose an action** page, select **Transaction**.
4. In the **Included Resource Types** field, select the resource types that this connection creates. Use the **Ctrl** key to select multiple resource types. The connection creates one resource of each type that you select.
5. Click **Next** to add this connection to the flow.
6. To populate fields in the new resources, add a data mapper step before this connection:
 - a. In the flow visualization, click the plus sign that is before the connection that you just added.
 - b. Click **Data Mapper**.
 - c. In the data mapper, map source fields to the target resource fields. The new resources contain only the target fields that you map to.
 - d. Click **Next** to add the data mapper step to the flow.

Result

The connection appears in the integration visualization where you added it. During execution, the connection adds all resources to the FHIR server or, if there is an error, the connection does not add any resources to the FHIR server. A successful action returns a transaction resource, which contains the resource ID for each new resource. You can map these resource IDs to subsequent steps in the flow.

9.8. DELETING A RESOURCE FROM A FHIR SERVER

In an integration, you can delete a resource from a FHIR server. To do this, add a FHIR connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a connection to the FHIR server that has the resource that you want to delete.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to select a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the FHIR connection that you want to use to delete the resource.
3. On the **Choose an action** page, select **Delete**.
4. Click in the **Resource Type** field to display a list of FHIR resource types. Select or enter the type of resource that you want to delete.
5. In the **Resource Id** field, specify the resource ID of the resource that you want to delete or leave this field blank if you plan to map the resource ID from an earlier step in the integration.
6. In the **Resource version** field, optionally specify a version ID for the resource. Leave this field blank to delete the most recent version of the resource or to map the version ID of the resource that you want to delete from a previous step.
7. Click **Next** to add this connection to the flow. .

Result

The connection appears in the integration visualization where you added it. During execution, the connection deletes the specified resource on the FHIR server and returns a **MethodOutcome** resource that includes an **id.idPart** field. This field contains the resource ID for the deleted resource.

Next steps

To map a value to the **Resource Id** field or the **Resource version** field, add a data mapper step before this connection.

CHAPTER 10. CONNECTING TO AN FTP OR SFTP SERVER

In an integration, you can connect to an FTP or SFTP server to download or upload files. To do this, create an FTP or SFTP connection and then add it to an integration flow. The following topics provide details:

- [Section 10.1, "Creating an FTP or SFTP connection"](#)
- [Section 10.2, "Obtaining files from an FTP or SFTP server"](#)
- [Section 10.3, "Uploading files to an FTP or SFTP server"](#)

10.1. CREATING AN FTP OR SFTP CONNECTION

In an integration, to download or upload files from/to an FTP or SFTP server, create a connection to that FTP or SFTP server. You can add the same connection to any number of integrations.

Prerequisite

You must know the host name of the server you want to connect to.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. To create a connection that uses File Transfer Protocol, click the **FTP** connector.
Or, to create a connection that uses Secure File Transfer Protocol, click the **SFTP** connector.
4. Configure the connection.
 - For an FTP connection:
 - **Host** is the only parameter that you must specify. Enter the host name of the server that you want to connect to. For example, if the name of your FTP host is **FTP.WEST**, then you would enter exactly that, **FTP.WEST**. Do not specify the protocol, for example, you should not specify something like this: **ftp://FTP.WEST**.
 - **Port** is required and has a default value of **21**. This is the port that the FTP server is listening on.
 - All other parameters are either not required or have default values. The defaults are suitable for most integrations. Descriptions of these parameters are after this procedure.
 - For an SFTP connection, there must be values for these parameters:
 - **Host** is the host name of the SFTP server that you want to connect to. For example, if the name of your SFTP host is **SFTP.EAST**, then you would enter exactly that, **SFTP.EAST**. Do not specify the protocol, for example, you should not specify something like this: **sftp://SFTP.EAST**.
 - **Port** has a default of **22**. This is the port that the SFTP server is listening on.
 - **User name** of the account that you want to use to access the SFTP server.

- **Password** that is associated with that user name.
 - All other parameters have default values. The defaults are suitable for most integrations. Descriptions of these parameters are after this procedure.
5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether or not validation is successful. If validation fails, revise the configuration details as needed and try again.
 6. When validation is successful, click **Next**.
 7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **XLight FTP Server**.
 8. In the **Description** field, optionally enter any information that is helpful to know about this connection.
 9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **XLight FTP Server** appears as a connection that you can choose to add to an integration.

Descriptions of other parameters

- **Connect timeout** defaults to **10000** milliseconds and indicates a maximum wait of 10 seconds to establish the connection. If 10 seconds elapse without a connection then Fuse Online waits for the number of milliseconds defined by **Reconnect delay** and then tries to reconnect.
- **Reconnect delay** defaults to **1000** milliseconds and indicates the wait time before trying to reconnect again.
- **Maximum reconnect attempts** defaults to **3**. Fuse Online tries as many as 3 times to establish a connection.
- **Binary file transfer mode** is used by default. Select **No** for ASCII transfer mode.
- **Passive connection mode** defaults to **Yes**, which is usually the preferred mode. In passive mode, the client opens communication channels with the server as a way to avoid firewall issues. If you select **No** then active mode is used.
- **Disconnect from the server after used** defaults to **No**. The connection remains established after it performs the action. Select **Yes** if you want to disconnect from the server after the connection performs the upload or download.
- **Data timeout** defaults to **30000** milliseconds and indicates the maximum length of time that Fuse Online waits for a reply.

10.2. OBTAINING FILES FROM AN FTP OR SFTP SERVER

To trigger integration execution when an FTP or SFTP connection finds the file(s) you are interested in, add an FTP or SFTP connection as an integration's start connection.

Prerequisite

You created an FTP or SFTP connection.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the FTP or SFTP connection that you want to use to poll an FTP or SFTP server.
4. On the **Choose an action** page, select **Download**.
5. In the **File name expression** field, if you are interested in a single file, then enter an [Apache Camel Simple language](#) expression that resolves to a file name. You cannot specify a regular expression. The connection polls (periodically checks) the server for this file and downloads it when it is found. Leave this field blank if you want to download more than one file.
6. In the **FTP directory** field, enter the absolute or relative path of the server directory to poll. The connection watches this directory for any content and downloads all files when it finds any content.
7. In the **Milliseconds before polling starts** field, accept the default of **1000** milliseconds or change the number of milliseconds.
8. In the **Milliseconds before the next poll** field, accept the default of **500** milliseconds or change the number of milliseconds. This is the interval between polls.
9. In the **Delete after download** field, accept the default of **No** or select **Yes** to download the file(s) and then delete it(them) from the server.
10. Click **Next** to specify the action's output type.
11. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
12. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 13. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.

You will see this data type name when you are creating or editing an integration that uses the

You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.

14. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
15. Click **Next**.

Result

The connection appears at the beginning of the integration visualization.

10.3. UPLOADING FILES TO AN FTP OR SFTP SERVER

In an integration, you can upload files to an FTP or SFTP server in the middle of a flow or to finish a simple integration. To do this, add an FTP or SFTP connection to the middle of a flow or as a simple integration's finish connection.

Prerequisite

- You created an FTP or SFTP connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the FTP or SFTP connection that you want to use to upload files.
3. On the **Choose an action** page, select **Upload**.
4. In the **File name expression** field, if you want to upload only one particular file, then enter an [Apache Camel Simple language](#) expression that resolves to a file name. This is the name of the file that the action uploads to the server. You cannot specify a regular expression. To upload more than one file, leave this field blank.
5. In the **FTP directory** field, enter the absolute or relative name of a server directory. If the **File name expression** field contains an expression, then the connection stores the specified file in this directory. If the **File name expression** field is blank, then the connection uploads to this directory all files that were received from the previous step.
6. In the **If file exists** field, indicate the behavior when you are uploading a file that has the same path and name as a file that is on the server. Accept the default, **Override**, to overwrite the file that is on the server with the file that you are uploading. Or, select one of the following:
 - **Append** adds the content in the file being uploaded to the file that is on the server.
 - **Fail** throws **GenericFileOperationException**. The integration does not enter an error state.
 - **Ignore** does not upload the file. The integration continues running under the assumption that everything is okay.
 - **Move** renames one of the files.

- **TryRename** uploads the file with a temporary name and renames the file to the desired name. This operation does not check for the existence of a file with the desired name, which makes the operation faster on most servers than when existence checks are done.
7. In the **Temporary file prefix while copying** field, specify a string. The connection prepends this string to the name of a file while it is being uploaded. This enables the connection to write to a temporary file on the server and then rename that temporary file to have the correct name. This is useful for reducing locks when uploading very large files.
 8. In the **Temporary file name while copying** field, specify a string. The connection renames a file being uploaded to have this name while it is being uploaded. This enables the connection to write to a temporary file on the server and then rename that temporary file to have the correct name. This is useful for reducing locks when uploading very large files.
 9. Click **Next** to specify the action's input type.
 10. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
11. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 12. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 13. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 14. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

CHAPTER 11. CONNECTING TO GOOGLE APPLICATIONS

An integration can connect to these Google applications: Gmail, Calendar, Sheets. See the following topics for details:

- [Section 11.1, “Registering Fuse Online as a Google client application”](#)
- [Section 11.2, “Connecting to Gmail”](#)
- [Section 11.3, “Connecting to Google Calendar”](#)
- [Section 11.4, “Connecting to Google Sheets”](#)

11.1. REGISTERING FUSE ONLINE AS A GOOGLE CLIENT APPLICATION

In an integration, to be able to connect to Gmail, Google Calendar, or Google Sheets, you must register your Fuse Online environment as a Google client application. During registration, you enable Google APIs and create credentials that Fuse Online uses to access the Google APIs that you have enabled.

With registration in place, you can create multiple connections to Gmail, Google Calendar, and Google Sheets. You can use each connection in multiple integrations. While each connection to a Google application can use the same Google client ID and Google client secret, which you obtain during registration, each connection can access a different Google account, which you choose.

This procedure instructs you to enable the Gmail API, the Google Calendar API, and the Google Sheets API. However, you can enable only the API(s) that you need rather than all three APIs. At a later time, if you need to create connections to the applications whose APIs you did not enable, you can return here and follow the instructions to enable their APIs.



IMPORTANT




You must create a new Google client application for Fuse Online. The credentials that Google provides for a new client application contain a refresh token that is used for refreshing expired access tokens. This refresh token is available only the first time that the Fuse Online client application uses the credentials. In Fuse Online, connections to Gmail, Google Calendar, and Google Sheets can all use the same Google client ID and Google client secret. If they do, the refresh token is available to all connections to Google applications. When you view connection details in the Fuse Online user interface, do not click the **Validate** button. Validation is a second use of the credentials and the refresh token is no longer part of the client credentials. You can, however, re-connect to Google applications.



In development environments, be careful if you choose to use the Google client ID and Google client secret that you are using for some other, non-Fuse Online, OAuth client. Fuse Online requires offline access that is requested on the first OAuth exchange. If another OAuth client already entered the OAuth exchange and did not request offline access, then Fuse Online cannot obtain offline access on subsequent OAuth exchanges. If you are unsure whether offline access was requested on the first exchange, create a new Google client application for Fuse Online.

Prerequisites

- You must be able to sign in to the Google account that you want to use to register Fuse Online as a Google client application.

Procedure

1. In Fuse Online:
 - a. In the left navigation panel, click **Settings**.
 - b. On the **Settings** page, near the top, to the right of the callback URL, click  to copy the callback URL for your Fuse Online environment to the clipboard. You will need this URL later in this procedure.
2. In another browser tab, go to <https://console.developers.google.com> and do the following:
 - a. Check that you are signed into the Google account that you want to use to register Fuse Online as a Google client application. Or, choose a different Google account and sign in to that account.
The name of the current Google project appears at the top of the Google APIs page.
 - b. To use the current project to grant authorization to Fuse Online, continue to the next step. To grant authorization to Fuse Online in another Google project, choose or create that project. If this Google account does not already have a project, you must create one.
 - c. Enable Google APIs:
 - i. In the upper left corner, click  and select **APIs and Services > Library**.
 - ii. If necessary, scroll down to see the **G Suite** row of cards.
 - iii. Click the **Google Calendar API** card, which displays a page that indicates that the Google Calendar API is enabled.
 - iv. Scroll down and click the **Gmail API** card, which displays a page that indicates that the Gmail API is enabled.
 - v. In the upper left corner, click  and select **APIs and Services > Library**.
 - vi. If necessary, scroll down to see the **G Suite** row of cards.
 - vii. Click the **Google Sheets API** card, which displays a page that indicates that the Google Sheets API is enabled.
 - d. Give your client application a name:
 - i. Click **MANAGE**.
 - ii. In the page that appears, in the left navigation panel, click **Credentials** and then on the right, click **Credentials in APIs & Services**
 - iii. Click the **OAuth consent screen** tab.
 - iv. In the page that appears, in the **Application Name** field, enter a name for the Fuse Online client application. For example, enter **Fuse Online client application**.
 - v. Skip the other fields.
 - vi. Click **Save**.
 - e. Obtain client application credentials as follows:

- i. To the right of **Create Credentials**, click the down arrow to display a menu and select **OAuth client ID**.
 - ii. In the page that appears, select **Web application** to display more content.
 - iii. In the **Name** field, enter a name for the OAuth client ID for your Fuse Online environment. This is different from the name that you entered for the client application itself. For example, enter **OAuth client ID for Fuse Online**.
 - iv. Skip **Authorized JavaScript origins**.
 - v. In the **Authorized redirect URIs** field, paste the callback URL that you copied from your Fuse Online environment at the beginning of this procedure.
 - vi. Click **Create** to display the client ID and client secret for your Fuse Online environment.
- f. To the right of the client ID field, click  to copy the client ID to your clipboard.
3. Return to the Fuse Online **Settings** page and do the following:
 - a. Expand the entries for Gmail, Google Calendar, and Google Sheets.
 - b. In the **Client ID** field for each Google application, paste the Google client ID that you just copied.
 4. Return to the Google developers site and to the right of the client secret field, click  to copy the client secret to your clipboard.
 5. Return to the Fuse Online **Settings** page and do the following in the entry for each Google application:
 - a. In the **Client Secret** field, paste the Google client secret that you just copied.
 - b. Click **Save**. You should get a **Registration Successful!** notification.
 - c. Collapse the entry.

Results

For each Google application API that you enabled, you can create a connection to that application.

All connections from Fuse Online to Google applications use the same Google client ID and Google client secret.



IMPORTANT

The Google client ID and Google client secret contain token refresh information to ensure that integrations that have connections to Google applications continuously work correctly. Consequently, you should **not** obtain new credentials. If you do, then you would need to recreate each Google connection, replace the old connections with new connections, and re-publish each integration that uses a Google connection.

11.2. CONNECTING TO GMAIL

To trigger execution of an integration when a particular Gmail account receives an email, add a Gmail connection to a simple integration as its start connection. In an integration, to send an email from a particular Gmail account, do either of the following:

- Add a Gmail connection to the middle of a flow.
- Add a Gmail connection to finish a simple integration.

The general steps for connecting to Gmail in an integration are:

1. [Registering Fuse Online as a Google client application](#) .
2. Creating a Gmail connection. When you do this you choose the Gmail account that the connection is authorized to access.
3. If your integration sends an email from a Gmail account, decide how to populate an email to send.
4. Adding a Gmail connection to an integration flow.
5. For a Gmail connection that sends an email, optionally mapping integration data to the email fields.

Information and instructions are in the following topics:

- [Section 11.2.1, "Creating a Gmail connection"](#)
- [Section 11.2.2, "Alternatives for populating email to send"](#)
- [Section 11.2.3, "Triggering an integration when polling returns a Gmail message"](#)
- [Section 11.2.4, "Sending an email from a Gmail account"](#)

11.2.1. Creating a Gmail connection

When you create a Gmail connection, you authorize the connection to access one particular Gmail account. After you create a Gmail connection, you can add it to multiple integrations.

Prerequisites

- You [registered Fuse Online as a Google client application](#) and enabled the Gmail API.
- The Fuse Online **Settings** page entry for Gmail has values for the client ID and client secret, which you obtained by registering Fuse Online as a Google client application.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display the available connectors. A connector is a template that you use to create one or more connections.
3. Click the **Gmail** connector.
4. In the **Configure Connection** page, click **Connect Gmail**, which takes you to a **Sign in with Gmail** page.
If **Connect Gmail** does not display, your Fuse Online environment is not registered as a Google

client application. See [Registering Fuse Online as a Google client application](#) . When you try to create a Gmail connection and your Fuse Online environment is not registered as a Google client application, then Fuse Online displays multiple fields that prompt for authorization information. While you can create a Gmail connection by entering values in these fields, it is not recommended.

5. In the page that is prompting you to sign in to Gmail, enter the email address of the Google account that you want this connection to access from Fuse Online and click **Next**.
6. In response to **openshiftapps.com wants to access your Google Account**, click **Allow** to return to Fuse Online.
7. In the Fuse Online **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Gmail Connect 1**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Gmail connection that uses jkim Gmail account credentials**.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Gmail Connect 1** appears as a connection that you can choose to add to an integration.

11.2.2. Alternatives for populating email to send

A Gmail connection that finishes a simple integration or that is in the middle of a flow sends an email from the Gmail account that the connection is authorized to access. There are several ways to populate the content of the email that the connection sends. Before you add a Gmail connection that sends an email, consider how you want to populate that email.

The alternatives for populating an email to send are as follows:

- Add a data mapper step just before the Gmail connection that sends an email. In this data mapper step, map data fields that are output from previous steps to Gmail connection **Send Email** action fields. The **Send Email** action fields are:
 - **Email to**
 - **Email subject**
 - **Email text**
 - **Email cc**
 - **Email bcc**

If you add a data mapper step then you can map one, some, or all **Send Email** action fields.

- When you add a Gmail connection to a flow, configure the action by specifying values in the **Send Email** action fields. You can specify values in one, some, or all fields.
- Use both a data mapper step and **Send Email** action configuration to populate the fields. In other words, you can configure the **Send Email** action by specifying one or more fields and also add a data mapper step that populates other fields.
A value that you specify directly in a **Send Email** action field has precedence over a value that is mapped to the **Send Email** action field. In other words, suppose you populate a **Send Email** field by specifying a value when you add the connection and configure the action and also by

mapping a value to the same field. The value that you specify in the action configuration always overrides the value that was mapped. For example, suppose you specify **people@redhat.com** in the **Email to** action field and you also map an email field from a previous step to the Gmail **Email to** field. The integration always uses **people@redhat.com** as the email address.

When you add a Gmail connection that sends an email, all action configuration parameters are optional. This is because you might choose to populate an email entirely by mapping integration data to the **Send Email** action fields. However, the presence of an email address in the **Email to** field, either by action configuration specification or by mapping, is required. Without an email address to send the message to, Fuse Online generates a runtime error and the integration stops executing.

11.2.3. Triggering an integration when polling returns a Gmail message

To trigger execution of an integration based on email received by a particular Gmail account, add a Gmail connection as the start connection of a simple integration. When the integration is running, the Gmail connection checks this account for emails at intervals that you control. When the connection finds an unread email, it passes the email to the next step in the integration and, by default, marks the email as **read**.

Prerequisites

- You created a Gmail connection that is authorized to access the Gmail account that you want to obtain emails from.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Gmail connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Receive Email** action.
5. To configure the **Receive Email** action:
 - a. In the **Delay** field, accept the default of 30 seconds or specify how often you want the integration to check for new email.
 - b. Leave the **Labels** field blank to obtain any unread email. To obtain only certain emails, specify a comma-separated list of labels that are used in the Gmail account that the connection is accessing. By default, the integration obtains the unread emails that have those labels.
 - c. Select **Mark as read** to ensure that the connection does not return the same email twice. If **Mark as read** is not selected, the connection returns emails that are in the account's in box, whether or not they were previously read. Or, if you specify one or more labels, then the integration return emails that have those labels whether or not they were already read.
 - d. In the **Max Results** field, accept the default of **5** or indicate the maximum number of emails that the connection can return for each poll. If the connection finds more than this number of unread emails, then it returns the most recent **Max Results** emails.
When a Gmail connection returns more than one email, the integration processes the emails as a batch. In other words, Fuse Online executes the integration once for the batch.

- e. Click **Next** to add this Gmail connection as the start connection in the integration. The connection appears as the first step in the integration flow.

11.2.4. Sending an email from a Gmail account

In an integration, you can send an email from a Gmail account either in the middle of a flow or to finish a simple integration. To do this, add a Gmail connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a Gmail connection.
- You are familiar with the [alternatives for populating an email to send](#) and you have a plan for populating such emails.
- Fuse Online is prompting you to add to the integration or to choose the finish connection for a simple integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the Gmail connection that you want to use to send an email.
3. On the **Choose an action** page, select **Send Email**.
4. On the **Configure Send Email** page, do one of the following:
 - Leave all fields blank if you plan to add a data mapper step just before this connection and you plan to map integration data to the **Send Email** fields.
 - Enter information in one or more of the following **Send Email** fields. Separate multiple email addresses with a comma.
 - a. **Email To**
 - b. **Email Subject**
 - c. **Email Text**
 - d. **Email cc**
 - e. **Email bcc**
 - Leave some fields blank and enter information in some fields.
If you plan to add a data mapper step just before this Gmail connection, and you want to map integration data to some email fields, leave those fields blank in the action configuration. Enter values in other action fields as needed.

A value that you specify in a **Send Email** action configuration field has precedence over a value that is mapped from a previous step.
5. Click **Next** to add the connection to the flow.

Result

The connection appears in the integration flow where you added it.

Next step

If you plan to add a data mapper step before this connection, first add any other connections that you plan to add to this flow. Then add the data mapper step.

11.3. CONNECTING TO GOOGLE CALENDAR

To trigger integration execution when a poll returns an update to a Google calendar, add a Google Calendar connection to a simple integration as its start connection. To add an event to a calendar or update an event in a calendar, you can do either of the following:

- Add a Google Calendar connection to the middle of a flow.
- Add a Google Calendar connection to finish a simple integration.

Details for connecting to Google Calendar are in the following topics:

- [Section 11.3.1, "Creating a Google Calendar connection"](#)
- [Section 11.3.2, "Triggering an integration when polling returns an event from a Google Calendar"](#)
- [Section 11.3.3, "Obtaining a particular event from a Google Calendar"](#)
- [Section 11.3.5, "Updating an event in a Google Calendar"](#)
- [Section 11.3.4, "Adding an event to a Google Calendar"](#)

11.3.1. Creating a Google Calendar connection

When you create a Google Calendar connection, you authorize the connection to access the Google Calendars that are associated with one particular Google account. After you create a Google Calendar connection, you can add it to multiple integrations.

Prerequisites

- You [registered Fuse Online as a Google client application](#) and enabled the Google Calendar API.
- The Fuse Online **Settings** page entry for Google Calendar has values for the client ID and client secret, which you obtained by registering Fuse Online as a Google client application.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display the available connectors. A connector is a template that you use to create one or more connections.
3. Click the **Google Calendar** connector.
4. In the **Configure Connection** page, click **Connect Google Calendar**, which takes you to a Google sign-in page.

If **Connect Google Calendar** does not display, then your Fuse Online environment is not registered as a Google client application with the Google Calendar API enabled. See [Registering Fuse Online as a Google client application](#). When your environment is not registered with

Google, then when you try to create a Google Calendar connection, Fuse Online displays multiple fields that prompt for authorization information. While you can create a Google Calendar connection by entering values in these fields, it is not recommended.

5. In the Google sign-in page, select the Google account that you want this connection to access from Fuse Online and click **Next**.
6. In response to the **openshiftapps.com wants to access your Google Account** prompt, click **Allow** to return to Fuse Online.
7. In the Fuse Online **Name** field, enter your choice of a name that helps you distinguish this connection from other connections. For example, enter **Google Calendar Work Connection**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Google Calendar connection that uses my Google work account**.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Google Calendar Work Connection** appears as a connection that you can choose to add to an integration.

11.3.2. Triggering an integration when polling returns an event from a Google Calendar

To trigger execution of an integration upon obtaining events from a Google Calendar that you specify, add a Google Calendar connection to a simple integration as its start connection. When the integration is running, the Google Calendar connection checks the Google Calendar for events at intervals that you control. When the connection finds events that comply with the way that you configured the Google Calendar **Get Events** action, the connection passes the events to the next step in the integration.

When a Google Calendar connection returns more than one event, Fuse Online executes the integration for each returned event. For example, if the poll returns 5 events then Fuse Online executes the integration five times.

Prerequisites

- You created a Google Calendar connection.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Google Calendar connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Get Events** action.
5. To configure the **Get Events** action:
 - a. In the **Delay** field, accept the default of 30 seconds or specify how often you want the integration to check the calendar.
 - b. In the **Calendar name** field, enter the name of a calendar that is accessible from the Google account that this Google Calendar connection is authorized to access.

- c. In the **Max Results** field, accept the default of **5** or indicate the maximum number of events that the connection can return for each poll.
 - d. Select one of the following to indicate the date that you want the connection to use to start checking for events. The connection checks that date and subsequent dates.
 - **Consume from the current date ahead** starts on the current date.
For example, if you select this option, and if **Max Results** is 5, then the Google Calendar connection starts checking for events on the current date and returns no more than the first five events that it finds. It does not matter whether or not these events have been updated or added since the last poll.
 - **Consume from the last event update date on the next poll** starts on the date of the most recently updated event that was returned in a previous poll.
For example, if you select this option, and if **Max Results** is 5, then the Google Calendar connection returns no more than 5 updated or new events. The connection starts checking for new or updated events on the date of the most recently updated event that was returned in a previous poll.
 - e. Optionally, in the **Query for events** field, specify text to filter the events that the poll can return. The connection returns only events that contain the specified text in at least one event field.
For example, suppose that you specify **Standup meeting** in the query field. A poll would return only those events that have **Standup meeting** in an event field.
6. Click **Next** to add this Google Calendar connection as the integration's start connection.

Result

The connection appears as the first step in the simple integration.

11.3.3. Obtaining a particular event from a Google Calendar

In an integration, you can obtain a particular Google Calendar event in the middle of a flow. Obtaining a particular event is useful, for example, when you want to:

- Update the event in a subsequent Google Calendar connection.
- Announce the event by using a subsequent Twitter connection.

To obtain one event, add a Google Calendar connection to the middle of a flow.




NOTE

In this release, while obtaining a specific event in a simple integration's finish connection is supported, it is not particularly useful. This is expected to change in a future release.

Prerequisites

- You created a Google Calendar connection that is authorized to access the Google Calendar that has the event that that you want to get.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection.
2. Click a Google Calendar connection that is authorized to access the calendar that you want to connect to.
3. On the **Choose an action** page, select **Get a Specific Event**
4. Specify the name of the calendar that has the event that you want.
5. Specify the ID of the event to get. To obtain the event ID, do one of the following:
 - Map it from a previous Google Calendar connection.
 - Manually obtain it from the calendar as follows:
 - a. In a browser, display the calendar that contains the event you want to get.
 - b. Append **?gsessionid=OK&eventdeb=1** to the URL and redisplay the calendar.
 - c. In the calendar, click the event that you want to get.
 - d. In the event popup, click  and select **Troubleshooting info**.
 - e. In the popup that Google Calendar displays, copy the string that follows **eid=**. For example, an event ID looks something like this:
p1pva2a4t504gbsha12di9ch6k_20181107T150000Z*.
6. Click **Next** to add the connection to the flow.

Result

The connection appears in the flow where you added it.

Next step

If you want to map any values from a previous step to the fields in this connection, add a data mapper step. First, add all needed connections to the flow. Then add a data mapper step immediately before this connection.

11.3.4. Adding an event to a Google Calendar

In an integration, you can add an event to a Google Calendar in the middle of a flow or to finish a simple integration. To do this, add a Google Calendar connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a Google Calendar connection that is authorized to access the Google Calendar to which you want to add an event.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.

2. Click a Google Calendar connection that is authorized to access the calendar that you want to add an event to.
3. On the **Choose an action** page, select the **Create Event** action.
4. Configure the **Create Event** action:
 - a. Enter a title for the new event.
 - b. Enter the name of the Google Calendar to add the event to.
 - c. For the other input parameters, you can enter data or you might want to map values from an event that you obtained in a previous Google Calendar connection.
5. Click **Next** to add the connection to the flow.

Result

The connection appears in the integration flow where you added it.

Next step

If you want to map any values to the fields in this Google Calendar connection, add a data mapper step to the flow. First, add all needed connections to the flow. Then add a data mapper step immediately before this Google Calendar connection.

11.3.5. Updating an event in a Google Calendar

In an integration, you can update an event in a Google Calendar in the middle of a flow or to finish a simple integration. To do this, add a Google Calendar connection to the middle of a flow or as a simple integration's finish connection.



IMPORTANT

In this release, the **Update Event** action requires a value in each event field. In most if not all cases, this means that you must add a Google Calendar connection that [obtains the event that you want to update](#), then add the Google Calendar connection that updates the event, and then insert a data mapper step between the two Google Calendar connections.

Prerequisites

- You created a Google Calendar connection that is authorized to access the Google Calendar that has the event that you want to update.
- In the flow, there is an earlier connection to Google Calendar and that connection obtains the event that you want to update.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.

2. Click a Google Calendar connection that is authorized to access the calendar that has the event that you want to update.
3. On the **Choose an action** page, select **Update Event**
4. To configure the **Update Event** action:
 - a. Enter the title of the event that you want to update.
 - b. Enter content in each event field that you want to update. Do not enter content in an event field when you want the content in that field to remain unchanged.
5. Click **Next** to add the connection to the flow. The connection appears in the integration visualization where you added it.
6. In the integration visualization, click the plus sign that is just before the connection that you just added.
7. Click **Data Mapper**.
8. In the data mapper, for each event field that remains the same in the updated event, map that field from the Google Calendar connection that obtained the event to the corresponding field in the Google Calendar connection that updates the event.
Do not map fields that you are updating. If you map a field and also specify an update for that field when you configure the **Update Event** action, Fuse Online uses the mapped value.
9. In the upper right, click **Done** to add the data mapper step.

11.4. CONNECTING TO GOOGLE SHEETS

To trigger execution of an integration when a Google Sheets connection returns spreadsheet data or spreadsheet properties, add a Google Sheets connection to a simple integration as its start connection. To finish a simple integration by updating spreadsheet values or properties, or by inserting a chart or pivot table into a spreadsheet, add a Google Sheets connection to a simple integration as its finish connection.

In the middle of a flow, you can add a Google Sheets connection that obtains, creates or updates values in a spreadsheet, or that inserts a chart or pivot table into a spreadsheet.

Details for connecting to Google Sheets are in the following topics:

- [Section 11.4.1, "Creating a Google Sheets connection"](#)
- [Section 11.4.2, "Obtaining spreadsheet data to trigger an integration or in the middle of a flow"](#)
- [Section 11.4.3, "Triggering an integration when polling returns spreadsheet properties"](#)
- [Section 11.4.4, "Creating a spreadsheet"](#)
- [Section 11.4.5, "Updating data in a sheet"](#)
- [Section 11.4.6, "Appending data to a sheet"](#)
- [Section 11.4.7, "Updating spreadsheet properties"](#)
- [Section 11.4.8, "Adding a chart to a sheet"](#)

- [Section 11.4.9, “Adding a pivot table to a sheet”](#)

11.4.1. Creating a Google Sheets connection

When you create a Google Sheets connection, you authorize the connection to access the Google Sheets spreadsheets that are associated with one particular Google account, which you choose. After you create a Google Sheets connection, you can add it to multiple integrations.

Prerequisites

- You [registered Fuse Online as a Google client application](#) and enabled the Google Sheets API.
- The Fuse Online **Settings** page entry for Google Sheets has values for the client ID and client secret, which you obtained by registering Fuse Online as a Google client application.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display the available connectors. A connector is a template that you use to create one or more connections.
3. Click the **Google Sheets** connector.
4. In the **Configure Connection** page, click **Connect Google Sheets**, which takes you to a Google sign-in page.
If **Connect Google Sheets** does not display, then your Fuse Online environment is not registered as a Google client application with the Google Sheets API enabled. See [Registering Fuse Online as a Google client application](#). When your environment is not registered with Google, then when you try to create a Google Sheets connection, Fuse Online displays multiple fields that prompt for authorization information. While you can create a Google Sheets connection by entering values in these fields, it is not recommended.
5. In the Google sign-in page, select the Google account that you want this connection to access from Fuse Online and click **Next**.
6. In response to the **openshiftapps.com wants to access your Google Account** prompt, click **Allow** to return to Fuse Online.
7. In the Fuse Online **Name** field, enter your choice of a name that helps you distinguish this connection from other connections. For example, enter **Google Sheets Work Connection**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Google Sheets connection that uses my Google work account**.
9. Click **Save** to see that the connection that you created is now available. If you entered the example name, you would see that **Google Sheets Work Connection** appears as a connection that you can choose to add to an integration.

11.4.2. Obtaining spreadsheet data to trigger an integration or in the middle of a flow

To trigger execution of an integration upon obtaining data from a Google Sheets spreadsheet, add a Google Sheets connection to a simple integration as its start connection. When the integration is

running, the Google Sheets connection polls the spreadsheet at the interval that you specified, obtains the data that you identified, and passes the data to the next step in the integration.

To obtain spreadsheet data in the middle of a flow, add a Google Sheets connection as a middle connection. During execution, Fuse Online polls the spreadsheet for the specified data as soon as it starts processing this connection. In other words, the connection does not wait for an interval to elapse before polling the spreadsheet.

To obtain data from a particular sheet in a spreadsheet, you specify the sheet name when you configure the action for the Google Sheets connection. A particular connection can obtain data from only one sheet.

Between polls, if there are no changes to the sheet values that the connection is configured to return, then the next poll returns the same values as the previous poll.

Prerequisites

- You created a Google Sheets connection that is authorized to access the spreadsheet that you want to obtain data from.
- If this Google Sheets connection is triggering integration execution, then you are creating an integration and Fuse Online is prompting you to choose the start connection.
- If this Google Sheets connection is in the middle of a flow, then the integration already has a start connection and a finish connection, and Fuse Online is prompting you to add to the integration by choosing a step.

Procedure

1. Click the Google Sheets connection that you want to use.
2. On the **Choose an action** page, for a start connection, select the **Get sheet values** action or for a middle connection, select the **Retrieve sheet values** action.
3. To configure the action:
 - a. In the **SpreadsheetId** field, enter the ID of a Google spreadsheet that is accessible from the Google account that this Google Sheets connection is authorized to access.
To obtain a spreadsheet ID, display the spreadsheet in a browser. The ID is the part of the URL between **d/** and **/edit**.
 - b. In the **Range** field, enter Google A1 notation that identifies the data that you want to obtain. The default is **A:A**.
For example, suppose that you want all data from a spreadsheet that has one sheet with 4 columns. Specify **A:D**. Or, to obtain data from rows 5 through 15, specify **A5:D15**.

If the spreadsheet from which you are obtaining data has more than one sheet, specify the sheet name as well as the start cell coordinate and the end cell coordinate. If there is more than one sheet, and you do not specify a sheet name, then the connection obtains data from the first sheet in the spreadsheet. For example, specification of **2019!A1:D5** specifies that you want to obtain data from the sheet whose name is **2019**. In that sheet, you want the data that is in columns A through D for rows 1 through 5.

- c. In the **Major dimension** field, accept **Rows**, which is the default, or select **Columns**.
Rows configures the action to return a collection of row objects where each row object contains a value for each desired column. When **Major dimension** is **Rows**, Fuse Online can

display meaningful column headings as field names in the data mapper, rather than **A, B, C**, and so on.

Columns configures the action to return a collection of column objects where each column object contains a value for each desired row.

- d. In the **Header row number** field, if **Major dimension** is set to **Rows**, optionally enter the number of the row that contains the column headings in the data that the connection obtains. Specification of a header row enables Fuse Online to obtain the headings from the spreadsheet. If you do not specify a header row, column headings default to a letter heading for each column in the range of data that the connection obtains. You can edit obtained headings or letter headings in the subsequent page.



NOTE

If you are configuring a Google Sheets middle connection, the rest of the configuration options are not needed and Fuse Online does not prompt for them. Skip to step 4.

- e. In the **Split results** field, accept **No**, which is the default, or select **Yes**. A setting of **No** configures the action to return data as a collection of values. That is, the connection passes a collection of row objects or a collection of column objects to the next step in the flow. Select **Yes** to enable the connection to split the returned data according to the setting of **Major dimension**. For example, if **Major dimension** is set to **Rows** then the connection returns row objects. Each row object triggers a separate execution of the flow. That is, Fuse Online executes the flow once for each returned row object. For example, if the poll returns 5 rows then Fuse Online executes the flow 5 times.
- Fuse Online also provides discrete split and aggregate steps, which you can add to a flow. If you want to process individual objects in one or more steps and then aggregate the row or column objects, do not split the Google Sheets connection result. Instead, accept the default, **No**, and then add a split step to the flow after this connection. A split step is required if you want an aggregate step in the flow.
- f. In the **Delay** field, accept the default of 30 seconds or specify how often you want the connection to obtain spreadsheet data.
- g. In the **Max results** field, accept the default of **0** if you do not want to restrict how many rows or columns polling can return. The setting of **Max results** applies to the setting of the major dimension in the result matrix. To limit the data that the connection returns for the major dimension, specify an integer.
- For example, suppose that the major dimension is rows and that **Max results** is set to **25**. The poll returns no more than 25 rows of values.

When **Range** specifies the major dimension and you also specify **Max results**, polling uses the lower number to determine how much data to return. Consequently, setting a value for **Max results** is more helpful when you specify only the minor dimension for **Range**. For example, consider a sheet that has 30 rows with three columns of values in each row. Suppose that **Major dimension** is **Rows** and **Range** is **A:C**. If you set **Max results** to **10**, polling returns 10 rows of data. If you accept **0** as the setting of **Max results**, polling returns 30 rows. However, if you specify **Range** as **A1:C15** and you also specify **Max results** as **25**, polling returns 15 rows. If you specify **Range** as **A1:C30** and you also specify **Max results** as **25**, polling returns 25 rows.

4. Click **Next** to view the column names in the data that the connection obtains when **Major dimension** is set to **Rows**. If **Major dimension** is **Columns**, content in this field is ignored and you can click **Next** now to complete this procedure.

The values that appear in the **Column names** field become the field names that a data mapper step displays. If you specified a header row number, Fuse Online displays the headings from that row in the sheet that you are obtaining data from. If you left the header row number field blank, Fuse Online displays a letter (**A, B, C**, and so on) for each column in the range of data that you are obtaining.

5. Optionally, edit the **Column names** field so it contains the field names that you want to see in a data mapper step. The field must contain a comma-separated list with no spaces, for example, **Name,Address,City,State,Zip**.
6. Click **Next** to add this Google Sheets connection to the flow.

Next steps

If you added a Google Sheets connection as a start connection, Fuse Online prompts you to add the integration's finish connection. With the start and finish connections in the integration, add any other connections that you want in the integration.

After the connection that obtains sheet values, add a data mapper step. In the data mapper, Fuse Online displays source fields according to how you configure the action that obtains spreadsheet values. That is, if the major dimension is **Rows**, then the data mapper lists the column names as fields that you can map to the target. If the major dimension is **Columns**, then the data mapper lists row indexes as fields that you can map to the target.

Additional resource

[Google AI notation](#) for specifying groups of cells in a spreadsheet

11.4.3. Triggering an integration when polling returns spreadsheet properties

To trigger execution of an integration upon obtaining properties from a Google Sheets spreadsheet, add a Google Sheets connection to a simple integration as its start connection. When the integration is running, the Google Sheets connection polls the spreadsheet at the interval that you specified, obtains the spreadsheet properties, and passes the result to the next step in the integration.

Properties include the spreadsheet's title, locale, and time zone. Between polls, if there are no changes to the sheet properties, then the next poll returns the same values as the previous poll.

Prerequisites

- You created a Google Sheets connection that is authorized to access the spreadsheet that you want to obtain properties from.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Google Sheets connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Get spreadsheet properties** action.
5. To configure the **Get spreadsheet properties** action:

- a. In the **SpreadsheetId** field, enter the ID of a Google spreadsheet that is accessible from the Google account that this Google Sheets connection is authorized to access.
To obtain a spreadsheet ID, display the spreadsheet in a browser. The ID is the part of the URL between **d/** and **/edit**.
 - b. In the **Delay** field, accept the default of 30 seconds or specify how often you want the connection to obtain properties.
6. Click **Next** to add this Google Sheets connection as the integration's start connection.

Result

The integration now has a start connection and Fuse Online is prompting you to choose the integration's finish connection.

11.4.4. Creating a spreadsheet

To create a new spreadsheet in the middle of a flow, add a Google Sheets connection between the start and finish connections. While you can also finish a simple integration with a Google Sheets connection that creates a spreadsheet, you cannot add data to a new spreadsheet in the same connection. Therefore, when you want to create a spreadsheet and add data to the spreadsheet in the same flow, the flow requires two Google Sheets connections. One connection creates the spreadsheet and then a subsequent connection adds data to the spreadsheet.

Prerequisites

- You created a Google Sheets connection that is authorized to access the Google account in which you want to create the spreadsheet.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click a Google Sheets connection that is authorized to access the Google account that you want to use to create the spreadsheet.
3. On the **Choose an action** page, select **Create spreadsheet**
4. To configure the **Create spreadsheet** action:
 - a. In the **Title** field, enter the title of the new spreadsheet.
 - b. In the **Time Zone** field, enter the time zone that the new spreadsheet should use, for example, **India Standard Time**, or **Tokyo**.
 - c. In the **Locale** field, enter the locale of the new spreadsheet, for example, **Canada**, or **Hong Kong**.
5. Click **Next** to add the connection to the flow. The connection appears in the integration visualization where you added it.

Result

A connection that creates a spreadsheet returns the spreadsheet ID for the new spreadsheet. In subsequent steps, you can map this spreadsheet ID to the spreadsheet ID in a connection that accesses the new spreadsheet, for example, to update it.

11.4.5. Updating data in a sheet

In an integration, you can update data in a spreadsheet in the middle of a flow or to finish a simple integration. To do this, add a Google Sheets connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a Google Sheets connection that is authorized to access the Google spreadsheet that you want to update.
- You have access to the spreadsheet ID for the spreadsheet that you want to update.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click a Google Sheets connection that is authorized to access the spreadsheet that you want to update.
3. On the **Choose an action** page, select **Update sheet values**.
4. To configure the **Update sheet values** action:
 - a. In the **SpreadsheetId** field, do one of the following:
 - Enter the ID of the spreadsheet that you want to update.
 - Leave the field blank. In this case, after you add this connection to the flow, you must add a data mapper step before this connection. In the data mapper step, map the spreadsheet ID from a previous connection to this connection. The previous connection must access the spreadsheet that you want to update in this connection.
 - b. In the **Range** field, use Google A1 notation to specify the spreadsheet cells that you want to update. Specify the start and end coordinates, for example, **A1:D4** updates the first 4 columns in the first 4 rows in the first sheet in the spreadsheet. The default is **A:A**, which updates the first column in the first sheet in the spreadsheet.
 - c. In the **Major dimension** field, accept **Rows**, which is the default, or select **Columns**. **Rows** configures the action to use row objects to update the sheet. Each row object contains a value for each column that you want to update. **Columns** configures the action to use column objects to update the sheet. Each column object contains a value for each row that you want to update.
 - d. In the **Value input option** field, indicate how you want Google sheets to interpret the data that it receives for updating the sheet. **Unspecified**, which is the default, enables Google Sheets to automatically convert data that it recognizes. For example, if the input data is a

date, then Google Sheets formats it as a date. If the input data is a decimal, then Google Sheets formats it as a decimal.

- **Unspecified** defaults to the Google Sheets API setting, which defaults to **User entered**.
 - **Raw** causes Google Sheets to insert the input data as is.
 - **User entered** enables automatic conversion of recognizable data.
- e. Click **Next** to add the connection to the flow. The connection appears in the integration visualization in the location where you added it.
5. If you want to add any other connections to the flow, add them now and then return to these instructions.
 6. After the flow has all desired connections, in the integration visualization, click the plus sign that is just before the Google Sheets connection that updates sheet values.
 7. Click the **Data Mapper** card to add a data mapping step to the flow.
 8. In the data mapper:
 - a. If you did not specify the spreadsheet ID when you configured the **Update sheet values** action, then map a source **spreadsheetId** to the target **spreadsheetId**.
 - b. Specify the data that you want to use to update the sheet by mapping fields from a source step to the target spreadsheet. For example, you might map fields from another spreadsheet or from a database.
If you need to, you can edit the Google Sheets connection that updates sheet values and change the settings for **Range** or **Major dimension**. Changing these settings causes the data mapper to display different target fields according to your changes.
 - c. In the upper right, click **Done** to add the data mapper step.

11.4.6. Appending data to a sheet

You can append data to a sheet in the middle of a flow or to finish a simple integration. To do this, add a Google Sheets connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a Google Sheets connection that is authorized to access the Google spreadsheet in which you want to append data.
- You have access to the ID for the spreadsheet in which you want to append data.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click a Google Sheets connection that is authorized to access the spreadsheet in which you want to append data.

3. On the **Choose an action** page, select **Append values to a sheet**
4. To configure the **Append values to a sheet** action:
 - a. In the **SpreadsheetId** field, do one of the following:
 - Enter the ID of the spreadsheet that you want to append values to.
 - Leave the field blank. In this case, after you add this connection to the flow, you must add a data mapper step before this connection. In the data mapper step, map the spreadsheet ID from a previous connection to this connection. The previous connection must access the spreadsheet that you want to append data to in this connection.
 - b. In the **Range** field, use Google A1 notation to specify the spreadsheet range that you want to append data to. Specify the start and end coordinates, for example, **A3:D3** appends data to the first sheet, after the third row for 4 columns. The default is **A:A**, which appends data to the first column in the first sheet in the spreadsheet.

The connection never overwrites data. The connection starts appending data after the range you specify, and then always appends data to the content that is in place.
 - c. In the **Major dimension** field, accept **Rows**, which is the default, or select **Columns**. **Rows** configures the action to use row objects to append data. Each row object contains a value for each column that you want to append data to. **Columns** configures the action to use column objects to append data. Each column object contains a value for each row that you want to append.
 - d. In the **Value input option** field, indicate how you want Google sheets to interpret the data that it receives for appending to a sheet. **Unspecified**, which is the default, enables Google Sheets to automatically convert data that it recognizes. For example, if the input data is a date, then Google Sheets formats it as a date. If the input data is a decimal, then Google Sheets formats it as a decimal.
 - **Unspecified** defaults to the Google Sheets API setting, which defaults to **User entered**.
 - **Raw** does nothing. Google Sheets inserts the input data as is.
 - **User entered** enables automatic conversion of recognizable data.
 - e. Click **Next** to add the connection to the flow. The connection appears in the integration visualization where you added it.

The values that you specify to configure the **Append values to a sheet** action determine the fields that the data mapper displays for mapping to or from this connection.
5. If you want to add any other connections to the flow, add them now and then return to these instructions.
6. After the flow has all desired connections, in the integration visualization, click the plus sign that is just before the Google Sheets connection that appends data to a sheet.
7. Click **Data Mapper** to add a data mapping step to the flow.
8. In the data mapper:
 - a. If you did not specify the spreadsheet ID when you configured the **Append values to a spreadsheet** action, then map a source **spreadsheetId** to the target **spreadsheetId**.

- b. Specify the data to append to the sheet by mapping fields from a source step to the target spreadsheet. For example, you might map fields from another spreadsheet or from a database.
If you need to, you can edit the Google Sheets connection that appends sheet values and change the settings for **Range** or **Major dimension**. Changing these settings causes the data mapper to display different target fields according to your changes.
- c. In the upper right, click **Done** to add the data mapper step.

11.4.7. Updating spreadsheet properties

In an integration, you can update the properties of a spreadsheet in the middle of a flow or to finish a simple integration. To do this, add a Google Sheets connection to the middle of a flow or as a simple integration's finish connection.

Properties include the spreadsheet's title, locale, and time zone.

When Fuse Online prompts you to configure the **Update spreadsheet properties** action, you can leave some or all fields blank. If you leave a field blank, then in a data mapper step that is in the flow (you add it later) before this connection, you map fields from previous steps to blank **Update spreadsheet properties** action configuration fields.

Prerequisites

- You created a Google Sheets connection that is authorized to access the Google spreadsheet whose properties you want to update.
- You have access to the spreadsheet ID for the spreadsheet whose properties you want to update.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click a Google Sheets connection that is authorized to access the spreadsheet whose properties you want to update.
3. On the **Choose an action** page, select **Update spreadsheet properties**.
4. To configure the **Update spreadsheet properties** action:
 - a. In the **SpreadsheetId** field, do one of the following:
 - Enter the ID of the spreadsheet whose properties you want to update.
 - Leave the field blank. In this case, after you add this connection to the flow, you must add a data mapper step that is before this connection. In the data mapper step, map the spreadsheet ID from a previous connection to this connection. The previous connection must access the spreadsheet that you want to update in this connection.

- b. In the other fields, enter a value only if you want to change the property. Alternatively, you can leave the fields blank. If you do, then in a data mapper step that you add later, just before this connection, you can map the fields that you want to change.
 - c. Click **Next** to add the connection to the flow. The connection appears in the integration visualization where you added it.
 5. If you want to add any other connections to the flow, add them now and then return to these instructions.
 6. After the flow has all desired connections, you might want to use a data mapper step to update spreadsheet properties:
 - a. In the integration visualization, click the plus sign that is just before the Google Sheets connection that updates properties.
 - b. Click **Data Mapper** to add a data mapping step to the flow.
 - c. In the data mapper, if you did not specify a spreadsheet ID when you configured the **Update spreadsheet properties** action, map a source **spreadsheetId** to the target **spreadsheetId**.
 - d. For each spreadsheet property that you want to change and for which you did not specify an updated value when you configured the **Update spreadsheet properties** action, map a field from a source step to the target spreadsheet property that you want to change.
 - e. In the upper right, click **Done** to add the data mapper step.

11.4.8. Adding a chart to a sheet

In the middle of a flow, or to finish a simple integration, you can add a basic chart or a pie chart to a Google Sheets spreadsheet. To do this, add a Google Sheets connection to the middle of a flow or as a simple integration's finish connection. Then add a data mapper step just before the connection. In the data mapper step, set options that determine the location, properties, and content of the chart.

When Fuse Online prompts you to configure the **Add charts** action, you can leave some or all fields blank. If you leave a field blank, you can map a value to that field in the data mapper step that you will add just before this connection.

Prerequisites

- You created a Google Sheets connection that is authorized to access the Google spreadsheet that you want to add a chart to.
- You have access to the ID for the spreadsheet that you want to add a chart to.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose the finish connection for a simple integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click a Google Sheets connection that is authorized to access the spreadsheet that you want to add a chart to.
3. On the **Choose an action** page, select **Add charts**.

4. To configure the **Add charts** action:
 - a. In the **SpreadsheetId** field, do one of the following:
 - Enter the ID of the spreadsheet that you want to add a chart to.
 - Leave the field blank. In the data mapper step that will be just before this connection, map the spreadsheet ID from a previous connection to this connection. The previous connection must access the spreadsheet that you want to add a chart to in this connection.
 - b. In the **Chart Title** field, enter a title.
Alternatively, leave the field blank. In the data mapper step that is just before this connection, map the chart title from a source field or property to the **title** target field.
 - c. In the **Subtitle** field, enter a subtitle.
Alternatively, leave the field blank. In the data mapper step that is just before this connection, map the chart subtitle from a source field or property to the **subtitle** target field.
5. Click **Next** to add the connection to the flow. The connection appears in the integration visualization where you added it.
6. If you want to add any other connections to the flow, add them now. Then return to these instructions.
7. In the integration visualization, click the plus sign that is just before the connection that adds a chart.
8. Click **Data Mapper**.
In the data mapper, map source properties, source fields, or source constants to the target Google Sheets connection, which is adding a chart. The following instructions assume that there is a source field, a source property, or a source constant that contains the value that you want to map to each target field.

If there is no source for the required value, then create a source property in the data mapper by clicking the + sign that is to the right of the **Properties** folder. In the **Create Property** dialog, give the property a name that makes it easy to map to the correct target field, for example, specify **overlayPosition** as the property name. For the property value, specify the value that you want the connection to use to create the chart. The chart's overlay position field requires A1 notation that identifies a cell. That is, it specifies a start position but an end position specification is not required, and it is ignored if it is present. For example, specify something like **D4** as the value of the **overlayPosition** source property. Save the new property.

When you configured the **Add charts** action, you might have specified a value for the spreadsheet ID, the chart title, and/or the chart subtitle. If you did, then do not map a value to that field.
9. To add a chart to a sheet, map source properties, source fields or source constants to target fields as follows:
 - a. Set the location of the chart by mapping an A1 notation value, which identifies a cell, to the **overlayPosition** target field. An end position is not required and it is ignored if present. The mapped value identifies the cell where Google Sheets places the chart. This cell is the upper left corner of the chart display.

If you do not map a value to the **overlayPosition** field, and you also do not map a value to the **sheetId** field, which identifies the sheet that you want to add the chart to, then the default behavior is that Google Sheets creates a new sheet and places the chart in A1.

You must map a value to the **overlayPosition** field if you plan to map a value to the **sheetId** field.

- b. Map a source **spreadsheetId** field to the target **spreadsheetId** field. The connection uses source data in this spreadsheet to add the chart to a sheet in this same spreadsheet. The source data and the chart can be in two different sheets in the same spreadsheet but they cannot be in two different spreadsheets.
- c. Set a chart title by mapping to the target **title** field. The connection inserts this string as the title of the chart.
- d. Set a chart subtitle by mapping to the target **subtitle** field. The connection inserts this string as a chart subtitle.
- e. Identify the sheet to add the chart to by mapping an integer to the **sheetId** field. If you map a value to the **sheetId** field then you must also map a value to the **overlayPosition** field.

If you do not map a value to the **sheetId** field and you also do not map a value to the **overlayPosition** field, then the connection creates a new sheet and adds the chart to the new sheet.

If you do not map a value to the **sheetId** field but you do map a value to the **overlayPosition** field, then the connection places the chart on the sheet identified by the **sourceSheetId** field. This is the sheet that provides the data for the chart.

0 identifies the first sheet in the spreadsheet. For subsequent sheets, the sheet ID is at the end of the URL when the sheet is visible in a browser. For example, at the end of the following URL, you can see **gid=206589330**:

<https://docs.google.com/spreadsheets/d/1pa...ngQbKkM/edit#gid=206589330>

This indicates that the sheet ID is **206589330** and that is the value that you would map to **sheetId**.

- f. Identify the sheet that provides the data for the chart by mapping its integer sheet ID to the target **sourceSheetId** field. The default is **0**, which identifies the first sheet in the spreadsheet.
You can add a basic chart or a pie chart. Follow one of the following sets of instructions according to the kind of chart that you want to add.
- g. To add basic chart, in the target panel, expand the **basicChart** folder and map source fields to target fields that are in the **basicChart** folder:
 - i. Set the chart type (**BAR**, **LINE**, **AREA**, or **COLUMN**) by mapping to the target **type** field. The default is **COLUMN**.
 - ii. Set the title for the bottom axis of the chart by mapping to the target **axisTitleBottom** field.
 - iii. Set the title for the left axis of the chart by mapping to the target **axisTitleLeft** field.
 - iv. Set the high level category of information that the chart shows by mapping to the

- target **domainRange** field. This field uses the Google Sheets A1 notation. For example, suppose that the first column in a source sheet provides a list of 5 products in **A2** through **A6**, and you want the chart to provide some data for each product. In this column, the first cell (**A1**) must contain a label, such as **Products**. The setting of **domainRange** would be **A1:A6**. The chart will contain the data that is in **A2** through **A6**. The chart does not display the label.
- v. Identify the location of the source data that the chart shows by mapping to the target **dataRange** field. This field uses the Google Sheets A1 notation. A chart can provide only one series of data. Continuing with the **domainRange** example, suppose that the second column in a source sheet shows the number sold for each of the 5 products that are listed in the first column and this is the data that you want the chart to show. In this column, the first cell (**B1**) must contain a label, such as **Number Sold**. The setting of **dataRange** would be **B1:B6**. The chart will contain the data that is in **B2** through **B6**. The chart does not display the label.
- h. To add a pie chart, in the target panel, expand the **pieChart** folder and map source fields to target fields that are in the **pieChart** folder:
 - i. Set the location of the pie chart legend by mapping to the target **legendPosition** field. The default is **LEFT_LEGEND**. The value must be **BOTTOM_LEGEND**, **LEFT_LEGEND**, **RIGHT_LEGEND**, **TOP_LEGEND**, or **NO_LEGEND**.
 - ii. Set the high level category of information that the pie chart shows by mapping to the target **domainRange** field. This field uses the Google Sheets A1 notation. For example, suppose that the first column in a source sheet provides a list of 5 products in **A2** through **A6**, and you want the chart to provide some data for each product. In this column, the first cell (**A1**) must contain a label, such as **Products**. The setting of **domainRange** would be **A1:A6**. The chart will contain the data that is in **A2** through **A6**. The chart does not display the label.
 - iii. Identify the location of the source data that the chart shows by mapping to the target **dataRange** field. This field uses the Google Sheets A1 notation. A chart can provide only one series of data. Continuing with the **domainRange** example, suppose that the second column in a source sheet shows the number sold for each of the 5 products that are listed in the first column and this is the data that you want the chart to show. In this column, the first cell (**B1**) must contain a label, such as **Number Sold**. The setting of **dataRange** would be **B1:B6**. The chart will contain the data that is in **B2** through **B6**. The chart does not display the label.
 - i. In the upper right, click **Done** to add the data mapper step.

11.4.9. Adding a pivot table to a sheet

In the middle of a flow, or to finish a simple integration, you can add a pivot table to a Google Sheets spreadsheet. A pivot table lets you aggregate, sort, or apply a function to spreadsheet data and display the results in the same spreadsheet. To add a pivot table, add a Google Sheets connection to the middle of a flow or as a simple integration's finish connection. Then add a data mapping step before the connection. In the data mapping step, you set options that determine the location, properties, and content of the pivot table.

In this release, the **Add pivot table** action is limited to defining one value group, one row pivot group, and one column pivot group. Support for multiple groups in a single action is expected to be added in a future release. As a workaround, you can add multiple Google Sheets connections that add pivot tables based on the same source spreadsheet.

Prerequisites

- You created a Google Sheets connection that is authorized to access the Google spreadsheet that you want to add a pivot table to.
- You have access to the ID for the spreadsheet that contains the source data for the pivot table.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose the finish connection for a simple integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click a Google Sheets connection that is authorized to access the spreadsheet that you want to add the pivot table to.
3. On the **Choose an action** page, select **Add pivot tables**.
4. To configure the **Add pivot tables** action, in the **SpreadsheetId** field, do one of the following:
 - Enter the ID of the spreadsheet that you want to add a pivot table to.
 - Leave the field blank. In the data mapper step that you will add just before this connection, you will map the spreadsheet ID from a previous connection to this connection. The previous connection must access the spreadsheet that you want to add a pivot table to in this connection.
5. Click **Next** to add the connection to the flow. The connection appears in the integration visualization where you added it.
6. If you want to add any other connections to this flow, add them now. Then return to these instructions.
7. In the integration visualization, click the plus sign that is just before the connection that adds a pivot table to a sheet.
8. Click **Data Mapper**.

In the data mapper, map source properties, source fields, or source constants to the target Google Sheets connection, which is adding a pivot table. The following instructions assume that there is a source field, source property, or source constant that contains the value that you want to map to each target field.

If there is no source for the required value, then create a source property in the data mapper by clicking the + sign that is to the right of the **Properties** folder. In the **Create Property** dialog, give the property a name that makes it easy to map to the correct target field, for example, specify **valueLayout** as the property name. Specify the value that you want the connection to use to create the pivot table. The pivot table's value layout field requires a value of **HORIZONTAL** or **VERTICAL** so you might specify **VERTICAL** as the value of the **valueLayout** property. Save the new property.

9. In the data mapper, configure a new pivot table as follows:
 - a. Map a source **spreadsheetId** field to the target **spreadsheetId** field. The connection uses source data in this spreadsheet to add the pivot table to a sheet in this same spreadsheet. The source data and the pivot table can be in two different sheets in the same spreadsheet

but they cannot be in two different spreadsheets.

- b. Identify the sheet to add the pivot table to by mapping an integer to the **sheetId** field. The default is **0**, which identifies the first sheet in the spreadsheet. For subsequent sheets, the sheet ID is at the end of the URL when the sheet is visible in a browser. For example, at the end of the following URL, you can **gid=206589330**:

<https://docs.google.com/spreadsheets/d/1pa...ngQbKkM/edit#gid=206589330>.

This indicates that the sheet ID is **206589330** and that is the value that you would map to **sheetId**.

- c. Identify the sheet that provides the data for generating the pivot table by mapping its integer sheet ID to the target **sourceSheetId** field. If you do not map a value to **sourceSheetId**, the connection uses the **sheetId** value, or **0** if no value is mapped to **sheetId**. **0** identifies the first sheet in the spreadsheet.
- d. Set the source data range for generating the pivot table by mapping an A1 notation value to the target **sourceRange** field. For example, **A2:D5**.
- e. Set the value layout to be used on the pivot table by mapping to the target **valueLayout** field. The value must be **VERTICAL** or **HORIZONTAL**, which is the default. **HORIZONTAL** specifies that values are laid out as columns.
- f. Set the top left cell of the pivot table by mapping an A1 notation cell coordinate to the target **start** field. When the connection adds the pivot table to the sheet that contains the source data, if you do not map a value to the **start** field, the default is that the top left cell of the pivot table is the cell that is in the first row of the source data range and in the first empty column after the source data range. When the source data is in one sheet and the pivot table will be in another sheet, the default is **A1**.
- g. To add a value group, expand **valueGroups** in the target panel, and map values to the fields under **valueGroups**:
- i. Map a value group name to the target **name** field.
 - ii. Map a function, which you want to apply to the value group, to the target **function** field. The value must be **SUM**, **COUNT**, **AVERAGE**, **MAX**, **MIN**, or **CUSTOM**. The default is **SUM**. Map **CUSTOM** to **function** when you are defining a formula.
 - iii. Map a custom formula, which you want to apply to the value group, to the target **formula** field if you mapped the **CUSTOM** value to the **function** field.
 - iv. Map a column name, which is the coordinate that builds the value group, to the target **sourceColumn** field.
- h. To add a row pivot group, expand **columnGroups** in the target panel, and map values to the fields under **columnGroups**:
- i. Map a row pivot group name to the target **label** field.
 - ii. Map the sort order that you want to apply to the row pivot group to the target **sortOrder** field. The value must be **ASCENDING** or **DESCENDING**. The default is **ASCENDING**.
 - iii. Map **true** or **false** to the target **showTotals** field. The default is **true**, which enables the display of totals for the row pivot group.

- iv. Map a column name, which is the coordinate that builds the row pivot group, to the target **sourceColumn** field.
- i. To add a column pivot group, expand **rowGroups** in the target panel, and map values to the fields under **rowGroups**:
 - i. Map a column pivot group name to the target **label** field.
 - ii. Map the sort order that you want to apply to the column pivot group to the target **sortOrder** field. The value must be **ASCENDING** or **DESCENDING**. The default is **ASCENDING**.
 - iii. Map **true** or **false** to the target **showTotals** field. The default is **true**, which enables the display of totals for the column pivot group.
 - iv. Map a column name, which is the coordinate that builds the column pivot group, to the target **sourceColumn** field.
- j. In the upper right, click **Done** to add the data mapper step.

Additional resource

[Google developers documentation for pivot tables](#)

CHAPTER 12. CONNECTING TO HTTP AND HTTPS ENDPOINTS

In an integration, you can connect to HTTP and HTTPS endpoints to execute the **GET, PUT, POST, DELETE, HEAD, OPTIONS, TRACE**, or **PATCH** method. To do this, create an HTTP or HTTPS connection and then add it to an integration flow. The following topics provide details:

- [Section 12.1, "Creating a connection to an HTTP or HTTPS endpoint"](#)
- [Section 12.2, "Adding an HTTP or HTTPS connection to an integration"](#)

12.1. CREATING A CONNECTION TO AN HTTP OR HTTPS ENDPOINT

In an integration, to execute the HTTP **GET, PUT, POST, DELETE, HEAD, OPTIONS, TRACE**, or **PATCH** method, create a connection to an HTTP or HTTPS endpoint. You can then add the connection to one or more integrations.

Prerequisite

You must know the URL for the endpoint that you want to connect to.

Procedures

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. If you want to use Hyper Text Transfer Protocol to connect to the endpoint, then click the **HTTP** connector. If you want to use Hyper Text Transfer Protocol Secure, then click the **HTTPS** connector.
4. In the **Base URL** field, enter the endpoint path. For example, **www.mycompany.com/sales**.
5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise specification of the base URL and try again.
6. If validation is successful, click **Next**.
7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **HTTPS My Company Sales**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **HTTPS My Company Sales** appears as a connection that you can choose to add to an integration.

12.2. ADDING AN HTTP OR HTTPS CONNECTION TO AN INTEGRATION

You can add an HTTP or HTTPS connection to any number of integrations.

Prerequisite

- You created an HTTP or HTTPS connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a start connection, or to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the HTTP or HTTPS connection that you want to add to the flow.
3. Select the action that you want the connection to perform:
 - If you are adding a start connection, then **Periodic invoke URL** is the only available action. This action invokes the endpoint at intervals that you specify and triggers the integration if the endpoint returns any data.
 - If you are adding a middle or finish connection, then **Invoke URL** is the only available action. This action invokes the endpoint once.
4. In the **URL Path** field, specify the location of the endpoint that you want to invoke.
5. In the **HTTP Method** field, select the method that you want the connection to perform. The default method is **GET**.
 - **GET** obtains the content at the URL path.
 - **PUT** replaces the content at the URL path with the integration data.
 - **POST** stores the integration data at the URL path to create new content.
 - **DELETE** removes content at the URL path.
 - **HEAD** obtains metadata about the content at the URL path.
 - **OPTIONS** obtains communication option settings at the URL path.
 - **TRACE** obtains information for testing and diagnostic purposes.
 - **PATCH** partially updates the content at the URL path according to the integration data.
6. If you are adding a start connection, which periodically invokes the URL, then in the **Period** field, accept the default interval of **1** second or specify a number and its unit (milliseconds, seconds, minutes, or hours) to indicate how long to wait between invocations.
7. Click **Next** to specify the action's input or output type.
8. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input/output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
9. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 10. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 11. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 12. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

CHAPTER 13. CONNECTING TO IRC

Internet Relay Chat (IRC) is a protocol that lets anyone with an IRC client send and receive text messages in real time. In an integration, a connection to IRC can do one of the following:

- Trigger execution of a simple integration when an IRC nickname that you specify receives a private message. The integration passes the message to the next step in the flow. For example, you can designate an IRC nickname for receiving names of possible customers. Upon receiving a message, the integration could connect to Salesforce to create a lead.
- Deliver a message to a particular channel. The message is from the nickname that you specify. For example, this is useful when an integration downloads a file from an FTP server and processes it in some way. An integration flow can send a message to a particular channel to indicate that the process was successful.

To connect to IRC in an integration, create an IRC connection and then add the connection to an integration flow. Details are in the following topics:

- [Section 13.1, “Creating an IRC connection”](#)
- [Section 13.2, “Adding an IRC connection to trigger integration execution upon receiving messages”](#)
- [Section 13.3, “Adding an IRC connection to send a message”](#)

13.1. CREATING AN IRC CONNECTION

In an integration, an IRC connection can retrieve messages that are sent to an IRC nickname that you specify or send messages to a nickname on a channel. You can use the same IRC connection in any number of integrations.

Prerequisites

- You know the hostname and port of the IRC server that you want to connect to.
- If the IRC server requires a password, you know the password.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **IRC** connector.
4. In the **Hostname** field, enter an IRC hostname. You can specify an IP address or a name, for example, **chat.freenode.net**.
5. In the **Port** field, enter the port that the IRC server is listening on, for example, **6665**.
6. In the **Password** field, if the IRC server requires a password, enter it here.
7. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the connection configuration values and try again.

8. If validation is successful, click **Next**.
9. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **IRC Freenode**.
10. In the **Description** field, optionally enter any information that is helpful to know about this connection.
11. Click **Save** to see the updated list of available connections, including the connection that you just created. If you entered the example name, you would see that **IRC Freenode** appears as a connection that you can choose to add to an integration. You can add this connection to any number of integrations.

13.2. ADDING AN IRC CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES

An IRC connection that starts an integration triggers execution of the integration when the connection finds private messages that are sent to an IRC nickname that you specify.

Prerequisites

- You created an IRC connection.
- You have an IRC nickname for receiving and sending messages.
- You are creating a simple integration and Fuse Online is prompting you to choose how you want to start the integration.

Procedure

1. Click the IRC connection that you want to use to start the integration.
2. Select the **IRC Receive Private Message** action.
3. In the **Channels** field, optionally specify one or more IRC channels separated with commas.
4. In the **Nickname** field, specify the IRC nickname that the integration uses. For any channels that you specify, this nickname joins the channel. During execution, the integration retrieves messages that are sent to this nickname and passes them to the next step in the integration.
5. In the **NickServ Password** field, if the specified nickname has a password, enter it.
6. Click **Next** to specify the action's output type.
7. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.

- **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
8. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 9. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 10. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 11. Click **Next** to add the connection to the flow.

Result

The connection is a simple integration's start connection and Fuse Online prompts you to choose the integration's finish connection.

13.3. ADDING AN IRC CONNECTION TO SEND A MESSAGE

In an integration, you can send a message to one or more IRC channels in the middle of a flow or to finish a simple integration. To do this, add an IRC connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created an IRC connection.
- You have an IRC nickname for receiving and sending messages.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the IRC connection that you want to add to the flow.
3. Select **IRC Send Message to Channel** to send a message to one or more channels.
 - In the **Channels** field, enter one or more IRC channels delimited by commas. During execution, this connection sends messages from the IRC nickname that you specify to these channels.

4. In the **Nickname** field, specify the IRC nickname that sends messages to the specified channels.
5. In the **NickServ password** field, if the nickname that you specified has a password, specify it here.
6. Click **Next** to specify the action's input type.
7. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
8. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 9. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 10. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 11. Click **Next** to add the connection to the flow.

Results

The connection appears in the flow visualization where you added it.

CHAPTER 14. CONNECTING TO JIRA

In an integration, you can connect to a Jira server to obtain, create, or update issues. Jira is a tool for planning, tracking, and managing software development projects. Each Jira environment allows customization of the workflow, which has an effect on the details for connecting to Jira in an integration. Consulting with your Jira administrator should clarify the details.

The following topics provide information and procedures for creating integrations that connect to a Jira server:

- [Section 14.1, “Registering Fuse Online with a Jira server that uses OAuth”](#)
- [Section 14.2, “Creating a Jira connection”](#)
- [Section 14.3, “Obtaining Jira issues or comments to trigger integration execution”](#)
- [Section 14.4, “Adding an issue to a Jira server”](#)
- [Section 14.5, “Adding a comment to a Jira issue”](#)
- [Section 14.6, “Attaching a file to a Jira issue”](#)
- [Section 14.7, “Adding and removing Jira issue watchers”](#)
- [Section 14.8, “Updating an issue on a Jira server”](#)
- [Section 14.9, “Transitioning a Jira issue to a new status”](#)

14.1. REGISTERING FUSE ONLINE WITH A JIRA SERVER THAT USES OAUTH

An integration can connect to a Jira server that uses the OAuth protocol to authenticate access. To enable this, register your Fuse Online environment as a Jira client application. Jira client applications are also referred to as Jira consumers. In other words, your Fuse Online environment is a Jira consumer.



NOTE

Registration is not required when a Jira server uses only basic authentication.

Follow the procedure here to obtain the Jira OAuth credentials that you need to create a Fuse Online connection to Jira. For more details about registering Jira consumers, including a tutorial that takes you through the steps with a sample server, see the [Jira documentation about OAuth for REST APIs](#)

After you register Fuse Online with a Jira server, you use Fuse Online to create a connection to that Jira server. Any number of integrations can use the same Jira connection. However, if you want to create another Jira connection, you must obtain another set of OAuth credentials by repeating the registration procedure provided here.

Overview of the main steps

The main steps in the registration procedure are:

- Obtain the Atlassian command line application that enables you to obtain OAuth credentials.
- Run the downloaded application to create a **config.properties** file.

- Create a public/private key pair, which Fuse Online uses to access a Jira server.
- Edit the **config.properties** file to update some of its values.
- Configure your Jira server to recognize your Fuse Online environment as a consumer application.
- Obtain a Jira access token that Fuse Online needs to access data on your Jira server.

Each of these steps has several substeps and the procedure below provides the details.

Prerequisites

- Jira server administration permissions.
- Familiarity with command line interfaces.

Procedure

1. Obtain the Atlassian command line application that enables you to obtain OAuth credentials:
 - a. Go to the [atlassian-oauth-examples](#) page.
 - b. In the left panel, at the bottom, click **Downloads**.
 - c. On the **Downloads** page, click **Download repository**.
 - d. Extract the file into a directory that you choose.
2. Run the downloaded application to create a **config.properties** file for OAuth credentials:
 - a. In a terminal, navigate to the directory that contains the extracted content.
 - b. Change to the **java** directory and build the client:

```
cd atlassianlabs-atlassian-oauth-examples-dd0264cad043/java
mvn clean compile assembly:single
```

- c. Change to the **target** directory and generate the **config.properties** file:

```
cd target
java -jar OAuthTutorialClient-1.0.jar requestToken
```

You can ignore the connection exception. In the **target** directory, there is now a **config.properties** file that contains some temporary keys.

3. Generate a public/private key pair that Fuse Online needs for access to a Jira server. While you can run these commands anywhere, the first instruction directs you to a particular directory for convenience:
 - a. Navigate to the directory that contains the downloaded application.
 - b. Generate a private key:

```
openssl genrsa -out jira_privatekey.pem 1024
```

- c. Obtain a public key:

```
openssl req -newkey rsa:1024 -x509 -key jira_privatekey.pem -out jira_publickey.cer -
days 365
```

This command prompts you to enter information about your Fuse Online environment. Alternatively, to avoid responding to prompts, add the **-subj** option to the command. For example, at the end of the command line above, add something like this:

```
-subj "/C=US/ST=New York/L=New York/O=MyCompany
Ltd./OU=IT/CN=mysubdomain.mydomain.com"
```

- d. Export the keys:

```
openssl pkcs8 -topk8 -nocrypt -in jira_privatekey.pem -out jira_privatekey.pcks8
openssl x509 -pubkey -noout -in jira_publickey.cer > jira_publickey.pem
```

You now have four files:

```
jira_privatekey.pcks8
jira_privatekey.pem
jira_publickey.cer
jira_publickey.pem
```

- e. Obtain the private key, without the header, line breaks, and footer:

```
cat jira_privatekey.pcks8 | grep -v 'PRIVATE'|awk '{print}' ORS=""
```

- f. Copy the private key to the clipboard.

4. Edit the **config.properties** file:

- Navigate to the **java/target** directory that contains the **config.properties** file and open the file for editing.
- In the **config.properties** file, replace the private key with the private key that you copied to the clipboard.
- Change the **jira_home** setting to the URL for your Jira server. Be sure to specify **https** if your Jira server uses **https**. Also, you need to escape the colon. For example:


```
jira_home=https\://issues.mycompany.org
```

- Change the **consumer_key** setting to **Fuse Online App**. For example:

```
consumer_key=Fuse Online App
```

- Save and close the **config.properties** file.

5. Configure your Jira server to recognize your Fuse Online environment as a consumer application. You must be logged in to the Jira server as an administrative user.

- Select **Settings** () > **Products** > **Application links**.

- b. In the **Create new link** input field, enter any URL, for example, enter: <https://example.com>. This displays a dialog that indicates that no response was received, which is okay because only one-way communication is required.
- c. Click **Continue** to display the **Link applications** dialog. In this dialog:
 - i. In the **Consumer Key** field, enter **Fuse Online App**.
 - ii. At the bottom, select **Create incoming link**.
 - iii. In each of the other fields, enter any value. Each field requires a value. The value that you enter does not matter because no response is needed.
 - iv. Click **Continue** to display another dialog.
 - v. In the **Consumer Key** field, enter **Fuse Online App**.
 - vi. In the **Consumer Name** field, enter **Fuse Online App**.
 - vii. In the **Public Key** field, paste the public key that is in the **jira_publickey.pem** file. Be sure to paste only the key without the header and footer. To display the key so that you can copy it, in the directory that contains the **jira_publickey.pem** file, enter **cat jira_publickey.pem**.
 - viii. Click **Continue**.
6. Obtain a Jira access token that Fuse Online needs to access data on your Jira server. In the Jira OAuth documentation that is linked to at the beginning of this procedure, this step is referred to as "The OAuth dance" because there are exchanges among Fuse Online, the Jira server, and the Jira administrator.
 - a. Navigate to the **java/target** directory in the directory that contains the command line application that you downloaded in the first step of this whole procedure.

- b. Obtain a request token from your Jira server:

```
java -jar OAuthTutorialClient-1.0.jar requestToken
```

This displays something like:

```
Token:      ec3dj4byySM5ek3XW7gl7f4oc99obAlo
Token Secret: OhONj0eF7zhXAMKZLbD2Rd3x7Dmxjy0d
Retrieved request token. go to
https://jira101.atlassian.net/plugins/servlet/oauth/authorize?
oauth_token=ec3dj4byySM5ek3XW7gl7f4oc99obAlo to authorize it
```

- c. In another browser tab, go to the URL provided in that output. That page welcomes you to Jira and prompts you to allow access to the Fuse Online App.
- d. Click **Allow**, which displays an **Access Approved** page with a verification code.
- e. Copy the verification code to the clipboard and paste it somewhere so that you can easily retrieve it.
- f. Obtain an access token by invoking a command such as the following. In the following command line example, the last value is a verification code. In the command that you run, replace the example verification code with the verification code that you copied in the

previous step. For example:

```
java -jar OAuthTutorialClient-1.0.jar accessToken qTJkPi
```

The output from this command is the access token that Fuse Online needs to access your Jira server.

Result

The Jira command line application updates the **config.properties** file so that it contains all values that you need to configure a Jira connection for Fuse Online.

Next step

Create a Jira connection.

14.2. CREATING A JIRA CONNECTION

In an integration, to obtain, create, or update a Jira issue, create a Jira connection, which you then add to an integration. You can add the same connection to any number of integrations.

If the Jira server that you want to connect to uses the OAuth protocol for authenticating access, you must have registered your Fuse Online environment as a client of the Jira server that you want to connect to. See [Registering Fuse Online with a Jira server that uses OAuth](#).

Prerequisites

- For a Jira server that uses basic authentication, you have a Jira user name and password.
- For a Jira server that uses OAuth, you have access to the **config.properties** file that contains values for the Jira access token, consumer key, private key, and verification code.

Procedure

1. In Fuse Online, in the navigation panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display the available connectors.
3. Click the **Jira** connector.
4. In the **Jira URL** field, enter the URL for the Jira server that you want an integration to connect to, for example, <https://issues.mycompany.org>.
For a connection to a Jira server uses OAuth, the procedure to register your Fuse Online environment as a Jira consumer application resulted in a **config.properties** file. The URL that you specify here should be the same URL that is in that **config.preperities** file. For example, you would see a line like this in the **config.properties** file:

```
jira_home=https\:\issues.mycompany.org
```

5. If this Jira server uses basic authentication:
 - a. In the **User name** field, enter a Jira user name. The connection uses this account to operate on the specified Jira server.
 - b. In the **Password** field, enter the specified user's password.

Skip the next step if the Jira server does not use OAuth authentication.

6. If the Jira server uses OAuth authentication:
 - a. Open the **config.properties** file that contains the OAuth access token, keys, and verification code. This is the file that is the result of the registration procedure. Copy values from that file and paste them into the connection configuration fields.
 - b. Copy the **access_token** value into the **Access Token** field.
 - c. Copy the **consumer_key** value into the **Consumer Key** field.
 - d. Copy the **private_key** value into the **Private Key** field.
 - e. Copy the **secret** value into the **Verification Code** field.
7. Click **Validate**. Fuse Online displays a message that indicates whether it can validate this connection. If validation fails, try again and be sure to enter the correct values.
8. When validation is successful, click **Next**.
9. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Jira Connect 1**.
10. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Jira connection that uses the jkim account**.
11. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Jira Connect 1** appears as a connection that you can choose to add to an integration.

14.3. OBTAINING JIRA ISSUES OR COMMENTS TO TRIGGER INTEGRATION EXECUTION

To trigger integration execution upon obtaining issues or comments from a Jira server, add a Jira connection as a simple integration's start connection.

Prerequisites

- You created a Jira connection.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Jira connection that you want to use to start the integration.
4. On the **Choose an action** page, select an action:
 - **Retrieve New Comments** uses a query that you specify to search the Jira server. For each issue that the query returns, the connection checks whether a comment has been added since the previous invocation of the query. The connection returns any new comments.

- **Retrieve New Issues** uses a query that you specify to search the Jira server. For each issue that the query returns, the connection checks its creation date. If the issue was created since the previous invocation of the query, the connection returns the issue to the integration. The first time that the connection executes this query, it returns all issues that it finds.
5. In the **Delay** field, accept the default of 5000 milliseconds (5 seconds) or enter the number of milliseconds that you want to elapse between query invocations.
 6. In the **Jira Query Language** field, enter a Jira query. For example:

```
project = GATE AND assignee = jkim AND (status = Open OR status = New OR status = Reopened)
```

This query finds issues in the **Gateway Online** project, that are assigned to **jkim** and that are unresolved. Every Jira project has a short name and a long name. In this example, the short name of the **Gateway Online** project is **GATE**. In queries, specify a project's short name.

The more specific the query is, the less time it takes to search the Jira server. When a query does not have any results, the connection does not trigger integration execution.

7. Click **Next**.

Result

The connection starts a simple integration and Fuse Online prompts you to choose the integration's finish connection.

14.4. ADDING AN ISSUE TO A JIRA SERVER

In the middle of a flow, or to finish a simple integration, you can connect to a Jira server to add an issue.

Prerequisites

- You created a Jira connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a simple integration's finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a Jira connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the Jira connection that you want the integration to use to connect to a Jira server.
3. On the **Choose an action** page, select **Add Issue**.
4. Configure the action. The required fields are **Issue type ID or name** and **Project key**. For the optional fields, you can enter values now, or, after you add this connection to an integration, you can add a data mapper step before this connection. In the data mapper step, map fields from previous steps to the optional fields in this connection.
 - a. Optionally, in the **Assignee** field, enter the Jira user name for the person that you want to assign this issue to.

- b. Optionally, in the **Components** field, enter the name of one or more components. Separate multiple names with commas. A Jira administrator defines the components that you can specify.
 - c. Optionally, in the **Priority ID or name** field, enter a priority for the new issue. A Jira administrator defines the priority values that you can enter.
 - d. Optionally, in the **Summary** field, enter a brief statement about the issue.
 - e. In the **Issue type ID or name** field, enter a value that describes the type of the issue. For example, this is often something like **Story, Epic, Chore, or Bug**.
In Jira, a user with administrator permissions can see a list of valid issue types by selecting **Project settings > Issue types**. A user without these permissions can click in an issue's type field and a list of allowable values should display.
 - f. Optionally, in the **Watchers** field, enter a comma-separated list of Jira user names. These people receive notifications when this issue is updated.
 - g. In the **Project Key** field, enter the short name of a Jira project that a Jira administrator has defined. The connection creates the new issue in this project. For example, a project key is something like **GATE**.
 - h. Optionally, in the **Description** field, enter any information about this issue that it is helpful to capture.
5. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

14.5. ADDING A COMMENT TO A JIRA ISSUE

In the middle of a flow, or to finish a simple integration, you can connect to a Jira server to add a comment to an issue.

Prerequisites

- You created a Jira connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a simple integration's finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a Jira connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the Jira connection that you want the integration to use to connect to a Jira server.
3. On the **Choose an action** page, select **Add Comment**.
4. In the **Comment** field, enter the comment that you want to add to the issue or plan to add a data mapper step before this connection. In that data mapper step, map the comment from a previous integration step to this connection's **comment** field.

5. In the **Issue Key** field, enter the Jira identifier for the issue. Examples of issue keys: **GATE-1234**, **Ent-239**.
6. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

Next steps

To map the comment from a previous integration step to this connection, add the connection that provides the comment content and then add a data mapper step before this Jira connection. For example, suppose a database connection obtains customer records. In the data mapper step, map the collection of customer records to the Jira connection's **comment** field.

14.6. ATTACHING A FILE TO A JIRA ISSUE

In the middle of a flow, or to finish a simple integration, you can connect to a Jira server to attach one or more files to an issue. In the integration, there must be a previous step that obtains the file(s) that you want to attach.

Prerequisites

- You created a Jira connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a simple integration's finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a Jira connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the Jira connection that you want the integration to use to connect to the Jira server.
3. On the **Choose an action** page, select **Attach File**.
4. In the **Issue Key** field, enter the Jira identifier of the issue that you want to attach a file to. Examples of issue keys: **GATE-1234**, **Ent-239**.
5. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

Next step

If the integration does not already have an earlier connection that obtains the file(s) that you want to attach to a Jira issue, add that connection to the integration. Make sure that it is before the Jira connection that attaches a file. For example, suppose you add an FTP connection and download one or more files from an FTP server. When the integration executes, the subsequent Jira connection attaches those files to the Jira issue that you specified when you configured the attach file action.

14.7. ADDING AND REMOVING JIRA ISSUE WATCHERS

In the middle of a flow, or to finish a simple integration, you can connect to a Jira server to add watchers to an issue and/or remove watchers from issue.

Prerequisites

- You created a Jira connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a simple integration's finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a Jira connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the Jira connection that you want the integration to use.
3. On the **Choose an action** page, select **Add Issue**.
4. In the **Issue Key** field, enter the Jira identifier of the issue that you want to add watchers to or remove watchers from. Examples of issue keys: **GATE-1234**, **Ent-239**.
5. Optionally, in the **Add Watchers** field, enter a comma-separated list of Jira user names. These people receive notifications when this issue is updated.
6. Optionally, in the **Remove Watchers** field, enter a comma-separated list of Jira user names that are already watching this issue. The connection removes these users from the list of watchers.
7. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

14.8. UPDATING AN ISSUE ON A JIRA SERVER

In the middle of a flow, or to finish a simple integration, you can connect to a Jira server to update an issue. The connection can update one or more issue fields. If the issue being updated already has a value for a field, the connection replaces that value with any value you specify for the connection or that you map to a connection field. For example, if the issue already has a description, and you specify text in the **Description** field when you configure the **Update Issue** action, the connection replaces the description that was there with this new description.

Prerequisites

- You created a Jira connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a simple integration's finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a Jira connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the Jira connection that you want the integration to use to connect to the Jira server.

3. On the **Choose an action** page, select **Update Issue**.
4. Configure the action. The only required field is **Issue Key**. For the optional fields, you can enter values now, or, after you add this connection to an integration, you can add a data mapper step before this connection. In the data mapper step, map fields from previous steps to the optional fields in this connection.
 - a. Optionally, in the **Assignee** field, enter the Jira user name for the person that you want to assign this issue to.
 - b. Optionally, in the **Components** field, enter the name of one or more components. Separate multiple names with commas. A Jira administrator defines the components that you can specify.
 - c. In the **Issue Key** field, enter the Jira identifier for the issue that you want the connection to update. Examples of issue keys: **GATE-1234**, **Ent-239**.
 - d. Optionally, in the **Priority ID or name** field, enter a priority for the new issue. A Jira administrator defines the priority values that you can enter.
 - e. Optionally, in the **Summary** field, enter a brief statement about the issue.
 - f. In the **Issue type ID or name** field, enter a value that describes the type of the issue. For example, this is often something like **Story**, **Epic**, **Chore**, or **Bug**.
 - g. Optionally, in the **Description** field, enter any information about this issue that it is helpful to capture.
5. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

14.9. TRANSITIONING A JIRA ISSUE TO A NEW STATUS

In the middle of a flow, or to finish a simple integration, you can connect to a Jira server to transition an issue to a new status, or to a new workflow stage. A Jira administrator defines what it means for an issue to transition as well as the values for transition IDs.

Prerequisites

- You created a Jira connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a simple integration's finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a Jira connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the Jira connection that you want the integration to use to connect to the Jira server.
3. On the **Choose an action** page, select **Transition Issue**.

You do not need to specify any values to configure the transition issue action. Instead, you can map values from previous integration steps to the fields in the this connection.

4. Optionally, in the **Comment** field, enter a comment that you want to add to the issue.
5. Optionally, in the **Issue Key** field, enter the Jira identifier for the issue that is transitioning. Examples of issue keys: **GATE-1234**, **Ent-239**.
6. Optionally, in the **ID of the transition** field, enter an integer that a Jira administrator has associated with a particular transition, such as when a Jira moves from being new to being worked on, or when it moves from being worked on to being tested.
A Jira administrator can view transition IDs in a project's workflow display. If you do not have administration permissions, obtain the allowed transition IDs from a Jira administrator.
7. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

Next steps

If you did not specify a value in each **Transition Issue** field, ensure that the integration has a step that obtains the value for each field. After the integration has all required connections, add a data mapper step before the Jira connection that transitions an issue. In the data mapper step, map fields from previous steps to the fields in the Jira connection that transitions an issue.

CHAPTER 15. CONNECTING TO KAFKA

Apache Kafka is a distributed streaming platform that you can use to obtain and publish data. In an integration, you can subscribe for data from a Kafka topic that you specify or publish data to a Kafka topic that you specify. To do this, create a connection to Kafka and add that connection to an integration flow. Details are in the following topics:

- [Section 15.1, “Creating a connection to a Kafka broker”](#)
- [Section 15.2, “Obtaining data from a Kafka broker to trigger integration execution”](#)
- [Section 15.3, “Publishing data to a Kafka broker”](#)

15.1. CREATING A CONNECTION TO A KAFKA BROKER

In an integration, to subscribe for data from a Kafka topic or publish data to a Kafka topic, create a connection to Kafka and then add that connection to an integration.

Prerequisite

- If you want to use Transport Layer Security (TLS) to encrypt your data, you have the Kafka broker’s PEM certificate text. Typically, you obtain the broker certificate text from your Kafka server administrator.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display connectors.
3. Click the **Kafka Message Broker** connector.
4. In the **Kafka broker URIs** field, select the broker that you want this connection to access, or enter a comma separated list of Kafka broker URIs. Each URI should be in the form *host:port*.
5. For the **Transport Protocol** field, select one of the following options:
 - If you want to encrypt your data to protect it in transit, select **TLS** (Transport Layer Security).
 - If you do not want to encrypt your data, select **Plain** and then skip to Step 7.
6. If you selected **TLS** in Step 5, then in the **Broker certificate** field, paste the Kafka broker’s PEM certificate text.
7. Optional. Click **Add** to specify **key:value** pairs to configure Kafka producer and consumer options.
For example, if you want a new integration to be able to consume old messages from a topic, change the **auto.offset.reset** value from the default (**latest**) to **earliest** by typing **auto.offset.reset** for the **Key** field and **earliest** for the **Value** field.

For details about Kafka producer configuration options, go to <https://kafka.apache.org/documentation/#producerconfigs>

For details about Kafka consumer configuration options, go to <https://kafka.apache.org/documentation/#consumerconfigs>

Note: If you add configuration attributes, Fuse Online does not include them as part of its validation process in the next step.

8. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the input parameter and try again.
9. If validation is successful, click **Next**.
10. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, you might type **Kafka West**.
11. In the **Description** field, optionally enter any information that is helpful to know about this connection.
12. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Kafka West** appears as a connection that you can choose to add to an integration.

15.2. OBTAINING DATA FROM A KAFKA BROKER TO TRIGGER INTEGRATION EXECUTION

To trigger execution of an integration upon receiving data from a Kafka broker, add a Kafka connection as the start connection. When the integration is running, the Kafka connection continuously watches for data in the Kafka topic that you specify. When the connection finds new data, it passes that data to the next step in the integration.

Prerequisite

You created a connection to a Kafka broker.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Kafka connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Subscribe** action to receive data from the topic that you specify.
5. In the **Topic Name** field, click the down carat to display a list of topics and click the topic that you want to subscribe to. Or, type a topic name to create that topic.
6. Click **Next** to specify the action's output type.
7. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the Kafka connection output to a subsequent step then you must specify the data type. The data mapper does not recognize unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
8. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 9. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 10. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 11. Click **Next**.

Result

The integration now has a start connection and Fuse Online prompts you to choose the finish connection.

15.3. PUBLISHING DATA TO A KAFKA BROKER

In an integration, you can publish data to a Kafka broker in the middle of a flow or to finish a simple integration. To do this, add a Kafka connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a connection to a Kafka broker.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a Kafka connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the Kafka connection that you want to use to publish messages.
3. On the **Choose an action** page, select **Publish**.
4. In the **Topic Name** field, click the down carat to display a list of topics and click the topic that you want to publish to.

5. Click **Next** to specify the action's input type.
6. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
7. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 8. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 9. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 10. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

CHAPTER 16. CONNECTING TO APACHE KUDU

Apache Kudu is a columnar storage manager developed for the Apache Hadoop platform. A Fuse Online integration can connect to a Kudu data store to scan a table, which returns all records in the table to the integration, or to insert records into a table. Details are in the following topics:

- [Section 16.1, “Creating a connection to an Apache Kudu data store”](#)
- [Section 16.2, “Triggering an integration when scanning returns records from a Kudu table”](#)
- [Section 16.3, “Inserting records into a Kudu table”](#)

16.1. CREATING A CONNECTION TO AN APACHE KUDU DATA STORE

In an integration, to obtain records from or insert records into a Kudu table, create a connection to a Kudu master host and then add that connection to an integration.

Prerequisite

- You must know the IP address or the hostname for the Kudu master host that you want to connect to.
- You must know the port that Kudu is listening on.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display connectors.
3. Click the **Apache Kudu** connector.
4. To configure the connection:
 - a. In the **Address of Kudu master host** field, enter the hostname or the IP address of the Kudu master host.
 - b. In the **Port to establish connection to** field, enter the port that Kudu is listening on. The default is **7051**.
5. Click **Next**.
6. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, you might enter **Kudu North**.
7. In the **Description** field, optionally enter any information that is helpful to know about this connection.
8. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Kudu North** appears as a connection that you can choose to add to an integration.

16.2. TRIGGERING AN INTEGRATION WHEN SCANNING RETURNS RECORDS FROM A KUDU TABLE

To trigger execution of an integration upon obtaining data from a Kudu table, add a Kudu connection to a simple integration as its start connection. When the integration is running, the Kudu connection scans the table that you specified at the interval that you specified, obtains all records in the table, and passes a collection of the records to the next step in the integration.

A Kudu connection can obtain data from only one table. Between scans, if there are no changes to the data in the table that the connection scans, then the next scan returns the same data as the previous scan.

Prerequisite

- You created a Kudu connection.
- The table that you want to obtain records from exists.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the Kudu connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Scan a Kudu table** action.
5. In the **Table** field, enter the name of the table that you want to obtain records from.
6. In the **Period** field, accept the default of one minute, or enter the interval at which you want the connection to scan the table and return the records that are in the table.
7. Click **Next**.

Result

The connection is the simple integration's start connection.

Next steps

Add the integration's finish connection and any other connections that you want to include in the integration. When the integration contains all the connections that are needed, consider whether you need to split the collection of records that the Kudu connection returns. If you want to execute integration steps for each record that you obtained from the Kudu table, then after the Kudu connection, add a split step. Also, you probably need to follow the Kudu connection with a data mapping step that maps data obtained from Kudu to fields in subsequent connections in the integration.

16.3. INSERTING RECORDS INTO A KUDU TABLE

In an integration, you can add records to a Kudu table in the middle of a flow or to finish a simple integration. To do this, add a Kudu connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a Kudu connection.

- You are creating or editing an integration and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.
- The table that you want to add records to exists.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the Kudu connection that you want to use. Note that when a Kudu connection inserts data, the connection does not return anything.
3. On the **Choose an action** page, select **Insert data into a Kudu table**
4. To configure the action, in the **Table** field, specify the name of the table to add records to. It is important for you to have an understanding of how the Kudu table that you are adding records to is set up. For example, a Kudu table that you are adding records to might have a unique key. If you try to add a record that contains a key value that is already in the table, the Kudu connection does not add that record.
5. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

Next steps

Consider whether you need to split a collection of records into individual records that a Kudu connection can add to a table. To do this, add a split step to the integration. The split step executes the subsequent steps in the integration once for each record. Also, you probably need a data mapper step before a Kudu connection that adds records to a table.

CHAPTER 17. CONNECTING TO MONGODB

MongoDB is a distributed NoSQL database. A Fuse Online integration can obtain content from a MongoDB database or update content in a MongoDB database. To do this, create a MongoDB connection, and add it to an integration.

Details for connecting to a MongoDB database are in the following topics:

- [Section 17.1, “Creating a connection to a MongoDB database”](#)
- [Section 17.2, “Triggering an integration when a MongoDB collection is updated”](#)
- [Section 17.3, “Operating on documents in a MongoDB collection”](#)

17.1. CREATING A CONNECTION TO A MONGODB DATABASE

Create a MongoDB connection so that you can connect to a MongoDB database in an integration.

Prerequisites

- You must know the host name for the MongoDB database that you want to connect to.
- You must have a user name and password that authorizes access to the MongoDB database.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display connectors.
3. Click the **MongoDB** connector.
4. Configure the connection:
 - a. In the **Database host(s)** field, specify one or more MongoDB database hosts that this connection can access. Separate multiple specifications of **host:port** with commas. Replace **host** with a host name, a virtual host name, or an IP address. For example:
mongodb0.example.com:1234,mongodb1.example.com:1234.
 - b. In the **Username** field, enter a user name that is authorized to access the database.
 - c. In the **Password** field, enter the password for the user name that you specified.
 - d. Optional. In the **Administration database** field, if the database has an administration database, enter the name of the MongoDB administration database that is used to grant access permission. A MongoDB administrator should let you know whether the database that you want to access has an administration database.
 - e. Optional. In the **Replica set name** field, specify the name of the MongoDB replica set (cluster) that the connection can access.
 - f. In the **Database** field, enter the name of the MongoDB database that contains the collection(s) that you want the connection to read.

5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the input parameter(s) and try again.
6. When validation is successful, click **Next**.
7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, you might enter **MongoDB North**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **MongoDB North** appears as a connection that you can choose to add to an integration.

Next step

Add your MongoDB connection to an integration.

17.2. TRIGGERING AN INTEGRATION WHEN A MONGODB COLLECTION IS UPDATED

To trigger execution of an integration when a document is added to a MongoDB collection, add a MongoDB connection to a simple integration as its start connection. When the integration is running, the MongoDB connection monitors the database collection that you specified when you created the integration. Insertion of a new document into the collection that the connection is configured to monitor triggers execution of the integration. The MongoDB connection returns the new document to the integration and this data is available to the next step in the integration.

Prerequisites

- You created a MongoDB connection.
- You know the name of the MongoDB collection that you want the connection to read.
- If the collection that you want the connection to monitor is a capped collection, then you must also know:
 - The name of the MongoDB collection field that tracks incoming documents.
 - Whether persistent tracking is enabled for the database that contains the collection.
 - How to specify tail tracking information related to the data that you want the connection to read. MongoDB connections can use tail tracking information to resume an action after an unexpected connection termination. Tail tracking ensures that when the connection resumes its activity, it does not return duplicate data to the integration nor does it drop any data that needs to be returned to the integration.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.

3. On the **Choose a connection** page, click the MongoDB connection that is configured to access the database that you want the integration to obtain updates from.
4. On the **Choose an action** page, select one of these actions:
 - **Retrieve documents (stream)** is typically the action that you want to select. It retrieves data from non-capped collections.
 - **Retrieve documents (tail)** is the action for retrieving data from capped collections.
5. Configure the action:
 - a. In the **Collection name** field, enter the name of the MongoDB collection that you want the connection to read.
If you are configuring the **Retrieve documents (stream)** action, this is the only required parameter. Go to step 6. If you are configuring the **Retrieve documents (tail)** action, follow the remaining substeps.
 - b. In the **Collection field used to track incoming documents** field, enter the name of the relevant MongoDB collection field. This field contains data that can be sorted, such as a date or an ID.
 - c. Select the **Persistent tracking enabled** checkbox if persistent tracking is enabled for the database that you want the connection to read.
 - d. Optional. In the **Unique id to identify this tracking process** field, specify a unique ID if there are multiple consumers that monitor the same collection. For more information, see the Camel documentation for [Tailable Cursor Consumer](#).
 - e. Optional. In the **DB used to store tail tracking** field, enter the name of the MongoDB database that contains tail tracking information.
 - f. Optional. In the **Collection used to store tail tracking** field, enter the name of the collection that contains tail tracking information.
 - g. Optional. In the **Field used to store tail tracking** field, enter the name of the field that stores tail tracking information for the collection that this connection is reading.

To identify the tail tracking field, you can specify the tail tracking database or tail tracking collection. With one of these pieces of information, the connection can find the tail tracking field.

6. Click **Next** to specify the action's output type.
7. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
- **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.

- **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
8. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 9. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 10. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 11. Click **Next**.

Result

The integration now has a start connection and Fuse Online is prompting you to choose the finish connection.

During execution, the connection returns the inserted document in JSON format.

17.3. OPERATING ON DOCUMENTS IN A MONGODB COLLECTION

In an integration, you can search for, update, delete, count, or add a document to a MongoDB collection. To do this, add a MongoDB connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a MongoDB connection.
- You know the name of the MongoDB collection that you want the connection to operate on.
- You are creating or editing an integration and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a MongoDB connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the MongoDB connection that you want to use.
3. On the **Choose an action** page, select the action that you want the connection to perform.
4. To configure the action, in the **Collection name** field, enter the name of the collection that you want the connection to operate on.
If you selected the **Insert** action:

- You are done configuring the connection.
 - Ensure that the data that the integration passes to this MongoDB connection contains JSON notation that specifies the document to add to the collection.
 - Click **Next** to add this connection to the integration.
5. For all other actions, the following table provides information about what to specify in the second field for configuring the action.
- The second field is a JSON notation expression that identifies the document(s) to operate on and possibly, details for the operation. If you plan to map an incoming source field to an identifier in the expression, specify **:#variable-name** in the expression.

For completeness, the **Insert** action is described in this table as well.

Action	What it does	Parameter field	Returns
Count	Counts the number of documents that satisfy the count expression that you specify.	In the Count expression field, specify a JSON filter expression in the form of {"test":"unit"} . The action counts the number of documents that have a test attribute value of unit .	An instance of java.lang.Long that specifies the number of documents that were found.
Delete	Removes one or more documents from the collection.	In the Delete expression field, specify a JSON expression in the form of {"test":"unit"} . The operation removes each document whose test attribute has a value of unit .	An instance of java.lang.Long that specifies the number of documents that were deleted.

Action	What it does	Parameter field	Returns
Find	Looks for all documents that match the filter expression that you specify.	In the Filter expression field, specify a JSON notation string that identifies one or more documents.	<p>JSON notation that specifies a list (an array). Each list element identifies a document that matches the filter expression and provides the document content. If no documents are found, the action returns an empty list.</p> <p>You must be familiar with the data model of the collection. If the collection adheres to a JSON schema, you must be familiar with this schema because the returned list elements adhere to this schema. For additional information, see MongoDB Data Models.</p> <p>To use output data from the Find action in a subsequent data mapper step, the collection must adhere to a JSON schema. This enables the data mapper to display data fields. For more information, see MongoDB documentation for JSON schema validation.</p>
Insert	Adds one or more documents to the collection.	There is no action configuration parameter for inserting a document. The data coming in to the MongoDB connection must contain JSON notation that specifies one or more documents to add to the collection.	JSON notation that specifies a list (an array). Each list element is a document that this action inserted.

Action	What it does	Parameter field	Returns
Update	Updates one or more documents in the collection.	In the Filter criteria field, specify an array of 2 arguments. The first argument is a filter expression that identifies the documents to update. The second argument is a MongoDB update statement that specifies how to update the documents. Update statement format is described in https://docs.mongodb.com/manual/reference/method/db.collection.update/ . For example: [{"_id":11},{\$set:{"test":"updated!"}}].	An instance of java.lang.Long that specifies the number of documents that were updated.
Upsert	Updates one or more documents in the collection or creates a document if no documents match the Upsert expression .	In the Upsert expression field, specify JSON notation that identifies one or more documents. The action uses this expression to detect any matching documents. If the action finds a matching document(s) in the collection, it updates it. If the action does not find a matching document, the action creates a new document. The data coming into the MongoDB connection must contain JSON notation that specifies: * An _id field to identify whether it is an insert or an update operation. * The content to add or update.	An instance of com.mongodb.client.result.UpdateResult that specifies either the number of updated documents or the ID of the new, inserted document.

Each action returns a response. If this is a finish connection, then the response is lost, but you can add a **Log** step to capture the response.

6. Click **Next**.
7. Optional. If this is a finish connection, add a **Log** step to finish the integration instead. Configure the **Log** step to capture the response.

Result

The connection appears in the integration visualization where you added it.

Next steps

Add any other needed connections to the flow. Add any other steps that process data. Complete the integration by adding any needed data mapping steps. When you configured the MongoDB connection action, if you specified any **:#variable-name** identifiers in an action expression, be sure to map a source field to the MongoDB connection variable field.

CHAPTER 18. CONNECTING TO MQTT

MQ Telemetry Transport (MQTT) is a lightweight, machine-to-machine, internet of things, connectivity protocol. In an integration, you can obtain messages from or publish messages to an MQTT broker. To do this, create a connection to the MQTT broker of interest and then add that connection to an integration flow. Details are in the following topics:

- [Section 18.1, “Creating a connection to an MQTT broker”](#)
- [Section 18.2, “Obtaining a message from an MQTT broker to trigger integration execution”](#)
- [Section 18.3, “Publishing a message to an MQTT broker”](#)

18.1. CREATING A CONNECTION TO AN MQTT BROKER

In an integration, to obtain messages from or publish messages to an MQTT broker, create a connection to the MQTT broker of interest and then add that connection to an integration.

Prerequisite

You must know the URL for the MQTT broker that you want to connect to.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display connectors.
3. Click the **MQTT Message Broker** connector.
4. To configure the connection:
 - a. In the **MQTT broker URL** field, enter the location of the MQTT broker that you want to send data to or obtain data from. This is the only required field.
 - b. In the **User Name** field, optionally enter the user name for the MQTT account whose credentials you want to use to access the broker.
 - c. In the **Password** field, if you specified a user name, then specify the password associated with that account.
 - d. In the **Client ID** field, optionally enter the ID that allows connections to close and reopen without missing messages. The connection must subscribe to or publish to a topic.
5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the input parameters and try again.
6. If validation is successful, click **Next**.
7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, you might enter **MQTT West**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection.

9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **MQTT West** appears as a connection that you can choose to add to an integration.

18.2. OBTAINING A MESSAGE FROM AN MQTT BROKER TO TRIGGER INTEGRATION EXECUTION

To trigger execution of an integration based on receiving a message from an MQTT broker, add an MQTT connection as the start connection. When the integration is running, the MQTT connection continuously watches for messages on the MQTT queue or topic that you specify. When the connection finds a message, it passes it to the next step in the integration. An MQTT connection handles one message at a time.

Prerequisite

You created an MQTT connection.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the MQTT connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Subscribe** action to receive messages from the queue or topic that you specify.
5. In the **MQTT queue/topic name** field, enter the name of the queue or topic to subscribe to in order to receive data.
6. Click **Next** to specify the action's output type.
7. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection output in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
- **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
- **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
- **XML instance** is a document that contains XML data. The document's file extension is **.xml**.

8. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
9. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
10. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
11. Click **Next**.

Result

The integration now has a start connection and Fuse Online is prompting you to choose the finish connection.

18.3. PUBLISHING A MESSAGE TO AN MQTT BROKER

In an integration, you can publish a message to an MQTT broker in the middle of a flow or to finish a simple integration. To do this, add an MQTT connection to the middle of a flow or as the integration's finish connection.

Prerequisites

- You created an MQTT connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add an MQTT connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the MQTT connection that you want to use to publish a message.
3. On the **Choose an action** page, select **Publish**.
4. In the **MQTT queue/topic name** field, specify the name of the queue or topic to publish the message to.
5. Click **Next** to specify the action's input type.
6. In the **Select Type** field, if the data type does not need to be known, accept **Type specification not required** and click **Next**. You do not need to follow the rest of these instructions. However, a structured data type is recommended. For example, if you want to map the connection input in a data mapper step then you must specify the data type. The data mapper cannot display fields for unstructured data.

To specify the data type, click in the **Select Type** field and select one of the following as the schema type:

- **JSON schema** is a document that describes the structure of JSON data. The document's media type is **application/schema+json**.
 - **JSON instance** is a document that contains JSON data. The document's media type is **application/json**.
 - **XML schema** is a document that describes the structure of XML data. The document's file extension is **.xsd**.
 - **XML instance** is a document that contains XML data. The document's file extension is **.xml**.
7. In the **Definition** input box, paste a definition that conforms to the schema type you selected. For example, if you select **JSON schema** then you would paste the content of a JSON schema file, which has a media type of **application/schema+json**.
 8. In the **Data Type Name** field, enter a name that you choose for the data type. For example, if you are specifying a JSON schema for vendors then you might specify **Vendor** as the data type name.
You will see this data type name when you are creating or editing an integration that uses the connection for which you are specifying this type. Fuse Online displays the type name in the integration visualization and in the data mapper.
 9. In the **Data Type Description** field, provide information that helps you distinguish this type. This description appears in the data mapper when you hover over the step that processes this type.
 10. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

CHAPTER 19. CONNECTING TO ODATA

Open Data Protocol (OData) is a standard for building and consuming REST APIs. An OData service provides services to clients, such as Fuse Online, through OData-compliant HTTP requests. A Fuse Online integration can obtain entities from an OData service, and can update, create, or delete entities managed by an OData service. To do this, create an OData connection, and add it to an integration.

It is assumed that you are familiar with the OData specification [Version 4](#) or [Version 2](#).

Details for connecting to an OData service are in the following topics:

- [Section 19.1, “Creating a connection to an OData service”](#)
- [Section 19.2, “Triggering an integration when polling returns data from an OData service”](#)
- [Section 19.3, “Updating, creating, and deleting data that is managed by an OData service”](#)

19.1. CREATING A CONNECTION TO AN ODATA SERVICE

In an integration, to obtain, update, create, or delete entities that are managed by an OData service, you must first create a connection to that OData service. You can create a connection for version 2 or a version 4 OData.

Prerequisites

- You must know the base URL for the OData service that you want to connect to.
- If that service uses authentication then you must have the required credentials, and, if required, an SSL certificate. However, most OData services are public and do not require authentication.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display connectors.
3. Click the **OData v2** or the **OData v4** connector.
4. To configure the connection:
 - a. In the **Service Root URL** field, enter the base URL for the OData service that you want to access.
 - b. In the **User Name** field, if the service uses basic authentication, then enter your user name.
 - c. In the **Password** field, if the service uses basic authentication, then enter your password.
 - d. In the **Server Certificate** field, if the service requires it, paste the content of an SSL certificate.

Typically, a public OData service does not require a certificate in addition to the certificates provided by the browser. However, for an internal OData service, you might have created your own SSL certificate and self-signed it. Since this certificate is not trusted by a certificate authority, connections to your OData service would fail. To enable connections, paste the self-signed certificate here.

One way to get the certificate is to load the service in a browser. The steps after that

depend on which browser you are using, but it will be something like the following: click the **Not secure** padlock symbol next to the address bar, then click **View Certificate**, export the displayed certificate to a file, copy the certificate, and paste it into this field.

5. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the input parameter(s) and try again.
6. When validation is successful, click **Next**.
7. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, you might enter **OData North**.
8. In the **Description** field, optionally enter any information that is helpful to know about this connection.
9. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **OData North** appears as a connection that you can choose to add to an integration.

Next step

Add your OData connection to an integration.

19.2. TRIGGERING AN INTEGRATION WHEN POLLING RETURNS DATA FROM AN ODATA SERVICE

To trigger execution of an integration upon obtaining data from an OData service, add an OData connection to a simple integration as its start connection. When the integration is running, the OData connection polls the service at intervals that you specify. When the connection finds data that satisfies the connection configuration, the connection passes the data to the next step in the integration.

Prerequisite

You created an OData connection.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the OData connection that you want to use to start the integration.
4. On the **Choose an action** page, select the **Read** action.
5. Configure the **Read** action:
 - a. In the **Resource Collection** field, select the name of the OData resource that you want to query. Fuse Online fetches data from the OData service to provide a list of available resource collections.
 - b. In the **Entity Key Predicate** field, to obtain a particular entity, identify the entity that you want by specifying its key predicate. For example, specify something like **UserName='Bob'** or **Categories(1)**. To obtain multiple entities, leave this field blank.

- c. In the **Query Options** field, enter a query that you want to apply to the resource. Use OData syntax. For example, **\$filter=startswith(name, 'N')** returns a message for each entity in the resource that has a **name** field that starts with **N**.

You can specify both **Entity Key Predicate** and **Query Options**. If you do, the OData service obtains the specified entity and applies the query to that entity. For example, suppose that you set **Entity Key Predicate** to **UserName='russellwhyte'/Emails** and you set **Query Options** to **\$filter=contains(\$it,'example')**. The connection creates a request that looks something like this:

```
https://services.odata.org/TripPinRESTierService/People(UserName='russellwhyte')/Emails
?$filter=contains($it, 'example')
```

The service returns all email addresses for Russell Whyte that contain the domain **example**.

- d. Select the **Filter Old Results** checkbox to obtain a particular message only once.
- e. Select the **Split Results** checkbox if you want the connection to return individual messages rather than a collection of messages.
Fuse Online also provides discrete split and aggregate steps, which you can add to a flow. If you want to process individual messages in one or more steps and then aggregate the messages into a collection, do not select the **Split Results** checkbox. Instead, leave the checkbox empty and then add a split step to the flow after this connection. A split step is required if you want an aggregate step in the flow.
- f. In the **Interval Before Polling Starts** field, accept the default of 1 second, or enter the length of time that you want to elapse before the connection starts to poll the OData service.
- g. In the **Delay** field, accept the default of 30 seconds, or enter the interval at which you want the connection to poll the OData service.
- h. In the **Backoff Idle Threshold** field, accept the default of 1 or enter an integer that indicates the number of consecutive polls that can return no data. After this number of polls, the connection increases the interval between subsequent polls. The connection determines the new length of the polling interval by multiplying the **Delay** value by the **Backoff Multiplier** value.
For example, suppose that the polling interval (the **Delay** value) is the default of 30 seconds, **Backoff Idle Threshold** is set to 5, and **Backoff Multiplier** is set to 12. After 5 consecutive polls that return no data, the connection waits 360 seconds (30 x 12) before polling again. The connection continues to poll every 360 seconds until a poll returns data. After a poll returns data, the connection resumes polling every 30 seconds.
- i. In the **Backoff Multiplier** field, accept the default of 1 or enter an integer that indicates the multiplier for increasing the polling interval if the value set for the **Backoff Idle Threshold** is reached.
If you accept the default of 1 for the **Backoff Multiplier**, then the connection continues to poll at the specified interval no matter how many consecutive polls return no results.

The values that you specify for **Backoff Idle Threshold** and **Backoff Multiplier** are useful for reducing CPU overhead since the connection can automatically poll less often during quiet periods.

6. Click **Next**.

Result

The integration now has a start connection and Fuse Online is prompting you to choose the finish connection.

During execution, what the connection returns depends on what you specified in the **Entity Key Predicate** and **Query Options** fields. The OData connection can return:

- A collection of entities or a collection of entity properties
For example, this might be all **Person** entities in the resource, or perhaps all **Age** properties for all **Person** entities. The connection returns the collection in one message. Fuse Online executes each subsequent step in the flow once for the collection. However, when you configure the **Read** action, if you select **Split Results**, then the connection returns each entity or each property in its own message. Fuse Online executes each subsequent step in the flow once for each message.
- An entity or an entity property
For example, this might be the **Person** entity whose **UserName** property is **Bob**, or perhaps the **Age** property for the **Person** entity whose **UserName** is **Bob**. The connection returns the entity or the entity property in a message that it passes to the next step in the flow.

Next steps

Add the integration's finish connection and any other connections that you want to include in the integration. When the integration contains all the connections that are needed, if the OData connection returns a collection, consider whether you need to add a split step after the OData connection. An integration usually needs to map the data returned by the OData connection to fields that a subsequent connection in the flow can use. Sometimes you can map a collection, but more often you need to split the collection in order to map to the target fields.

After the OData connection, add a data mapper step to the flow. Exactly where in the flow depends on what you want the flow to do. For example, after the OData connection, you might add a basic filter step and then add a data mapper step.

19.3. UPDATING, CREATING, AND DELETING DATA THAT IS MANAGED BY AN ODATA SERVICE

In an integration, you can update a resource that is managed by an OData service in the middle of a flow or to finish a simple integration. To do this, add an OData connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created an OData connection.
- You are creating or editing an integration and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add an OData connection. Skip this step if you are adding a simple integration's finish connection.
2. Click the OData connection that you want to use. Note that when an OData connection updates or deletes an entity, the connection does not return anything. When the OData connection creates an entity, the connection returns the new entity.
3. On the **Choose an action** page, select the action that you want the connection to perform:

- **Create** adds an entity to an OData resource.
- **Delete** removes an entity from an OData resource.
- **Update** changes an entity that is in an OData resource.
For OData Version 2 connections only, when you create or update an entity there are three options that you can set. These three options specify the way that data is serialized in the request:
 - **Content Only** - By default, OData Version 2 adds metadata as part of a request. To disable this default behavior, select the **Content Only** option.
 - **Omit ETag** - By default, OData Version 2 requires that, when you send an update to a request, you must specify all mandatory property values in the update request. To disable this default behavior so that you can specify only the property values that you want to change, select the **Omit ETag** option.
 - **Omit Json wrapper** - By default, OData Version 2 wraps a request in JSON format. To disable this default behavior, select the **Omit Json wrapper** option.

4. Configure the action by selecting the OData resource that you want to update.

It is important for you to have an understanding of how the OData resource that you are updating is set up. The backing data source for an OData service determines the rules for updates and resolving conflicts. For example, suppose an OData connection tries to create a new entity but an entity with that predicate key already exists. The OData service might overwrite the existing entity, or it might update some fields in the existing entity, or it might ignore the operation. It is up to you to know how the OData service behaves in this situation.

5. Click **Next**.

Result

The connection appears in the integration visualization where you added it.

Next steps

Add a data mapper step before the OData connection. You must map source fields that provide the data that is required to create a new entity, to update an entity, or to delete an entity. See [Mapping integration data to fields for the next connection](#).

CHAPTER 20. CONNECTING TO SALESFORCE

In an integration, to connect to Salesforce, you must register your Fuse Online environment as a Salesforce client application. This authorizes Fuse Online to access Salesforce. With registration in place, you create a Salesforce connection, which you can then add to any number of integrations. For details, see the following topics:

- [Section 20.1, “Registering Fuse Online as a Salesforce client application”](#)
- [Section 20.2, “Creating a Salesforce connection”](#)
- [Section 20.3, “Adding a Salesforce connection to an integration”](#)

20.1. REGISTERING FUSE ONLINE AS A SALESFORCE CLIENT APPLICATION


In an integration, to connect to Salesforce, the first thing you must do is register your Fuse Online environment as a client application that can access Salesforce. This lets you create any number of integrations that connect to Salesforce. In other words, you need to register a particular Fuse Online environment with Salesforce only once.

In each Fuse Online environment, there can be only one registration of Fuse Online as a Salesforce client application. However, while each Salesforce connection uses the same registration, it can use different user credentials.


Prerequisite

You are logged in to Fuse Online.

Procedure

1. In Fuse Online:
 - a. In the left panel, click **Settings**.
 - b. On the **Settings** page, near the top, to the right of the callback URL, click  to copy the callback URL for your Fuse Online environment to the clipboard. You will need this URL toward the end of this procedure.
 - c. Click the **Salesforce** entry to display the **Client ID** and **Client Secret** fields.
2. In another browser tab, log in to your Salesforce account and follow the steps below to create a connected app. These instructions assume that you are using the Salesforce Classic user interface. To switch from the Salesforce Lightning Experience interface, click your profile icon and select **Switch to Salesforce Classic**. For additional information, see the Salesforce documentation for [Create a Connected App](#).
 - a. In Salesforce, in the upper right, click **Setup**.
 - b. In the left panel, select **Build > Create > Apps**.
 - c. Scroll down to **Connected Apps** and click **New**.
 - d. Enter the required information and then select **Enable OAuth Settings**.

- e. In the **Callback URL** field, paste your Fuse Online URL, which you copied at the beginning of this procedure. For example: **https://app-proj912876.7b63.fuse-ignite.openshiftapps.com/api/v1/credentials/callback**.
 - f. For **OAuth Scopes**, add:
 - **Access and manage your data (api)**
 - **Allow access to your unique identifier (openid)**
 - **Perform requests on your behalf at any time (refresh_token, offline_access)**
 - g. Select **Configure ID token** and then **Include Standard Claims**.
 - h. Scroll down and click **Save**.
 - i. Scroll up to see that Salesforce indicates a short wait:

New Connected App [Help for this Page](#) 

Allow from 2-10 minutes for your changes to take effect on the server before using the connected app.
 - j. Click **Continue**.
 - k. Copy the consumer key that Salesforce provides.
3. Return to your Fuse Online **Settings** page and paste the Salesforce-provided consumer key into the Fuse Online Salesforce **Client ID** field.
 4. Return to Salesforce and copy the consumer secret that Salesforce provides.
 5. Return to your Fuse Online **Settings** page and paste the Salesforce-provided consumer secret into the Fuse Online Salesforce **Client Secret** field.
 6. Click **Save**.
 7. Click the **Salesforce** entry to collapse it.

20.2. CREATING A SALESFORCE CONNECTION

To create an integration that accesses data in Salesforce, you must first create a Salesforce connection. After you create a Salesforce connection, you can use it in multiple integrations.

Prerequisites

- You are logged in to Fuse Online.
- Fuse Online is open in a web browser.
- You must have already registered your Fuse Online environment as an application that can access Salesforce.
- You added the Salesforce client ID and client secret that you received after registration to the Fuse Online **Settings** page.
Be sure to wait 2 - 10 minutes after registering your Fuse Online installation as a Salesforce client before you try to create a Salesforce connection.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display available connections.
2. Click **Create Connection** to display the available connectors. A connector is a template for creating one or more connections.
3. Click the **Salesforce** connector.
4. Click **Connect Salesforce** to display a Salesforce authorization page. You might need to log in to Salesforce before you see the authorization page.
If **Connect Salesforce** does not appear, then your Fuse Online environment is not registered as a Salesforce client application. See [Registering Fuse Online as a Salesforce client application](#) .
When you try to create a Salesforce connection and your Fuse Online environment is not registered as a Salesforce client application, then Fuse Online displays multiple fields that prompt for authorization information. While you can create a Salesforce connection by entering values in these fields, it is not recommended.



NOTE

The following error indicates that Salesforce does not have the correct Fuse Online callback URL:

error=redirect_uri_mismatch&error_description=redirect_uri%20must%20match%20configuration

If you get this error message, then in Salesforce, ensure that the Fuse Online callback URL is specified according to the instructions in [Registering Fuse Online as a Salesforce client application](#).

5. Click **Allow** to return to Fuse Online.
6. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **SF Connect 1**.
7. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Salesforce connection that uses my Salesforce login credentials**.
8. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **SF Connect 1** appears as a connection that you can choose to add to an integration.

20.3. ADDING A SALESFORCE CONNECTION TO AN INTEGRATION

In an integration, you can connect to Salesforce in the middle of a flow or to start or finish a simple integration. To do this, add a Salesforce connection to the integration.

Prerequisites

- You created a Salesforce connection.
- You are creating or updating an integration.

- Fuse Online is prompting you to choose a start connection, or to choose a finish connection, or to add to the integration.

Procedure

1. If you are adding to the Salesforce connection to the middle of a flow, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting for a start or finish connection.
2. Click the Salesforce connection that you want to add to the flow. When the integration uses the connection that you select to connect to Salesforce, Fuse Online uses the credentials defined in that connection.
3. Select the action that you want the selected connection to perform. Each Salesforce connection that you add to a flow performs only the action you choose.
4. Specify the Salesforce object that the action operates on, for example, it might be a contact, lead or price book entry. Click in the **Object** field to select from a list of Salesforce objects or enter the name of the object.
5. Click **Next** to add the connection to the flow.

CHAPTER 21. CONNECTING TO SAP CONCUR

SAP Concur manages business expenses, travel, and invoices. In an integration, you can connect to SAP Concur and perform any one of a large variety of SAP Concur actions. For example, suppose that you store project codes in a SQL database and you need the same project codes in SAP Concur so that expenses can be associated with projects. You can create an integration that connects to your SQL database and runs a stored procedure that obtains any new project codes. The integration can then connect to SAP Concur and upload the new project codes to the appropriate list.

See the following topics:

- [Section 21.1, "User roles for connecting to SAP Concur"](#)
- [Section 21.2, "How to Obtain SAP Concur implementation site OAuth credentials"](#)
- [Section 21.3, "How to obtain SAP Concur production site OAuth credentials"](#)
- [Section 21.4, "Configuring the SAP Concur connector"](#)
- [Section 21.5, "Creating a SAP Concur connection"](#)
- [Section 21.6, "Adding a SAP Concur connection to an integration"](#)
- [Section 21.7, "Example of mapping integration data fields to SAP Concur fields"](#)

21.1. USER ROLES FOR CONNECTING TO SAP CONCUR

SAP Concur has an implementation site for development work and a production site for live use. The implementation site simulates the production site. This lets you create and refine an integration before you use it in production with the live SAP Concur site.

At any one time, a Fuse Online environment can connect to the SAP Concur implementation site or the SAP Concur production site. In other words, a particular Fuse Online environment does not support connections to both SAP Concur sites at the same time. Each Fuse Online environment requires its own credentials for accessing each SAP Concur site and the credentials for the implementation site are different from the credentials for the production site.

Consequently, the expectation is that someone in a system administrator-like role would do the following:

1. Obtain two sets of OAuth credentials from SAP Concur:
 - One set for access to the SAP Concur implementation site
 - Another set for access to the SAP Concur production site
2. Configure the SAP Concur connector for access to the appropriate SAP Concur site.
3. Create a SAP Concur connection.

A business user can then create an integration that uses the SAP Concur connection.

21.2. HOW TO OBTAIN SAP CONCUR IMPLEMENTATION SITE OAUTH CREDENTIALS

To obtain credentials for accessing the SAP Concur implementation site, contact SAP Concur directly and tell them:

- You want to register Fuse Online as a new app that is authorized to access the SAP Concur implementation site.
- You want a new set of OAuth credentials for their implementation site.
- The credentials must include the **LIST** scope.
- Optionally, to obtain permission to perform actions other than the list actions, ask for other [scopes](#).
- The OAuth grant type for these credentials should be **Authorization Grant Flow**. To use a REST client, such as Postman, to send a request to the SAP Concur implementation site, you need credentials with an OAuth grant type of **Password**.
- The Fuse Online callback URL for the environment that that you want credentials for, which is something like this:

<https://syndesis.my-minishift.syndesis.io/api/v1/credentials/callback>

In this URL, **syndesis.my-minishift.syndesis.io** matches the OpenShift route to your Fuse Online environment.

The response from SAP Concur should provide:

- A username and password for logging in to the SAP Concur implementation site.
- Client ID and client secret values that you will specify in the Fuse Online development environment **Settings** page to configure the Fuse Online SAP Concur connector.

21.3. HOW TO OBTAIN SAP CONCUR PRODUCTION SITE OAUTH CREDENTIALS

To obtain OAuth credentials that authorize Fuse Online to access the SAP Concur production site, go to the [SAP Concur Developer Center Getting Started](#) page and follow the instructions there.

21.4. CONFIGURING THE SAP CONCUR CONNECTOR

To connect to SAP Concur in an integration, you must configure the Fuse Online SAP Concur connector. You can then use the connector to create a connection to SAP Concur.

Prerequisites

- You know whether you want to configure the SAP Concur connector to access the SAP Concur implementation site or the SAP Concur production site.
- You obtained OAuth credentials that authorize your Fuse Online environment to access the appropriate SAP Concur site.

Procedure

1. In Fuse Online, in the left panel, click **Settings**.
2. On the **Settings** page, expand the **SAP Concur** entry.

3. In the **Client ID** field, enter the client ID that you received from SAP Concur.
4. In the **Client Secret** field, enter the client secret that you received from SAP Concur. Fuse Online populates the other fields.
5. Click **Save**.
Fuse Online immediately tries to validate the configuration. If validation is not successful, correct the input values and try again. If validation is successful, you can create a SAP Concur connection, which you can add to an integration.
6. Click the **SAP Concur** entry to collapse it.

Next steps

Create a SAP Concur connection.

21.5. CREATING A SAP CONCUR CONNECTION

To connect to SAP Concur in an integration, you must first create a SAP Concur connection, which you can then add to any number of integrations. When you create a SAP Concur connection, you authorize the connection to access SAP Concur with the login credentials that you enter when you create the connection.

Prerequisites

- In the Fuse Online environment in which you are creating the connection, you must have configured the SAP Concur connector.
- You should know whether the connector is configured for access to the SAP Concur implementation site or the SAP Concur production site.
- You must have a user name and password for logging in to the SAP Concur site for which the SAP Concur connector is configured.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display the available connectors. A connector is a template that you use to create one or more connections.
3. Click the **SAP Concur** connector.
4. In the **Configure Connection** page, click **Connect SAP Concur**, which takes you to the SAP Concur site for which the connector is configured.
If **Connect SAP Concur** does not appear, then the SAP Concur connector in your Fuse Online environment is not configured. See [Configuring the SAP Concur connector](#).

If **redirect_uri is improper or not previously registered** appears, then the SAP Concur connector configuration is incorrect. Return to the Fuse Online **Settings** page to update and validate the connector configuration.
5. On the SAP Concur OAuth site:
 - a. Enter the email address for the SAP Concur account that you want this connection to use to access SAP Concur.

- b. Ensure that **Username** is selected.
 - c. Click **Continue**.
 - d. Enter the SAP Concur password associated with the email address.
 - e. Click **Sign In**, which returns you to Fuse Online.
6. In the Fuse Online **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **SAP Concur Test1**.
 7. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample SAP Concur connection to the implementation site**.
 8. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **SAP Concur Test1** appears as a connection that you can choose to add to an integration.

21.6. ADDING A SAP CONCUR CONNECTION TO AN INTEGRATION

You can add a SAP Concur connection to the middle of a flow or as the finish connection in a simple integration. A connection to SAP Concur can perform any one of 85 actions.

Prerequisites

- You created a SAP Concur connection.
- You are creating or editing a flow.
- Fuse Online is prompting you to add to the integration, or to choose the finish connection in a simple integration.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the SAP Concur connection that you want to add to the flow. When the integration uses the connection that you select, Fuse Online uses the credentials defined in that connection to connect to SAP Concur.
3. Select the action that you want the connection to perform. Each SAP Concur connection that you add to a flow performs only the action you choose.
For details about SAP Concur actions, visit the [SAP Concur developer center](#) and expand **v3.0**.
4. Click **Next** to add the connection to the flow.

Result

The connection appears in the integration visualization where you added it.

21.7. EXAMPLE OF MAPPING INTEGRATION DATA FIELDS TO SAP CONCUR FIELDS

In most integrations, you need to add a data mapping step before a connection to SAP Concur. In the

data mapping step, you map data fields that are available from previous integration steps to SAP Concur action parameters. In the data mapper, the **Target** panel displays the SAP Concur parameters for the action that you selected when you added the SAP Concur connection to the integration.

Suppose that an integration starts by executing a SQL stored procedure that obtains new project codes. The integration finishes by adding new project codes to SAP Concur. The following procedure provides an example of a data mapper step before the SAP Concur connection. The integration visualization displays and Fuse Online is prompting you to add to the integration.

1. In the integration visualization, click the plus sign that is before the SAP Concur finish connection.
2. Click **Data Mapper**. When the data fields appear, the **Sources** panel on the left displays the fields that are available from the database connection. In this example, the source fields include **concur-list-id** and **project-code**. The **Target** panel on the right displays the SAP Concur **id** and **content** parameters for the update list action, which the connection performs.
3. Map the **concur-list-id** source field to the **id** target field.
4. Map the **project-code** source field to the **content** target field.
5. In the upper right, click **Done** to add the data mapper step to the integration.

CHAPTER 22. CONNECTING TO SERVICENOW

An integration can retrieve records from a ServiceNow table or add records to a ServiceNow import set, which ServiceNow uses to update a table. In an integration, to connect to ServiceNow, create a ServiceNow connection and then add that connection to an integration. For details, see:

- [Section 22.1, "Creating a ServiceNow connection"](#)
- [Section 22.2, "Obtaining records from ServiceNow to trigger integration execution"](#)
- [Section 22.3, "Creating an import set in ServiceNow"](#)
- [Section 22.4, "Copying records to ServiceNow during or to finish an integration"](#)
- [Section 22.5, "Example Salesforce to ServiceNow integrations"](#)

22.1. CREATING A SERVICENOW CONNECTION

In an integration, to connect to your company's ServiceNow instance, you must create a ServiceNow connection.

Prerequisites

- A ServiceNow administrator at your site must have created a ServiceNow account for you.
- You must know the URL for your ServiceNow instance and your ServiceNow user name and password.
- If the ServiceNow administrator also created a ServiceNow client ID and client secret for you, you must know these values.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **ServiceNow** connector.
4. Configure this ServiceNow connection:
 - a. In the **Instance Name** field, enter the name of the ServiceNow instance that you want to obtain records from or copy records to. For example, if the URL for your ServiceNow instance is **https://abc12345.service-now.com**, the instance name is **abc12345**.
 - b. In the **User Name** field, enter your ServiceNow user name.
 - c. In the **User Password** field, enter your ServiceNow password.
 - d. Optionally, in the **Client ID** field, enter your client ID if you received one from your ServiceNow administrator.
 - e. Optionally, in the **Client Secret** field, enter your client secret if you received one from your ServiceNow administrator.

- f. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, update the configuration details as needed and try again.
 - g. When validation is successful, click **Next**.
5. In the **Name** field, enter a name that helps you distinguish this connection from other connections. For example, enter **ServiceNow Con 1**.
 6. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **ServiceNow connection that uses administrative credentials**.
 7. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **ServiceNow Con 1** appears as a connection that you can choose to add to an integration.

22.2. OBTAINING RECORDS FROM SERVICENOW TO TRIGGER INTEGRATION EXECUTION

To trigger execution of an integration upon receiving records from ServiceNow, add a ServiceNow connection to a simple integration as its start connection.

Prerequisites

- You created a ServiceNow connection.
- You know the name of the table that you want to retrieve records from.
- You should have already defined a ServiceNow query that obtains only the records that you want. You can find information about ServiceNow queries here: [ServiceNow encoded queries](#).

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the ServiceNow connection that you want to use to start the integration.
4. On the **Choose an action** page, select **Retrieve Record** to obtain records from a ServiceNow table that you select.
5. Configure the **Retrieve Record** action:
 - a. Click in the **Table name** field and select the table that you want to obtain records from.
 - b. In the **Query to filter the result set** field, enter a ServiceNow query. For example, consider the **state=1^impact=2** query on a table that keeps records about incidents. This query returns records for new incidents (**state=1**) that have a medium impact (**impact=2**). If you do not enter a query and the records in the table do not change, the connection obtains the same records every time.

- c. In the **Limit of elements per page** field, enter the maximum number of records that you want the connection to obtain. In this release, you must enter a value, the recommendation is to enter **1000** or less, and pagination is not supported.
- d. In the **Period** field, indicate how often you want to obtain records. The default is every minute. In other words, by default, Fuse Online executes this integration every 60 seconds.
- e. Click **Next**.

Results

Fuse Online generates a JSON schema that defines the structure of the obtained records. This enables you to add a data mapping step before the next connection in the integration if data mapping is needed.

Fuse Online prompts you to choose a finish connection.

22.3. CREATING AN IMPORT SET IN SERVICENOW

In a Fuse Online integration, a ServiceNow connection cannot directly update a ServiceNow table. To update ServiceNow data in an integration, a prerequisite is an import set that stages updates for a ServiceNow table.

Often, the easiest way to create an import set is for a ServiceNow administrator to create a ServiceNow inbound web service. This implicitly creates a ServiceNow import set. The import set is based on the ServiceNow target table that the administrator selects when creating the web service. A ServiceNow connection updates this import set, and ServiceNow uses the import set to update the corresponding ServiceNow table.

Prerequisites

You must have ServiceNow administrative privileges.

Procedure in ServiceNow

1. In ServiceNow, search for **web services**.
2. In the results, under **System Web Services > Inbound**, click **Create New**.
3. In the **Create Web Service** page:
 - a. In the **Label** field, specify the display name for the web service. The web service's import set will also have this name.
 - b. In the **Target table** field, select the ServiceNow table that this service updates.
 - c. Select **Copy fields from target table**. This creates an import set that has the same schema as the target table. The import set is a staging area for updating the target table.
 - d. Select **Create transform map**. This map enables ServiceNow to copy and transform data from the import set to the target table.
4. Click **Create**.
5. In the next display, under **Related Links**, click **Auto Map Matching Fields** to display a list of fields in the target table that you selected.
6. Select one target table field to be the correlation (or coalesce) field.

When the value of the correlation field in a record in the import set matches the value of a correlation field in the target table, ServiceNow updates that record in the target table rather than creating a new record.

7. Select **Coalesce** to identify the field that you just selected as the correlation field. Without a correlation field, ServiceNow adds each record in the import set to the target table.
8. Click **Update**.
9. Confirm that the transform map was created:
 - a. In ServiceNow, search for **transform map**.
 - b. Under **System Import Sets**, click **Transform Maps** to display a list of transform maps.
 - c. In this list, confirm that there is a transform map whose name is the value that you specified for the label of the web service that you created.

Additional resource

[ServiceNow documentation for import sets](#)

22.4. COPYING RECORDS TO SERVICENOW DURING OR TO FINISH AN INTEGRATION

You can copy records to ServiceNow in the middle of a flow or to finish a simple integration. To do this, add a ServiceNow connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites


- You created a ServiceNow connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.
- You know the name of the ServiceNow import set that you want to add records to. Your ServiceNow administrator can help you identify the appropriate import set. If the import set does not exist, see [Creating an import set in ServiceNow](#) .
- The ServiceNow import set is configured to handle the addition of records.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the ServiceNow connection that you want to add to the integration.
3. Select the **Add Record** action.
4. Click in the **Import Set** field and select the import set that you want to add records to.
5. Click **Next**.

Results

Fuse Online adds the connection to the flow.

Typically, a data mapper step is needed before this connection. In the integration visualization, Fuse Online displays  on the connection. In most integrations, you need to map a source field to the target field used as the correlation field in the ServiceNow table.

22.5. EXAMPLE SALESFORCE TO SERVICENOW INTEGRATIONS

This example describes two simple integrations:

- One integration obtains new cases from Salesforce and adds them as incidents to ServiceNow.
- The other integration obtains updated cases from Salesforce and updates a corresponding incident in ServiceNow.

Prerequisites (in ServiceNow)

For both integrations, a prerequisite is for a ServiceNow administrator to create an inbound web service. This implicitly creates a ServiceNow import set, which is required for an integration to add data to ServiceNow. For this example:

- The name of the web service is **Cases from Salesforce**.
- The service's target table is **Incidents**. This table contains the data to be updated.
- The import set has the same schema as the **Incidents** table because of the selection of **Copy fields from target table**. The name of the import set is also **Cases from Salesforce**.
- ServiceNow can copy and transform data from the **Cases from Salesforce** import set to the **Incidents** target table because of the selection of **Create transform map**.
- In the import set, the correlation field is **correlation_Id** because of the selection of the **correlation_Id** field followed by selection of **Coalesce**.

Procedure overview (in Fuse Online)

In Fuse Online, you create the Salesforce and ServiceNow connections.

The two integrations are the same except for the action performed by the Salesforce connection, as noted in the following steps. To create the integrations, you would perform these steps twice, that is, once to create each integration:

1. Add the Salesforce connection as the start connection.
 - To create the integration that obtains new cases, select the **On create** action.
 - To create the integration that obtains updated cases, select the **On update** action.
2. Select the **Case** object for the action to operate on. This Salesforce connection returns new **Case** objects or updated **Case** objects according to the chosen action.
3. Add the ServiceNow connection as the finish connection.
4. Select the **Create Record** action, and then select **Cases from Salesforce** as the import set that the integration updates.

This ServiceNow connection adds new or updated Salesforce cases to the **Cases from Salesforce** import set.

5. Add a data mapper step that maps:
 - Salesforce case **id** to the ServiceNow import set's **correlation_id**
 - Salesforce **subject** to the ServiceNow **short_description**
 - Salesforce **description** to the ServiceNow **description**
6. Give the integration a name and then publish it.
 - For the integration that obtains new cases, use **On SF Create Case**
 - For the integration that obtains updated cases, **On SF Update Case**

Confirm that the integrations work

When both integrations are running, you can confirm that the integrations work:

1. In Salesforce, create a case.
2. In Fuse Online, view the summary for the **On SF Create Case** integration. Click its **Activity** tab to see that Fuse Online executed the integration once.
3. In ServiceNow, view the **Incidents** table. You should see a new incident that has the subject and description that you specified in Salesforce.
4. Back in Salesforce, update the case that you just created by changing its subject.
5. In Fuse Online, view the summary for the **On SF Update Case** integration. Click its **Activity** tab to see that Fuse Online executed the integration once.
6. In ServiceNow, view the **Incidents** table and expand the entry for the incident that was previously new. You should see that this incident has an updated **short_description** value. ServiceNow checks the import set entry for the value of its **correlation_id**. If this value already exists in the **Incidents** table, ServiceNow updates the incident that has that value.

CHAPTER 23. CONNECTING TO SLACK

As a business user, you can create an integration that connects to Slack. A connection to Slack can do either one of the following:

- Trigger execution of a simple integration when a Slack channel that you specify receives a message. The integration passes the message to the next step in the flow. For example, you can monitor a Slack channel for keyword instances such as product names. Upon finding messages that contain those product names, the integration can notify the appropriate contact in a Gmail connection.
- Deliver a message to a particular user or to a channel. For example, this behavior is useful when an integration downloads a file from an FTP server and processes it in some way. An integration flow can notify a Slack channel or user that the process was successful.

To connect to Slack in an integration, create a Slack connection and then add the connection to an integration flow. Details are in the following topics:

- [Section 23.1, “Creating a Slack connection”](#)
- [Section 23.2, “Adding a Slack connection to trigger integration execution upon receiving messages”](#)
- [Section 23.3, “Adding a Slack connection to send a message to a Slack channel or user”](#)

23.1. CREATING A SLACK CONNECTION

In an integration, a Slack connection can retrieve messages from a channel that you specify or send a message to a channel or user. You can use the same Slack connection in any number of integrations.

Prerequisites

- You [created and installed a Slack app](#) for connecting Fuse Online to Slack.
- You can obtain the Slack webhook URL for your Slack app.
- You can obtain the **Bot User OAuth Access Token** that authorizes access to your Slack app.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **Slack** connector.
4. In the **Slack webhook URL** field, enter the webhook URL for your Slack app.
5. In the **Token for accessing Slack API** field, enter the **Bot User OAuth Access Token**, which you can obtain from the Slack app’s **OAuth & Permissions** page.
6. Optionally, enter values for additional parameters:
 - In the **Sending username for messages** field, enter the user name that the bot has when it sends messages to Slack.

- In the **Message avatar emoji** field, specify one emoji, which the bot uses as the message avatar when it sends a message. Examples: **:smile;** **:wave;** **:question:**.

TIP

Search the web for **emoji cheat sheet** to see some emoji codes.

- In the **Message avatar icon URL** field, specify the URL of the avatar that the bot uses when it sends messages to Slack.

If you specify an emoji and an icon URL, then the integration uses the icon URL. If you specify neither an emoji nor an icon URL, then the message is sent without an avatar.

7. Click **Validate**. Fuse Online immediately tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the connection configuration values and try again.
8. If validation is successful, click **Next**.
9. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Slack for Tracking Company Sales**.
10. In the **Description** field, optionally enter any information that is helpful to know about this connection.
11. Click **Save** to see the updated list of available connections, including the connection that you just created. If you entered the example name, you would see that **Slack for Tracking Company Sales** appears as a connection that you can choose to add to an integration. You can add this connection to any number of integrations.

23.2. ADDING A SLACK CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES

A Slack connection that starts an integration triggers execution of the integration when the connection finds messages on a Slack channel that you specify.

Prerequisites

- You created a Slack connection.
- You are creating an integration and Fuse Online is prompting you to choose how you want to start the integration.

Procedure

1. Click the Slack connection that you want to use to start the integration.
2. Select the **Read Messages** action.
3. In the **Channel** field, specify the Slack channel from which you want to obtain messages.
4. In the **Delay** field, accept the default of 500 milliseconds as the time that elapses between polls for messages. Or, to specify a different interval for checking for messages, enter a number and select its time unit.

5. In the **Maximum Messages to Retrieve** field, accept the default of 10 or indicate the maximum number of messages that the connection can return for each poll. If the connection finds more than this number of unread messages, then it returns the most recent messages. The connection returns a particular message only once.

For example, if you accept the default of 10 and there are 15 messages at the time of a poll then the connection returns the 10 most recent messages. At the next poll, the connection checks for messages that have a time stamp that is after the most recent message that the connection previously returned. This means that the 5 messages that were not returned in the first example poll are never returned.

When a Slack connection returns more than one message, the integration processes the messages as a batch. In other words, Fuse Online executes the integration once for the batch.

6. Click **Next** to add the connection to the integration.

23.3. ADDING A SLACK CONNECTION TO SEND A MESSAGE TO A SLACK CHANNEL OR USER

In an integration, you can send a message to a Slack channel or Slack user in the middle of a flow or to finish a simple integration. To do this, add a Slack connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a Slack connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the Slack connection that you want to add to the flow.
3. Select the action that you want the connection to perform.
 - Select **Username** to send a message to one user. To configure this action, in the **User name** field, specify the Slack name of the user to send the message to.
 - Select **Channel** to publish a message on a channel. To configure this action, in the **Channel** field, specify the channel to publish the message to.
4. Click **Next** to add the connection to the flow.
5. Optionally, add additional connections to the flow. Whether additional connections are needed depends on what you want the flow to do. The important point is to add all connections before you continue.
6. Add a data mapper step just before the Slack connection that you added in this procedure. In the mapping step, map a string from a data mapping source to the Slack **message** field. This string should contain the message that you want to send to the Slack user or channel. See [Adding a data mapper step](#).

CHAPTER 24. CONNECTING TO SQL DATABASES

In an integration, you can connect to any of the following types of SQL databases:

- Apache Derby
- MySQL
- PostgreSQL

Create a connection to the database that you want to access in an integration. Then create an integration and add that database connection to the integration.

To connect to other types of databases, you must upload a JDBC driver for that database.

See the following topics for details:

- [Section 24.1, "Creating a database connection"](#)
- [Section 24.2, "How to specify the schema in a database connection"](#)
- [Section 24.3, "Obtaining database records to trigger integration execution"](#)
- [Section 24.4, "About parameter placeholders and values in SQL statements that update data"](#)
- [Section 24.5, "Accessing a database in the middle or to complete an integration"](#)
- [Section 24.6, "Connecting to proprietary databases"](#)

24.1. CREATING A DATABASE CONNECTION

You create a separate connection for each database that you want to connect to in an integration. You can use the same connection in multiple integrations.

A database connection operates on a database table that you specify or invokes a stored procedure that you specify.

Prerequisite

The database table or the stored procedure must exist when an integration connects to the database.

Procedure

1. Ensure that the JDBC driver for the database that you want to connect to is on your classpath. If you uploaded a JDBC driver library extension to connect to a proprietary database, then the upload process puts the driver on your classpath. See [Creating JDBC driver library extensions](#).
2. In Fuse Online, in the left panel, click **Connections** to display any available connections.
3. Click **Create Connection** to display Fuse Online connectors.
4. Click the **Database** connector.
5. Configure the connection by entering:
 - a. In the **Connection URL** field, enter the JDBC URL for the database that you want to connect to. For example, enter **jdbc:postgresql://ignite-db1234/sampledb**.

- b. In the **Username** field, enter the name of the account that you want to use to access the database. Ensure that the specified password and user name are for the same account.
 - c. In the **Password** field, enter the password associated with the user account you want to use to access the database.
 - d. In the **Schema** field, enter the name of the schema for the database. How you specify the database schema varies for each type of database. Details are in the next section: [How to specify the schema in a database connection](#).
6. Click **Validate**. Fuse Online tries to validate the connection and displays a message that indicates whether validation is successful. If validation fails, revise the configuration details as needed and try again.
 7. If validation is successful, click **Next**.
 8. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **PostgreSQL DB 1**.
 9. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample PostgreSQL connection that uses my login credentials**.
 10. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **PostgreSQL DB 1** appears as a connection that you can choose to add to an integration.

24.2. HOW TO SPECIFY THE SCHEMA IN A DATABASE CONNECTION

In Fuse Online, when you create a database connection, the user interface prompts you to specify the database's schema. How you specify the schema varies for each database. The table below shows what each database requires.

Database	Example connection configuration	Notes
Apache Derby	Connection URL (JDBC URL): jdbc:derby:memory:testdb;create=true Username: sa Password: any value Schema: sample	For testing purposes only. The default username is sa and the password can be anything but you must enter a value. In this example configuration, the connection uses the sample schema, which is like a namespace. For example, you can reference the mytable table with sample.mytable .
MS SQLServer	Connection URL (JDBC URL): jdbc:sqlserver://localhost:1433/sampledb Username: kurt Password: mypw Schema: sampledb	Upload the driver by using the extension mechanism . Then create a connection. Connection verification fails if you have not already uploaded the driver. You must specify the same schema at the end of the connection URL and in the Schema field.

Database	Example connection configuration	Notes
MySQL	<p>Connection URL (JDBC URL): sql-connector.url=jdbc:mysql://mysql-host:3307/test?allowPublicKeyRetrieval=true&useSSL=false&useUnicode=true&useJDBCCompliantTimezoneShift=true&useLegacyDatetimeCode=false&serverTimezone=UTC</p> <p>Username: kurt</p> <p>Password: mypw</p> <p>Schema:</p>	<p>MySQL does not support schemas. When you create a connection to a MySQL database, leave the Schema field blank. MySQL expects all configuration in the connection (JDBC) URL.</p>
Oracle DB	<p>Connection URL (JDBC URL): jdbc:oracle:thin:@10.192.212.255:1521:xe</p> <p>Username: kurt</p> <p>Password: mypw</p> <p>Schema:</p>	<p>Use the Fuse Online extension mechanism. to upload an Oracle database driver. Then create the connection. Connection verification fails if the driver has not been uploaded. The schema is the database name. You must have permission to access this database instance, which is referred to as a schema in Oracle terminology. Leave the Schema field blank. In the Connection field, you must reference the Oracle system identifier (SID) of this database instance (xe in this example).</p>
PostgreSQL	<p>Connection URL (JDBC URL): jdbc:postgresql://syndesis-db:5432/sampledb</p> <p>Username: kurt</p> <p>Password: mypw</p> <p>Schema: sampledb</p>	<p>You must specify the database in the connection (JDBC) URL. If you want to use a schema you must specify it in the Schema field. A query can refer to a table in the form <i>database.schema.table</i>. When a reference specifies only a table name, the connection first searches the schema that you specify when you configure the connection. If the table is not found, then the connection searches public resources for the specified table. For more details, see PostgreSQL schema documentation.</p>

24.3. OBTAINING DATABASE RECORDS TO TRIGGER INTEGRATION EXECUTION

To trigger execution of an integration based on the result of invoking a SQL statement or a SQL stored procedure, choose a database connection as the integration's start connection.

Prerequisite

You created a database connection.

Procedure

1. In the Fuse Online panel on the left, click **Integrations**.
2. Click **Create Integration**.
3. On the **Choose a connection** page, click the database connection that you want to use to start an integration.
4. On the **Choose an action** page, select one of the following:
 - **Periodic SQL invocation** obtains data by periodically invoking the SQL statement that you specify.
Note that the Database Connector accepts most basic SQL syntax. If you want to use a complex SQL statement, you should use a stored procedure instead since the Database Connector does not validate the SQL syntax in a stored procedure.
 - **Periodic stored procedure invocation** obtains data by periodically invoking the stored procedure that you specify or select.
5. If you selected **Periodic SQL invocation**, in the **Query** field, enter a SQL **SELECT** statement or some other standard SQL statement that obtains one or more records. For example: **SELECT * from my_db_table**. The database table that contains the data you want must already exist. If you selected **Periodic stored procedure invocation**, in the **Procedure name** field, select or enter the stored procedure to invoke to obtain the data of interest. The stored procedure you specify must already exist. The database administrator should have created any stored procedures you need to use in an integration.
6. In the **Period** field, enter an integer and indicate whether the unit is milliseconds, seconds, minutes, hours, or days. For example, if you specify **5 minutes** then the connection invokes the specified statement or stored procedure every five minutes.
7. Click **Next**.

Limitations on the use of SQL extensions

SQL statements that you enter in the **Query** field must be standard SQL constructs. Fuse Online does not recognize or parse SQL extensions such as Procedural Language/PostgreSQL (PL/pgSQL) or Oracle Procedural Language Extensions to SQL (PL/SQL). However, you can use SQL extensions within stored procedures.

Result

Fuse Online tries to validate the connection, which includes checking that a specified SQL statement is syntactically correct and confirming that the statement or stored procedure target data exists. If verification is successful then Fuse Online adds the start connection to the integration. If verification fails then Fuse Online displays a message about the problem. Update your input as needed and try again.

24.4. ABOUT PARAMETER PLACEHOLDERS AND VALUES IN SQL STATEMENTS THAT UPDATE DATA

A database connection that is in the middle of a flow, or that finishes a simple integration, can execute a SQL statement that updates data. When you add a database connection to an integration, you can specify placeholder parameters in the SQL statement to be executed. During execution, the connection can perform a batch update when the input parameter values are in a collection.

Specifying parameters in SQL statements

When you create or edit an integration and you add a connection that updates a database, you can specify placeholder parameters in the SQL statement that the connection executes at runtime or there can be placeholders in the stored procedure that will be executed at runtime. For example:

```
INSERT INTO TODO(task, completed) VALUES(:#param_1, :#param_2)
DELETE FROM TODO WHERE task LIKE :#param_3
```

To specify the values of these placeholders, add a data mapping step to the flow before the database connection. In the data mapping step, map the appropriate source data fields to the target data fields, for example, map source data to the **:#param_1**, **:#param_2**, and **:#param_3** target fields. See [Adding a data mapper step](#).

Batch update with a collection of parameter values

At runtime, when a database connection executes a SQL statement that inserts, deletes, or updates data, the SQL statement being executed often specifies one or more placeholder parameters, for example, **:#task**. When it does, the input to the connection can be a single set of parameters or a collection of parameter sets, where each element in a set defines a value for the corresponding placeholder parameter.

The input to the database connection comes from an earlier connection in the flow, for example, an HTTP request (Webhook) or a request sent to the REST API service for an API provider integration. When the input is a collection, the connection uses batch mode to update the table. For example, consider this SQL statement:

```
insert into todo (task) values (:#task)
```

If the input collection contains 3 values, the connection inserts three records, one for each value. Now consider a SQL statement with two placeholder parameters:

```
insert into todo (task, completed) values (:#task, :#completed)
```

In the input to the connection that executes this SQL statement, a data shape specification could specify a single element, for example:

```
{"task": "write some docs", "completed": 0}
```

Or it could specify a collection, for example:

```
[{"task": "write doc", "completed": 1},
 {"task": "publish doc", "completed": 0}]
```

With a collection as input, the connection executes the insert operation once for each set of parameter values. In this example, the connection adds two records to the table, one for each set of parameter values.

24.5. ACCESSING A DATABASE IN THE MIDDLE OR TO COMPLETE AN INTEGRATION

In an integration, you can access a database in the middle of a flow or to finish a simple integration. To do this, add a database connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a database connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the database connection for the database that you want to access.
3. On the **Choose an action** page, select one of the following:
 - **Invoke SQL** operates on data by executing the SQL statement you specify. Note that the Database Connector accepts most basic SQL syntax. If you want to use a complex SQL statement, you should use a stored procedure instead since the Database Connector does not validate the SQL syntax in a stored procedure.
 - **Invoke stored procedure** operates on data by invoking the stored procedure that you specify or select.
4. If you selected **Invoke SQL**, in the **SQL Statement** field:
 - For a middle connection, enter a SQL **SELECT** statement that obtains one or more records or enter a SQL **INSERT**, **UPDATE**, or **DELETE** statement that operates on one or more records. The database table that contains the data must already exist.
 - For a finish connection, enter a SQL **INSERT**, **UPDATE** or **DELETE** statement to operate on one or more records.
 - In the **Batch update** field, accept **No**, which is the default, or select **Yes**. The setting of **Batch update** affects connection behavior when the input to this action is a collection, and the SQL statement inserts, deletes, or updates records. The default behavior (**Batch update** is **No**) is that the connection accepts only individual objects and executes the SQL statement once for each object. When **Batch update** is **Yes**, the connection accepts a collection as the input to the action. The connection executes the SQL statement once and uses all collection items as input to a batch update operation.

If you selected **Invoke stored procedure**, in the **Procedure name** field, select or enter the name of the stored procedure to invoke to operate on the data of interest. The stored procedure you specify must already exist. The database administrator should have created any stored procedures you need to use in an integration.

5. Click **Next**.

Result

Fuse Online tries to validate the connection, which includes checking that a specified SQL query is syntactically correct and confirming that the query or stored procedure target data exists. If verification is successful then Fuse Online adds the connection to the flow. If verification fails then Fuse Online displays a message about the problem. Update your input as needed and try again.

Additional resource

[About parameter placeholders and values in SQL statements that update data](#) .

24.6. CONNECTING TO PROPRIETARY DATABASES

To connect to a proprietary SQL database, the main tasks that must be accomplished are as follows:

1. A developer creates a library extension that contains the JDBC driver for the database that you want to access in an integration. See [Creating JDBC driver library extensions](#).
2. The developer provides a **.jar** file that contains the library extension.
3. You upload that **.jar** file to Fuse Online. See [Making extensions available](#).
4. You create a connection to your database by selecting the Fuse Online **Database** connector and specifying the connection URL for your database. See [Creating a database connection](#).
5. In an integration, you add the connection to your database. See [Starting an integration by accessing a database](#) or [Accessing a database in the middle or to complete an integration](#).

CHAPTER 25. CONNECTING TO TELEGRAM

As a business user, you can create an integration that connects to Telegram. A connection to Telegram can do either one of the following:

- Trigger execution of a simple integration when a Telegram bot that you specify receives a message. The integration passes the message to the next step in the flow. For example, after a simple integration receives a message there might be a filter step that watches for keyword instances such as product names. Upon finding messages that contain those product names, the integration can notify the appropriate contact in a Gmail connection or in a different Telegram connection.
- Deliver a message to a particular Telegram chat. For example, this behavior is useful when an integration downloads a file from an FTP server and processes it in some way. You can add a Telegram connection that notifies a Telegram chat that the process was successful.

To connect to Telegram in an integration, create a Telegram connection and then add the connection to an integration flow. Details are in the following topics:

- [Section 25.1, “Creating a Telegram connection”](#)
- [Section 25.2, “Adding a Telegram connection to trigger integration execution upon receiving messages”](#)
- [Section 25.3, “Adding a Telegram connection to send a message to a Telegram chat”](#)

25.1. CREATING A TELEGRAM CONNECTION

In an integration, a Telegram connection can receive messages that have been sent to a particular chat. A chat bot that you create forwards the messages to Fuse Online. A Telegram connection can also send messages to chats that the connection has access to. You can use the same Telegram connection:

- In any number of integrations that use the connection to send messages to a chat.
- In addition, you can use it in one integration that uses the connection to receive messages from a Telegram chat.

In other words, you cannot use the same Telegram connection in more than one integration if you want that connection to receive Telegram chat messages in both integrations. This is a Telegram limitation.

Prerequisites

- In Telegram, you created a bot for the chat that you want to obtain messages from and send messages to. For help with this, see [Bots, an introduction for developers](#).
- You obtained a bot authorization token from the Telegram BotFather.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.
2. Click **Create Connection** to display Fuse Online connectors.
3. Click the **Telegram** connector.

4. In the **Authorization Token** field, enter the Telegram authorization token for the bot that you want to get messages from and send messages to.
5. Click **Next**.
6. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Telegram for Product Mentions**.
7. In the **Description** field, optionally enter any information that is helpful to know about this connection.
8. Click **Save** to see the updated list of available connections, including the connection that you just created. If you entered the example name, you would see that **Telegram for Product Mentions** appears as a connection that you can choose to add to an integration. You can add this connection to any number of integrations.

25.2. ADDING A TELEGRAM CONNECTION TO TRIGGER INTEGRATION EXECUTION UPON RECEIVING MESSAGES

A Telegram connection that starts an integration triggers execution of the integration each time that the connection receives a message from a Telegram chat bot that you specify.

Prerequisites

- You created a Telegram connection.
- You are creating a simple integration and Fuse Online is prompting you to choose how you want to start the integration.

Procedure

1. Click the Telegram connection that you want to use to start the integration.
2. Select the **Read Messages** action to receive all messages that are sent to the chat bot. The connection configuration identifies the chat bot that you want to receive messages from. No other configuration is required.

25.3. ADDING A TELEGRAM CONNECTION TO SEND A MESSAGE TO A TELEGRAM CHAT

In an integration, you can send a message to a Telegram chat in the middle of a flow or to finish a simple integration. To do this, add a Telegram connection to the middle of a flow or as a simple integration's finish connection.

Prerequisites

- You created a Telegram connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add the connection. Skip this step if Fuse Online is prompting you to choose the finish connection.
2. Click the Telegram connection that you want to add to the flow.
3. Select the **Send a Text Message** action.
4. In the **Chat Id** field, enter the ID for the Telegram chat that you are sending a message to. If you leave this field blank, and if there is an earlier Telegram connection that receives messages, then Fuse Online uses the chat ID that is in an incoming message.

To obtain the ID for a chat:

- a. In Telegram, add a bot to the chat that you want to send a message to. The BotFather response includes a bot access token.
 - b. Copy the access token to the clipboard.
 - c. In Telegram, send a message directly to that chat. Do not use the bot to send the message.
 - d. Read messages that are sent to that chat by invoking a **curl** command in the following format. Replace **bot-access-token** with the access token in the clipboard.
curl https://api.telegram.org/bot-access-token/getUpdates?offset=0
- The response is in JSON format. The JSON **chat** object contains the chat ID.
5. Click **Next** to add the connection to the flow.

CHAPTER 26. CONNECTING TO TWITTER

To connect to Twitter in an integration, the main steps are:

- [Section 26.1, “Registering Fuse Online as a Twitter client application”](#)
- [Section 26.2, “Creating a Twitter connection”](#)
- [Section 26.3, “Adding a Twitter connection to trigger integration execution”](#)
- [Section 26.4, “Adding a Twitter connection that sends a direct message”](#)

You need a Twitter developer account to authorize access from your Fuse Online environment to Twitter. If you do not already have a Twitter developer account, go to <https://apps.twitter.com>, sign in to Twitter, and click **Apply for a developer account**. Obtaining the developer account is quick when you provide a professional email address, such as **me@redhat.com** rather than a personal address such as **you@gmail.com**.

26.1. REGISTERING FUSE ONLINE AS A TWITTER CLIENT APPLICATION


In an integration, to connect to Twitter, the first thing you must do is register your Fuse Online environment as a client application that can access Twitter. This lets you create any number of integrations that connect to Twitter. In other words, you need to register a particular Fuse Online environment with Twitter only once.

In each Fuse Online environment, there can be only one registration of Fuse Online as a Twitter client application. However, while each Twitter connection uses the same registration, it can use different user credentials.

Prerequisite

You are logged in to Fuse Online.

Procedure

1. In Fuse Online:
 - a. In the left panel, click **Settings**.
 - b. On the **Settings** page, near the top, to the right of the callback URL, click  to copy the callback URL for your installation of Fuse Online to the clipboard. You will need this URL later in this procedure.
 - c. Click the **Twitter** entry to display the **Consumer API Key** and **Consumer API Secret Key** fields.
2. In another browser tab, go to your [Twitter developer account](#), sign in if you need to, and then do the following:
 - a. Click **Projects & Apps**
 - b. On the **Overview** page, scroll down to click **Create an app**
 - c. In the **App name** field, enter a name such as **My Fuse Online Client**.

- d. In the **Application description** field, enter a tip such as **For leveraging tweets**.
 - e. Scroll down to **Set up Your App** and then click **App settings**.
 - f. Next to **Authentication Settings**, click **Edit**.
 - g. Switch on the **Enable 3-legged OAuth** option.
 - h. In the **Callback URLs** field, paste the URL that you copied at the beginning of this procedure. It should be something like this: **https://app-proj912876.7b63.fuse-ignite.openshiftapps.com/api/v1/credentials/callback**
 - i. In the **Website URL** field, paste the URL again and remove **api/v1/credentials/callback** from the end of the URL.
You can skip the next few fields.
 - j. Click **Save**.
 - k. At the top of the page for the app that you just created, click the **Keys and tokens** tab.
 - l. Under **Consumer Keys**, click **View keys**.
 - m. Copy the API key.
3. Return to your Fuse Online **Settings** page and paste the Twitter consumer API key into the Fuse Online Twitter **Consumer API Key** field.
 4. Return to the Twitter **Keys and tokens** tab and copy the consumer API secret key.
 5. Return to your Fuse Online **Settings** page and paste the Twitter consumer API secret key into the Fuse Online Twitter **Consumer API Secret Key** field.
 6. Click **Save**.
 7. Click the **Twitter** entry to collapse it.

26.2. CREATING A TWITTER CONNECTION

To create an integration that obtains data from Twitter, you must first create a Twitter connection. After you create a Twitter connection, you can use it in any number of integrations.

Prerequisites

- You are logged in to Fuse Online.
- Fuse Online is open in a web browser.
- You registered your Fuse Online environment as an application that can access Twitter.
- You added the Twitter consumer API key and consumer API secret key that you received after registration to the Fuse Online **Settings** page.

Procedure

1. In Fuse Online, in the left panel, click **Connections** to display any available connections.

2. Click **Create Connection** to display the available connectors. A connector is a template that you use to create one or more connections.
3. Click the **Twitter** connector.
4. Click **Connect Twitter** to display a Twitter authorization page. You might need to log in to Twitter before you see the authorization page.
If **Connect Twitter** does not appear, then your Fuse Online environment is not registered as a Twitter client application. See [Registering Fuse Online as a Twitter client application](#) . When you try to create a Twitter connection and your Fuse Online environment is not registered as a Twitter client application, then Fuse Online displays multiple fields that prompt for authorization information. While you can create a Twitter connection by entering values in these fields, it is not recommended.
5. Click **Authorize app** to return to Fuse Online.
6. In the **Name** field, enter your choice of a name that helps you distinguish this connection from any other connections. For example, enter **Twitter Connect 1**.
7. In the **Description** field, optionally enter any information that is helpful to know about this connection. For example, enter **Sample Twitter connection that uses my Twitter login credentials**.
8. Click **Save** to see that the connection you created is now available. If you entered the example name, you would see that **Twitter Connect 1** appears as a connection that you can choose to add to an integration.

26.3. ADDING A TWITTER CONNECTION TO TRIGGER INTEGRATION EXECUTION

In a simple integration, the start connection can be a Twitter connection that triggers execution of the integration when it finds certain tweets or direct messages.

Prerequisites

- You created a Twitter connection.
- You are creating or editing a simple integration and Fuse Online is prompting you to choose the start connection.

Procedure

1. Click the Twitter connection that starts the integration. When the integration uses the selected connection to connect to Twitter, Fuse Online uses the credentials defined in that connection.
2. Select the action that you want the connection to perform. A Twitter connection that you add to an integration performs only the action that you choose:
 - **Mention** monitors Twitter for tweets that contain the Twitter handle for the Twitter account that the connection is authorized to access. Upon finding such a tweet, the connection returns it to Fuse Online, which triggers execution of the integration.
 - **Retrieve** periodically polls Twitter for direct messages sent to the Twitter account that the Twitter connection is authorized to access. Upon finding such messages, the connection returns them to Fuse Online, which triggers execution of the integration.

- **Search** periodically polls Twitter for tweets that match criteria that you specify. Upon finding such tweets, the connection returns them to Fuse Online, which triggers execution of the integration.
3. Configure the action that you selected:
- **Mention** does not require any configuration.
 - **Retrieve**
 - **Count** has a default of 100 and you should not need to change this value, which affects internal behavior. However, do not set this value to less than 50 because doing so might decrease performance.
The **Retrieve** action always returns all previously unreturned direct messages received in the last 30 days. If you do not select **Ignore direct messages previously found**, then the **Retrieve** action returns all messages that have been received in the last 30 days.
 - **Delay** is the period of time between polls. Twitter enforces rate limits, so you should not poll too often. The default interval is 5 seconds.
 - **Ignore direct messages previously found** returns only new messages when selected.
 - **Search**
 - **Delay** is the period of time between polls. Twitter enforces rate limits, so you should not poll too often. The default interval is 5 seconds.
 - **Ignore tweets previously found** returns only new tweets when selected.
 - **Query** is a Twitter-formatted search expression that specifies the tweets that you want the connection to return. The following table provides examples of what you can enter. More details are in this [Twitter document for search operators](#).

Query	Results
My Product	Obtains tweets that contain both My and Product , but not necessarily My Product .
"My Product"	Obtains tweets that contain an instance of My Product .
My OR Product	Obtains tweets that contain an instance of My or Product or an instance of each one.
My -Product	Obtains tweets that contain an instance of My and do not contain an instance of Product .
#MyProduct	Obtains tweets that contain the MyProduct hashtag.

4. Click **Next** to add the connection to the integration.

Result

The integration now has a start connection and Fuse Online is prompting you to choose the finish connection.

26.4. ADDING A TWITTER CONNECTION THAT SENDS A DIRECT MESSAGE

In the middle of a flow, or to finish a simple integration, you can add a Twitter connection that sends a direct message to a Twitter user. A direct message is a private message that goes to only the specified user.

Prerequisites

- You created a Twitter connection.
- You are creating or editing a flow and Fuse Online is prompting you to add to the integration. Or, for a simple integration, Fuse Online is prompting you to choose a finish connection.

Procedure

1. On the **Add to Integration** page, click the plus sign where you want to add a Twitter connection.
2. Click the Twitter connection that you want to add to the integration. When the integration uses the selected connection to connect to Twitter, Fuse Online uses the credentials defined in that connection.
3. Select the **Send** action.
4. In the **Default Message** field, enter the message that you want the connection to send when a data mapper step does not map the direct message content from a previous step to this Twitter connection. While you must enter a message when you configure this Twitter connection, a message that you map from a previous step has precedence over the message that you specify here.
5. In the **User** field, enter the Twitter handle of the user who you want to send a direct message to. For example, both **Aslan** and **@Aslan** are correct.
6. Click **Next** to add the connection to the integration.

Result

The connection appears in the middle or at the end of an integration visualization.