



JBoss Enterprise Application Platform Continuous Delivery 14

Using the JBoss Server Migration Tool

For Migrating Server Configurations to Red Hat JBoss Enterprise Application Platform
7.2

JBoss Enterprise Application Platform Continuous Delivery 14 Using the JBoss Server Migration Tool

For Migrating Server Configurations to Red Hat JBoss Enterprise Application Platform 7.2

Legal Notice

Copyright © 2018 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This guide describes how to use the JBoss Server Migration Tool to migrate your application server configuration from a previous release of JBoss EAP to JBoss EAP 7.2.

Table of Contents

PREFACE	6
CHAPTER 1. INTRODUCTION	7
1.1. ABOUT RED HAT JBOSS ENTERPRISE APPLICATION PLATFORM 7	7
1.2. ABOUT THE JBOSS SERVER MIGRATION TOOL	7
1.3. ABOUT THE USE OF EAP_HOME IN THIS DOCUMENT	8
JBoss EAP Installation Path	8
CHAPTER 2. BEFORE YOU BEGIN	10
2.1. UPGRADE YOUR CURRENT SOURCE SERVER INSTALLATION	10
2.2. RUN WITH A CLEAN TARGET SERVER INSTALLATION	10
2.3. CUSTOMIZE THE MIGRATION	10
CHAPTER 3. RUNNING THE JBOSS SERVER MIGRATION TOOL	11
3.1. RUN THE JBOSS SERVER MIGRATION TOOL IN INTERACTIVE MODE	11
3.2. RUN THE JBOSS SERVER MIGRATION TOOL IN NON-INTERACTIVE MODE	13
CHAPTER 4. REVIEWING THE RESULTS OF JBOSS SERVER MIGRATION TOOL EXECUTION	14
4.1. REVIEW THE MIGRATED CONFIGURATION FILES	14
4.2. TRACKING MIGRATION TASK EXECUTION	15
4.3. REVIEW THE TASK SUMMARY LOG	16
4.4. REVIEW THE JBOSS SERVER MIGRATION TOOL REPORTS	16
4.4.1. JBoss Server Migration Tool HTML Report	16
4.4.2. JBoss Server Migration Tool XML Report	16
CHAPTER 5. CONFIGURING THE JBOSS SERVER MIGRATION TOOL	18
5.1. CONFIGURING THE JBOSS SERVER MIGRATION TOOL PROPERTIES	18
5.1.1. Configure the JBoss Server Migration Tool Using the Tool Properties	18
5.1.2. Configure the JBoss Server Migration Tool Using User Properties	18
5.1.3. Configure the JBoss Server Migration Tool Using System Properties	18
5.2. CONFIGURING LOGGING FOR JBOSS SERVER MIGRATION TOOL	19
5.3. CONFIGURING MODULES MIGRATION	19
5.3.1. Modules Environment Properties	19
5.3.2. Configuring Modules Properties	20
5.4. CONFIGURING REPORTING FOR JBOSS SERVER MIGRATION TOOL	20
5.4.1. Configuring the Task Summary Log	20
5.4.2. Configuring the HTML Report	21
5.4.3. Configuring the XML Report	21
5.5. CONFIGURING THE MIGRATION OF THE STANDALONE SERVER CONFIGURATION	21
5.6. CONFIGURING THE MIGRATION OF A MANAGED DOMAIN CONFIGURATION	22
5.7. CONFIGURE THE MIGRATION TASKS PERFORMED BY THE JBOSS SERVER MIGRATION TOOL	23
CHAPTER 6. MIGRATING JBOSS EAP 6.4 CONFIGURATIONS TO JBOSS EAP 7.2	24
6.1. MIGRATING A JBOSS EAP 6.4 STANDALONE SERVER TO JBOSS EAP 7.2	24
6.1.1. Remove Unsupported Subsystems	25
6.1.2. Migrate Referenced Modules	26
6.1.3. Migrate Referenced Paths	26
6.1.4. Migrate the Jacorb Subsystem	27
6.1.5. Migrate the Web Subsystem	27
6.1.6. Migrate the Messaging Subsystem	27
6.1.7. Update the Infinispan Subsystem	27
6.1.8. Update the EE Subsystem	28
Configuring Concurrency Utilities in the EE Subsystem	29

Configuring Default Resources in the EE Subsystem	29
6.1.9. Update the EJB 3 Subsystem	30
6.1.10. Update the JGroups Subsystem	30
6.1.11. Update the Remoting Subsystem	31
6.1.12. Update the Transactions Subsystem	31
6.1.13. Update the Undertow Subsystem	31
6.1.14. Update the Messaging-ActiveMQ Subsystem	32
6.1.15. Add the Batch JBeret Subsystem	33
6.1.16. Add the Core Management Subsystem	33
6.1.17. Add the Discovery Subsystem	33
6.1.18. Add the EE Security Subsystem	33
6.1.19. Add the Elytron Subsystem	33
6.1.20. Add the Request Controller Subsystem	33
6.1.21. Add the Security Manager Subsystem	34
6.1.22. Add the Singleton Subsystem	34
6.1.23. Set Up HTTP Upgrade Management	34
6.1.24. Set Up the Private Interface	34
6.1.25. Add Socket Binding Port Expressions	34
6.1.26. Add Socket Binding Multicast Address Expressions	35
6.1.27. Migrate Compatible Security Realms	35
6.1.28. Add the Default SSL Server Identity to the ApplicationRealm	35
6.1.29. Migrate Deployments	35
6.1.29.1. Migrate Persistent Deployments	36
6.1.29.2. Migrate Deployment Scanner Deployments	37
6.1.29.3. Migrate Deployment Overlays	38
6.2. MIGRATING A JBOSS EAP 6.4 MANAGED DOMAIN TO JBOSS EAP 7.2	39
6.2.1. Remove Unsupported Subsystems	40
6.2.2. Migrate Referenced Modules	41
6.2.3. Migrate Referenced Paths	42
6.2.4. Migrate the Jacorb Subsystem	42
6.2.5. Migrate the Web Subsystem	42
6.2.6. Migrate the Messaging Subsystem	42
6.2.7. Update the Infinispan Subsystem	42
6.2.8. Update the EE Subsystem	43
Configuring Concurrency Utilities in the EE Subsystem	44
Configuring Default Resources in the EE Subsystem	44
6.2.9. Update the EJB 3 Subsystem	45
6.2.10. Update the JGroups Subsystem	46
6.2.11. Update the Remoting Subsystem	46
6.2.12. Update the Transactions Subsystem	46
6.2.13. Update the Undertow Subsystem	47
6.2.14. Update the Messaging-ActiveMQ Subsystem	48
6.2.15. Add the Batch JBeret Subsystem	48
6.2.16. Add the Core Management Subsystem	48
6.2.17. Add the Discovery Subsystem	48
6.2.18. Add the EE Security Subsystem	48
6.2.19. Add the Elytron Subsystem	49
6.2.20. Add the Request Controller Subsystem	49
6.2.21. Add the Security Manager Subsystem	49
6.2.22. Add the Singleton Subsystem	49
6.2.23. Update the Unsecure Interface	49
6.2.24. Set Up the Private Interface	49
6.2.25. Add Socket Binding Port Expressions	50


6.2.26. Add Socket Binding Multicast Address Expressions	50
6.2.27. Add the Load Balancer Profile	50
6.2.28. Add Host Excludes	50
6.2.29. Remove the PermGen Attributes from the JVM Configurations	51
6.2.30. Migrate Deployments	51
6.2.30.1. Migrate Persistent Deployments	52
6.2.30.2. Migrate Deployment Overlays	53
6.3. MIGRATING A JBOSS EAP 6.4 HOST CONFIGURATION TO JBOSS EAP 7.2	53
6.3.1. Migrate Referenced Modules	53
6.3.2. Migrate Referenced Paths	54
6.3.3. Add the Core Management Subsystem	54
6.3.4. Add the Elytron Subsystem	54
6.3.5. Add the JMX Subsystem to the Host Configuration	54
6.3.6. Remove the unsecure Interface	54
6.3.7. Set Up HTTP Upgrade Management	54
6.3.8. Remove the PermGen Attributes from the JVM Configurations	55
6.3.9. Migrate Compatible Security Realms	55
6.3.10. Add the Default SSL Server Identity to the ApplicationRealm	55
CHAPTER 7. MIGRATING JBOSS EAP 7.0 CONFIGURATIONS TO JBOSS EAP 7.2	56
7.1. MIGRATING A JBOSS EAP 7.0 STANDALONE SERVER TO JBOSS EAP 7.2	56
7.1.1. Remove Unsupported Subsystems	56
7.1.2. Migrate Referenced Modules	57
7.1.3. Migrate Referenced Paths	58
7.1.4. Update the Infinispan Subsystem	58
7.1.5. Update the JGroups Subsystem	59
7.1.6. Update the Undertow Subsystem	59
7.1.7. Add the Core Management Subsystem	60
7.1.8. Add the Discovery Subsystem	60
7.1.9. Add the EE Security Subsystem	60
7.1.10. Add the Elytron Subsystem	60
7.1.11. Add Socket Binding Multicast Address Expressions	61
7.1.12. Migrate Compatible Security Realms	61
7.1.13. Add the Default SSL Server Identity to the ApplicationRealm	61
7.1.14. Migrate Deployments	61
7.1.14.1. Migrate Persistent Deployments	62
7.1.14.2. Migrate Deployment Scanner Deployments	63
7.1.14.3. Migrate Deployment Overlays	64
7.2. MIGRATING A JBOSS EAP 7.0 MANAGED DOMAIN TO JBOSS EAP 7.2	65
7.2.1. Remove Unsupported Subsystems	66
7.2.2. Migrate Referenced Modules	66
7.2.3. Migrate Referenced Paths	67
7.2.4. Update the Infinispan Subsystem	67
7.2.5. Update the JGroups Subsystem	68
7.2.6. Update the Undertow Subsystem	68
7.2.7. Add the Core Management Subsystem	69
7.2.8. Add the Discovery Subsystem	69
7.2.9. Add the EE Security Subsystem	69
7.2.10. Add the Elytron Subsystem	69
7.2.11. Add Socket Binding Multicast Address Expressions	70
7.2.12. Add the Load Balancer Profile	70
7.2.13. Add Host Excludes	70
7.2.14. Migrate Deployments	70

7.2.14.1. Migrate Persistent Deployments	71
7.2.14.2. Migrate Deployment Overlays	72
7.3. MIGRATING A JBOSS EAP 7.0 HOST CONFIGURATION TO JBOSS EAP 7.2	72
7.3.1. Migrate Referenced Modules	73
7.3.2. Migrate Referenced Paths	73
7.3.3. Add the Core Management Subsystem	74
7.3.4. Add the Elytron Subsystem	74
7.3.5. Migrate Compatible Security Realms	74
7.3.6. Add the Default SSL Server Identity to the ApplicationRealm	74
CHAPTER 8. MIGRATING JBOSS EAP 7.1 CONFIGURATIONS TO JBOSS EAP 7.2	75
8.1. MIGRATING A JBOSS EAP 7.1 STANDALONE SERVER TO JBOSS EAP 7.2	75
8.1.1. Remove Unsupported Subsystems	75
8.1.2. Migrate Referenced Modules	76
8.1.3. Migrate Referenced Paths	76
8.1.4. Update the Infinispan Subsystem	77
8.1.5. Update the JGroups Subsystem	77
8.1.6. Update the Undertow Subsystem	77
8.1.7. Add the Discovery Subsystem	78
8.1.8. Add the EE Security Subsystem	78
8.1.9. Migrate Compatible Security Realms	78
8.1.10. Migrate Deployments	78
8.1.10.1. Migrate Persistent Deployments	79
8.1.10.2. Migrate Deployment Scanner Deployments	80
8.1.10.3. Migrate Deployment Overlays	82
8.2. MIGRATING A JBOSS EAP 7.1 MANAGED DOMAIN TO JBOSS EAP 7.2	82
8.2.1. Remove Unsupported Subsystems	82
8.2.2. Migrate Referenced Modules	83
8.2.3. Migrate Referenced Paths	84
8.2.4. Update the Infinispan Subsystem	84
8.2.5. Update the JGroups Subsystem	84
8.2.6. Update the Undertow Subsystem	84
8.2.7. Add the Discovery Subsystem	85
8.2.8. Add the EE Security Subsystem	85
8.2.9. Add Host Excludes	85
8.2.10. Migrate Deployments	86
8.2.10.1. Migrate Persistent Deployments	86
8.2.10.2. Migrate Deployment Overlays	87
8.3. MIGRATING A JBOSS EAP 7.1 HOST CONFIGURATION TO JBOSS EAP 7.2	88
8.3.1. Migrate Referenced Modules	88
8.3.2. Migrate Referenced Paths	88
8.3.3. Migrate Compatible Security Realms	88
APPENDIX A. REFERENCE MATERIAL	89
A.1. EXAMPLE TASK SUMMARY REPORT	89
A.2. EXAMPLE HTML REPORT	89
A.3. EXAMPLE XML REPORT	91

PREFACE

This document is *not* intended for use with the JBoss Enterprise Application Platform continuous delivery release 14. Content from this guide is referenced from other documents in the JBoss Enterprise Application Platform continuous delivery release 14. This guide is published as reference material only. It is not intended for direct access or reading.

Some features described in this document might not work or might not be available on Red Hat OpenShift Online and Red Hat OpenShift Container Platform. For specific details about the feature differences in the JBoss EAP CD release, see the [Release Limitations](#) section in the *JBoss EAP Continuous Delivery 14 Release Notes*.



IMPORTANT

This continuous delivery release for JBoss EAP is provided as Technology Preview only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

See [Technology Preview Features Support Scope](#) on the Red Hat Customer Portal for information about the support scope for Technology Preview features.

CHAPTER 1. INTRODUCTION

1.1. ABOUT RED HAT JBOSS ENTERPRISE APPLICATION PLATFORM 7

Red Hat JBoss Enterprise Application Platform 7 (JBoss EAP) is a middleware platform built on open standards and compliant with the Java Enterprise Edition 7 specification.

JBoss EAP provides two operating modes for server instances.

Standalone server

The standalone server operating mode represents running JBoss EAP as a single server instance.

Managed domain

The managed domain operating mode allows for the management of multiple JBoss EAP instances from a single control point.

JBoss EAP includes APIs and development frameworks for quickly developing secure and scalable Java EE applications. Many of the APIs and capabilities that are exposed to applications deployed to JBoss EAP servers are organized into subsystems that are configured in the server configuration files. For example, you configure database access information in the **datasources** subsystem so that it can be accessed by applications deployed to JBoss EAP standalone servers or managed domains. The introduction of new features and deprecation of other features can require modification of the server configurations from one release of JBoss EAP to another.

For more information about Red Hat JBoss Enterprise Application Platform, see the [Product Documentation for JBoss EAP](#) located on the Red Hat Customer Portal.

1.2. ABOUT THE JBOSS SERVER MIGRATION TOOL

Migrating an existing application server configuration from one release to another is a complex task. To plan and execute a successful migration not only requires a complete understanding the current server configuration, but also knowledge of features and changes in the target server configuration. With a manual migration, you generally copy and edit several configuration files, and then make the updates needed to keep the same behavior in the target release. If this is not done correctly, the target server does not work as expected. This is often because some functionality is not supported by the target server.

The JBoss Server Migration Tool is a Java application that automatically migrates JBoss EAP server configurations with minimal or no interaction required. It is the preferred method to update your JBoss EAP server configuration to include the new features and settings in JBoss EAP 7 while keeping your existing configuration. The JBoss Server Migration Tool reads your existing source server configuration files and adds configurations for any new subsystems, updates the existing subsystem configurations with new features, and removes any obsolete subsystem configurations.

The JBoss Server Migration Tool supports the migration of standalone servers and managed domains for the following configurations.

Migrating to JBoss EAP 7.2

The JBoss Server Migration Tool ships with JBoss EAP 7.2, so there is no separate download or installation required. This tool supports migration to JBoss EAP 7.2 from the previous major release of the product, which is JBoss EAP 6.4, and from the previous minor release of the product, which is JBoss EAP 7.1.

You run the tool by executing the **jboss-server-migration** script located in the **EAP_HOME/bin** directory. For more information about how to run the tool, see [Running the JBoss Server Migration Tool](#).

It is recommended that you use this version of the JBoss Server Migration Tool to migrate your server configuration to JBoss EAP 7.2 as this version of the tool is [supported](#).



IMPORTANT

Migration to JBoss EAP 7.2 from JBoss EAP 7.0 is provided as Technology Preview only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

See [Technology Preview Features Support Scope](#) on the Red Hat Customer Portal for information about the support scope for Technology Preview features.

Migrating from WildFly to JBoss EAP

If you want to migrate from the WildFly server to JBoss EAP, you must download the latest binary distribution of the JBoss Server Migration Tool from the [wildfly-server-migration](#) GitHub repository. This open source, standalone version of the tool supports migration from several versions of the WildFly server to JBoss EAP. For information about how to install and run this version of the tool, see the JBoss Server Migration Tool [User Guide](#).



IMPORTANT

The binary distribution of the JBoss Server Migration Tool is not supported. If you are migrating from a previous release of JBoss EAP, it is recommended that you use this [supported version of the tool](#) to migrate your server configuration to JBoss EAP 7.2 instead.

1.3. ABOUT THE USE OF EAP_HOME IN THIS DOCUMENT

In this document, the variable **EAP_HOME** is used to denote the path to the target server installation. Replace this variable with the actual path to your server installation.



NOTE

EAP_HOME is a replaceable variable, not an environment variable. **JBOSS_HOME** is the environment variable used in scripts.

JBoss EAP Installation Path

- If you installed JBoss EAP using the ZIP install method, the install directory is the **jboss-eap-7.2** directory where you extracted the ZIP archive.
- If you installed JBoss EAP using the RPM install method, the install directory is **/opt/rh/eap7/root/usr/share/wildfly/**.

- If you used the installer to install JBoss EAP, the default path for ***EAP_HOME*** is **`${user.home}/EAP-7.2.0:`**
 - For Red Hat Enterprise Linux, Solaris, and HP-UX: **`/home/USER_NAME/EAP-7.2.0/`**
 - For Microsoft Windows: **`C:\Users\USER_NAME\EAP-7.2.0\`**
- If you used the JBoss Developer Studio installer to install and configure the JBoss EAP server, the default path for ***EAP_HOME*** is **`${user.home}/jbdevstudio/runtimes/jboss-eap:`**
 - For Red Hat Enterprise Linux: **`/home/USER_NAME/jbdevstudio/runtimes/jboss-eap/`**
 - For Microsoft Windows: **`C:\Users\USER_NAME\jbdevstudio\runtimes\jboss-eap`** or **`C:\Documents and Settings\USER_NAME\jbdevstudio\runtimes\jboss-eap\`**

CHAPTER 2. BEFORE YOU BEGIN

2.1. UPGRADE YOUR CURRENT SOURCE SERVER INSTALLATION

Before you migrate your current source server configuration, be sure to apply the most recent patches and updates that are available for that version of the JBoss EAP software. For information about how to upgrade your server configuration, see the [Patching and Upgrading Guide](#) for JBoss EAP.

2.2. RUN WITH A CLEAN TARGET SERVER INSTALLATION

Because the JBoss Server Migration Tool creates the configuration files based on the configuration of a previous release, it is intended to be run on a clean and unconfigured target server installation. The JBoss Server Migration Tool creates a backup of the target server's configuration files by appending **.beforeMigration** to the file names. It then creates totally new configuration files for the target server using the source server's configuration files, and migrates the configuration to run in target server configuration.



WARNING

When you run the JBoss Server Migration Tool, all changes on the target server made between installation and running the migrate tool are lost.

Also, be aware that if you run the tool against the target server directory more than once, the subsequent runs will overwrite the original target configuration files that were backed up on the first run of the tool. This is because each run of the tool backs up the configuration files by appending **.beforeMigration**, resulting in the loss of any existing backed up configuration files.

2.3. CUSTOMIZE THE MIGRATION


The JBoss Server Migration Tool provides the ability to configure logging, reporting, and the execution of migration tasks. By default, when you run the JBoss Server Migration Tool in non-interactive mode, it migrates the entire server configuration. You can configure the JBoss Server Migration Tool to customize logging and reporting output. You can also configure it to skip any part of the configuration that you do not want to migrate.

For instructions on how to configure properties to control the migration process, see [Configuring the JBoss Server Migration Tool](#).

CHAPTER 3. RUNNING THE JBOSS SERVER MIGRATION TOOL

You can run the JBoss Server Migration Tool in either of the following ways.

- **Interactive mode:** This mode, which is the default, allows you to choose exactly which configurations you want to migrate.
- **Non-interactive mode:** This mode allows you to run the tool without prompts.



IMPORTANT

You must stop both the source and the target JBoss EAP servers before you run the JBoss Server Migration Tool.

3.1. RUN THE JBOSS SERVER MIGRATION TOOL IN INTERACTIVE MODE

By default, the JBoss Server Migration Tool runs interactively. This mode allows you to choose exactly which server configurations you want to migrate.



NOTE

Interactive mode does not allow you to choose which subsystems to migrate. For information on how to configure the tool at the subsystem or task level, see [Configure the Migration Tasks Performed by the JBoss Server Migration Tool](#).

The following are the basic steps that are performed for a minimal migration. If the server from which you are migrating includes custom configurations, for example deployments, or if it is missing default resources, the tool provides additional prompts.

1. To run the tool in interactive mode, navigate to the target server installation directory and run the following command, providing the **source** argument as the path to the source server installation.

```
$ EAP_HOME/bin/jboss-server-migration.sh --source EAP_PREVIOUS_HOME
```

2. You are prompted to determine if you want to migrate the source server's standalone configurations, which are located in the **EAP_PREVIOUS_HOME/standalone/configuration/** directory, to the target server's standalone configurations, which are located in the **EAP_HOME/standalone/configuration/** directory.

```
Migrate the source's standalone server?
yes/no? yes
```

If you respond with **no**, standalone server migration is skipped and no standalone server configuration files are migrated.

If you respond with **yes**, you see the following prompt.

```
Migrate all configurations?
yes/no? yes
```

Respond with **yes** to migrate all of the source server's standalone server configuration files.

Respond with **no** to receive a prompt for each individual **standalone*.xml** configuration file.

- Next, you are prompted to determine if you want to migrate the source server's managed domain configurations, which are located in the **EAP_PREVIOUS_HOME/domain/configuration/** directory, to the target server's managed domain configurations, which are located in the **EAP_HOME/domain/configuration/** directory.

```
Migrate the source's managed domain?
yes/no? yes
```

If you respond with **no**, managed domain migration is skipped and no managed domain configuration files are migrated.

If you respond with **yes**, the tool begins migrating the managed domain content of the source server. A ciphered repository is used to store data, such as deployments and deployment overlays, that are referenced by the source server's managed domain and host configurations. Because the source and target servers use a similar content repository, the tool simply copies the data from the source server to the target server and prints the results to the console and the server log.

```
INFO [ServerMigrationTask#397] Migrating domain content found:
[22/caa450a9ba3b84eaf5a15b6da418b92ce6c98e/content,
23/b62a37ba8a4830622bfcdb960280577cc6796e/content]
INFO [ServerMigrationTask#398] Resource with path
/___EAP_HOME___/domain/data/content/22/caa450a9ba3b84eaf5a15b6da418b92
ce6c98e/content migrated.
INFO [ServerMigrationTask#399] Resource with path
/___EAP_HOME___/domain/data/content/23/b62a37ba8a4830622bfcdb960280577
cc6796e/content migrated.
```

- Next, the migration tool scans the source server for managed domain configuration files, prints the results to the console, and provides the following prompt.

```
Migrate all configurations?
yes/no? yes
```

Respond with **yes** to migrate all of the source server's managed domain configuration files.

Respond with **no** to receive a prompt for each individual managed domain configuration file.

- Next, the migration tool scans the source server for host configurations files, prints the results to the console, and provides the following prompt.

```
INFO [ServerMigrationTask#457] Retrieving source's host
configurations...
INFO [ServerMigrationTask#457] /jboss-eap-
6.4/domain/configuration/host-master.xml
INFO [ServerMigrationTask#457] /jboss-eap-
```



```
6.4/domain/configuration/host-slave.xml
INFO [ServerMigrationTask#457] /jboss-eap-
6.4/domain/configuration/host.xml
```

```
Migrate all configurations?
yes/no? yes
```

Respond with **yes** to migrate all of the source server's host configuration files.

Respond with **no** to receive a prompt for each individual host configuration file.

6. Upon completion, you should see the following message in the server console.

```
Migration Result: SUCCESS
```

3.2. RUN THE JBOSS SERVER MIGRATION TOOL IN NON-INTERACTIVE MODE

You can run the JBoss Server Migration Tool in non-interactive mode. This mode allows it to run without prompts.



NOTE

The JBoss Server Migration Tool automatically migrates all subsystem configurations for all server configuration files. For information on how to configure the tool at the subsystem or task level, see [Configure the Migration Tasks Performed by the JBoss Server Migration Tool](#).

1. To run the tool in non-interactive mode, navigate to the target server installation directory and run the following command, providing the **source** argument as the path to the source server installation and setting the **--interactive** or **-i** argument to **false**.

```
$ EAP_HOME/bin/jboss-server-migration.sh --source EAP_PREVIOUS_HOME
--interactive false
```

2. By default, the tool automatically migrates all of the source server's standalone and managed domain configuration files. However, you can configure the tool's properties to skip migration of specific configurations. Upon completion, you should see the following message in the server console.

```
Migration Result: SUCCESS
```

CHAPTER 4. REVIEWING THE RESULTS OF JBOSS SERVER MIGRATION TOOL EXECUTION

4.1. REVIEW THE MIGRATED CONFIGURATION FILES

When the migration is complete, review the migrated server configuration files in the ***EAP_HOME/standalone/configuration/*** and ***EAP_HOME/domain/configuration/*** directories.

- Note that any original ***EAP_HOME*** target server configuration file names selected for migration are backed up and are now appended with ***.beforeMigration***.
- The ***EAP_HOME*** target server configuration file names not appended with ***.beforeMigration*** are now updated with the content migrated from the ***EAP_PREVIOUS_HOME*** source server configuration.
- The original configuration files located in the ***EAP_PREVIOUS_HOME*** source server configuration directories remain untouched.
- The ***logging.properties*** and ***standalone-load-balancer.xml*** files in the target configuration directories remain untouched.

If you choose to migrate all of the available configurations, you should see the following configuration files in the target server directories.

Example: List of Configuration Files on the Target Server

```
$ ls EAP_HOME/standalone/configuration/
application-roles.properties
application-roles.properties.beforeMigration
application-users.properties
application-users.properties.beforeMigration
logging.properties
mgmt-groups.properties
mgmt-groups.properties.beforeMigration
mgmt-users.properties
mgmt-users.properties.beforeMigration
standalone-full-ha.xml
standalone-full-ha.xml.beforeMigration
standalone-full.xml
standalone-full.xml.beforeMigration
standalone-ha.xml
standalone-ha.xml.beforeMigration
standalone-load-balancer.xml
standalone-osgi.xml
standalone-osgi.xml.beforeMigration
standalone.xml
standalone.xml.beforeMigration

$ ls EAP_HOME/domain/configuration/
application-roles.properties
application-roles.properties.beforeMigration
application-users.properties
application-users.properties.beforeMigration
domain.xml
```

```

domain.xml.beforeMigration
host-master.xml
host-master.xml.beforeMigration
host-slave.xml
host-slave.xml.beforeMigration
host.xml
host.xml.beforeMigration
logging.properties
mgmt-groups.properties
mgmt-groups.properties.beforeMigration
mgmt-users.properties
mgmt-users.properties.beforeMigration

```

4.2. TRACKING MIGRATION TASK EXECUTION

The JBoss Server Migration Tool begins each target server migration by executing a root task, which can then execute subtasks. Those subtasks can then also execute additional tasks and subtasks. As it executes, the tool tracks each migration task, along with any subtasks, and saves the results in a tree structure that is later used to build the reports.

Each migration task is given a name, which consists of a task name concatenated with optional attributes using the following syntax.

```

TASK_NAME(ATTRIBUTE_1_NAME=ATTRIBUTE_1_VALUE, ATTRIBUTE_2_NAME=ATTRIBUTE_2_
VALUE, ...)

```

The name defines the task subject or type, and the attributes are used to distinguish between subtasks and sibling tasks. For example, all of the following are names to distinguish **ejb3** subsystem update tasks.

```

subsystem.ejb3.update
subsystem.ejb3.update.activate-ejb3-remoting-http-
connector(resource=/subsystem=ejb3)
subsystem.ejb3.update.setup-default-sfsb-passivation-disabled-
cache(resource=/subsystem=ejb3)
subsystem.ejb3.update.add-infinispan-passivation-store-and-distributable-
cache(resource=/subsystem=ejb3)

```

Since a migration task can be executed multiple times under different parent tasks, each task is stored in the tree using each of its parent task names, starting with root, separated by a > character. The task execution tree is used to build the migration reports.

A task execution can result in one of the following statuses.

Status	Description
Success	The task executed successfully.
Skipped	The task skipped the execution, either because it was not needed or because it was configured to be skipped.
Fail	The task execution failed.

4.3. REVIEW THE TASK SUMMARY LOG

The Task Summary is generated and printed to the migration console and to the JBoss Server Migration Tool log file. It provides a high-level overview of the migration results, by component and subtask, as a hierarchical list.

An [example Task Summary report](#) is located in the appendix of this guide.

See [Configuring the Task Summary](#) for options to configure the resulting output.

4.4. REVIEW THE JBOSS SERVER MIGRATION TOOL REPORTS

The JBoss Server Migration Tool generates nicely formatted HTML and XML reports in the ***EAP_HOME/migration/reports/*** directory. These reports provide a detailed analysis of the migration process and how the target server was configured during the migration. The default names for these reports are ***migration-report.html*** and ***migration-report.xml***. Each of these names is configurable. For information about how to configure the reports, see [Configuring Reporting for JBoss Server Migration Tool](#).

This section provides a brief overview of the content of these reports.

- The [JBoss Server Migration Report](#) HTML file.
- The [Server Migration Report](#) XML file.

4.4.1. JBoss Server Migration Tool HTML Report

The HTML report consists of three sections.

Summary

This section provides the execution start time, information about the source and target servers, and the result of the migration.

Environment

This section lists the environment properties that were used for the migration.

Tasks

This section, which includes collapsible subsections, provides statistics and a map of the executed migration tasks. Each task is listed by its name and is color-coded according to the status of the completion of the task:

- Green if it was successful.
- Red if it failed.
- Gray if it was skipped.

An [example HTML report](#) is located in the appendix of this guide.

See [Configuring the HTML Report](#) for options to configure the resulting output.

4.4.2. JBoss Server Migration Tool XML Report

The XML Report is a low level report that provides all of the migration data gathered by the tool. It is formatted in a way that it can be imported into and manipulated by third-party spreadsheet or other data manipulation tools.

An [example XML report](#) is located in the appendix of this guide.

See [Configuring the XML Report](#) for options to configure the resulting output.

CHAPTER 5. CONFIGURING THE JBOSS SERVER MIGRATION TOOL

5.1. CONFIGURING THE JBOSS SERVER MIGRATION TOOL PROPERTIES

You use properties to configure the JBoss Server Migration Tool logging and reporting output and to determine which components and configurations you want to migrate. You can configure these properties using a combination of the following methods.

- You can configure the [properties file defined within the tool](#).
- You can pass [user properties on the command line](#).
- You can configure [system environment variables](#).

5.1.1. Configure the JBoss Server Migration Tool Using the Tool Properties

You can configure the JBoss Server Migration Tool using the **environment.properties** file located in the **EAP_HOME/migration/configuration/** directory. This standard Java properties file provides the default values for all of the valid properties that can be configured when migrating to the target server. To change a default value, remove the **#** comment character that precedes the property and set it to the value you need.

5.1.2. Configure the JBoss Server Migration Tool Using User Properties

If you prefer, you can create a standard Java properties file that defines JBoss Server Migration Tool configuration properties and pass its path on the command line using the **--environment** or **-e** argument. This path can be an absolute path or a path relative to the current directory.

```
$ EAP_HOME/bin/jboss-server-migration.sh --source EAP_PREVIOUS_HOME --
environment path/to/my-server-migration.properties
```

Properties defined in files passed on the command line using the **--environment** or **-e** argument override the ones defined in the **EAP_HOME/migration/configuration/environment.properties** file.

5.1.3. Configure the JBoss Server Migration Tool Using System Properties

You can configure the JBoss Server Migration Tool by passing system properties on the command line using the following syntax.

```
$ EAP_HOME/bin/jboss-server-migration.sh --source EAP_PREVIOUS_HOME -
Djboss.server.migration.PROPERTY_NAME=PROPERTY_VALUE
```

The system property name should be specified as **jboss.server.migration.** concatenated with the environment property name. The following example demonstrates how to specify the name of the XML report as **migration-report.xml** when starting the JBoss Server Migration Tool.

```
$ EAP_HOME/bin/jboss-server-migration.sh --source EAP_PREVIOUS_HOME -
Djboss.server.migration.report.xml.fileName=migration-report.xml
```

Environment properties specified on the command line override both user configuration properties and tool configuration properties.



WARNING

Configuring the JBoss Server Migration Tool by passing system properties on the command line does not currently work for the following properties.

- `report.html.fileName`
- `report.html.maxTaskPathSizeToDisplaySubtasks`
- `report.html.templateFileName`
- `report.summary.maxTaskPathSizeToDisplaySubtasks`
- `report.xml.fileName`

This is a known issue that should be addressed in the next version of JBoss EAP. For more information about this issue, see [JBEAP-12901](#).

5.2. CONFIGURING LOGGING FOR JBOSS SERVER MIGRATION TOOL

The JBoss Server Migration Tool uses the JBoss Logging framework to log the progress of the migration. Results are written to the console and also to a file named **migration.log**, which is located in the **EAP_HOME/migration/logs/** directory. This log file is created if it does not already exist, and its content is overwritten on each subsequent execution of the tool.

The logging configuration is provided by the **EAP_HOME/migration/logging.properties** file. You can modify this configuration file or you can specify an alternative logging configuration file by using the **logging.configuration** system property on the command line.

```
$ EAP_HOME/bin/jboss-server-migration.sh --source EAP_PREVIOUS_HOME -
Dlogging.configuration=file:EAP_PREVIOUS_HOME/migration/configuration/my-
alternate-logging.properties
```

5.3. CONFIGURING MODULES MIGRATION

The JBoss Server Migration Tool can migrate any module installed in the source server as long as that module is not already installed on the target server. Module migration can be done explicitly by request, or implicitly because another module or migrated server configuration depends on it.

5.3.1. Modules Environment Properties

You can control whether a module should be migrated or not by using the **modules.includes** and **modules.excludes** environment properties. The syntax for a module ID is **name:slot**. The **:slot** is optional and if it is not specified defaults to **main**.

- A module whose ID is referenced by the **modules.excludes** environment property is never migrated.
- A module whose ID is referenced by the **modules.includes** environment property is always migrated, unless it is referenced by the **modules.excludes** environment property.

5.3.2. Configuring Modules Properties

The environment properties used to migrate modules can be configured in any of the following ways:

- You can configure the properties in the tool's **EAP_HOME/migration/configuration/environment.properties** file.

```
modules.includes=com.example.moduleA,com.example.moduleB
modules.excludes=com.example.moduleC
```

- You can include the above properties in your own custom properties file, and then pass the properties file name on the command line using the **--environment** argument.

```
$ EAP_HOME/bin/jboss-server-migration.sh --source EAP_PREVIOUS_HOME
--environment PATH_TO_MY_PROPERTIES_FILE
```

- You can pass the information on the command line using a system property. The environment property names must be prefixed with **jboss.server.migration.**, for example:

```
$ EAP_HOME/bin/jboss-server-migration.sh --source EAP_PREVIOUS_HOME
-Djboss.server.migration.modules.includes="com.example.moduleA" -
-Djboss.server.migration.modules.excludes="com.example.moduleC,com.ex
ample.moduleD"
```



WARNING

The JBoss Server Migration Tool does not verify that the source module is compatible with the target server. An incompatible migrated module can cause the target server to malfunction or not work at all. A module can be incompatible due to a dependency on a module that is installed on both the source and target servers, but includes or exposes different resources on each one.

5.4. CONFIGURING REPORTING FOR JBOSS SERVER MIGRATION TOOL

5.4.1. Configuring the Task Summary Log

You can customize the generation of the Task Summary using the following environment property.

Property Name	Type	Property Description and Default Value
report.summary.maxTaskPathSizeToDisplaySubtasks	Integer	<p>Include migrated subtasks in the summary where the level is less than or equal to the specified integer.</p> <p>Defaults to 5.</p>

5.4.2. Configuring the HTML Report

You can customize the HTML report using the following environment properties.

Property Name	Type	Property Description and Default Value
report.html.fileName	String	<p>The name of the HTML report file. If not set, the report is not generated.</p> <p>Defaults to <code>EAP_HOME/migration/reports/migration-report.html</code>.</p>
report.html.maxTaskPathSizeToDisplaySubtasks	Integer	<p>Include migrated subtasks in the summary where the level is less than or equal to the specified integer.</p> <p>Defaults to 4.</p>
report.html.templateFileName	String	<p>The HTML report template file name.</p> <p>Defaults to <code>migration-report-template.html</code>.</p>

5.4.3. Configuring the XML Report

You can customize the XML report using the following environment properties.

Property Name	Type	Property Description and Default Value
report.xml.fileName	String	<p>The name of the XML report file. If not set, the report is not generated.</p> <p>Defaults to <code>EAP_HOME/migration/reports/migration-report.xml</code>.</p>

5.5. CONFIGURING THE MIGRATION OF THE STANDALONE SERVER CONFIGURATION

You can configure the JBoss Server Migration Tool to skip the migration of a standalone server entirely, to provide the configuration file names that you want to migrate, or to provide alternate paths for the source or target server's base and configuration directories.

You can customize the migration of the standalone server configuration using the following environment properties.

Table 5.1. Standalone Server Migration Environment Properties

Property Name	Property Description
<code>standalone.skip</code>	If set to true , the tool skips the entire standalone server migration.
<code>server.source.standalone.serverDir</code>	Defines an alternative path for the source server's standalone directory, which defaults to the source server's <code>EAP_HOME/standalone/</code> directory.
<code>server.source.standalone.configDir</code>	Defines an alternative path for the source server's standalone configuration directory, which defaults to the source server's <code>EAP_HOME/standalone/configuration/</code> directory.
<code>server.source.standalone.configFiles</code>	A comma-delimited list of the source server's standalone configurations to be migrated.
<code>server.target.standalone.serverDir</code>	Defines an alternative path for the target server's standalone directory, which defaults to the target server's <code>EAP_HOME/standalone/</code> directory.
<code>server.target.standalone.configDir</code>	Defines an alternative path for the target server's standalone configuration directory, which defaults to the target server's <code>EAP_HOME/standalone/configuration/</code> directory.

For information about how to configure the JBoss Server Migration Tool using these properties, see [Configuring the JBoss Server Migration Tool](#).

5.6. CONFIGURING THE MIGRATION OF A MANAGED DOMAIN CONFIGURATION

You can configure the JBoss Server Migration Tool to skip the migration of a managed domain entirely, to provide the configuration file names that you want to migrate, or to provide alternate paths for the source or target server's base and configuration directories.

You can customize the migration of the managed domain configuration using the following environment properties.

Table 5.2. Managed Domain Migration Environment Properties

Property Name	Property Description
domain.skip	If set to true , the tool skips the entire managed domain migration.
server.source.domain.domainDir	Defines an alternative path for the source server's managed domain directory, which defaults to the source server's EAP_HOME/domain/ directory.
server.source.domain.configDir	Defines an alternative path for the source server's managed domain configuration directory, which defaults to the source server's EAP_HOME/domain/configuration/ directory.
server.source.domain.domainConfigFiles	A comma-delimited list of the source server's managed domain configuration files that are to be migrated.
server.source.domain.hostConfigFiles	A comma-delimited list of the source server's host configuration files that are to be migrated.
server.target.domain.domainDir	Defines an alternative path for the target server's managed domain directory, which defaults to the target server's EAP_HOME/domain/ directory.
server.target.domain.configDir	Defines an alternative path for the target server's managed domain configuration directory, which defaults to the target server's EAP_HOME/domain/configuration/ directory.

For information about how to configure the JBoss Server Migration Tool using these properties, see [Configuring the JBoss Server Migration Tool](#).

5.7. CONFIGURE THE MIGRATION TASKS PERFORMED BY THE JBOSS SERVER MIGRATION TOOL

By default, the JBoss Server Migration Tool automatically migrates all components and subsystems for each standalone server, managed domain, and host configuration you choose to migrate. You can customize the execution of specific tasks and subtasks performed by the tool using environment properties. For example, you can configure the tool to skip the removal of unsupported subsystems or to skip the migration of deployments. The tasks performed by the tool are dependent upon the type of server configuration and the version of the source server from which you are migrating.

Information about how to configure environment properties to customize the tasks performed by the JBoss Server Migration Tool can be found in the following sections.

CHAPTER 6. MIGRATING JBOSS EAP 6.4 CONFIGURATIONS TO JBOSS EAP 7.2

6.1. MIGRATING A JBOSS EAP 6.4 STANDALONE SERVER TO JBOSS EAP 7.2

By default, the JBoss Server Migration Tool performs the following tasks when migrating a standalone server configuration from JBoss EAP 6.4 to JBoss EAP 7.2.

- Remove any unsupported subsystems.
- Migrate any referenced modules.
- Migrate any referenced paths.
- Migrate the **jacorb** subsystem.
- Migrate the **web** subsystem.
- Migrate the **messaging** subsystem.
- Update the **infinispan** subsystem.
- Update the **ee** subsystem.
- Update the **ejb3** subsystem.
- Update the **jgroups** subsystem.
- Update the **remoting** subsystem.
- Update the **transactions** subsystem.
- Update the **undertow** subsystem.
- Update the **messaging-activemq** subsystem.
- Add the **batch-jberet** subsystem.
- Add the **core-management** subsystem.
- Add the **discovery** Subsystem.
- Add the **ee-security** Subsystem.
- Add the **elytron** subsystem.
- Add the **request-controller** subsystem.
- Add the **security-manager** subsystem.
- Add the **singleton** subsystem.
- Set up HTTP Upgrade management.

- [Set up the private interface.](#)
- [Add socket binding port expressions.](#)
- [Migrate compatible security realms.](#)
- [Add the default SSL server identity to the `ApplicationRealm`.](#)
- [Migrate deployments.](#)

6.1.1. Remove Unsupported Subsystems

The following JBoss EAP 6.4 subsystems are not supported by JBoss EAP 7:

Subsystem Name	Configuration Namespace	Extension Module
cmp	urn:jboss:domain:cmp:*	org.jboss.as.cmp
configadmin	urn:jboss:domain:configadmin:*	org.jboss.as.configadmin
jaxr	urn:jboss:domain:jaxr:*	org.jboss.as.jaxr
osgi	urn:jboss:domain:osgi:*	org.jboss.as.osgi
threads	urn:jboss:domain:threads:*	org.jboss.as.threads

The JBoss Server Migration Tool removes all unsupported subsystem configurations and extensions from migrated server configurations. The tool logs each subsystem and extension to its log file and to the console as it is removed.

To skip removal of the unsupported subsystems, set the **`subsystems.remove-unsupported-subsystems.skip`** environment property to **`true`**.

You can override the default behavior of the JBoss Server Migration Tool and specify which subsystems and extensions should be included or excluded during the migration using the following environment properties.

Property Name	Property Description
<code>extensions.excludes</code>	A list of module names of extensions that should never be migrated, for example, <code>com.example.extension1,com.example.extension3</code> .
<code>extensions.includes</code>	A list of module names of extensions that should always be migrated, for example, <code>com.example.extension2,com.example.extension4</code> .

Property Name	Property Description
subsystems.excludes	A list of subsystem namespaces, stripped of the version, that should never be migrated, for example, urn:jboss:domain:logging, urn:jboss:domain:ejb3.
subsystems.includes	A list of subsystem namespaces, stripped of the version, that should always be migrated, for example, urn:jboss:domain:security, urn:jboss:domain:ee.

6.1.2. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a standalone server configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.
- A module referenced by the **datasource** subsystem configuration is migrated as a datasource driver module.
- A module referenced by the **ee** subsystem configuration is migrated as a global module.
- A module referenced by the **naming** subsystem configuration is migrated as an object factory module.
- A module referenced by the **messaging** subsystem configuration is migrated as a JMS bridge module.
- A module referenced by a vault configuration is migrated to the new configuration.
- Any extension that is not installed on the target configuration is migrated to the target server configuration.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

6.1.3. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **paths.migrate-paths-requested-by-configuration.vault.skip** environment property to **true**.

6.1.4. Migrate the Jacorb Subsystem

The **jacorb** subsystem is deprecated in JBoss EAP 7 and is replaced by the **iiop-openjdk** subsystem. By default, the JBoss Server Migration Tool automatically migrates the **jacorb** subsystem configuration to its replacement **iiop-openjdk** subsystem configuration and logs the results to its log file and to the console.

To skip the automatic migration to the **iiop-openjdk** subsystem configuration, set the **subsystem.jacorb.migrate.skip** environment property value to **true**.

6.1.5. Migrate the Web Subsystem

The **web** subsystem is deprecated in JBoss EAP 7 and is replaced by the **undertow** subsystem. By default, the JBoss Server Migration Tool automatically migrates the **web** subsystem configuration to its replacement **undertow** subsystem configuration and logs the results to its log file and to the console.

To skip automatic migration of the **web** subsystem, set the **subsystem.web.migrate.skip** environment property value to **true**.

6.1.6. Migrate the Messaging Subsystem

The **messaging** subsystem is deprecated in JBoss EAP 7 and is replaced by the **messaging-activemq** subsystem. The JBoss Server Migration Tool automatically migrates the **messaging** subsystem configuration to its replacement **messaging-activemq** subsystem configuration and logs the results to its log file and to the console.

To skip automatic migration of the **messaging** subsystem, set the **subsystem.messaging.migrate.skip** environment property value to **true**.

6.1.7. Update the Infinispan Subsystem

The JBoss Server Migration Tool updates the **infinispan** subsystem configuration to better align with the default JBoss EAP 7.2 configurations.

- It adds the EJB cache container, which is present in the JBoss EAP 7.2 default configuration, to configurations where it is not already included.
- It adds the server cache container, which is present in the JBoss EAP 7.2 default configuration.
- It updates the module name in the Hibernate cache container configuration.
- It adds the concurrent cache to the web cache container, which is present in the JBoss EAP 7.2 default configuration.

The JBoss Server Migration Tool automatically updates the **infinispan** subsystem configuration and logs the results to its log file and to the console.

You can customize the update of the **infinispan** system by setting the following environment properties.

Property Name	Property Description
subsystem.infinispan.update.skip	If set to true , skip the update of the infinispan subsystem.
subsystem.infinispan.update.add-infinispan-ejb-cache.skip	If set to true , do not add the EJB cache container.
subsystem.infinispan.update.add-infinispan-server-cache.skip	If set to true , do not add the server cache container.
subsystem.infinispan.update.fix-hibernate-cache-module-name.skip	If set to true , do not update the module name in the Hibernate cache container configuration.
subsystem.infinispan.update-infinispan-web-cache	If set to true , do not add the concurrent cache to the web cache container configuration.

6.1.8. Update the EE Subsystem

The JBoss Server Migration Tool updates the **ee** subsystem to configure the Java EE features supported in JBoss EAP 7.2.

- It configures instances of Java EE concurrency utilities, such as container-managed executors, that are present in the JBoss EAP 7.2 default configuration and logs the results to its log file and to the console.
- It defines the Java EE default resources, such as the default datasource, that are present in default JBoss EAP 6.4 configuration. If the resources are not found, the tool lists all available resources in the configuration, and then provides a prompt to select a resource from the list or to provide the JNDI address of the resource that should be set as the default.



NOTE

JNDI names that are specified are assumed to be valid. JNDI names are not validated by the tool.

The JBoss Server Migration Tool automatically updates the **ee** subsystem configuration and logs the results to its log file and to the console.

You can customize the update of the **ee** system by setting the following environment properties.

Property Name	Property Description
subsystem.ee.update.skip	If set to true , skip the update of the ee subsystem.
subsystem.ee.update.setup-ee-concurrency-utilities.skip	If set to true , do not add the default instances of concurrency utilities.
subsystem.ee.update.setup-javaee7-default-bindings.skip	If set to true , do not set up Java EE default resources.

Property Name	Property Description
subsystem.ee.update.setup-javaee7-default-bindings.defaultDataSourceName	Specifies the name of the default datasource to look for in the source configuration.
subsystem.ee.update.setup-javaee7-default-bindings.defaultDataSourceJndiName	Specifies the JNDI name for the default datasource.
subsystem.ee.update.setup-javaee7-default-bindings.defaultJmsConnectionFactoryName	Specifies the name of the default JMS connection factory.
subsystem.ee.update.setup-javaee7-default-bindings.defaultJmsConnectionFactoryJndiName	Specifies the JNDI name for the default JMS connection factory.

Configuring Concurrency Utilities in the EE Subsystem

If you choose to configure the Java EE concurrency utilities, then the tool automatically configures the instances that are present in the default JBoss EAP 7.2 configurations and logs the results to its log file and to the console.

```
INFO [ServerMigrationTask#49] Default ContextService added to EE
subsystem configuration.
INFO [ServerMigrationTask#49] Default ManagedThreadFactory added to EE
subsystem configuration.
INFO [ServerMigrationTask#49] Default ManagedExecutorService added to EE
subsystem configuration.
INFO [ServerMigrationTask#49] Default ManagedScheduledExecutorService
added to EE subsystem configuration.
```

Configuring Default Resources in the EE Subsystem

When defining the Java EE default resources the tool automatically selects those that are present in the default JBoss EAP 7.2 configuration.

```
INFO [ServerMigrationTask#50] Java EE Default Datasource configured with
JNDI name java:jboss/datasources/ExampleDS.
```

If no default resource is found, the tool lists all resources that are available in the configuration, and then provides a prompt to select the default resource or to provide the JNDI address of the resource that should be set as the default.

The following is an example of the interaction that occurs when migrating a configuration file with an **ExampleDS** datasource.

```
INFO [ServerMigrationTask#22] Default datasource not found.
0. ExampleDS
1. Unconfigured data source, I want to enter the JNDI name...
Please select Java EE's Default Datasource: (0): 0
INFO [ServerMigrationTask#22] Java EE Default Datasource configured with
JNDI name java:jboss/datasources/ExampleDS.
```

Save this Java EE Default Datasource JNDI name and use it when migrating other config files?
yes/no? y



NOTE

If you run the JBoss Server Migration Tool in non-interactive mode and the expected JBoss EAP 6.4 default resources, such as the default JMS connection factory, are not available, the tool does not configure those resources.

6.1.9. Update the EJB 3 Subsystem

The JBoss Server Migration Tool makes the following updates to the **ejb3** subsystem to better align with the default JBoss EAP 7.2 configurations.

- It updates the remote service configuration to reference the HTTP connector.
- It configures the **default-sfsb-passivation-disabled-cache** attribute to use the **default-sfsb-cache**.
- It replaces the legacy passivation store and cache configurations with the JBoss EAP 7.2 default values.

The JBoss Server Migration Tool automatically updates the **ejb3** subsystem configuration and logs the results to its log file and to the console.

Upon successful update of the **ejb3** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

INFO Subsystem ejb3 updated.

You can customize the update of the **ejb3** system by setting the following environment properties.

Property Name	Property Description
subsystem.ejb3.update.skip	If set to true , skip the update of the ejb3 subsystem.
subsystem.ejb3.update.add-infinispan-passivation-store-and-distributable-cache.skip	If set to true , do not replace the passivation-store and cache configurations.
subsystem.ejb3.update.setup-default-sfsb-passivation-disabled-cache.skip	If set to true , do not update the default-sfsb-passivation-disabled-cache configuration.
subsystem.ejb3.update.activate-ejb3-remoting-http-connector.skip	If set to true , do not update the EJB remoting configuration.

6.1.10. Update the JGroups Subsystem

The JBoss Server Migration Tool updates the **jgroups** subsystem to align with the JBoss EAP 7.2 configurations.

- It replaces the **MERGE2** protocol with **MERGE3**.
- It replaces the **FD** protocol with **FD_ALL**.
- It replaces the **pbcast.NAKACK** protocol with **pbcast.NAKACK2**.
- It replaces the **UNICAST2** protocol with **UNICAST3**.
- It removes the **RSVP** protocol.
- It replaces the **FRAG2** protocol with the **FRAG3** protocol.

Upon successful migration of the **jgroups** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem jgroups updated.
```

To skip the automatic migration of the **jgroups** subsystem, set the **subsystem.jgroups.update.skip** environment property to **true**.

6.1.11. Update the Remoting Subsystem

JBoss EAP 7 includes an HTTP connector that replaces all legacy remoting protocols and ports using a single port. The JBoss Server Migration Tool automatically updates the **remoting** subsystem to use the HTTP connector.

To skip the automatic update of the **remoting** subsystem configuration, set the **subsystem.remoting.update.skip** environment property to **true**.

6.1.12. Update the Transactions Subsystem

The JBoss Server Migration Tool updates the **transactions** subsystem with the configuration changes required by the JBoss EAP 7.2 server.

The JBoss Server Migration Tool removes the **path** and **relative-to** attributes from the **transactions** subsystem and replaces them with the equivalent **object-store-path** and **object-store-relative-to** attributes.

To skip the automatic update of the **transactions** subsystem configuration, set the **subsystem.transactions.update-xml-object-store-paths.skip** environment property to **true**.

6.1.13. Update the Undertow Subsystem

In addition to migrating the **web** subsystem for JBoss EAP 7.2, the JBoss Server Migration Tool updates its replacement **undertow** subsystem to add the features it supports.

- It sets the default HTTP listener redirect socket.
- It adds support for Java EE WebSockets.
- It sets the default HTTPS listener.
- It adds support for HTTP2.

- It removes the **Server** response header.
- It removes the **X-Powered-By** response header.
- It sets the default HTTP **Invoker**.

The JBoss Server Migration Tool automatically updates the **undertow** subsystem configuration and logs the results to its log file and to the console.

Upon successful migration of the **undertow** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem undertow updated.
```

You can customize the update of the **undertow** system by setting the following environment properties.

Property Name	Property Description
subsystem.undertow.update.skip	If set to true , skip the update of the undertow subsystem.
subsystem.undertow.update.set-default-http-listener-redirect-socket.skip	If set to true , do not set the default HTTP listener redirect socket.
subsystem.undertow.update.add-undertow-websockets.skip	If set to true , do not add support for WebSockets.
subsystem.undertow.update.add-undertow-https-listener.skip	If set to true , do not set the default HTTPS listener.
subsystem.undertow.update.enable-http2.skip	If set to true , do not add support for HTTP2.
subsystem.undertow.update.add-response-header.server-header.skip	If set to true , do not set the default Server response header.
subsystem.undertow.update.add-response-header.x-powered-by-header.skip	If set to true , do not set the default X-Powered-By response header.
subsystem.undertow.update.add-http-invoker.skip	If set to true , do not set the default HTTP Invoker .

6.1.14. Update the Messaging-ActiveMQ Subsystem

In addition to migrating the **messaging** subsystem for JBoss EAP 7.2, the JBoss Server Migration Tool updates its replacement **messaging-activemq** subsystem to add the new features it supports.

- It adds the default HTTP connector and acceptor to enable the HTTP-based remote messaging clients.

The JBoss Server Migration Tool automatically updates the **messaging-activemq** subsystem configuration and logs the results to its log file and to the console.

To skip the automatic update of the **messaging-activemq** subsystem, set the **subsystem.messaging-activemq.update.skip** environment property to **true**.

6.1.15. Add the Batch JBeret Subsystem

The JBoss EAP 7.2 **batch-jberet** subsystem provides support for [JSR 352: Batch Applications for the Java Platform](#). The JBoss Server Migration Tool automatically adds the default **batch-jberet** subsystem configuration to the migrated configuration file.

To skip the addition of the **batch-jberet** subsystem configuration, set the **subsystem.batch-jberet.add.skip** environment property to **true**.

6.1.16. Add the Core Management Subsystem

The JBoss EAP 7.2 **core-management** subsystem provides management-related resources, which were previously configured in the management core service. Examples of these resources include the ability to view a history of configuration changes made to the server and the ability to monitor for server lifecycle events. The JBoss Server Migration Tool automatically adds the default **core-management** subsystem configuration to the migrated configuration file.

To skip the addition of the **core-management** subsystem configuration, set the **subsystem.core-management.add.skip** environment property to **true**.

6.1.17. Add the Discovery Subsystem

The JBoss Server Migration Tool automatically adds the default **discovery** subsystem configuration to the migrated configuration file.

To skip the addition of the **discovery** subsystem configuration, set the **subsystem.discovery.add.skip** environment property to **true**.

6.1.18. Add the EE Security Subsystem

The JBoss EAP 7.2 **ee-security** subsystem provides support for [JSR 375](#) and compliance for Java EE 8 security. The JBoss Server Migration Tool automatically adds the default **ee-security** subsystem configuration to the migrated configuration file.

To skip the addition of the **ee-security** subsystem configuration, set the **subsystem.ee-security.add.skip** environment property to **true**.

6.1.19. Add the Elytron Subsystem

The JBoss EAP 7.2 **elytron** subsystem provides a single unified security framework that can manage and configure access for both standalone servers and managed domains. It can also be used to configure security access for applications deployed to JBoss EAP servers. The JBoss Server Migration Tool automatically adds the default **elytron** subsystem configuration to the migrated configuration file.

To skip the addition of the **elytron** subsystem configuration, set the **subsystem.elytron.add.skip** environment property to **true**.

6.1.20. Add the Request Controller Subsystem

The JBoss EAP 7.2 **request-controller** subsystem provides congestion control and graceful shutdown functionality. The JBoss Server Migration Tool automatically adds the default **request-controller** subsystem configuration to the migrated configuration file.

To skip the addition of the **request-controller** subsystem configuration, set the **subsystem.request-controller.add.skip** environment property to **true**.

6.1.21. Add the Security Manager Subsystem

The JBoss EAP 7.2 **security-manager** subsystem provides support for Java EE security permissions. The JBoss Server Migration Tool automatically adds the default **security-manager** subsystem configuration to the migrated configuration file.

To skip the addition of the **security-manager** subsystem configuration, set the **subsystem.security-manager.add.skip** environment property to **true**.

6.1.22. Add the Singleton Subsystem

The JBoss EAP 7.2 **singleton** subsystem provides singleton functionality. The JBoss Server Migration Tool automatically adds the default **singleton** subsystem configuration to the migrated configuration file.

To skip the addition of the **singleton** subsystem configuration, set the **subsystem.singleton.add.skip** environment property to **true**.

6.1.23. Set Up HTTP Upgrade Management

The addition of Undertow in JBoss EAP 7 added HTTP Upgrade, which allows for multiple protocols to be multiplexed over a single port. This means a management client can make an initial connection over HTTP, but then send a request to upgrade that connection to another protocol. The JBoss Server Migration Tool automatically updates the configuration to support HTTP Upgrade management.

To skip configuration of HTTP Upgrade management, set the **management.setup-http-upgrade.skip** environment property to **true**.

6.1.24. Set Up the Private Interface

The JBoss EAP 7 default configuration uses a private interface on all **jgroups** socket bindings. The JBoss Server Migration Tool automatically updates the migrated **jgroups** socket bindings to use same configuration.

To skip the configuration of the private interface, set the **interface.private.setup.skip.environment** property to **true**.

6.1.25. Add Socket Binding Port Expressions

The JBoss EAP 7.2 default configurations use value expressions for the port attribute of the following socket bindings:

- **ajp**
- **http**

- **https**

The JBoss Server Migration Tool automatically adds these value expressions to the migrated server configurations.

To skip update of the socket binding port expressions, set the **socket-bindings.add-port-expressions.skip** environment property to **true**.

6.1.26. Add Socket Binding Multicast Address Expressions

The JBoss EAP 7.2 default configuration uses value expressions in the **multicast-address** attribute of `mod_cluster` socket bindings. The JBoss Server Migration Tool automatically adds these value expressions to the migrated configuration files.

To skip the addition of these expressions, set the **socket-bindings.multicast-address.add-expressions.skip** environment property to **true**.

6.1.27. Migrate Compatible Security Realms

Because the JBoss EAP 7.2 security realm configurations are fully compatible with the JBoss EAP 6.4 security realm configurations, they require no update by the JBoss Server Migration Tool. However, if the **application-users.properties**, **application-roles.properties**, **mgmt-users.properties**, and **mgmt-groups.properties** files are not referenced using an absolute path, the tool copies them to the path expected by the migrated configuration file.

To skip the security realms migration, set the **security-realms.migrate-properties.skip** environment property to **true**.

6.1.28. Add the Default SSL Server Identity to the ApplicationRealm

The JBoss EAP 7.2 default configuration includes an SSL server identity for the default **ApplicationRealm** security realm. The JBoss Server Migration Tool automatically adds this identity to the migrated configuration files.

To skip the addition of this identity, set the **security-realm.ApplicationRealm.add-ssl-server-identity.skip** environment property to **true**.

6.1.29. Migrate Deployments

The JBoss Server Migration Tool can migrate the following types of standalone server deployment configurations.

- Deployments it references, also known as [persistent deployments](#).
- Deployments found in directories monitored by its [deployment scanners](#).
- [Deployment overlays](#) it references.

The migration of a deployment consists of installing related file resources on the target server, and possibly updating the migrated configuration.

The JBoss Server Migration Tool is preconfigured to skip deployments by default when running in non-interactive mode. To enable migration of deployments, set the **deployments.migrate-deployments.skip** environment property to **false**.



IMPORTANT

Be aware that when you run the JBoss Server Migration Tool in interactive mode and enter invalid input, the resulting behavior depends on the value of the **`deployments.migrate-deployments`** environment property.

- If **`deployments.migrate-deployments.skip`** is set to **`false`** and you enter invalid input, the tool will try to migrate the deployments.
- If **`deployments.migrate-deployments.skip`** is set to **`true`** and you enter invalid input, the tool will skip the deployments migration.

To enable the migration of specific types of deployments, see the following sections.



WARNING

The JBoss Server Migration Tool does not determine whether deployed resources are compatible with the target server. This means that applications or resources might not deploy, might not work as expected, or might not work at all. Also be aware that artifacts such as JBoss EAP 6.4 `*-jms.xml` configuration files are copied without modification and can cause the JBoss EAP server to boot with errors.

Red Hat recommends that you use the Red Hat Application Migration Toolkit to analyze deployments to determine compatibility among different JBoss EAP servers. For more information, see the Red Hat Application Migration Toolkit [product documentation](#).

6.1.29.1. Migrate Persistent Deployments

To enable migration of persistent deployments when running in non-interactive mode, set the **`deployments.migrate-persistent-deployments.skip`** environment property to **`false`**.

The JBoss Server Migration Tool searches for any persistent deployment references and lists them to the console.

```
INFO [ServerMigrationTask#67] Persistent deployments found: [cmtool-helloworld3.war, cmtool-helloworld4.war, cmtool-helloworld2.war, cmtool-helloworld1.war]
```

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Persistent Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the persistent deployments. Persistent deployments are migrated only if both the **`deployments.migrate-deployments.skip`** and **`deployments.migrate-persistent-deployments.skip`** properties are set to **`false`**.

Migrating Persistent Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the persistent deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if persistent deployments found are
compatible with the target server, skip persistent deployments
migration?
yes/no?
```

- Respond with **yes** to skip migration of persistent deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **no** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all persistent deployments found?
yes/no?
```

- Respond with **yes** to automatically migrate all deployments and end this part of the migration process.
- Respond with **no** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate persistent deployment 'helloworld01.war'?
yes/no?
```

- Respond with **yes** to migrate the deployment.
- Respond with **no** to remove the deployment from the migrated configuration.

```
INFO [ServerMigrationTask#68] Removed persistent deployment from
configuration /deployment=helloworld01.war
```

6.1.29.2. Migrate Deployment Scanner Deployments

Deployment scanners, which are only used in standalone server configurations, monitor a directory for new files and manage their deployment automatically or through special deployment marker files.

To enable migration of deployments that are located in directories watched by a deployment scanner when running in non-interactive mode, set the **deployments.migrate-deployment-scanner-deployments.skip** environment property to **false**.

When migrating a standalone server configuration, the JBoss Server Migration Tool first searches for any configured deployment scanners. For each scanner found, it searches its monitored directories for deployments marked as deployed and prints the results to the console.

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Deployment Scanner Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the deployment scanner deployments. Deployment scanner deployments are migrated only if both the **`deployments.migrate-deployments.skip`** and **`deployments.migrate-deployment-scanner-deployments.skip`** properties are set to **`false`**.

Migrating Deployment Scanner Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the deployment scanner deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if the scanner's deployments found
are compatible with the target server, skip scanner's deployments
migration?
yes/no?
```

- Respond with **`yes`** to skip migration of deployment scanner deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **`no`** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all scanner's deployments found?
yes/no?
```

- Respond with **`yes`** to automatically migrate all deployments and end this part of the migration process.
- Respond with **`no`** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate scanner's deployment 'helloworld02.war'?
yes/no?
```

- Respond with **`yes`** to migrate the deployment.
- Respond with **`no`** to remove the deployment from the migrated configuration.

```
INFO [ServerMigrationTask#69] Resource with path
EAP_HOME/standalone/deployments/helloworld02.war migrated.
```

6.1.29.3. Migrate Deployment Overlays

The migration of deployment overlays is a fully automated process. If you have enabled migration of deployments by setting the **`deployments.migrate-deployments.skip`** environment property to **`false`**, the JBoss Server Migration Tool searches for deployment overlays referenced in the standalone server configuration that are linked to migrated deployments. It automatically migrates those that are found, removes those that are not referenced, and logs the results to its log file and to the console.

6.2. MIGRATING A JBOSS EAP 6.4 MANAGED DOMAIN TO JBOSS EAP 7.2



WARNING

When you use the JBoss Server Migration Tool to migrate a domain controller to a new release of JBoss EAP, it can cause the hosts that connect to it, but still run on a previous release of the server, to fail to boot. For this reason, you should migrate your hosts before you migrate your domain controller. If you do not want to migrate your hosts, be sure to read the following information before you begin.

Review [Configure a JBoss EAP 7.x Domain Controller to Administer JBoss EAP 6 Instances](#) in the *Configuration Guide* for JBoss EAP. Pay particular attention to the section entitled [Prevent the JBoss EAP 6 Instances from Receiving JBoss EAP 7 Updates](#).

For additional information, see [Managing Multiple JBoss EAP Versions](#) in the *Configuration Guide* for JBoss EAP.

By default, the JBoss Server Migration Tool performs the following tasks when migrating a managed domain configuration from JBoss EAP 6.4 to JBoss EAP 7.2.

- [Remove any unsupported subsystems.](#)
- [Migrate any referenced modules.](#)
- [Migrate any referenced paths.](#)
- [Migrate the **jacorb** subsystem.](#)
- [Migrate the **web** subsystem.](#)
- [Migrate the **messaging** subsystem.](#)
- [Update the **infinispan** subsystem.](#)
- [Update the **ee** subsystem.](#)
- [Update the **ejb3** subsystem.](#)
- [Update the **jgroups** subsystem.](#)
- [Update the **remoting** subsystem.](#)
- [Update the **transactions** subsystem.](#)
- [Update the **undertow** subsystem.](#)
- [Update the **messaging-activemq** subsystem.](#)
- [Add the **batch-jberet** subsystem.](#)

- Add the **core-management** subsystem.
- Add the **discovery** Subsystem.
- Add the **ee-security** Subsystem.
- Add the **elytron** subsystem.
- Add the **request-controller** subsystem.
- Add the **security-manager** subsystem.
- Add the **singleton** subsystem.
- Update the **unsecure** interface.
- Set up the private interface.
- Add socket binding port expressions.
- Add socket binding multicast address expressions.
- Add the load balancer profile.
- Add the host excludes configuration.
- Remove the **PermGen** attributes from the JVM configurations.
- Migrate deployments.

6.2.1. Remove Unsupported Subsystems

The following JBoss EAP 6.4 subsystems are not supported by JBoss EAP 7:

Subsystem Name	Configuration Namespace	Extension Module
cmp	urn:jboss:domain:cmp:*	org.jboss.as.cmp
configadmin	urn:jboss:domain:configadmin:*	org.jboss.as.configadmin
jaxr	urn:jboss:domain:jaxr:*	org.jboss.as.jaxr
osgi	urn:jboss:domain:osgi:*	org.jboss.as.osgi
threads	urn:jboss:domain:threads:*	org.jboss.as.threads

The JBoss Server Migration Tool removes all unsupported subsystem configurations and extensions from migrated server configurations. The tool logs each subsystem and extension to its log file and to the console as it is removed.

To skip removal of the unsupported subsystems, set the **subsystems.remove-unsupported-subsystems.skip** environment property to **true**.

You can override the default behavior of the JBoss Server Migration Tool and specify which subsystems and extensions should be included or excluded during the migration using the following environment properties.

Property Name	Property Description
extensions.excludes	A list of module names of extensions that should never be migrated, for example, com.example.extension1,com.example.extension3.
extensions.includes	A list of module names of extensions that should always be migrated, for example, com.example.extension2,com.example.extension4.
subsystems.excludes	A list of subsystem namespaces, stripped of the version, that should never be migrated, for example, urn:jboss:domain:logging, urn:jboss:domain:ejb3.
subsystems.includes	A list of subsystem namespaces, stripped of the version, that should always be migrated, for example, urn:jboss:domain:security, urn:jboss:domain:ee.

6.2.2. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a managed domain configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.
- A module referenced by the **datasource** subsystem configuration is migrated as a datasource driver module.
- A module referenced by the **ee** subsystem configuration is migrated as a global module.
- A module referenced by the **naming** subsystem configuration is migrated as an object factory module.
- A module referenced by the **messaging** subsystem configuration is migrated as a JMS bridge module.
- A module referenced by a vault configuration is migrated to the new configuration.
- Any extension that is not installed on the target configuration is migrated to the target server configuration.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

6.2.3. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **paths.migrate-paths-requested-by-configuration.vault.skip** environment property to **true**.

6.2.4. Migrate the Jacorb Subsystem

The **jacorb** subsystem is deprecated in JBoss EAP 7 and is replaced by the **iiop-openjdk** subsystem. By default, the JBoss Server Migration Tool automatically migrates the **jacorb** subsystem configuration to its replacement **iiop-openjdk** subsystem configuration and logs the results to its log file and to the console.

To skip the automatic migration to the **iiop-openjdk** subsystem configuration, set the **subsystem.jacorb.migrate.skip** environment property value to **true**.

6.2.5. Migrate the Web Subsystem

The **web** subsystem is deprecated in JBoss EAP 7 and is replaced by the **undertow** subsystem. By default, the JBoss Server Migration Tool automatically migrates the **web** subsystem configuration to its replacement **undertow** subsystem configuration and logs the results to its log file and to the console.

To skip automatic migration of the **web** subsystem, set the **subsystem.web.migrate.skip** environment property value to **true**.

6.2.6. Migrate the Messaging Subsystem

The **messaging** subsystem is deprecated in JBoss EAP 7 and is replaced by the **messaging-activemq** subsystem. The JBoss Server Migration Tool automatically migrates the **messaging** subsystem configuration to its replacement **messaging-activemq** subsystem configuration and logs the results to its log file and to the console.

To skip automatic migration of the **messaging** subsystem, set the **subsystem.messaging.migrate.skip** environment property value to **true**.

6.2.7. Update the Infinispan Subsystem

The JBoss Server Migration Tool updates the **infinispan** subsystem configuration to better align with the default JBoss EAP 7.2 configurations.

- It adds the EJB cache container, which is present in the JBoss EAP 7.2 default configuration, to configurations where it is not already included.

- It adds the server cache container, which is present in the JBoss EAP 7.2 default configuration.
- It updates the module name in the Hibernate cache container configuration.
- It adds the concurrent cache to the web cache container, which is present in the JBoss EAP 7.2 default configuration.

The JBoss Server Migration Tool automatically updates the **infinispan** subsystem configuration and logs the results to its log file and to the console.

You can customize the update of the **infinispan** system by setting the following environment properties.

Property Name	Property Description
subsystem.infinispan.update.skip	If set to true , skip the update of the infinispan subsystem.
subsystem.infinispan.update.add-infinispan-ejb-cache.skip	If set to true , do not add the EJB cache container.
subsystem.infinispan.update.add-infinispan-server-cache.skip	If set to true , do not add the server cache container.
subsystem.infinispan.update.fix-hibernate-cache-module-name.skip	If set to true , do not update the module name in the Hibernate cache container configuration.
subsystem.infinispan.update-infinispan-web-cache	If set to true , do not add the concurrent cache to the web cache container configuration.

6.2.8. Update the EE Subsystem

The JBoss Server Migration Tool updates the **ee** subsystem to configure the Java EE features supported in JBoss EAP 7.2.

- It configures instances of Java EE concurrency utilities, such as container-managed executors, that are present in the JBoss EAP 7.2 default configuration and logs the results to its log file and to the console.
- It defines the Java EE default resources, such as the default datasource, that are present in default JBoss EAP 6.4 configuration. If the resources are not found, the tool lists all available resources in the configuration, and then provides a prompt to select a resource from the list or to provide the JNDI address of the resource that should be set as the default.



NOTE

JNDI names that are specified are assumed to be valid. JNDI names are not validated by the tool.

The JBoss Server Migration Tool automatically updates the **ee** subsystem configuration and logs the results to its log file and to the console.

You can customize the update of the **ee** system by setting the following environment properties.

Property Name	Property Description
<code>subsystem.ee.update.skip</code>	If set to true , skip the update of the ee subsystem.
<code>subsystem.ee.update.setup-ee-concurrency-utilities.skip</code>	If set to true , do not add the default instances of concurrency utilities.
<code>subsystem.ee.update.setup-javaee7-default-bindings.skip</code>	If set to true , do not set up Java EE default resources.
<code>subsystem.ee.update.setup-javaee7-default-bindings.defaultDataSourceName</code>	Specifies the name of the default datasource to look for in the source configuration.
<code>subsystem.ee.update.setup-javaee7-default-bindings.defaultDataSourceJndiName</code>	Specifies the JNDI name for the default datasource.
<code>subsystem.ee.update.setup-javaee7-default-bindings.defaultJmsConnectionFactoryName</code>	Specifies the name of the default JMS connection factory.
<code>subsystem.ee.update.setup-javaee7-default-bindings.defaultJmsConnectionFactoryJndiName</code>	Specifies the JNDI name for the default JMS connection factory.

Configuring Concurrency Utilities in the EE Subsystem

If you choose to configure the Java EE concurrency utilities, then the tool automatically configures the instances that are present in the default JBoss EAP 7.2 configurations and logs the results to its log file and to the console.

```
INFO [ServerMigrationTask#49] Default ContextService added to EE
subsystem configuration.
INFO [ServerMigrationTask#49] Default ManagedThreadFactory added to EE
subsystem configuration.
INFO [ServerMigrationTask#49] Default ManagedExecutorService added to EE
subsystem configuration.
INFO [ServerMigrationTask#49] Default ManagedScheduledExecutorService
added to EE subsystem configuration.
```

Configuring Default Resources in the EE Subsystem

When defining the Java EE default resources the tool automatically selects those that are present in the default JBoss EAP 7.2 configuration.

```
INFO [ServerMigrationTask#50] Java EE Default Datasource configured with
JNDI name java:jboss/datasources/ExampleDS.
```

If no default resource is found, the tool lists all resources that are available in the configuration, and then provides a prompt to select the default resource or to provide the JNDI address of the resource that should be set as the default.

The following is an example of the interaction that occurs when migrating a configuration file with an **ExampleDS** datasource.


```
INFO [ServerMigrationTask#22] Default datasource not found.
0. ExampleDS
1. Unconfigured data source, I want to enter the JNDI name...
Please select Java EE's Default Datasource: (0): 0
INFO [ServerMigrationTask#22] Java EE Default Datasource configured with
JNDI name java:jboss/datasources/ExampleDS.

Save this Java EE Default Datasource JNDI name and use it when migrating
other config files?
yes/no? y
```



NOTE

If you run the JBoss Server Migration Tool in non-interactive mode and the expected JBoss EAP 6.4 default resources, such as the default JMS connection factory, are not available, the tool does not configure those resources.

6.2.9. Update the EJB 3 Subsystem

The JBoss Server Migration Tool makes the following updates to the **ejb3** subsystem to better align with the default JBoss EAP 7.2 configurations.

- It updates the remote service configuration to reference the HTTP connector.
- It configures the **default-sfsb-passivation-disabled-cache** attribute to use the **default-sfsb-cache**.
- It replaces the legacy passivation store and cache configurations with the JBoss EAP 7.2 default values.

The JBoss Server Migration Tool automatically updates the **ejb3** subsystem configuration and logs the results to its log file and to the console.

Upon successful update of the **ejb3** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem ejb3 updated.
```

You can customize the update of the **ejb3** system by setting the following environment properties.

Property Name	Property Description
subsystem.ejb3.update.skip	If set to true , skip the update of the ejb3 subsystem.
subsystem.ejb3.update.add-infinispan-passivation-store-and-distributable-cache.skip	If set to true , do not replace the passivation-store and cache configurations.
subsystem.ejb3.update.setup-default-sfsb-passivation-disabled-cache.skip	If set to true , do not update the default-sfsb-passivation-disabled-cache configuration.

Property Name	Property Description
<code>subsystem.ejb3.update.activate-ejb3-remoting-http-connector.skip</code>	If set to true , do not update the EJB remoting configuration.

6.2.10. Update the JGroups Subsystem

The JBoss Server Migration Tool updates the **jgroups** subsystem to align with the JBoss EAP 7.2 configurations.

- It replaces the **MERGE2** protocol with **MERGE3**.
- It replaces the **FD** protocol with **FD_ALL**.
- It replaces the **pbcast.NAKACK** protocol with **pbcast.NAKACK2**.
- It replaces the **UNICAST2** protocol with **UNICAST3**.
- It removes the **RSVP** protocol.
- It replaces the **FRAG2** protocol with the **FRAG3** protocol.

Upon successful migration of the **jgroups** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem jgroups updated.
```

To skip the automatic migration of the **jgroups** subsystem, set the **subsystem.jgroups.update.skip** environment property to **true**.

6.2.11. Update the Remoting Subsystem

JBoss EAP 7 includes an HTTP connector that replaces all legacy remoting protocols and ports using a single port. The JBoss Server Migration Tool automatically updates the **remoting** subsystem to use the HTTP connector.

To skip the automatic update of the **remoting** subsystem configuration, set the **subsystem.remoting.update.skip** environment property to **true**.

6.2.12. Update the Transactions Subsystem

The JBoss Server Migration Tool updates the **transactions** subsystem with the configuration changes required by the JBoss EAP 7.2 server.

The JBoss Server Migration Tool removes the **path** and **relative-to** attributes from the **transactions** subsystem and replaces them with the equivalent **object-store-path** and **object-store-relative-to** attributes.

To skip the automatic update of the **transactions** subsystem configuration, set the **subsystem.transactions.update-xml-object-store-paths.skip** environment property to **true**.

6.2.13. Update the Undertow Subsystem

In addition to migrating the **web** subsystem for JBoss EAP 7.2, the JBoss Server Migration Tool updates its replacement **undertow** subsystem to add the features it supports.

- It sets the default HTTP listener redirect socket.
- It adds support for Java EE WebSockets.
- It sets the default HTTPS listener.
- It adds support for HTTP2.
- It removes the **Server** response header.
- It removes the **X-Powered-By** response header.
- It sets the default HTTP **Invoker**.

The JBoss Server Migration Tool automatically updates the **undertow** subsystem configuration and logs the results to its log file and to the console.

Upon successful migration of the **undertow** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem undertow updated.
```

You can customize the update of the **undertow** system by setting the following environment properties.

Property Name	Property Description
subsystem.undertow.update.skip	If set to true , skip the update of the undertow subsystem.
subsystem.undertow.update.set-default-http-listener-redirect-socket.skip	If set to true , do not set the default HTTP listener redirect socket.
subsystem.undertow.update.add-undertow-websockets.skip	If set to true , do not add support for WebSockets.
subsystem.undertow.update.add-undertow-https-listener.skip	If set to true , do not set the default HTTPS listener.
subsystem.undertow.update.enable-http2.skip	If set to true , do not add support for HTTP2.
subsystem.undertow.update.add-response-header.server-header.skip	If set to true , do not set the default Server response header.
subsystem.undertow.update.add-response-header.x-powered-by-header.skip	If set to true , do not set the default X-Powered-By response header.

Property Name	Property Description
<code>subsystem.undertow.update.add-http-invoker.skip</code>	If set to true , do not set the default HTTP Invoker .

6.2.14. Update the Messaging-ActiveMQ Subsystem

In addition to migrating the **messaging** subsystem for JBoss EAP 7.2, the JBoss Server Migration Tool updates its replacement **messaging-activemq** subsystem to add the new features it supports.

- It adds the default HTTP connector and acceptor to enable the HTTP-based remote messaging clients.

The JBoss Server Migration Tool automatically updates the **messaging-activemq** subsystem configuration and logs the results to its log file and to the console.

To skip the automatic update of the **messaging-activemq** subsystem, set the **subsystem.messaging-activemq.update.skip** environment property to **true**.

6.2.15. Add the Batch JBeret Subsystem

The JBoss EAP 7.2 **batch-jberet** subsystem provides support for [JSR 352: Batch Applications for the Java Platform](#). The JBoss Server Migration Tool automatically adds the default **batch-jberet** subsystem configuration to the migrated configuration file.

To skip the addition of the **batch-jberet** subsystem configuration, set the **subsystem.batch-jberet.add.skip** environment property to **true**.

6.2.16. Add the Core Management Subsystem

The JBoss EAP 7.2 **core-management** subsystem provides management-related resources, which were previously configured in the management core service. Examples of these resources include the ability to view a history of configuration changes made to the server and the ability to monitor for server lifecycle events. The JBoss Server Migration Tool automatically adds the default **core-management** subsystem configuration to the migrated configuration file.

To skip the addition of the **core-management** subsystem configuration, set the **subsystem.core-management.add.skip** environment property to **true**.

6.2.17. Add the Discovery Subsystem

The JBoss Server Migration Tool automatically adds the default **discovery** subsystem configuration to the migrated configuration file.

To skip the addition of the **discovery** subsystem configuration, set the **subsystem.discovery.add.skip** environment property to **true**.

6.2.18. Add the EE Security Subsystem

The JBoss EAP 7.2 **ee-security** subsystem provides support for [JSR 375](#) and compliance for Java EE 8 security. The JBoss Server Migration Tool automatically adds the default **ee-security** subsystem configuration to the migrated configuration file.

To skip the addition of the **ee-security** subsystem configuration, set the **subsystem.ee-security.add.skip** environment property to **true**.

6.2.19. Add the Elytron Subsystem

The JBoss EAP 7.2 **elytron** subsystem provides a single unified security framework that can manage and configure access for both standalone servers and managed domains. It can also be used to configure security access for applications deployed to JBoss EAP servers. The JBoss Server Migration Tool automatically adds the default **elytron** subsystem configuration to the migrated configuration file.

To skip the addition of the **elytron** subsystem configuration, set the **subsystem.elytron.add.skip** environment property to **true**.

6.2.20. Add the Request Controller Subsystem

The JBoss EAP 7.2 **request-controller** subsystem provides congestion control and graceful shutdown functionality. The JBoss Server Migration Tool automatically adds the default **request-controller** subsystem configuration to the migrated configuration file.

To skip the addition of the **request-controller** subsystem configuration, set the **subsystem.request-controller.add.skip** environment property to **true**.

6.2.21. Add the Security Manager Subsystem

The JBoss EAP 7.2 **security-manager** subsystem provides support for Java EE security permissions. The JBoss Server Migration Tool automatically adds the default **security-manager** subsystem configuration to the migrated configuration file.

To skip the addition of the **security-manager** subsystem configuration, set the **subsystem.security-manager.add.skip** environment property to **true**.

6.2.22. Add the Singleton Subsystem

The JBoss EAP 7.2 **singleton** subsystem provides singleton functionality. The JBoss Server Migration Tool automatically adds the default **singleton** subsystem configuration to the migrated configuration file.

To skip the addition of the **singleton** subsystem configuration, set the **subsystem.singleton.add.skip** environment property to **true**.

6.2.23. Update the Unsecure Interface

The JBoss Server Migration Tool automatically updates the **unsecure** interface configuration to align with the JBoss EAP 7.2 default configuration.

To skip configuration of the **unsecure** interface, set the **interface.unsecure.update.skip** environment property to **true**.

6.2.24. Set Up the Private Interface

The JBoss EAP 7 default configuration uses a private interface on all **jgroups** socket bindings. The JBoss Server Migration Tool automatically updates the migrated **jgroups** socket bindings to use same configuration.

To skip the configuration of the private interface, set the **`interface.private.setup.skip.environment`** property to **`true`**.

6.2.25. Add Socket Binding Port Expressions

The JBoss EAP 7.2 default configurations use value expressions for the port attribute of the following socket bindings:

- **`ajp`**
- **`http`**
- **`https`**

The JBoss Server Migration Tool automatically adds these value expressions to the migrated server configurations.

To skip update of the socket binding port expressions, set the **`socket-bindings.add-port-expressions.skip`** environment property to **`true`**.

6.2.26. Add Socket Binding Multicast Address Expressions

The JBoss EAP 7.2 default configuration uses value expressions in the **`multicast-address`** attribute of `mod_cluster` socket bindings. The JBoss Server Migration Tool automatically adds these value expressions to the migrated configuration files.

To skip the addition of these expressions, set the **`socket-bindings.multicast-address.add-expressions.skip`** environment property to **`true`**.

6.2.27. Add the Load Balancer Profile

JBoss EAP 7.2 includes a default profile specifically tailored for hosts that serve as load balancers. The JBoss Server Migration Tool automatically adds and configures this profile to all migrated managed domain configurations.

To skip the addition of this profile, set the **`profile.load-balancer.add.skip`** environment property to **`true`**.

6.2.28. Add Host Excludes

The JBoss EAP 7.2 domain controller can potentially include functionality that is not supported by hosts running on older versions of the server. The **`host-exclude`** configuration specifies the resources that should be hidden from those older versions.

When migrating a domain controller configuration, the JBoss Server Migration Tool adds to or replaces the source server's **`host-exclude`** configuration with the configuration of the target JBoss EAP 7.2 server.

The JBoss Server Migration Tool automatically updates the **`host-exclude`** configuration and logs the results to its log file and to the console.

```
INFO  Host-excludes configuration added.
```

6.2.29. Remove the PermGen Attributes from the JVM Configurations

The usage of **PermGen** attributes in JVM configurations is deprecated in JBoss EAP 7. The JBoss Server Migration Tool automatically removes them from all JVM configurations for all server groups.

To skip removal of the **PermGen** attributes, set the `jvms.remove-permgen-attributes.skip` environment property value to **true**.

6.2.30. Migrate Deployments

The JBoss Server Migration Tool can migrate the following types of managed domain deployment configurations.

- Deployments it references, also known as [persistent deployments](#).
- [Deployment overlays](#) it references.

The migration of a deployment consists of installing related file resources on the target server, and possibly updating the migrated configuration.

The JBoss Server Migration Tool is preconfigured to skip deployments by default when running in non-interactive mode. To enable migration of deployments, set the `deployments.migrate-deployments.skip` environment property to **false**.



IMPORTANT

Be aware that when you run the JBoss Server Migration Tool in interactive mode and enter invalid input, the resulting behavior depends on the value of the `deployments.migrate-deployments` environment property.

- If `deployments.migrate-deployments.skip` is set to **false** and you enter invalid input, the tool will try to migrate the deployments.
- If `deployments.migrate-deployments.skip` is set to **true** and you enter invalid input, the tool will skip the deployments migration.

To enable the migration of specific types of deployments, see the following sections.



WARNING

The JBoss Server Migration Tool does not determine whether deployed resources are compatible with the target server. This means that applications or resources might not deploy, might not work as expected, or might not work at all. Also be aware that artifacts such as JBoss EAP 6.4 `*-jms.xml` configuration files are copied without modification and can cause the JBoss EAP server to boot with errors.

Red Hat recommends that you use the Red Hat Application Migration Toolkit to analyze deployments to determine compatibility among different JBoss EAP servers. For more information, see the Red Hat Application Migration Toolkit [product documentation](#).

6.2.30.1. Migrate Persistent Deployments

To enable migration of persistent deployments when running in non-interactive mode, set the **`deployments.migrate-persistent-deployments.skip`** environment property to **`false`**.

The JBoss Server Migration Tool searches for any persistent deployment references and lists them to the console.

```
INFO [ServerMigrationTask#67] Persistent deployments found: [cmtool-
helloworld3.war, cmtool-helloworld4.war, cmtool-helloworld2.war, cmtool-
helloworld1.war]
```

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Persistent Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the persistent deployments. Persistent deployments are migrated only if both the **`deployments.migrate-deployments.skip`** and **`deployments.migrate-persistent-deployments.skip`** properties are set to **`false`**.

Migrating Persistent Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the persistent deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if persistent deployments found are
compatible with the target server, skip persistent deployments
migration?
yes/no?
```

- Respond with **yes** to skip migration of persistent deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **no** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all persistent deployments found?
yes/no?
```

- Respond with **yes** to automatically migrate all deployments and end this part of the migration process.
- Respond with **no** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate persistent deployment 'helloworld01.war'?
yes/no?
```

- Respond with **yes** to migrate the deployment.

- Respond with **no** to remove the deployment from the migrated configuration.

```
INFO [ServerMigrationTask#68] Removed persistent deployment from
configuration /deployment=helloworld01.war
```

6.2.30.2. Migrate Deployment Overlays

The migration of deployment overlays is a fully automated process. If you have enabled migration of deployments by setting the **deployments.migrate-deployments.skip** environment property to **false**, the JBoss Server Migration Tool searches for deployment overlays referenced in the standalone server configuration that are linked to migrated deployments. It automatically migrates those that are found, removes those that are not referenced, and logs the results to its log file and to the console.

6.3. MIGRATING A JBOSS EAP 6.4 HOST CONFIGURATION TO JBOSS EAP 7.2

By default, the JBoss Server Migration Tool performs the following tasks when migrating a host server configuration from JBoss EAP 6.4 to JBoss EAP 7.2.

- [Migrate any referenced modules](#).
- [Migrate any referenced paths](#).
- [Add the **core-management** subsystem](#).
- [Add the **elytron** subsystem](#).
- [Add the **jmx** subsystem](#).
- [Remove the **unsecure** interface](#).
- [Set up HTTP Upgrade management](#).
- [Remove the **PermGen** attributes from the JVM configurations](#).
- [Migrate compatible security realms](#).
- [Add the default SSL server identity to the **ApplicationRealm**](#).

6.3.1. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a host server configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

6.3.2. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **`paths.migrate-paths-requested-by-configuration.vault.skip`** environment property to **`true`**.

6.3.3. Add the Core Management Subsystem

The JBoss EAP 7.2 **`core-management`** subsystem provides management-related resources, which were previously configured in the management core service. Examples of these resources include the ability to view a history of configuration changes made to the server and the ability to monitor for server lifecycle events. The JBoss Server Migration Tool automatically adds the default **`core-management`** subsystem configuration to the migrated configuration file.

To skip the addition of the **`core-management`** subsystem configuration, set the **`subsystem.core-management.add.skip`** environment property to **`true`**.

6.3.4. Add the Elytron Subsystem

The JBoss EAP 7.2 **`elytron`** subsystem provides a single unified security framework that can manage and configure access for both standalone servers and managed domains. It can also be used to configure security access for applications deployed to JBoss EAP servers. The JBoss Server Migration Tool automatically adds the default **`elytron`** subsystem configuration to the migrated configuration file.

To skip the addition of the **`elytron`** subsystem configuration, set the **`subsystem.elytron.add.skip`** environment property to **`true`**.

6.3.5. Add the JMX Subsystem to the Host Configuration

The JBoss EAP 7 **`jmx`** subsystem provides the ability to manage and monitor systems. The JBoss Server Migration Tool automatically adds this subsystem to the migrated configuration file.

To skip the addition of the **`jmx`** subsystem configuration, set the **`subsystem.jmx.add.skip`** environment property to **`true`**.

6.3.6. Remove the unsecure Interface

The JBoss Server Migration Tool automatically removes the **`unsecure`** interface configuration to align with the JBoss EAP 7.2 default configuration.

To skip removal of the **`unsecure`** interface, set the **`interface.unsecure.remove.skip`** environment property to **`true`**.

6.3.7. Set Up HTTP Upgrade Management

The addition of Undertow in JBoss EAP 7 added HTTP Upgrade, which allows for multiple protocols to

be multiplexed over a single port. This means a management client can make an initial connection over HTTP, but then send a request to upgrade that connection to another protocol. The JBoss Server Migration Tool automatically updates the configuration to support HTTP Upgrade management.

To skip configuration of HTTP Upgrade management, set the **management.setup-http-upgrade.skip** environment property to **true**.

6.3.8. Remove the PermGen Attributes from the JVM Configurations

The usage of **PermGen** attributes in JVM configurations is deprecated in JBoss EAP 7. The JBoss Server Migration Tool automatically removes them from all JVM configurations for all server groups.

To skip removal of the **PermGen** attributes, set the **jvms.remove-permgen-attributes.skip** environment property value to **true**.

6.3.9. Migrate Compatible Security Realms

Because the JBoss EAP 7.2 security realm configurations are fully compatible with the JBoss EAP 6.4 security realm configurations, they require no update by the JBoss Server Migration Tool. However, if the **application-users.properties**, **application-roles.properties**, **mgmt-users.properties**, and **mgmt-groups.properties** files are not referenced using an absolute path, the tool copies them to the path expected by the migrated configuration file.

To skip the security realms migration, set the **security-realms.migrate-properties.skip** environment property to **true**.

6.3.10. Add the Default SSL Server Identity to the ApplicationRealm


The JBoss EAP 7.2 default configuration includes an SSL server identity for the default **ApplicationRealm** security realm. The JBoss Server Migration Tool automatically adds this identity to the migrated configuration files.

To skip the addition of this identity, set the **security-realm.ApplicationRealm.add-ssl-server-identity.skip** environment property to **true**.

CHAPTER 7. MIGRATING JBOSS EAP 7.0 CONFIGURATIONS TO JBOSS EAP 7.2

7.1. MIGRATING A JBOSS EAP 7.0 STANDALONE SERVER TO JBOSS EAP 7.2

By default, the JBoss Server Migration Tool performs the following tasks when migrating a standalone server configuration from JBoss EAP 7.0 to JBoss EAP 7.2.



IMPORTANT

Migration to JBoss EAP 7.2 from JBoss EAP 7.0 is provided as Technology Preview only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

See [Technology Preview Features Support Scope](#) on the Red Hat Customer Portal for information about the support scope for Technology Preview features.

- [Remove any unsupported subsystems.](#)
- [Migrate any referenced modules.](#)
- [Migrate any referenced paths.](#)
- [Update the **infinispan** subsystem.](#)
- [Update the **jgroups** subsystem.](#)
- [Update the **undertow** subsystem.](#)
- [Add the **core-management** subsystem.](#)
- [Add the **discovery** Subsystem.](#)
- [Add the **ee-security** Subsystem.](#)
- [Add the **elytron** subsystem.](#)
- [Add socket binding multicast address expressions.](#)
- [Migrate compatible security realms.](#)
- [Add the default SSL server identity to the **ApplicationRealm**.](#)
- [Migrate deployments.](#)

7.1.1. Remove Unsupported Subsystems

The JBoss Server Migration Tool removes all unsupported subsystem configurations and extensions from migrated server configurations. The tool logs each subsystem and extension to its log file and to the console as it is removed.

NOTE

Any subsystem that was not supported in JBoss EAP 7.0, but was added by an administrator to that server, is also not supported in JBoss EAP 7.2 and will be removed.

To skip removal of the unsupported subsystems, set the **subsystems.remove-unsupported-subsystems.skip** environment property to **true**.

You can override the default behavior of the JBoss Server Migration Tool and specify which subsystems and extensions should be included or excluded during the migration using the following environment properties.

Property Name	Property Description
extensions.excludes	A list of module names of extensions that should never be migrated, for example, com.example.extension1,com.example.extension3.
extensions.includes	A list of module names of extensions that should always be migrated, for example, com.example.extension2,com.example.extension4.
subsystems.excludes	A list of subsystem namespaces, stripped of the version, that should never be migrated, for example, urn:jboss:domain:logging, urn:jboss:domain:ejb3.
subsystems.includes	A list of subsystem namespaces, stripped of the version, that should always be migrated, for example, urn:jboss:domain:security, urn:jboss:domain:ee.

7.1.2. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a standalone server configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.
- A module referenced by the **datasource** subsystem configuration is migrated as a datasource driver module.
- A module referenced by the **ee** subsystem configuration is migrated as a global module.

- A module referenced by the **naming** subsystem configuration is migrated as an object factory module.
- A module referenced by the **messaging** subsystem configuration is migrated as a JMS bridge module.
- A module referenced by a vault configuration is migrated to the new configuration.
- Any extension that is not installed on the target configuration is migrated to the target server configuration.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

7.1.3. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **paths.migrate-paths-requested-by-configuration.vault.skip** environment property to **true**.

7.1.4. Update the Infinispan Subsystem

The JBoss Server Migration Tool updates the **infinispan** subsystem configuration to better align with the default JBoss EAP 7.2 configurations.

- It updates the module name in the Hibernate cache container configuration.
- It adds the concurrent cache to the web cache container, which is present in the JBoss EAP 7.2 default configuration.

The JBoss Server Migration Tool automatically updates the **infinispan** subsystem configuration and logs the results to its log file and to the console.

You can customize the update of the **infinispan** system by setting the following environment properties.

Property Name	Property Description
subsystem.infinispan.update.skip	If set to true , skip the update of the infinispan subsystem.
subsystem.infinispan.update.fix-hibernate-cache-module-name.skip	If set to true , do not update the module name in the Hibernate cache container configuration.

Property Name	Property Description
<code>subsystem.infinispan.update-infinispan-web-cache</code>	If set to true , do not add the concurrent cache to the web cache container configuration.

7.1.5. Update the JGroups Subsystem

The JBoss Server Migration Tool updates the **jgroups** subsystem to align with the JBoss EAP 7.2 configurations.

- It replaces the **FRAG2** protocol with the **FRAG3** protocol.

Upon successful migration of the **jgroups** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem jgroups updated.
```

To skip the automatic migration of the **jgroups** subsystem, set the **subsystem.jgroups.update.skip** environment property to **true**.

7.1.6. Update the Undertow Subsystem

In addition to migrating the **web** subsystem for JBoss EAP 7.2, the JBoss Server Migration Tool updates its replacement **undertow** subsystem to add the features it supports.

- It sets the default HTTPS listener.
- It adds support for HTTP2.
- It removes the **Server** response header.
- It removes the **X-Powered-By** response header.
- It sets the default HTTP **Invoker**.

The JBoss Server Migration Tool automatically updates the **undertow** subsystem configuration and logs the results to its log file and to the console.

Upon successful migration of the **undertow** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem undertow updated.
```

You can customize the update of the **undertow** system by setting the following environment properties.

Property Name	Property Description
<code>subsystem.undertow.update.skip</code>	If set to true , skip the update of the undertow subsystem.

Property Name	Property Description
<code>subsystem.undertow.update.add-undertow-https-listener.skip</code>	If set to true , do not set the default HTTPS listener.
<code>subsystem.undertow.update.enable-http2.skip</code>	If set to true , do not add support for HTTP2.
<code>subsystem.undertow.update.add-response-header.server-header.skip</code>	If set to true , do not set the default Server response header.
<code>subsystem.undertow.update.add-response-header.x-powered-by-header.skip</code>	If set to true , do not set the default X-Powered-By response header.
<code>subsystem.undertow.update.add-http-invoker.skip</code>	If set to true , do not set the default HTTP Invoker .

7.1.7. Add the Core Management Subsystem

The JBoss EAP 7.2 **core-management** subsystem provides management-related resources, which were previously configured in the management core service. Examples of these resources include the ability to view a history of configuration changes made to the server and the ability to monitor for server lifecycle events. The JBoss Server Migration Tool automatically adds the default **core-management** subsystem configuration to the migrated configuration file.

To skip the addition of the **core-management** subsystem configuration, set the **subsystem.core-management.add.skip** environment property to **true**.

7.1.8. Add the Discovery Subsystem

The JBoss Server Migration Tool automatically adds the default **discovery** subsystem configuration to the migrated configuration file.

To skip the addition of the **discovery** subsystem configuration, set the **subsystem.discovery.add.skip** environment property to **true**.

7.1.9. Add the EE Security Subsystem

The JBoss EAP 7.2 **ee-security** subsystem provides support for [JSR 375](#) and compliance for Java EE 8 security. The JBoss Server Migration Tool automatically adds the default **ee-security** subsystem configuration to the migrated configuration file.

To skip the addition of the **ee-security** subsystem configuration, set the **subsystem.ee-security.add.skip** environment property to **true**.

7.1.10. Add the Elytron Subsystem

The JBoss EAP 7.2 **elytron** subsystem provides a single unified security framework that can manage and configure access for both standalone servers and managed domains. It can also be used to configure security access for applications deployed to JBoss EAP servers. The JBoss Server Migration Tool automatically adds the default **elytron** subsystem configuration to the migrated configuration file.

To skip the addition of the **elytron** subsystem configuration, set the **subsystem.elytron.add.skip** environment property to **true**.

7.1.11. Add Socket Binding Multicast Address Expressions

The JBoss EAP 7.2 default configuration uses value expressions in the **multicast-address** attribute of **mod_cluster** socket bindings. The JBoss Server Migration Tool automatically adds these value expressions to the migrated configuration files.

To skip the addition of these expressions, set the **socket-bindings.multicast-address.add-expressions.skip** environment property to **true**.

7.1.12. Migrate Compatible Security Realms

Because the JBoss EAP 7.2 security realm configurations are fully compatible with the JBoss EAP 7.0 security realm configurations, they require no update by the JBoss Server Migration Tool. However, if the **application-users.properties**, **application-roles.properties**, **mgmt-users.properties**, and **mgmt-groups.properties** files are not referenced using an absolute path, the tool copies them to the path expected by the migrated configuration file.

To skip the security realms migration, set the **security-realms.migrate-properties.skip** environment property to **true**.

7.1.13. Add the Default SSL Server Identity to the ApplicationRealm

The JBoss EAP 7.2 default configuration includes an SSL server identity for the default **ApplicationRealm** security realm. The JBoss Server Migration Tool automatically adds this identity to the migrated configuration files.

To skip the addition of this identity, set the **security-realm.ApplicationRealm.add-ssl-server-identity.skip** environment property to **true**.

7.1.14. Migrate Deployments

The JBoss Server Migration Tool can migrate the following types of standalone server deployment configurations.

- Deployments it references, also known as [persistent deployments](#).
- Deployments found in directories monitored by its [deployment scanners](#).
- [Deployment overlays](#) it references.

The migration of a deployment consists of installing related file resources on the target server, and possibly updating the migrated configuration.

The JBoss Server Migration Tool is preconfigured to skip deployments by default when running in non-interactive mode. To enable migration of deployments, set the **deployments.migrate-deployments.skip** environment property to **false**.



IMPORTANT

Be aware that when you run the JBoss Server Migration Tool in interactive mode and enter invalid input, the resulting behavior depends on the value of the **`deployments.migrate-deployments`** environment property.

- If **`deployments.migrate-deployments.skip`** is set to **`false`** and you enter invalid input, the tool will try to migrate the deployments.
- If **`deployments.migrate-deployments.skip`** is set to **`true`** and you enter invalid input, the tool will skip the deployments migration.

To enable the migration of specific types of deployments, see the following sections.



WARNING

The JBoss Server Migration Tool does not determine whether deployed resources are compatible with the target server. This means that applications or resources might not deploy, might not work as expected, or might not work at all. Also be aware that artifacts such as JBoss EAP 6.4 **`*-jms.xml`** configuration files are copied without modification and can cause the JBoss EAP server to boot with errors.

Red Hat recommends that you use the Red Hat Application Migration Toolkit to analyze deployments to determine compatibility among different JBoss EAP servers. For more information, see the Red Hat Application Migration Toolkit [product documentation](#).

7.1.14.1. Migrate Persistent Deployments

To enable migration of persistent deployments when running in non-interactive mode, set the **`deployments.migrate-persistent-deployments.skip`** environment property to **`false`**.

The JBoss Server Migration Tool searches for any persistent deployment references and lists them to the console.

```
INFO [ServerMigrationTask#67] Persistent deployments found: [cmtool-helloworld3.war, cmtool-helloworld4.war, cmtool-helloworld2.war, cmtool-helloworld1.war]
```

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Persistent Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the persistent deployments. Persistent deployments are migrated only if both the **`deployments.migrate-deployments.skip`** and **`deployments.migrate-persistent-deployments.skip`** properties are set to **`false`**.

Migrating Persistent Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the persistent deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if persistent deployments found are
compatible with the target server, skip persistent deployments
migration?
yes/no?
```

- Respond with **yes** to skip migration of persistent deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **no** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all persistent deployments found?
yes/no?
```

- Respond with **yes** to automatically migrate all deployments and end this part of the migration process.
- Respond with **no** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate persistent deployment 'helloworld01.war'?
yes/no?
```

- Respond with **yes** to migrate the deployment.
- Respond with **no** to remove the deployment from the migrated configuration.

```
INFO [ServerMigrationTask#68] Removed persistent deployment from
configuration /deployment=helloworld01.war
```

7.1.14.2. Migrate Deployment Scanner Deployments

Deployment scanners, which are only used in standalone server configurations, monitor a directory for new files and manage their deployment automatically or through special deployment marker files.

To enable migration of deployments that are located in directories watched by a deployment scanner when running in non-interactive mode, set the **deployments.migrate-deployment-scanner-deployments.skip** environment property to **false**.

When migrating a standalone server configuration, the JBoss Server Migration Tool first searches for any configured deployment scanners. For each scanner found, it searches its monitored directories for deployments marked as deployed and prints the results to the console.

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Deployment Scanner Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the deployment scanner deployments. Deployment scanner deployments are migrated only if both the **`deployments.migrate-deployments.skip`** and **`deployments.migrate-deployment-scanner-deployments.skip`** properties are set to **`false`**.

Migrating Deployment Scanner Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the deployment scanner deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if the scanner's deployments found
are compatible with the target server, skip scanner's deployments
migration?
yes/no?
```

- Respond with **`yes`** to skip migration of deployment scanner deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **`no`** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all scanner's deployments found?
yes/no?
```

- Respond with **`yes`** to automatically migrate all deployments and end this part of the migration process.
- Respond with **`no`** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate scanner's deployment 'helloworld02.war'?
yes/no?
```

- Respond with **`yes`** to migrate the deployment.
- Respond with **`no`** to remove the deployment from the migrated configuration.

```
INFO [ServerMigrationTask#69] Resource with path
EAP_HOME/standalone/deployments/helloworld02.war migrated.
```

7.1.14.3. Migrate Deployment Overlays

The migration of deployment overlays is a fully automated process. If you have enabled migration of deployments by setting the **`deployments.migrate-deployments.skip`** environment property to **`false`**, the JBoss Server Migration Tool searches for deployment overlays referenced in the standalone server configuration that are linked to migrated deployments. It automatically migrates those that are found, removes those that are not referenced, and logs the results to its log file and to the console.

7.2. MIGRATING A JBOSS EAP 7.0 MANAGED DOMAIN TO JBOSS EAP 7.2




WARNING

When you use the JBoss Server Migration Tool to migrate a domain controller to a new release of JBoss EAP, it can cause the hosts that connect to it, but still run on a previous release of the server, to fail to boot. For this reason, you should migrate your hosts before you migrate your domain controller. If you do not want to migrate your hosts, be sure to read the following information before you begin.

Review [Configure a JBoss EAP 7.1 Domain Controller to Administer JBoss EAP 7.0 Instances](#) in the *Configuration Guide* for JBoss EAP. Pay particular attention to the section entitled [Prevent the JBoss EAP 7.0 Instances from Receiving JBoss EAP 7.1 Updates](#).

For additional information, see [Managing Multiple JBoss EAP Versions](#) in the *Configuration Guide* for JBoss EAP.

By default, the JBoss Server Migration Tool performs the following tasks when migrating a managed domain configuration from JBoss EAP 7.0 to JBoss EAP 7.2.



IMPORTANT

Migration to JBoss EAP 7.2 from JBoss EAP 7.0 is provided as Technology Preview only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

See [Technology Preview Features Support Scope](#) on the Red Hat Customer Portal for information about the support scope for Technology Preview features.

- [Remove any unsupported subsystems.](#)
- [Migrate any referenced modules.](#)
- [Migrate any referenced paths.](#)
- [Update the **infinispan** subsystem.](#)
- [Update the **jgroups** subsystem.](#)
- [Update the **undertow** subsystem.](#)
- [Add the **core-management** subsystem.](#)
- [Add the **discovery** Subsystem.](#)

- [Add the **ee-security** Subsystem.](#)
- [Add the **elytron** Subsystem.](#)
- [Add socket binding multicast address expressions.](#)
- [Add the load balancer profile.](#)
- [Add the host excludes configuration.](#)
- [Migrate deployments.](#)

7.2.1. Remove Unsupported Subsystems

The JBoss Server Migration Tool removes all unsupported subsystem configurations and extensions from migrated server configurations. The tool logs each subsystem and extension to its log file and to the console as it is removed.

NOTE

Any subsystem that was not supported in JBoss EAP 7.0, but was added by an administrator to that server, is also not supported in JBoss EAP 7.2 and will be removed.

To skip removal of the unsupported subsystems, set the **subsystems.remove-unsupported-subsystems.skip** environment property to **true**.

You can override the default behavior of the JBoss Server Migration Tool and specify which subsystems and extensions should be included or excluded during the migration using the following environment properties.

Property Name	Property Description
extensions.excludes	A list of module names of extensions that should never be migrated, for example, com.example.extension1,com.example.extension3.
extensions.includes	A list of module names of extensions that should always be migrated, for example, com.example.extension2,com.example.extension4.
subsystems.excludes	A list of subsystem namespaces, stripped of the version, that should never be migrated, for example, urn:jboss:domain:logging,urn:jboss:domain:ejb3.
subsystems.includes	A list of subsystem namespaces, stripped of the version, that should always be migrated, for example, urn:jboss:domain:security,urn:jboss:domain:ee.

7.2.2. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a managed domain configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.
- A module referenced by the **datasource** subsystem configuration is migrated as a datasource driver module.
- A module referenced by the **ee** subsystem configuration is migrated as a global module.
- A module referenced by the **naming** subsystem configuration is migrated as an object factory module.
- A module referenced by the **messaging** subsystem configuration is migrated as a JMS bridge module.
- A module referenced by a vault configuration is migrated to the new configuration.
- Any extension that is not installed on the target configuration is migrated to the target server configuration.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

7.2.3. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **paths.migrate-paths-requested-by-configuration.vault.skip** environment property to **true**.

7.2.4. Update the Infinispan Subsystem

The JBoss Server Migration Tool updates the **infinispan** subsystem configuration to better align with the default JBoss EAP 7.2 configurations.

- It updates the module name in the Hibernate cache container configuration.
- It adds the concurrent cache to the web cache container, which is present in the JBoss EAP 7.2 default configuration.

The JBoss Server Migration Tool automatically updates the **infinispan** subsystem configuration and logs the results to its log file and to the console.

You can customize the update of the **infinispan** system by setting the following environment properties.

Property Name	Property Description
<code>subsystem.infinispan.update.skip</code>	If set to true , skip the update of the infinispan subsystem.
<code>subsystem.infinispan.update.fix-hibernate-cache-module-name.skip</code>	If set to true , do not update the module name in the Hibernate cache container configuration.
<code>subsystem.infinispan.update-infinispan-web-cache</code>	If set to true , do not add the concurrent cache to the web cache container configuration.

7.2.5. Update the JGroups Subsystem

The JBoss Server Migration Tool updates the **jgroups** subsystem to align with the JBoss EAP 7.2 configurations.

- It replaces the **FRAG2** protocol with the **FRAG3** protocol.

Upon successful migration of the **jgroups** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem jgroups updated.
```

To skip the automatic migration of the **jgroups** subsystem, set the **subsystem.jgroups.update.skip** environment property to **true**.

7.2.6. Update the Undertow Subsystem

In addition to migrating the **web** subsystem for JBoss EAP 7.2, the JBoss Server Migration Tool updates its replacement **undertow** subsystem to add the features it supports.

- It sets the default HTTPS listener.
- It adds support for HTTP2.
- It removes the **Server** response header.
- It removes the **X-Powered-By** response header.
- It sets the default HTTP **Invoker**.

The JBoss Server Migration Tool automatically updates the **undertow** subsystem configuration and logs the results to its log file and to the console.

Upon successful migration of the **undertow** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem undertow updated.
```


You can customize the update of the **undertow** system by setting the following environment properties.

Property Name	Property Description
<code>subsystem.undertow.update.skip</code>	If set to true , skip the update of the undertow subsystem.
<code>subsystem.undertow.update.add-undertow-https-listener.skip</code>	If set to true , do not set the default HTTPS listener.
<code>subsystem.undertow.update.enable-http2.skip</code>	If set to true , do not add support for HTTP2.
<code>subsystem.undertow.update.add-response-header.server-header.skip</code>	If set to true , do not set the default Server response header.
<code>subsystem.undertow.update.add-response-header.x-powered-by-header.skip</code>	If set to true , do not set the default X-Powered-By response header.
<code>subsystem.undertow.update.add-http-invoker.skip</code>	If set to true , do not set the default HTTP Invoker .

7.2.7. Add the Core Management Subsystem

The JBoss EAP 7.2 **core-management** subsystem provides management-related resources, which were previously configured in the management core service. Examples of these resources include the ability to view a history of configuration changes made to the server and the ability to monitor for server lifecycle events. The JBoss Server Migration Tool automatically adds the default **core-management** subsystem configuration to the migrated configuration file.

To skip the addition of the **core-management** subsystem configuration, set the **subsystem.core-management.add.skip** environment property to **true**.

7.2.8. Add the Discovery Subsystem

The JBoss Server Migration Tool automatically adds the default **discovery** subsystem configuration to the migrated configuration file.

To skip the addition of the **discovery** subsystem configuration, set the **subsystem.discovery.add.skip** environment property to **true**.

7.2.9. Add the EE Security Subsystem

The JBoss EAP 7.2 **ee-security** subsystem provides support for [JSR 375](#) and compliance for Java EE 8 security. The JBoss Server Migration Tool automatically adds the default **ee-security** subsystem configuration to the migrated configuration file.

To skip the addition of the **ee-security** subsystem configuration, set the **subsystem.ee-security.add.skip** environment property to **true**.

7.2.10. Add the Elytron Subsystem

The JBoss EAP 7.2 **elytron** subsystem provides a single unified security framework that can manage and configure access for both standalone servers and managed domains. It can also be used to configure security access for applications deployed to JBoss EAP servers. The JBoss Server Migration Tool automatically adds the default **elytron** subsystem configuration to the migrated configuration file.

To skip the addition of the **elytron** subsystem configuration, set the **subsystem.elytron.add.skip** environment property to **true**.

7.2.11. Add Socket Binding Multicast Address Expressions

The JBoss EAP 7.2 default configuration uses value expressions in the **multicast-address** attribute of `mod_cluster` socket bindings. The JBoss Server Migration Tool automatically adds these value expressions to the migrated configuration files.

To skip the addition of these expressions, set the **socket-bindings.multicast-address.add-expressions.skip** environment property to **true**.

7.2.12. Add the Load Balancer Profile

JBoss EAP 7.2 includes a default profile specifically tailored for hosts that serve as load balancers. The JBoss Server Migration Tool automatically adds and configures this profile to all migrated managed domain configurations.

To skip the addition of this profile, set the **profile.load-balancer.add.skip** environment property to **true**.

7.2.13. Add Host Excludes

The JBoss EAP 7.2 domain controller can potentially include functionality that is not supported by hosts running on older versions of the server. The **host-exclude** configuration specifies the resources that should be hidden from those older versions.

When migrating a domain controller configuration, the JBoss Server Migration Tool adds to or replaces the source server's **host-exclude** configuration with the configuration of the target JBoss EAP 7.2 server.

The JBoss Server Migration Tool automatically updates the **host-exclude** configuration and logs the results to its log file and to the console.

```
INFO Host-excludes configuration added.
```

7.2.14. Migrate Deployments

The JBoss Server Migration Tool can migrate the following types of managed domain deployment configurations.

- Deployments it references, also known as [persistent deployments](#).
- [Deployment overlays](#) it references.

The migration of a deployment consists of installing related file resources on the target server, and possibly updating the migrated configuration.

The JBoss Server Migration Tool is preconfigured to skip deployments by default when running in non-interactive mode. To enable migration of deployments, set the **`deployments.migrate-deployments.skip`** environment property to **`false`**.



IMPORTANT

Be aware that when you run the JBoss Server Migration Tool in interactive mode and enter invalid input, the resulting behavior depends on the value of the **`deployments.migrate-deployments`** environment property.

- If **`deployments.migrate-deployments.skip`** is set to **`false`** and you enter invalid input, the tool will try to migrate the deployments.
- If **`deployments.migrate-deployments.skip`** is set to **`true`** and you enter invalid input, the tool will skip the deployments migration.

To enable the migration of specific types of deployments, see the following sections.



WARNING

The JBoss Server Migration Tool does not determine whether deployed resources are compatible with the target server. This means that applications or resources might not deploy, might not work as expected, or might not work at all. Also be aware that artifacts such as JBoss EAP 6.4 `*-jms.xml` configuration files are copied without modification and can cause the JBoss EAP server to boot with errors.

Red Hat recommends that you use the Red Hat Application Migration Toolkit to analyze deployments to determine compatibility among different JBoss EAP servers. For more information, see the Red Hat Application Migration Toolkit [product documentation](#).

7.2.14.1. Migrate Persistent Deployments

To enable migration of persistent deployments when running in non-interactive mode, set the **`deployments.migrate-persistent-deployments.skip`** environment property to **`false`**.

The JBoss Server Migration Tool searches for any persistent deployment references and lists them to the console.

```
INFO [ServerMigrationTask#67] Persistent deployments found: [cmtool-helloworld3.war, cmtool-helloworld4.war, cmtool-helloworld2.war, cmtool-helloworld1.war]
```

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Persistent Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the persistent deployments. Persistent deployments are migrated only if both the

`deployments.migrate-deployments.skip` and `deployments.migrate-persistent-deployments.skip` properties are set to **false**.

Migrating Persistent Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the persistent deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if persistent deployments found are
compatible with the target server, skip persistent deployments
migration?
yes/no?
```

- Respond with **yes** to skip migration of persistent deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **no** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all persistent deployments found?
yes/no?
```

- Respond with **yes** to automatically migrate all deployments and end this part of the migration process.
- Respond with **no** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate persistent deployment 'helloworld01.war'?
yes/no?
```

- Respond with **yes** to migrate the deployment.
- Respond with **no** to remove the deployment from the migrated configuration.


```
INFO [ServerMigrationTask#68] Removed persistent deployment from
configuration /deployment=helloworld01.war
```

7.2.14.2. Migrate Deployment Overlays

The migration of deployment overlays is a fully automated process. If you have enabled migration of deployments by setting the `deployments.migrate-deployments.skip` environment property to **false**, the JBoss Server Migration Tool searches for deployment overlays referenced in the standalone server configuration that are linked to migrated deployments. It automatically migrates those that are found, removes those that are not referenced, and logs the results to its log file and to the console.

7.3. MIGRATING A JBOSS EAP 7.0 HOST CONFIGURATION TO JBOSS EAP 7.2

By default, the JBoss Server Migration Tool performs the following tasks when migrating a host server configuration from JBoss EAP 7.0 to JBoss EAP 7.2.



IMPORTANT

Migration to JBoss EAP 7.2 from JBoss EAP 7.0 is provided as Technology Preview only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

See [Technology Preview Features Support Scope](#) on the Red Hat Customer Portal for information about the support scope for Technology Preview features.

- [Migrate any referenced modules](#).
- [Migrate any referenced paths](#).
- [Add the **core-management** subsystem](#).
- [Add the **elytron** subsystem](#).
- [Migrate compatible security realms](#).
- [Add the default SSL server identity to the **ApplicationRealm**](#).

7.3.1. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a host server configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

7.3.2. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **paths.migrate-paths-requested-by-configuration.vault.skip** environment property to **true**.

7.3.3. Add the Core Management Subsystem

The JBoss EAP 7.2 **core-management** subsystem provides management-related resources, which were previously configured in the management core service. Examples of these resources include the ability to view a history of configuration changes made to the server and the ability to monitor for server lifecycle events. The JBoss Server Migration Tool automatically adds the default **core-management** subsystem configuration to the migrated configuration file.

To skip the addition of the **core-management** subsystem configuration, set the **subsystem.core-management.add.skip** environment property to **true**.

7.3.4. Add the Elytron Subsystem

The JBoss EAP 7.2 **elytron** subsystem provides a single unified security framework that can manage and configure access for both standalone servers and managed domains. It can also be used to configure security access for applications deployed to JBoss EAP servers. The JBoss Server Migration Tool automatically adds the default **elytron** subsystem configuration to the migrated configuration file.

To skip the addition of the **elytron** subsystem configuration, set the **subsystem.elytron.add.skip** environment property to **true**.

7.3.5. Migrate Compatible Security Realms

Because the JBoss EAP 7.2 security realm configurations are fully compatible with the JBoss EAP 7.0 security realm configurations, they require no update by the JBoss Server Migration Tool. However, if the **application-users.properties**, **application-roles.properties**, **mgmt-users.properties**, and **mgmt-groups.properties** files are not referenced using an absolute path, the tool copies them to the path expected by the migrated configuration file.

To skip the security realms migration, set the **security-realms.migrate-properties.skip** environment property to **true**.

7.3.6. Add the Default SSL Server Identity to the ApplicationRealm

The JBoss EAP 7.2 default configuration includes an SSL server identity for the default **ApplicationRealm** security realm. The JBoss Server Migration Tool automatically adds this identity to the migrated configuration files.

To skip the addition of this identity, set the **security-realm.ApplicationRealm.add-ssl-server-identity.skip** environment property to **true**.

CHAPTER 8. MIGRATING JBOSS EAP 7.1 CONFIGURATIONS TO JBOSS EAP 7.2

8.1. MIGRATING A JBOSS EAP 7.1 STANDALONE SERVER TO JBOSS EAP 7.2

- Remove any unsupported subsystems.
- Migrate any referenced modules.
- Migrate any referenced paths.
- Update the **infinispan** subsystem.
- Update the **jgroups** subsystem.
- Update the **undertow** subsystem.
- Add the **discovery** Subsystem.
- Add the **ee-security** Subsystem.
- Migrate compatible security realms.
- Migrate deployments.

8.1.1. Remove Unsupported Subsystems

The JBoss Server Migration Tool removes all unsupported subsystem configurations and extensions from migrated server configurations. The tool logs each subsystem and extension to its log file and to the console as it is removed.

NOTE

Any subsystem that was not supported in JBoss EAP 7.1, but was added by an administrator to that server, is also not supported in JBoss EAP 7.2 and will be removed.

To skip removal of the unsupported subsystems, set the **subsystems.remove-unsupported-subsystems.skip** environment property to **true**.

You can override the default behavior of the JBoss Server Migration Tool and specify which subsystems and extensions should be included or excluded during the migration using the following environment properties.

Property Name	Property Description
extensions.excludes	A list of module names of extensions that should never be migrated, for example, com.example.extension1,com.example.extension3 .

Property Name	Property Description
extensions.includes	A list of module names of extensions that should always be migrated, for example, com.example.extension2,com.example.extension4.
subsystems.excludes	A list of subsystem namespaces, stripped of the version, that should never be migrated, for example, urn:jboss:domain:logging, urn:jboss:domain:ejb3.
subsystems.includes	A list of subsystem namespaces, stripped of the version, that should always be migrated, for example, urn:jboss:domain:security, urn:jboss:domain:ee.

8.1.2. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a standalone server configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.
- A module referenced by the **datasource** subsystem configuration is migrated as a datasource driver module.
- A module referenced by the **ee** subsystem configuration is migrated as a global module.
- A module referenced by the **naming** subsystem configuration is migrated as an object factory module.
- A module referenced by the **messaging** subsystem configuration is migrated as a JMS bridge module.
- A module referenced by a vault configuration is migrated to the new configuration.
- Any extension that is not installed on the target configuration is migrated to the target server configuration.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

8.1.3. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as

relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **paths.migrate-paths-requested-by-configuration.vault.skip** environment property to **true**.

8.1.4. Update the Infinispan Subsystem

The JBoss Server Migration Tool updates the **infinispan** subsystem configuration to better align with the default JBoss EAP 7.2 configurations.

- It updates the module name in the Hibernate cache container configuration.

The JBoss Server Migration Tool automatically updates the **infinispan** subsystem configuration and logs the results to its log file and to the console.

You can customize the update of the **infinispan** system by setting the following environment properties.

Property Name	Property Description
subsystem.infinispan.update.skip	If set to true , skip the update of the infinispan subsystem.
subsystem.infinispan.update.fix-hibernate-cache-module-name.skip	If set to true , do not update the module name in the Hibernate cache container configuration.

8.1.5. Update the JGroups Subsystem

The JBoss Server Migration Tool updates the **jgroups** subsystem to align with the JBoss EAP 7.2 configurations.

- It replaces the **FRAG2** protocol with the **FRAG3** protocol.

Upon successful migration of the **jgroups** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem jgroups updated.
```

To skip the automatic migration of the **jgroups** subsystem, set the **subsystem.jgroups.update.skip** environment property to **true**.

8.1.6. Update the Undertow Subsystem

In addition to migrating the **web** subsystem for JBoss EAP 7.2, the JBoss Server Migration Tool updates its replacement **undertow** subsystem to add the features it supports.

- It removes the **Server** response header.

- It removes the **X-Powered-By** response header.

The JBoss Server Migration Tool automatically updates the **undertow** subsystem configuration and logs the results to its log file and to the console.

Upon successful migration of the **undertow** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem undertow updated.
```

You can customize the update of the **undertow** system by setting the following environment properties.

Property Name	Property Description
<code>subsystem.undertow.update.skip</code>	If set to true , skip the update of the undertow subsystem.

8.1.7. Add the Discovery Subsystem

The JBoss Server Migration Tool automatically adds the default **discovery** subsystem configuration to the migrated configuration file.

To skip the addition of the **discovery** subsystem configuration, set the **subsystem.discovery.add.skip** environment property to **true**.

8.1.8. Add the EE Security Subsystem

The JBoss EAP 7.2 **ee-security** subsystem provides support for [JSR 375](#) and compliance for Java EE 8 security. The JBoss Server Migration Tool automatically adds the default **ee-security** subsystem configuration to the migrated configuration file.

To skip the addition of the **ee-security** subsystem configuration, set the **subsystem.ee-security.add.skip** environment property to **true**.

8.1.9. Migrate Compatible Security Realms

Because the JBoss EAP 7.2 security realm configurations are fully compatible with the JBoss EAP 7.1 security realm configurations, they require no update by the JBoss Server Migration Tool. However, if the **application-users.properties**, **application-roles.properties**, **mgmt-users.properties**, and **mgmt-groups.properties** files are not referenced using an absolute path, the tool copies them to the path expected by the migrated configuration file.

To skip the security realms migration, set the **security-realms.migrate-properties.skip** environment property to **true**.

8.1.10. Migrate Deployments

The JBoss Server Migration Tool can migrate the following types of standalone server deployment configurations.

- Deployments it references, also known as [persistent deployments](#).

- Deployments found in directories monitored by its [deployment scanners](#).
- [Deployment overlays](#) it references.

The migration of a deployment consists of installing related file resources on the target server, and possibly updating the migrated configuration.

The JBoss Server Migration Tool is preconfigured to skip deployments by default when running in non-interactive mode. To enable migration of deployments, set the **deployments.migrate-deployments.skip** environment property to **false**.



IMPORTANT

Be aware that when you run the JBoss Server Migration Tool in interactive mode and enter invalid input, the resulting behavior depends on the value of the **deployments.migrate-deployments** environment property.

- If **deployments.migrate-deployments.skip** is set to **false** and you enter invalid input, the tool will try to migrate the deployments.
- If **deployments.migrate-deployments.skip** is set to **true** and you enter invalid input, the tool will skip the deployments migration.

To enable the migration of specific types of deployments, see the following sections.



WARNING

The JBoss Server Migration Tool does not determine whether deployed resources are compatible with the target server. This means that applications or resources might not deploy, might not work as expected, or might not work at all. Also be aware that artifacts such as JBoss EAP 6.4 *-**jms.xml** configuration files are copied without modification and can cause the JBoss EAP server to boot with errors.

Red Hat recommends that you use the Red Hat Application Migration Toolkit to analyze deployments to determine compatibility among different JBoss EAP servers. For more information, see the Red Hat Application Migration Toolkit [product documentation](#).

8.1.10.1. Migrate Persistent Deployments

To enable migration of persistent deployments when running in non-interactive mode, set the **deployments.migrate-persistent-deployments.skip** environment property to **false**.

The JBoss Server Migration Tool searches for any persistent deployment references and lists them to the console.

```
INFO [ServerMigrationTask#67] Persistent deployments found: [cmtool-
helloworld3.war, cmtool-helloworld4.war, cmtool-helloworld2.war, cmtool-
helloworld1.war]
```

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Persistent Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the persistent deployments. Persistent deployments are migrated only if both the `deployments.migrate-deployments.skip` and `deployments.migrate-persistent-deployments.skip` properties are set to **false**.

Migrating Persistent Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the persistent deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if persistent deployments found are
compatible with the target server, skip persistent deployments
migration?
yes/no?
```

- Respond with **yes** to skip migration of persistent deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **no** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all persistent deployments found?
yes/no?
```

- Respond with **yes** to automatically migrate all deployments and end this part of the migration process.
- Respond with **no** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate persistent deployment 'helloworld01.war'?
yes/no?
```

- Respond with **yes** to migrate the deployment.
- Respond with **no** to remove the deployment from the migrated configuration.

```
INFO [ServerMigrationTask#68] Removed persistent deployment from
configuration /deployment=helloworld01.war
```

8.1.10.2. Migrate Deployment Scanner Deployments

Deployment scanners, which are only used in standalone server configurations, monitor a directory for new files and manage their deployment automatically or through special deployment marker files.

To enable migration of deployments that are located in directories watched by a deployment scanner when running in non-interactive mode, set the `deployments.migrate-deployment-scanner-deployments.skip` environment property to **false**.

When migrating a standalone server configuration, the JBoss Server Migration Tool first searches for any configured deployment scanners. For each scanner found, it searches its monitored directories for deployments marked as deployed and prints the results to the console.

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Deployment Scanner Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the deployment scanner deployments. Deployment scanner deployments are migrated only if both the `deployments.migrate-deployments.skip` and `deployments.migrate-deployment-scanner-deployments.skip` properties are set to **false**.

Migrating Deployment Scanner Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the deployment scanner deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if the scanner's deployments found
are compatible with the target server, skip scanner's deployments
migration?
yes/no?
```

- Respond with **yes** to skip migration of deployment scanner deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **no** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all scanner's deployments found?
yes/no?
```

- Respond with **yes** to automatically migrate all deployments and end this part of the migration process.
- Respond with **no** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate scanner's deployment 'helloworld02.war'?
yes/no?
```

- Respond with **yes** to migrate the deployment.
- Respond with **no** to remove the deployment from the migrated configuration.

```
INFO [ServerMigrationTask#69] Resource with path
EAP_HOME/standalone/deployments/helloworld02.war migrated.
```

8.1.10.3. Migrate Deployment Overlays

The migration of deployment overlays is a fully automated process. If you have enabled migration of deployments by setting the **deployments.migrate-deployments.skip** environment property to **false**, the JBoss Server Migration Tool searches for deployment overlays referenced in the standalone server configuration that are linked to migrated deployments. It automatically migrates those that are found, removes those that are not referenced, and logs the results to its log file and to the console.

8.2. MIGRATING A JBOSS EAP 7.1 MANAGED DOMAIN TO JBOSS EAP 7.2

- [Remove any unsupported subsystems.](#)
- [Migrate any referenced modules.](#)
- [Migrate any referenced paths.](#)
- [Update the **infinispan** subsystem.](#)
- [Update the **jgroups** subsystem.](#)
- [Update the **undertow** subsystem.](#)
- [Add the **discovery** Subsystem.](#)
- [Add the **ee-security** Subsystem.](#)
- [Add the host excludes configuration.](#)
- [Migrate deployments.](#)

8.2.1. Remove Unsupported Subsystems

The JBoss Server Migration Tool removes all unsupported subsystem configurations and extensions from migrated server configurations. The tool logs each subsystem and extension to its log file and to the console as it is removed.

NOTE

Any subsystem that was not supported in JBoss EAP 7.1, but was added by an administrator to that server, is also not supported in JBoss EAP 7.2 and will be removed.

To skip removal of the unsupported subsystems, set the **subsystems.remove-unsupported-subsystems.skip** environment property to **true**.

You can override the default behavior of the JBoss Server Migration Tool and specify which subsystems and extensions should be included or excluded during the migration using the following environment properties.

Property Name	Property Description
extensions.excludes	A list of module names of extensions that should never be migrated, for example, com.example.extension1,com.example.extension3.
extensions.includes	A list of module names of extensions that should always be migrated, for example, com.example.extension2,com.example.extension4.
subsystems.excludes	A list of subsystem namespaces, stripped of the version, that should never be migrated, for example, urn:jboss:domain:logging,urn:jboss:domain:ejb3.
subsystems.includes	A list of subsystem namespaces, stripped of the version, that should always be migrated, for example, urn:jboss:domain:security,urn:jboss:domain:ee.

8.2.2. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a managed domain configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.
- A module referenced by the **datasource** subsystem configuration is migrated as a datasource driver module.
- A module referenced by the **ee** subsystem configuration is migrated as a global module.
- A module referenced by the **naming** subsystem configuration is migrated as an object factory module.
- A module referenced by the **messaging** subsystem configuration is migrated as a JMS bridge module.
- A module referenced by a vault configuration is migrated to the new configuration.
- Any extension that is not installed on the target configuration is migrated to the target server configuration.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

8.2.3. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **`paths.migrate-paths-requested-by-configuration.vault.skip`** environment property to **`true`**.

8.2.4. Update the Infinispan Subsystem

The JBoss Server Migration Tool updates the **`infinispan`** subsystem configuration to better align with the default JBoss EAP 7.2 configurations.

- It updates the module name in the Hibernate cache container configuration.

The JBoss Server Migration Tool automatically updates the **`infinispan`** subsystem configuration and logs the results to its log file and to the console.

You can customize the update of the **`infinispan`** system by setting the following environment properties.

Property Name	Property Description
<code>subsystem.infinispan.update.skip</code>	If set to <code>true</code> , skip the update of the <code>infinispan</code> subsystem.
<code>subsystem.infinispan.update.fix-hibernate-cache-module-name.skip</code>	If set to <code>true</code> , do not update the module name in the Hibernate cache container configuration.

8.2.5. Update the JGroups Subsystem

The JBoss Server Migration Tool updates the **`jgroups`** subsystem to align with the JBoss EAP 7.2 configurations.

- It replaces the **`FRAG2`** protocol with the **`FRAG3`** protocol.

Upon successful migration of the **`jgroups`** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem jgroups updated.
```

To skip the automatic migration of the **`jgroups`** subsystem, set the **`subsystem.jgroups.update.skip`** environment property to **`true`**.

8.2.6. Update the Undertow Subsystem

In addition to migrating the **`web`** subsystem for JBoss EAP 7.2, the JBoss Server Migration Tool updates

its replacement **undertow** subsystem to add the features it supports.

- It removes the **Server** response header.
- It removes the **X-Powered-By** response header.

The JBoss Server Migration Tool automatically updates the **undertow** subsystem configuration and logs the results to its log file and to the console.

Upon successful migration of the **undertow** subsystem configuration, the JBoss Server Migration Tool logs the results to its log file and to the console.

```
INFO Subsystem undertow updated.
```

You can customize the update of the **undertow** system by setting the following environment properties.

Property Name	Property Description
<code>subsystem.undertow.update.skip</code>	If set to true , skip the update of the undertow subsystem.

8.2.7. Add the Discovery Subsystem

The JBoss Server Migration Tool automatically adds the default **discovery** subsystem configuration to the migrated configuration file.

To skip the addition of the **discovery** subsystem configuration, set the **subsystem.discovery.add.skip** environment property to **true**.

8.2.8. Add the EE Security Subsystem

The JBoss EAP 7.2 **ee-security** subsystem provides support for [JSR 375](#) and compliance for Java EE 8 security. The JBoss Server Migration Tool automatically adds the default **ee-security** subsystem configuration to the migrated configuration file.

To skip the addition of the **ee-security** subsystem configuration, set the **subsystem.ee-security.add.skip** environment property to **true**.

8.2.9. Add Host Excludes

The JBoss EAP 7.2 domain controller can potentially include functionality that is not supported by hosts running on older versions of the server. The **host-exclude** configuration specifies the resources that should be hidden from those older versions.

When migrating a domain controller configuration, the JBoss Server Migration Tool adds to or replaces the source server's **host-exclude** configuration with the configuration of the target JBoss EAP 7.2 server.

The JBoss Server Migration Tool automatically updates the **host-exclude** configuration and logs the results to its log file and to the console.

```
INFO Host-excludes configuration added.
```

8.2.10. Migrate Deployments

The JBoss Server Migration Tool can migrate the following types of managed domain deployment configurations.

- Deployments it references, also known as [persistent deployments](#).
- [Deployment overlays](#) it references.

The migration of a deployment consists of installing related file resources on the target server, and possibly updating the migrated configuration.

The JBoss Server Migration Tool is preconfigured to skip deployments by default when running in non-interactive mode. To enable migration of deployments, set the **`deployments.migrate-deployments.skip`** environment property to **false**.



IMPORTANT

Be aware that when you run the JBoss Server Migration Tool in interactive mode and enter invalid input, the resulting behavior depends on the value of the **`deployments.migrate-deployments.skip`** environment property.

- If **`deployments.migrate-deployments.skip`** is set to **false** and you enter invalid input, the tool will try to migrate the deployments.
- If **`deployments.migrate-deployments.skip`** is set to **true** and you enter invalid input, the tool will skip the deployments migration.

To enable the migration of specific types of deployments, see the following sections.



WARNING

The JBoss Server Migration Tool does not determine whether deployed resources are compatible with the target server. This means that applications or resources might not deploy, might not work as expected, or might not work at all. Also be aware that artifacts such as JBoss EAP 6.4 * - **`jms.xml`** configuration files are copied without modification and can cause the JBoss EAP server to boot with errors.

Red Hat recommends that you use the Red Hat Application Migration Toolkit to analyze deployments to determine compatibility among different JBoss EAP servers. For more information, see the Red Hat Application Migration Toolkit [product documentation](#).

8.2.10.1. Migrate Persistent Deployments

To enable migration of persistent deployments when running in non-interactive mode, set the **`deployments.migrate-persistent-deployments.skip`** environment property to **false**.

The JBoss Server Migration Tool searches for any persistent deployment references and lists them to the console.

```
INFO [ServerMigrationTask#67] Persistent deployments found: [cmtool-
helloworld3.war, cmtool-helloworld4.war, cmtool-helloworld2.war, cmtool-
helloworld1.war]
```

The processing workflow then depends on whether you are running the tool in [interactive mode](#) or in [non-interactive mode](#), as described below.

Migrating Persistent Deployments in Non-interactive Mode

If you run the tool in non-interactive mode, the tool uses the preconfigured properties to determine whether to migrate the persistent deployments. Persistent deployments are migrated only if both the `deployments.migrate-deployments.skip` and `deployments.migrate-persistent-deployments.skip` properties are set to **false**.

Migrating Persistent Deployments in Interactive Mode

If you run the tool in interactive mode, the JBoss Server Migration Tool prompts you for each deployment using the following workflow.

1. After printing the persistent deployments it finds to the console, you see the following prompt.

```
This tool is not able to assert if persistent deployments found are
compatible with the target server, skip persistent deployments
migration?
yes/no?
```

- Respond with **yes** to skip migration of persistent deployments. All deployment references are removed from the migrated configuration and you end this part of the migration process.
- Respond with **no** to continue with the migration.

2. If you choose to continue, you see the following prompt.

```
Migrate all persistent deployments found?
yes/no?
```

- Respond with **yes** to automatically migrate all deployments and end this part of the migration process.
- Respond with **no** to continue with the migration.

3. If you choose to continue, you receive a prompt asking to confirm the migration for each referenced deployment.

```
Migrate persistent deployment 'helloworld01.war'?
yes/no?
```

- Respond with **yes** to migrate the deployment.
- Respond with **no** to remove the deployment from the migrated configuration.

```
INFO [ServerMigrationTask#68] Removed persistent deployment from
configuration /deployment=helloworld01.war
```

8.2.10.2. Migrate Deployment Overlays

The migration of deployment overlays is a fully automated process. If you have enabled migration of deployments by setting the **deployments.migrate-deployments.skip** environment property to **false**, the JBoss Server Migration Tool searches for deployment overlays referenced in the standalone server configuration that are linked to migrated deployments. It automatically migrates those that are found, removes those that are not referenced, and logs the results to its log file and to the console.

8.3. MIGRATING A JBOSS EAP 7.1 HOST CONFIGURATION TO JBOSS EAP 7.2

- [Migrate any referenced modules](#).
- [Migrate any referenced paths](#).
- [Migrate compatible security realms](#).

8.3.1. Migrate Referenced Modules

A configuration that is migrated from a source server to a target server might reference or depend on a module that is not installed on the target server. The JBoss Server Migration Tool detects this and automatically migrates the referenced modules, plus their dependent modules, from the source server to the target server.

A module referenced by a host server configuration is migrated using the following process.

- A module referenced by a security realm configuration is migrated as a plug-in module.

The console logs a message noting the module ID for any module that is migrated. It is possible to exclude the migration of specific modules by specifying the module ID in the **modules.excludes** environment property. See [Configuring the Migration of Modules](#) for more information.

8.3.2. Migrate Referenced Paths

A configuration that is migrated from a source server to a target server might reference or depend on file paths and directories that must also be migrated to the target server. The JBoss Server Migration Tool does not migrate absolute path references. It only migrates files or directories that are configured as relative to the source configuration. The console logs a message noting each path that is migrated.

The JBoss Server Migration Tool automatically migrates the following path references:

- Vault keystore and encrypted file's directory.

To skip the migration of referenced paths, set the **paths.migrate-paths-requested-by-configuration.vault.skip** environment property to **true**.

8.3.3. Migrate Compatible Security Realms

Because the JBoss EAP 7.2 security realm configurations are fully compatible with the JBoss EAP 7.1 security realm configurations, they require no update by the JBoss Server Migration Tool. However, if the **application-users.properties**, **application-roles.properties**, **mgmt-users.properties**, and **mgmt-groups.properties** files are not referenced using an absolute path, the tool copies them to the path expected by the migrated configuration file.

To skip the security realms migration, set the **security-realms.migrate-properties.skip** environment property to **true**.

APPENDIX A. REFERENCE MATERIAL

A.1. EXAMPLE TASK SUMMARY REPORT

The following is an example of the Task Summary report.

```

-----
Task Summary
-----

server
.....
..... SUCCESS
standalone
.....
..... SUCCESS
standalone-configurations
.....
..... SUCCESS
standalone-configuration(source=/home/username/jboss-eap-
6.4/standalone/configuration/standalone-full-ha.xml) .. SUCCESS
standalone-configuration(source=/home/username/jboss-eap-
6.4/standalone/configuration/standalone-full.xml) ..... SUCCESS
standalone-configuration(source=/home/username/jboss-eap-
6.4/standalone/configuration/standalone-ha.xml) ..... SUCCESS
standalone-configuration(source=/home/username/jboss-eap-
6.4/standalone/configuration/standalone-osgi.xml) ..... SUCCESS
standalone-configuration(source=/home/username/jboss-eap-
6.4/standalone/configuration/standalone.xml) ..... SUCCESS
domain
.....
..... SUCCESS
domain-configurations
.....
..... SUCCESS
domain-configuration(source=/home/username/jboss-eap-
6.4/domain/configuration/domain.xml) ..... SUCCESS
host-configurations
.....
..... SUCCESS
host-configuration(source=/home/username/jboss-eap-
6.4/domain/configuration/host-master.xml) ..... SUCCESS
host-configuration(source=/home/username/jboss-eap-
6.4/domain/configuration/host-slave.xml) ..... SUCCESS
host-configuration(source=/home/username/jboss-eap-
6.4/domain/configuration/host.xml) ..... SUCCESS

-----
Migration Result: SUCCESS
-----

```

A.2. EXAMPLE HTML REPORT

The following is an example of the JBoss Server Migration HTML report.

Figure A.1. Example: Overview of Sections

JBoss Server Migration Report

Summary

Start Time: Mon, 30 Oct 2017 16:13:30 UTC
Source Server: EAP 6.4.0.GA
Source Path: /home/username/jboss-eap-6.4
Target Server: JBoss EAP 7.1.0.GA
Target Path: /home/username/jboss-eap-7.1
Result: SUCCESS

Environment

baseDir: /home/username/jboss-eap-7.1/migration
deployments.migrate-deployment-scanner-deployments.processedDeploymentScannerDirs: /home/username/jboss-eap-6.4/standalone/deployments
report.html.fileName: migration-report.html
report.html.templateFileName: migration-report-template.html
report.summary.maxTaskPathSizeToDisplaySubtasks: 3
report.xml.fileName: migration-report.xml
subsystem.ee.update.setup-javaee7-default-bindings.defaultDataSourceName: ExampleDS
subsystem.ee.update.setup-javaee7-default-bindings.defaultJmsConnectionFactoryName: hornetq-ra
subsystem.logging.update.remove-console-handler.skip: true

Tasks

Executed: 664
Successful: 564
Skipped: 100
Failed: 0

server

Task Number: 1
Task Name: server
Task Path: server
Logger Name: org.jboss.migration.core.task.ServerMigrationTask#1
Result Status: SUCCESS
Subtasks: [modules.migrate-modules-requested-by-user](#)
[standalone](#)
[domain](#)

modules.migrate-modules-requested-by-user

standalone +

domain +

Figure A.2. Example: Tasks Detail Page

Tasks

Executed: 664
 Successful: 564
 Skipped: 100
 Failed: 0

server

Task Number: 1
Task Name: server
Task Path: server
Logger Name: org.jboss.migration.core.task.ServerMigrationTask#1
Result Status: SUCCESS
Subtasks: [modules.migrate-modules-requested-by-user](#)
[standalone](#)
[domain](#)

modules.migrate-modules-requested-by-user

Task Number: 2
Task Name: modules.migrate-modules-requested-by-user
Task Path: server > modules.migrate-modules-requested-by-user
Logger Name: org.jboss.migration.core.task.ServerMigrationTask#2
Result Status: SKIPPED

standalone

Task Number: 3
Task Name: standalone
Task Path: server > standalone
Logger Name: org.jboss.migration.core.task.ServerMigrationTask#3
Result Status: SUCCESS
Subtasks: [contents.standalone.migrate-content-dir](#)
[standalone-configurations](#)

contents.standalone.migrate-content-dir

standalone-configurations

standalone-configuration(source=/home/sgilda/tools/jboss-eap-6.4/standalone/configuration/standalone-full-ha.xml)

subsystems.remove-unsupported-subsystems

subsystems.remove-unsupported-subsystems.remove-unsupported-extension(module=org.jboss.as.cmp)

subsystems.remove-unsupported-subsystems.remove-unsupported-extension(module=org.jboss.as.jaxr)

subsystems.remove-unsupported-subsystems.remove-unsupported-extension(module=org.jboss.as.threads)

subsystems.remove-unsupported-subsystems.remove-unsupported-subsystem(namespace=urn:jboss:domain:cmp:1.1)

subsystems.remove-unsupported-subsystems.remove-unsupported-subsystem(namespace=urn:jboss:domain:jaxr:1.1)

A.3. EXAMPLE XML REPORT

The following is an example of the JBoss Server Migration XML report.

```

<?xml version="1.0" ?>

<server-migration-report xmlns="urn:jboss:server-migration:1.0" start-
time="Mon, 30 Oct 2017 16:13:30 UTC">
  <servers>
    <source name="EAP" version="6.4.0.GA" base-
dir="/home/username/tools/jboss-eap-6.4"/>
    <target name="JBoss EAP" version="7.1.0.GA" base-
dir="/home/username/tools/jboss-eap-7.1"/>
  </servers>
  <environment>
    <property name="baseDir" value="/home/username/tools/jboss-eap-
7.1/migration"/>
    <property name="deployments.migrate-deployment-scanner-
deployments.processedDeploymentScannerDirs"
value="/home/username/tools/jboss-eap-6.4/standalone/deployments"/>
  </environment>
</server-migration-report>

```

```

        <property name="report.html.fileName" value="migration-report.html"/>
        <property name="report.html.maxTaskPathSizeToDisplaySubtasks"
value="4"/>
        <property name="report.html.templateFileName" value="migration-report-
template.html"/>
        <property name="report.summary.maxTaskPathSizeToDisplaySubtasks"
value="3"/>
        <property name="report.xml.fileName" value="migration-report.xml"/>
        <property name="subsystem.ee.update.setup-javaee7-default-
bindings.defaultDataSourceName" value="ExampleDS"/>
        <property name="subsystem.ee.update.setup-javaee7-default-
bindings.defaultJmsConnectionFactoryName" value="hornetq-ra"/>
        <property name="subsystem.logging.update.remove-console-handler.skip"
value="true"/>
    </environment>
    <task number="1" name="server">
        <logger logger="org.jboss.migration.core.task.ServerMigrationTask#1"/>
        <result status="SUCCESS"/>
        <subtasks>
            <task number="2" name="modules.migrate-modules-requested-by-user">
                <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#2"/>
                <result status="SKIPPED"/>
            </task>
            <task number="3" name="standalone">
                <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#3"/>
                <result status="SUCCESS"/>
                <subtasks>
                    <task number="4" name="contents.standalone.migrate-content-
dir">
                        <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#4"/>
                        <result status="SKIPPED"/>
                    </task>
                    <task number="5" name="standalone-configurations">
                        <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#5"/>
                        <result status="SUCCESS"/>
                        <subtasks>
                            <task number="6" name="standalone-
configuration(source=/home/username/tools/jboss-eap-
6.4/standalone/configuration/standalone-full-ha.xml)">
                                <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#6"/>
                                <result status="SUCCESS"/>
                                <subtasks>
                                    <task number="7" name="subsystems.remove-unsupported-
subsystems">
                                        <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#7"/>
                                        <result status="SUCCESS"/>
                                        <subtasks>
                                            <task number="8" name="subsystems.remove-
unsupported-subsystems.remove-unsupported-
extension(module=org.jboss.as.cmp)">

```



```

        <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#8"/>
        <result status="SUCCESS"/>
    </task>
</subtasks>
</task>
...
<task number="644" name="hosts">
    <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#644"/>
    <result status="SUCCESS"/>
    ...
    <subtasks>
        ...
        <task number="645" name="host(name=master)">
            <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#645"/>
            <result status="SUCCESS"/>
            <subtasks>
                ...
                <task number="661" name="security-
realms.migrate-properties">
                    <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#661"/>
                    <result status="SUCCESS"/>
                    <subtasks>
                        <task number="662" name="security-
realm.ManagementRealm.migrate-properties">
                            <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#662"/>
                            <result status="SUCCESS"/>
                        </task>
                        <task number="663" name="security-
realm.ApplicationRealm.migrate-properties">
                            <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#663"/>
                            <result status="SUCCESS"/>
                        </task>
                    </subtasks>
                </task>
                <task number="664" name="security-
realm.ApplicationRealm.add-ssl-server-identity">
                    <logger
logger="org.jboss.migration.core.task.ServerMigrationTask#664"/>
                    <result status="SUCCESS"/>
                </task>
            </subtasks>
        </task>
    </subtasks>
</task>
</subtasks>
</task>
</subtasks>
</task>
</subtasks>
</task>
</subtasks>
</task>
</subtasks>
</task>

```

```
        </subtasks>
      </task>
</server-migration-report>
```

Revised on 2018-09-27 10:40:29 UTC