



OpenShift Container Platform 4.3

Installing on bare metal

Installing OpenShift Container Platform 4.3 bare metal clusters

OpenShift Container Platform 4.3 Installing on bare metal

Installing OpenShift Container Platform 4.3 bare metal clusters

Legal Notice

Copyright © 2020 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document provides instructions for installing OpenShift Container Platform 4.3 clusters on bare metal infrastructure.

Table of Contents

CHAPTER 1. INSTALLING ON BARE METAL	5
1.1. INSTALLING A CLUSTER ON BARE METAL	5
1.1.1. Prerequisites	5
1.1.2. Internet and Telemetry access for OpenShift Container Platform	5
1.1.3. Machine requirements for a cluster with user-provisioned infrastructure	6
1.1.3.1. Required machines	6
1.1.3.2. Network connectivity requirements	6
1.1.3.3. Minimum resource requirements	6
1.1.3.4. Certificate signing requests management	7
1.1.4. Creating the user-provisioned infrastructure	7
1.1.4.1. Networking requirements for user-provisioned infrastructure	7
Network topology requirements	8
Load balancers	8
1.1.4.2. User-provisioned DNS requirements	10
1.1.5. Generating an SSH private key and adding it to the agent	12
1.1.6. Obtaining the installation program	13
1.1.7. Installing the CLI by downloading the binary	14
1.1.7.1. Installing the CLI on Linux	14
1.1.7.2. Installing the CLI on Windows	15
1.1.7.3. Installing the CLI on macOS	15
1.1.8. Manually creating the installation configuration file	16
1.1.8.1. Sample install-config.yaml file for bare metal	16
1.1.8.2. Configuring the cluster-wide proxy during installation	18
1.1.9. Creating the Kubernetes manifest and Ignition config files	20
1.1.10. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines	21
1.1.10.1. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines using an ISO image	21
1.1.10.2. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines by PXE or iPXE booting	23
1.1.11. Creating the cluster	25
1.1.12. Logging in to the cluster	26
1.1.13. Approving the CSRs for your machines	26
1.1.14. Initial Operator configuration	28
1.1.14.1. Image registry removed during installation	28
1.1.14.2. Image registry storage configuration	29
1.1.14.2.1. Configuring registry storage for bare metal	29
1.1.14.2.2. Configuring storage for the image registry in non-production clusters	30
1.1.15. Completing installation on user-provisioned infrastructure	31
1.1.16. Next steps	32
1.2. INSTALLING A CLUSTER ON BARE METAL WITH NETWORK CUSTOMIZATIONS	33
1.2.1. Prerequisites	33
1.2.2. Internet and Telemetry access for OpenShift Container Platform	33
1.2.3. Machine requirements for a cluster with user-provisioned infrastructure	33
1.2.3.1. Required machines	33
1.2.3.2. Network connectivity requirements	34
1.2.3.3. Minimum resource requirements	34
1.2.3.4. Certificate signing requests management	34
1.2.4. Creating the user-provisioned infrastructure	35
1.2.4.1. Networking requirements for user-provisioned infrastructure	35
Network topology requirements	36
Load balancers	36
1.2.4.2. User-provisioned DNS requirements	38
1.2.5. Generating an SSH private key and adding it to the agent	40

1.2.6. Obtaining the installation program	41
1.2.7. Installing the CLI by downloading the binary	42
1.2.7.1. Installing the CLI on Linux	42
1.2.7.2. Installing the CLI on Windows	43
1.2.7.3. Installing the CLI on macOS	43
1.2.8. Manually creating the installation configuration file	44
1.2.8.1. Sample install-config.yaml file for bare metal	45
1.2.8.2. Network configuration parameters	46
1.2.9. Modifying advanced network configuration parameters	47
1.2.10. Cluster Network Operator configuration	49
1.2.10.1. Configuration parameters for the OpenShift SDN default CNI network provider	50
1.2.10.2. Cluster Network Operator example configuration	51
1.2.11. Creating the Ignition config files	51
1.2.12. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines	52
1.2.12.1. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines using an ISO image	52
1.2.12.2. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines by PXE or iPXE booting	54
1.2.13. Creating the cluster	56
1.2.14. Logging in to the cluster	57
1.2.15. Approving the CSRs for your machines	57
1.2.16. Initial Operator configuration	59
1.2.16.1. Image registry removed during installation	59
1.2.16.2. Image registry storage configuration	60
1.2.17. Completing installation on user-provisioned infrastructure	60
1.2.18. Next steps	62
1.3. INSTALLING A CLUSTER ON BARE METAL IN A RESTRICTED NETWORK	62
1.3.1. Prerequisites	62
1.3.2. About installations in restricted networks	63
1.3.2.1. Additional limits	63
1.3.3. Internet and Telemetry access for OpenShift Container Platform	63
1.3.4. Machine requirements for a cluster with user-provisioned infrastructure	64
1.3.4.1. Required machines	64
1.3.4.2. Network connectivity requirements	64
1.3.4.3. Minimum resource requirements	64
1.3.4.4. Certificate signing requests management	65
1.3.5. Creating the user-provisioned infrastructure	65
1.3.5.1. Networking requirements for user-provisioned infrastructure	65
Network topology requirements	66
Load balancers	66
1.3.5.2. User-provisioned DNS requirements	68
1.3.6. Generating an SSH private key and adding it to the agent	70
1.3.7. Manually creating the installation configuration file	71
1.3.7.1. Sample install-config.yaml file for bare metal	72
1.3.7.2. Configuring the cluster-wide proxy during installation	74
1.3.8. Creating the Kubernetes manifest and Ignition config files	76
1.3.9. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines	77
1.3.9.1. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines using an ISO image	77
1.3.9.2. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines by PXE or iPXE booting	79
1.3.10. Creating the cluster	81
1.3.11. Logging in to the cluster	82
1.3.12. Approving the CSRs for your machines	82
1.3.13. Initial Operator configuration	84
1.3.13.1. Image registry storage configuration	84
1.3.13.1.1. Configuring registry storage for bare metal	85

1.3.13.1.2. Configuring storage for the image registry in non-production clusters	86
1.3.14. Completing installation on user-provisioned infrastructure	86
1.3.15. Next steps	88

CHAPTER 1. INSTALLING ON BARE METAL

1.1. INSTALLING A CLUSTER ON BARE METAL

In OpenShift Container Platform version 4.3, you can install a cluster on bare metal infrastructure that you provision.



IMPORTANT

While you might be able to follow this procedure to deploy a cluster on virtualized or cloud environments, you must be aware of additional considerations for non-bare metal platforms. Review the information in the [guidelines for deploying OpenShift Container Platform on non-tested platforms](#) before you attempt to install an OpenShift Container Platform cluster in such an environment.

1.1.1. Prerequisites

- Review details about the [OpenShift Container Platform installation and update](#) processes.
- If you use a firewall, you must [configure it to allow the sites](#) that your cluster requires access to.



NOTE

Be sure to also review this site list if you are configuring a proxy.

1.1.2. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the [Red Hat OpenShift Cluster Manager \(OCM\)](#).

Once you confirm that your Red Hat OpenShift Cluster Manager inventory is correct, either maintained automatically by Telemetry or manually using OCM, [use subscription watch](#) to track your OpenShift Container Platform subscriptions at the account or multi-cluster level.

You must have internet access to:

- Access the [Red Hat OpenShift Cluster Manager](#) page to download the installation program and perform subscription management. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster.
- Access [Quay.io](#) to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



IMPORTANT

If your cluster cannot have direct internet access, you can perform a restricted network installation on some types of infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

1.1.3. Machine requirements for a cluster with user-provisioned infrastructure

For a cluster that contains user-provisioned infrastructure, you must deploy all of the required machines.

1.1.3.1. Required machines


The smallest OpenShift Container Platform clusters require the following hosts:

- One temporary bootstrap machine
- Three control plane, or master, machines
- At least two compute machines, which are also known as worker machines



NOTE

The cluster requires the bootstrap machine to deploy the OpenShift Container Platform cluster on the three control plane machines. You can remove the bootstrap machine after you install the cluster.



IMPORTANT

To maintain high availability of your cluster, use separate physical hosts for these cluster machines.

The bootstrap, control plane, and compute machines must use the Red Hat Enterprise Linux CoreOS (RHCOS) as the operating system.

Note that RHCOS is based on Red Hat Enterprise Linux 8 and inherits all of its hardware certifications and requirements. See [Red Hat Enterprise Linux technology capabilities and limits](#) .

1.1.3.2. Network connectivity requirements

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config files from the Machine Config Server. During the initial boot, the machines require either a DHCP server or that static IP addresses be set in order to establish a network connection to download their Ignition config files.

1.1.3.3. Minimum resource requirements

Each cluster machine must meet the following minimum requirements:

Machine	Operating System	vCPU	Virtual RAM	Storage
Bootstrap	RHCOS	4	16 GB	120 GB
Control plane	RHCOS	4	16 GB	120 GB
Compute	RHCOS or RHEL 7.6	2	8 GB	120 GB

1.1.3.4. Certificate signing requests management

Because your cluster has limited access to automatic machine management when you use infrastructure that you provision, you must provide a mechanism for approving cluster certificate signing requests (CSRs) after installation. The **kube-controller-manager** only approves the kubelet client CSRs. The **machine-approver** cannot guarantee the validity of a serving certificate that is requested by using kubelet credentials because it cannot confirm that the correct machine issued the request. You must determine and implement a method of verifying the validity of the kubelet serving certificate requests and approving them.

1.1.4. Creating the user-provisioned infrastructure

Before you deploy an OpenShift Container Platform cluster that uses user-provisioned infrastructure, you must create the underlying infrastructure.

Prerequisites

- Review the [OpenShift Container Platform 4.x Tested Integrations](#) page before you create the supporting infrastructure for your cluster.

Procedure

1. Configure DHCP or set static IP addresses on each node.
2. Provision the required load balancers.
3. Configure the ports for your machines.
4. Configure DNS.
5. Ensure network connectivity.

1.1.4.1. Networking requirements for user-provisioned infrastructure

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config from the Machine Config Server.

During the initial boot, the machines require either a DHCP server or that static IP addresses be set on each host in the cluster in order to establish a network connection, which allows them to download their Ignition config files.

It is recommended to use the DHCP server to manage the machines for the cluster long-term. Ensure that the DHCP server is configured to provide persistent IP addresses and host names to the cluster machines.

The Kubernetes API server, which runs on each master node after a successful cluster installation, must be able to resolve the node names of the cluster machines. If the API servers and worker nodes are in different zones, you can configure a default DNS search zone to allow the API server to resolve the node names. Another supported approach is to always refer to hosts by their fully-qualified domain names in both the node objects and all DNS requests.

You must configure the network connectivity between machines to allow cluster components to communicate. Each machine must be able to resolve the host names of all other machines in the cluster.

Table 1.1. All machines to all machines

Protocol	Port	Description
ICMP	N/A	Network reachability tests
TCP	9000-9999	Host level services, including the node exporter on ports 9100-9101 and the Cluster Version Operator on port 9099 .
	10250-10259	The default ports that Kubernetes reserves
	10256	openshift-sdn
UDP	4789	VXLAN and GENEVE
	6081	VXLAN and GENEVE
	9000-9999	Host level services, including the node exporter on ports 9100-9101 .
TCP/UDP	30000-32767	Kubernetes NodePort

Table 1.2. All machines to control plane

Protocol	Port	Description
TCP	2379-2380	etcd server, peer, and metrics ports
	6443	Kubernetes API

Network topology requirements

The infrastructure that you provision for your cluster must meet the following network topology requirements.




IMPORTANT

OpenShift Container Platform requires all nodes to have internet access to pull images for platform containers and provide telemetry data to Red Hat.

Load balancers

Before you install OpenShift Container Platform, you must provision two load balancers that meet the following requirements:

1. **API load balancer.** Provides a common endpoint for users, both human and machine, to interact with and configure the platform. Configure the following conditions:
 - Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
 - A stateless load balancing algorithm. The options vary based on the load balancer implementation.



NOTE

Session persistence is not required for the API load balancer to function properly.

Configure the following ports on both the front and back of the load balancers:

Table 1.3. API load balancer

Port	Back-end machines (pool members)	Internal	External	Description
6443	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane. You must configure the /readyz endpoint for the API server health check probe.	X	X	Kubernetes API server
22623	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane.	X		Machine Config server



NOTE

The load balancer must be configured to take a maximum of 30 seconds from the time the API server turns off the **/readyz** endpoint to the removal of the API server instance from the pool. Within the time frame after **/readyz** returns an error or becomes healthy, the endpoint must have been removed or added. Probing every 5 or 10 seconds, with two successful requests to become healthy and three to become unhealthy, are well-tested values.

2. **Application Ingress load balancer.** Provides an Ingress point for application traffic flowing in from outside the cluster. Configure the following conditions:
 - Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
 - A connection-based or session-based persistence is recommended, based on the options available and types of applications that will be hosted on the platform.


Configure the following ports on both the front and back of the load balancers:

Table 1.4. Application Ingress load balancer

Port	Back-end machines (pool members)	Internal	External	Description
443	The machines that run the Ingress router pods, compute, or worker, by default.	X	X	HTTPS traffic
80	The machines that run the Ingress router pods, compute, or worker by default.	X	X	HTTP traffic

TIP

If the true IP address of the client can be seen by the load balancer, enabling source IP-based session persistence can improve performance for applications that use end-to-end TLS encryption.



NOTE


A working configuration for the Ingress router is required for an OpenShift Container Platform cluster. You must configure the Ingress router after the control plane initializes.

1.1.4.2. User-provisioned DNS requirements

The following DNS records are required for an OpenShift Container Platform cluster that uses user-provisioned infrastructure. In each record, **<cluster_name>** is the cluster name and **<base_domain>** is the cluster base domain that you specify in the **install-config.yaml** file. A complete DNS record takes the form: **<component>.<cluster_name>.<base_domain>..**

Table 1.5. Required DNS records

Component	Record	Description
Kubernetes API	api.<cluster_name>.<base_domain>..	This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.

Component	Record	Description
	api-int.<cluster_name>.<base_domain>.	<p>This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable from all the nodes within the cluster.</p> <div data-bbox="1038 517 1147 987" style="background-color: black; color: white; padding: 5px; display: inline-block; vertical-align: top;">  </div> <p>IMPORTANT</p> <p>The API server must be able to resolve the worker nodes by the host names that are recorded in Kubernetes. If it cannot resolve the node names, proxied API calls can fail, and you cannot retrieve logs from Pods.</p>
Routes	*.apps.<cluster_name>.<base_domain>.	<p>A wildcard DNS A/AAAA or CNAME record that points to the load balancer that targets the machines that run the Ingress router pods, which are the worker nodes by default. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.</p>
etcd	etcd-<index>.<cluster_name>.<base_domain>.	<p>OpenShift Container Platform requires DNS A/AAAA records for each etcd instance to point to the control plane machines that host the instances. The etcd instances are differentiated by <index> values, which start with 0 and end with n-1, where n is the number of control plane machines in the cluster. The DNS record must resolve to an unicast IPv4 address for the control plane machine, and the records must be resolvable from all the nodes in the cluster.</p>

Component	Record	Description
	<code>_etcd-server-ssl._tcp.<cluster_name>.<base_domain>.</code>	<p>For each control plane machine, OpenShift Container Platform also requires a SRV DNS record for etcd server on that machine with priority 0, weight 10 and port 2380. A cluster that uses three control plane machines requires the following records:</p> <pre># _service._proto.name. TTL class SRV priority weight port target. _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 0.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 1.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 2.<cluster_name>. <base_domain></pre>

1.1.5. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



NOTE

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's `~/.ssh/authorized_keys` list.



NOTE

You must use a local key, not one that you configured with platform-specific approaches such as [AWS key pairs](#).

Procedure

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N "" \
-f <path>/<file_name> 1
```

- 1 Specify the path and file name, such as `~/.ssh/id_rsa`, of the SSH key. Do not specify an existing SSH key, as it will be overwritten.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1
Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```

- 1 Specify the path and file name for your SSH private key, such as `~/.ssh/id_rsa`

Next steps

- When you install OpenShift Container Platform, provide the SSH public key to the installation program. If you install a cluster on infrastructure that you provision, you must provide this key to your cluster's machines.

1.1.6. Obtaining the installation program


Before you install OpenShift Container Platform, download the installation file on a local computer.

Prerequisites


- You must install the cluster from a computer that uses Linux or macOS.
- You need 500 MB of local disk space to download the installation program.

Procedure

1. Access the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.
2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.

**IMPORTANT**

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.

**IMPORTANT**

Deleting the files created by the installation program does not remove your cluster, even if the cluster failed during installation. You must complete the OpenShift Container Platform uninstallation procedures outlined for your specific cloud provider to remove your cluster entirely.

3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:

```
$ tar xvf <installation_program>.tar.gz
```

4. From the [Pull Secret](#) page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a **.txt** file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

1.1.7. Installing the CLI by downloading the binary

You can install the OpenShift CLI (**oc**) in order to interact with OpenShift Container Platform from a command-line interface. You can install **oc** on Linux, Windows, or macOS.

**IMPORTANT**

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

1.1.7.1. Installing the CLI on Linux

You can install the OpenShift CLI (**oc**) binary on Linux by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.
2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **Linux** from the drop-down menu and click **Download command-line tools**.
4. Unpack the archive:

```
$ tar xvzf <file>
```

5. Place the **oc** binary in a directory that is on your **PATH**. To check your **PATH**, execute the following command:

```
$ echo $PATH
```

After you install the CLI, it is available using the **oc** command:

```
$ oc <command>
```

1.1.7.2. Installing the CLI on Windows

You can install the OpenShift CLI (**oc**) binary on Windows by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.
2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **Windows** from the drop-down menu and click **Download command-line tools**.
4. Unzip the archive with a ZIP program.
5. Move the **oc** binary to a directory that is on your **PATH**.
To check your **PATH**, open the command prompt and execute the following command:

```
C:\> path
```

After you install the CLI, it is available using the **oc** command:

```
C:\> oc <command>
```

1.1.7.3. Installing the CLI on macOS

You can install the OpenShift CLI (**oc**) binary on macOS by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.
2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **MacOS** from the drop-down menu and click **Download command-line tools**.
4. Unpack and unzip the archive.
5. Move the **oc** binary to a directory on your PATH.
To check your **PATH**, open a terminal and execute the following command:

```
$ echo $PATH
```

After you install the CLI, it is available using the **oc** command:

```
$ oc <command>
```

1.1.8. Manually creating the installation configuration file

For installations of OpenShift Container Platform that use user-provisioned infrastructure, you must manually generate your installation configuration file.

Prerequisites

- Obtain the OpenShift Container Platform installation program and the access token for your cluster.

Procedure

1. Create an installation directory to store your required installation assets in:

```
$ mkdir <installation_directory>
```



IMPORTANT

You must create a directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.


2. Customize the following **install-config.yaml** file template and save it in the **<installation_directory>**.



NOTE

You must name this configuration file **install-config.yaml**.

3. Back up the **install-config.yaml** file so that you can use it to install multiple clusters.



IMPORTANT

The **install-config.yaml** file is consumed during the next step of the installation process. You must back it up now.

1.1.8.1. Sample install-config.yaml file for bare metal

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.

```
apiVersion: v1
baseDomain: example.com 1
compute:
- hyperthreading: Enabled 2 3
  name: worker
```

```

replicas: 0 4
controlPlane:
  hyperthreading: Enabled 5 6
  name: master 7
  replicas: 3 8
metadata:
  name: test 9
networking:
  clusterNetwork:
  - cidr: 10.128.0.0/14 10
    hostPrefix: 23 11
  networkType: OpenShiftSDN
  serviceNetwork: 12
  - 172.30.0.0/16
platform:
  none: {} 13
fips: false 14
pullSecret: '{"auths": ...}' 15
sshKey: 'ssh-ed25519 AAAA...' 16

```

- 1 The base domain of the cluster. All DNS records must be sub-domains of this base and include the cluster name.
- 2 5 The **controlPlane** section is a single mapping, but the compute section is a sequence of mappings. To meet the requirements of the different data structures, the first line of the **compute** section must begin with a hyphen, -, and the first line of the **controlPlane** section must not. Although both sections currently define a single machine pool, it is possible that future versions of OpenShift Container Platform will support defining multiple compute pools during installation. Only one control plane pool is used.
- 3 6 7 Whether to enable or disable simultaneous multithreading, or **hyperthreading**. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores. You can disable it by setting the parameter value to **Disabled**. If you disable simultaneous multithreading in some cluster machines, you must disable it in all cluster machines.



IMPORTANT

If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.

- 4 You must set the value of the **replicas** parameter to **0**. This parameter controls the number of workers that the cluster creates and manages for you, which are functions that the cluster does not perform when you use user-provisioned infrastructure. You must manually deploy worker machines for the cluster to use before you finish installing OpenShift Container Platform.
- 8 The number of control plane machines that you add to the cluster. Because the cluster uses this values as the number of etcd endpoints in the cluster, the value must match the number of control plane machines that you deploy.
- 9 The cluster name that you specified in your DNS records.
- 10 A block of IP addresses from which Pod IP addresses are allocated. This block must not overlap with existing physical networks. These IP addresses are used for the Pod network. If you need to access the Pods from an external network, you must configure load balancers and routers to

manage the traffic.

- 11 The subnet prefix length to assign to each individual node. For example, if **hostPrefix** is set to **23**, then each node is assigned a **/23** subnet out of the given **cidr**, which allows for 510 ($2^{(32 - 23)} - 2$) pod IPs addresses. If you are required to provide access to nodes from an external network, configure load balancers and routers to manage the traffic.
- 12 The IP address pool to use for service IP addresses. You can enter only one IP address pool. If you need to access the services from an external network, configure load balancers and routers to manage the traffic.
- 13 You must set the platform to **none**. You cannot provide additional platform configuration variables for bare metal infrastructure.
- 14 Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the cryptography modules that are provided with RHCOS instead.
- 15 The pull secret that you obtained from the [Pull Secret](#) page on the Red Hat OpenShift Cluster Manager site. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.
- 16 The public portion of the default SSH key for the **core** user in Red Hat Enterprise Linux CoreOS (RHCOS).




NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

1.1.8.2. Configuring the cluster-wide proxy during installation

Production environments can deny direct access to the Internet and instead have an HTTP or HTTPS proxy available. You can configure a new OpenShift Container Platform cluster to use a proxy by configuring the proxy settings in the **install-config.yaml** file.



NOTE

For bare metal installations, if you do not assign node IP addresses from the range that is specified in the **networking.machineCIDR** field in the **install-config.yaml** file, you must include them in the **proxy.noProxy** field.

Prerequisites

- An existing **install-config.yaml** file.
- Review the sites that your cluster requires access to and determine whether any need to bypass the proxy. By default, all cluster egress traffic is proxied, including calls to hosting cloud provider APIs. Add sites to the Proxy object's **spec.noProxy** field to bypass the proxy if necessary.



NOTE

The Proxy object's **status.noProxy** field is populated by default with the instance metadata endpoint (**169.254.169.254**) and with the values of the **networking.machineCIDR**, **networking.clusterNetwork.cidr**, and **networking.serviceNetwork[]** fields from your installation configuration.

Procedure

1. Edit your **install-config.yaml** file and add the proxy settings. For example:

```
apiVersion: v1
baseDomain: my.domain.com
proxy:
  httpProxy: http://<username>:<pswd>@<ip>:<port> 1
  httpsProxy: http://<username>:<pswd>@<ip>:<port> 2
  noProxy: example.com 3
  additionalTrustBundle: | 4
    -----BEGIN CERTIFICATE-----
    <MY_TRUSTED_CA_CERT>
    -----END CERTIFICATE-----
  ...
```

- 1 A proxy URL to use for creating HTTP connections outside the cluster. The URL scheme must be **http**. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must not specify an **httpProxy** value.
- 2 A proxy URL to use for creating HTTPS connections outside the cluster. If this field is not specified, then **httpProxy** is used for both HTTP and HTTPS connections. The URL scheme must be **http**; **https** is currently not supported. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must not specify an **httpsProxy** value.
- 3 A comma-separated list of destination domain names, domains, IP addresses, or other network CIDRs to exclude proxying. Preface a domain with **.** to include all subdomains of that domain. Use ***** to bypass proxy for all destinations.
- 4 If provided, the installation program generates a ConfigMap that is named **user-ca-bundle** in the **openshift-config** namespace that contains one or more additional CA certificates that are required for proxying HTTPS connections. The Cluster Network Operator then creates a **trusted-ca-bundle** ConfigMap that merges these contents with the Red Hat Enterprise Linux CoreOS (RHCOS) trust bundle, and this ConfigMap is referenced in the Proxy object's **trustedCA** field. The **additionalTrustBundle** field is required unless the proxy's identity certificate is signed by an authority from the RHCOS trust bundle. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must provide the MITM CA certificate.




NOTE

The installation program does not support the proxy **readinessEndpoints** field.

2. Save the file and reference it when installing OpenShift Container Platform.

The installation program creates a cluster-wide proxy that is named **cluster** that uses the proxy settings in the provided **install-config.yaml** file. If no proxy settings are provided, a **cluster** Proxy object is still created, but it will have a nil **spec**.



NOTE

Only the Proxy object named **cluster** is supported, and no additional proxies can be created.

1.1.9. Creating the Kubernetes manifest and Ignition config files

Because you must modify some cluster definition files and manually start the cluster machines, you must generate the Kubernetes manifest and Ignition config files that the cluster needs to make its machines.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must complete your cluster installation and keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

Prerequisites

- Obtain the OpenShift Container Platform installation program.
- Create the **install-config.yaml** installation configuration file.

Procedure

1. Generate the Kubernetes manifests for the cluster:


```
$ ./openshift-install create manifests --dir=<installation_directory> 1
```

```
INFO Consuming Install Config from target directory
WARNING Making control-plane schedulable by setting MastersSchedulable to true for
Scheduler cluster settings
```

- 1** For **<installation_directory>**, specify the installation directory that contains the **install-config.yaml** file you created.

Because you create your own compute machines later in the installation process, you can safely ignore this warning.

2. Modify the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** Kubernetes manifest file to prevent Pods from being scheduled on the control plane machines:
 - a. Open the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** file.
 - b. Locate the **mastersSchedulable** parameter and set its value to **False**.
 - c. Save and exit the file.

**NOTE**

Currently, due to a [Kubernetes limitation](#), router Pods running on control plane machines will not be reachable by the ingress load balancer. This step might not be required in a future minor version of OpenShift Container Platform.

3. Obtain the Ignition config files:

```
$ ./openshift-install create ignition-configs --dir=<installation_directory> 1
```

- 1 For **<installation_directory>**, specify the same installation directory.

The following files are generated in the directory:

```
.
├── auth
│   ├── kubeadmin-password
│   └── kubeconfig
├── bootstrap.ign
├── master.ign
├── metadata.json
└── worker.ign
```

1.1.10. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines

Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. Follow either the steps to use an ISO image or network PXE booting to create the machines.

1.1.10.1. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines using an ISO image

Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. You can use an ISO image to create the machines.

Prerequisites

- Obtain the Ignition config files for your cluster.
- Have access to an HTTP server that you can access from your computer and that the machines that you create can access.

Procedure

1. Upload the control plane, compute, and bootstrap Ignition config files that the installation program created to your HTTP server. Note the URLs of these files.
2. Obtain the RHCOS images that are required for your preferred method of installing operating system instances from the [Product Downloads](#) page on the Red Hat customer portal or the [RHCOS image mirror](#) page.



IMPORTANT

The RHCOS images might not change with every release of OpenShift Container Platform. You must download images with the highest version that is less than or equal to the OpenShift Container Platform version that you install. Use the image versions that match your OpenShift Container Platform version if they are available.


You must download the ISO file and the RAW disk file. Those file names resemble the following examples:

- ISO: **rhcos-<version>-installer.<architecture>.iso**
 - Compressed metal RAW: **rhcos-<version>-metal.<architecture>.raw.gz**
3. Upload either the RAW RHCOS image file to your HTTP server and note its URL.
 4. Use the ISO to start the RHCOS installation. Use one of the following installation options:
 - Burn the ISO image to a disk and boot it directly.
 - Use ISO redirection via a LOM interface.
 5. After the instance boots, press the **TAB** or **E** key to edit the kernel command line.
 6. Add the parameters to the kernel command line:

```
coreos.inst=yes
coreos.inst.install_dev=sda 1
coreos.inst.image_url=<image_URL> 2
coreos.inst.ignition_url=http://example.com/config.ign 3
ip=<dhcp or static IP address> 4 5
```

- 1 Specify the block device of the system to install to.
- 2 Specify the URL of the RAW image that you uploaded to your server.
- 3 Specify the URL of the Ignition config file for this machine type.
- 4 Set **ip=dhcp** or set an individual static IP address (**ip=**) and DNS server (**nameserver=**) on each node. For example, setting **ip=10.10.10.2::10.10.10.254:255.255.255.0:core0.example.com:enp1s0:none nameserver=4.4.4.41** sets:
 - Node's IP address to **10.10.10.2**
 - Gateway address to **10.10.10.254**
 - Netmask to **255.255.255.0**
 - Hostname to **core0.example.com**
 - The DNS server address to **4.4.4.41**
- 5 If you use multiple network interfaces or DNS servers, you can further customize the IP address configuration in the following ways:

- If your system has multiple network interfaces, you can add multiple IP address configurations by specifying multiple **ip=** entries.
 - If your system has multiple network interfaces, you can use a combination of DHCP and static IP configurations. You must specify the interface to use, for example **ip=enp1s0:dhcp**
ip=10.10.10.2::10.10.10.254:255.255.255.0:core0.example.com:enp2s0:none.
 - You can provide multiple DNS servers by adding a **nameserver=** entry for each server, such as **nameserver=1.1.1.1 nameserver=8.8.8.8**.
7. Press Enter to complete the installation. After RHCOS installs, the system reboots. After the system reboots, it applies the Ignition config file that you specified.
 8. Continue to create the machines for your cluster.



IMPORTANT

You must create the bootstrap and control plane machines at this time. Because some pods are deployed on compute machines by default, also create at least two compute machines before you install the cluster.

1.1.10.2. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines by PXE or iPXE booting


Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. You can use PXE or iPXE booting to create the machines.

Prerequisites

- Obtain the Ignition config files for your cluster.
- Configure suitable PXE or iPXE infrastructure.
- Have access to an HTTP server that you can access from your computer.

Procedure

1. Upload the master, worker, and bootstrap Ignition config files that the installation program created to your HTTP server. Note the URLs of these files.
2. Obtain the RHCOS ISO image, compressed metal RAW image, **kernel** and **initramfs** files from the [Product Downloads](#) page on the Red Hat customer portal or the [RHCOS image mirror](#) page.



IMPORTANT

The RHCOS images might not change with every release of OpenShift Container Platform. You must download images with the highest version that is less than or equal to the OpenShift Container Platform version that you install. Use the image versions that match your OpenShift Container Platform version if they are available.

The file names contain the OpenShift Container Platform version number. They resemble the following examples:

- ISO: **rhcos-`<version>`-installer.`<architecture>`.iso**
 - Compressed metal RAW image: **rhcos-`<version>`metal.`<architecture>`.raw.gz**
 - **kernel: rhcos-`<version>`-installer-kernel-`<architecture>`**
 - **initramfs: rhcos-`<version>`-installer-initramfs.`<architecture>`.img**
3. Upload the compressed metal RAW image and the **kernel** and **initramfs** files to your HTTP server.
 4. Configure the network boot infrastructure so that the machines boot from their local disks after RHCOS is installed on them.
 5. Configure PXE or iPXE installation for the RHCOS images.
Modify one of the following example menu entries for your environment and verify that the image and Ignition files are properly accessible:

- For PXE:

```

DEFAULT pxeboot
TIMEOUT 20
PROMPT 0
LABEL pxeboot
  KERNEL http://<HTTP_server>/rhcos-<version>-installer-kernel-<architecture> 1
  APPEND ip=dhcp rd.neednet=1 initrd=http://<HTTP_server>/rhcos-<version>-installer-
initramfs.<architecture>.img console=tty0 console=ttyS0 coreos.inst=yes
coreos.inst.install_dev=sda coreos.inst.image_url=http://<HTTP_server>/rhcos-
<version>-metal.<architecture>.raw.gz
coreos.inst.ignition_url=http://<HTTP_server>/bootstrap.ign 2 3

```

- 1** Specify the location of the **kernel** file that you uploaded to your HTTP server.
- 2** If you use multiple NICs, specify a single interface in the **ip** option. For example, to use DHCP on a NIC that is named **eno1**, set **ip=eno1:dhcp**.
- 3** Specify locations of the RHCOS files that you uploaded to your HTTP server. The **initrd** parameter value is the location of the **initramfs** file, the **coreos.inst.image_url** parameter value is the location of the compressed metal RAW image, and the **coreos.inst.ignition_url** parameter value is the location of the bootstrap Ignition config file.

- For iPXE:


```

kernel http://<HTTP_server>/rhcos-<version>-installer-kernel-<architecture> ip=dhcp
rd.neednet=1 initrd=http://<HTTP_server>/rhcos-<version>-installer-initramfs.
<architecture>.img console=tty0 console=ttyS0 coreos.inst=yes
coreos.inst.install_dev=sda coreos.inst.image_url=http://<HTTP_server>/rhcos-
<version>-metal.<architecture>.raw.gz
coreos.inst.ignition_url=http://<HTTP_server>/bootstrap.ign 1 2
initrd http://<HTTP_server>/rhcos-<version>-installer-initramfs.<architecture>.img 3
boot

```

- 1 Specify locations of the RHCOS files that you uploaded to your HTTP server. The **kernel** parameter value is the location of the **kernel** file, the **initrd** parameter value is the location of the **initramfs** file, the **coreos.inst.image_url** parameter value is the location of the compressed metal RAW image, and the **coreos.inst.ignition_url** parameter value is the location of the bootstrap Ignition config file.
- 2 If you use multiple NICs, specify a single interface in the **ip** option. For example, to use DHCP on a NIC that is named **eno1**, set **ip=eno1:dhcp**.
- 3 Specify the location of the **initramfs** file that you uploaded to your HTTP server.

6. Continue to create the machines for your cluster.



IMPORTANT

You must create the bootstrap and control plane machines at this time. Because some pods are deployed on compute machines by default, also create at least two compute machine before you install the cluster.

1.1.11. Creating the cluster

To create the OpenShift Container Platform cluster, you wait for the bootstrap process to complete on the machines that you provisioned by using the Ignition config files that you generated with the installation program.

Prerequisites

- Create the required infrastructure for the cluster.
- You obtained the installation program and generated the Ignition config files for your cluster.
- You used the Ignition config files to create RHCOS machines for your cluster.
- Your machines have direct internet access.

Procedure


1. Monitor the bootstrap process:

```
$ ./openshift-install --dir=<installation_directory> wait-for bootstrap-complete \ 1
--log-level=info 2
INFO Waiting up to 30m0s for the Kubernetes API at https://api.test.example.com...
INFO API v1.16.2 up
INFO Waiting up to 30m0s for bootstrapping to complete...
INFO It is now safe to remove the bootstrap resources
```

- 1 For **<installation_directory>**, specify the path to the directory that you stored the installation files in.
- 2 To view different installation details, specify **warn**, **debug**, or **error** instead of **info**.

The command succeeds when the Kubernetes API server signals that it has been bootstrapped on the control plane machines.

2. After bootstrap process is complete, remove the bootstrap machine from the load balancer.



IMPORTANT

You must remove the bootstrap machine from the load balancer at this point. You can also remove or reformat the machine itself.

1.1.12. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

Prerequisites

- Deploy an OpenShift Container Platform cluster.
- Install the **oc** CLI.

Procedure

1. Export the **kubeadmin** credentials:

```
$ export KUBECONFIG=<installation_directory>/auth/kubeconfig 1
```

- 1** For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

2. Verify you can run **oc** commands successfully using the exported configuration:

```
$ oc whoami
system:admin
```

1.1.13. Approving the CSRs for your machines

When you add machines to a cluster, two pending certificates signing request (CSRs) are generated for each machine that you added. You must confirm that these CSRs are approved or, if necessary, approve them yourself.

Prerequisites

- You added machines to your cluster.

Procedure

1. Confirm that the cluster recognizes the machines:

```
$ oc get nodes

NAME     STATUS    ROLES    AGE   VERSION
master-0 Ready     master   63m   v1.16.2
```

```

master-1 Ready   master 63m v1.16.2
master-2 Ready   master 64m v1.16.2
worker-0 NotReady worker 76s v1.16.2
worker-1 NotReady worker 70s v1.16.2

```

The output lists all of the machines that you created.

- Review the pending certificate signing requests (CSRs) and ensure that you see a client and server request with **Pending** or **Approved** status for each machine that you added to the cluster:

```

$ oc get csr

NAME          AGE   REQUESTOR                                 CONDITION
csr-8b2br     15m   system:serviceaccount:openshift-machine-config-operator:node-
bootstrapper Pending 1
csr-8vnps     15m   system:serviceaccount:openshift-machine-config-operator:node-
bootstrapper Pending
csr-bfd72     5m26s system:node:ip-10-0-50-126.us-east-2.compute.internal
Pending 2
csr-c57lv     5m26s system:node:ip-10-0-95-157.us-east-2.compute.internal
Pending
...

```

- A client request CSR.
- A server request CSR.

In this example, two machines are joining the cluster. You might see more approved CSRs in the list.

- If the CSRs were not approved, after all of the pending CSRs for the machines you added are in **Pending** status, approve the CSRs for your cluster machines:



NOTE

Because the CSRs rotate automatically, approve your CSRs within an hour of adding the machines to the cluster. If you do not approve them within an hour, the certificates will rotate, and more than two certificates will be present for each node. You must approve all of these certificates. After you approve the initial CSRs, the subsequent node client CSRs are automatically approved by the cluster **kube-controller-manager**. You must implement a method of automatically approving the kubelet serving certificate requests.

- To approve them individually, run the following command for each valid CSR:

```
$ oc adm certificate approve <csr_name> 1
```

- <csr_name>** is the name of a CSR from the list of current CSRs.

- To approve all pending CSRs, run the following command:

```
$ oc get csr -o go-template='{{range .items}}{{if not .status}}{{.metadata.name}}{\n"}\n{{end}}\n{{end}}' | xargs oc adm certificate approve
```

1.1.14. Initial Operator configuration

After the control plane initializes, you must immediately configure some Operators so that they all become available.

Prerequisites

- Your control plane has initialized.

Procedure

- Watch the cluster components come online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED	SINCE
authentication	4.3.0	True	False	False	69s
cloud-credential	4.3.0	True	False	False	12m
cluster-autoscaler	4.3.0	True	False	False	11m
console	4.3.0	True	False	False	46s
dns	4.3.0	True	False	False	11m
image-registry	4.3.0	True	False	False	5m26s
ingress	4.3.0	True	False	False	5m36s
kube-apiserver	4.3.0	True	False	False	8m53s
kube-controller-manager	4.3.0	True	False	False	7m24s
kube-scheduler	4.3.0	True	False	False	12m
machine-api	4.3.0	True	False	False	12m
machine-config	4.3.0	True	False	False	7m36s
marketplace	4.3.0	True	False	False	7m54m
monitoring	4.3.0	True	False	False	7h54s
network	4.3.0	True	False	False	5m9s
node-tuning	4.3.0	True	False	False	11m
openshift-apiserver	4.3.0	True	False	False	11m
openshift-controller-manager	4.3.0	True	False	False	5m943s
openshift-samples	4.3.0	True	False	False	3m55s
operator-lifecycle-manager	4.3.0	True	False	False	11m
operator-lifecycle-manager-catalog	4.3.0	True	False	False	11m
service-ca	4.3.0	True	False	False	11m
service-catalog-apiserver	4.3.0	True	False	False	5m26s
service-catalog-controller-manager	4.3.0	True	False	False	5m25s
storage	4.3.0	True	False	False	5m30s

- Configure the Operators that are not available.

1.1.14.1. Image registry removed during installation

On platforms that do not provide shareable object storage, the OpenShift Image Registry Operator bootstraps itself as **Removed**. This allows **openshift-installer** to complete installations on these platform types.

After installation, you must edit the Image Registry Operator configuration to switch the **ManagementState** from **Removed** to **Managed**.



NOTE

The Prometheus console provides an **ImageRegistryRemoved** alert, for example:

"Image Registry has been removed. **ImageStreamTags**, **BuildConfigs** and **DeploymentConfigs** which reference **ImageStreamTags** may not work as expected. Please configure storage and update the config to **Managed** state by editing `configs.imageregistry.operator.openshift.io`."

1.1.14.2. Image registry storage configuration

The **image-registry** Operator is not initially available for platforms that do not provide default storage. After installation, you must configure your registry to use storage so the Registry Operator is made available.

Instructions for both configuring a PersistentVolume, which is required for production clusters, and for configuring an empty directory as the storage location, which is available for only non-production clusters, are shown.

1.1.14.2.1. Configuring registry storage for bare metal


As a cluster administrator, following installation you must configure your registry to use storage.

Prerequisites

- Cluster administrator permissions.
- A cluster on bare metal.
- Provision persistent storage for your cluster, such as Red Hat OpenShift Container Storage. To deploy a private image registry, your storage must provide ReadWriteMany access mode.
- Must have "100Gi" capacity.

Procedure

1. To configure your registry to use storage, change the **spec.storage.pvc** in the **configs.imageregistry/cluster** resource.



NOTE

When using shared storage such as NFS, it is strongly recommended to use the **supplementalGroups** strategy, which dictates the allowable supplemental groups for the Security Context, rather than the **fsGroup** ID. Refer to the **NFS Group IDs** documentation for details.

2. Verify you do not have a registry Pod:

```
$ oc get pod -n openshift-image-registry
```

**NOTE**

- If the storage type is **emptyDIR**, the replica number cannot be greater than **1**.
- If the storage type is **NFS**, you must enable the **no_wdelay** and **root_squash** mount options. For example:

```
# cat /etc/exports
/mnt/data *(rw,sync,no_wdelay,root_squash,insecure,fsid=0)
sh-4.3# exportfs -rv
exporting */mnt/data
```

3. Check the registry configuration:

```
$ oc edit configs.imageregistry.operator.openshift.io

storage:
pvc:
claim:
```

Leave the **claim** field blank to allow the automatic creation of an **image-registry-storage** PVC.

4. Check the **clusteroperator** status:

```
$ oc get clusteroperator image-registry
```

1.1.14.2.2. Configuring storage for the image registry in non-production clusters

You must configure storage for the image registry Operator. For non-production clusters, you can set the image registry to an empty directory. If you do so, all images are lost if you restart the registry.

Procedure

- To set the image registry storage to an empty directory:

```
$ oc patch configs.imageregistry.operator.openshift.io cluster --type merge --patch '{"spec": {"storage":{"emptyDir":{}}}'
```

**WARNING**

Configure this option for only non-production clusters.

If you run this command before the Image Registry Operator initializes its components, the **oc patch** command fails with the following error:

```
Error from server (NotFound): configs.imageregistry.operator.openshift.io "cluster" not found
```

Wait a few minutes and run the command again.

1.1.15. Completing installation on user-provisioned infrastructure

After you complete the Operator configuration, you can finish installing the cluster on infrastructure that you provide.

Prerequisites

- Your control plane has initialized.
- You have completed the initial Operator configuration.

Procedure

1. Confirm that all the cluster components are online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED	SINCE
authentication	4.3.0	True	False	False	10m
cloud-credential	4.3.0	True	False	False	22m
cluster-autoscaler	4.3.0	True	False	False	21m
console	4.3.0	True	False	False	10m
dns	4.3.0	True	False	False	21m
image-registry	4.3.0	True	False	False	16m
ingress	4.3.0	True	False	False	16m
kube-apiserver	4.3.0	True	False	False	19m
kube-controller-manager	4.3.0	True	False	False	18m
kube-scheduler	4.3.0	True	False	False	22m
machine-api	4.3.0	True	False	False	22m
machine-config	4.3.0	True	False	False	18m
marketplace	4.3.0	True	False	False	18m
monitoring	4.3.0	True	False	False	18m
network	4.3.0	True	False	False	16m
node-tuning	4.3.0	True	False	False	21m
openshift-apiserver	4.3.0	True	False	False	21m
openshift-controller-manager	4.3.0	True	False	False	17m
openshift-samples	4.3.0	True	False	False	14m
operator-lifecycle-manager	4.3.0	True	False	False	21m
operator-lifecycle-manager-catalog	4.3.0	True	False	False	21m
service-ca	4.3.0	True	False	False	21m
service-catalog-apiserver	4.3.0	True	False	False	16m
service-catalog-controller-manager	4.3.0	True	False	False	16m
storage	4.3.0	True	False	False	16m

When all of the cluster Operators are **AVAILABLE**, you can complete the installation.

2. Monitor for cluster completion:

```
$ ./openshift-install --dir=<installation_directory> wait-for install-complete 1
INFO Waiting up to 30m0s for the cluster to initialize...
```

- 1 For `<installation_directory>`, specify the path to the directory that you stored the installation files in.

The command succeeds when the Cluster Version Operator finishes deploying the OpenShift Container Platform cluster from Kubernetes API server.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

3. Confirm that the Kubernetes API server is communicating with the Pods.
 - a. To view a list of all Pods, use the following command:

```
$ oc get pods --all-namespaces
```

NAMESPACE	NAME	READY	STATUS
RESTARTS	AGE		
openshift-apiserver-operator	openshift-apiserver-operator-85cb746d55-zqhs8	1/1	Running
1	9m		
openshift-apiserver	apiserver-67b9g	1/1	Running
3m			
openshift-apiserver	apiserver-ljcmx	1/1	Running
1m			
openshift-apiserver	apiserver-z25h4	1/1	Running
2m			
openshift-authentication-operator	authentication-operator-69d5d8bf84-vh2n8	1/1	Running
0	5m		
...			

- b. View the logs for a Pod that is listed in the output of the previous command by using the following command:

```
$ oc logs <pod_name> -n <namespace> 1
```

- 1 Specify the Pod name and namespace, as shown in the output of the previous command.

If the Pod logs display, the Kubernetes API server can communicate with the cluster machines.

1.1.16. Next steps

- [Customize your cluster.](#)
- If necessary, you can [opt out of remote health reporting](#) .
- [Set up your registry and configure registry storage](#) .

1.2. INSTALLING A CLUSTER ON BARE METAL WITH NETWORK CUSTOMIZATIONS

In OpenShift Container Platform version 4.3, you can install a cluster on bare metal infrastructure that you provision with customized network configuration options. By customizing your network configuration, your cluster can coexist with existing IP address allocations in your environment and integrate with existing MTU and VXLAN configurations.

You must set most of the network configuration parameters during installation, and you can modify only **kubeProxy** configuration parameters in a running cluster.

1.2.1. Prerequisites

- Review details about the [OpenShift Container Platform installation and update](#) processes.
- If you use a firewall, you must [configure it to access Red Hat Insights](#) .


1.2.2. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the [Red Hat OpenShift Cluster Manager \(OCM\)](#) .

Once you confirm that your Red Hat OpenShift Cluster Manager inventory is correct, either maintained automatically by Telemetry or manually using OCM, [use subscription watch](#) to track your OpenShift Container Platform subscriptions at the account or multi-cluster level.

You must have internet access to:

- Access the [Red Hat OpenShift Cluster Manager](#) page to download the installation program and perform subscription management. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster.
- Access [Quay.io](#) to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



IMPORTANT

If your cluster cannot have direct internet access, you can perform a restricted network installation on some types of infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.


1.2.3. Machine requirements for a cluster with user-provisioned infrastructure

For a cluster that contains user-provisioned infrastructure, you must deploy all of the required machines.

1.2.3.1. Required machines

The smallest OpenShift Container Platform clusters require the following hosts:

- One temporary bootstrap machine
- Three control plane, or master, machines
- At least two compute machines, which are also known as worker machines



NOTE

The cluster requires the bootstrap machine to deploy the OpenShift Container Platform cluster on the three control plane machines. You can remove the bootstrap machine after you install the cluster.



IMPORTANT

To maintain high availability of your cluster, use separate physical hosts for these cluster machines.

The bootstrap, control plane, and compute machines must use the Red Hat Enterprise Linux CoreOS (RHCOS) as the operating system.

Note that RHCOS is based on Red Hat Enterprise Linux 8 and inherits all of its hardware certifications and requirements. See [Red Hat Enterprise Linux technology capabilities and limits](#) .

1.2.3.2. Network connectivity requirements

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **inittamfs** during boot to fetch Ignition config files from the Machine Config Server. During the initial boot, the machines require either a DHCP server or that static IP addresses be set in order to establish a network connection to download their Ignition config files.

1.2.3.3. Minimum resource requirements

Each cluster machine must meet the following minimum requirements:

Machine	Operating System	vCPU	Virtual RAM	Storage
Bootstrap	RHCOS	4	16 GB	120 GB
Control plane	RHCOS	4	16 GB	120 GB
Compute	RHCOS or RHEL 7.6	2	8 GB	120 GB

1.2.3.4. Certificate signing requests management

Because your cluster has limited access to automatic machine management when you use infrastructure that you provision, you must provide a mechanism for approving cluster certificate signing requests (CSRs) after installation. The **kube-controller-manager** only approves the kubelet client CSRs. The **machine-approver** cannot guarantee the validity of a serving certificate that is requested by using

kubelet credentials because it cannot confirm that the correct machine issued the request. You must determine and implement a method of verifying the validity of the kubelet serving certificate requests and approving them.

1.2.4. Creating the user-provisioned infrastructure

Before you deploy an OpenShift Container Platform cluster that uses user-provisioned infrastructure, you must create the underlying infrastructure.

Prerequisites

- Review the [OpenShift Container Platform 4.x Tested Integrations](#) page before you create the supporting infrastructure for your cluster.

Procedure

1. Configure DHCP or set static IP addresses on each node.
2. Provision the required load balancers.
3. Configure the ports for your machines.
4. Configure DNS.
5. Ensure network connectivity.

1.2.4.1. Networking requirements for user-provisioned infrastructure

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config from the Machine Config Server.

During the initial boot, the machines require either a DHCP server or that static IP addresses be set on each host in the cluster in order to establish a network connection, which allows them to download their Ignition config files.

It is recommended to use the DHCP server to manage the machines for the cluster long-term. Ensure that the DHCP server is configured to provide persistent IP addresses and host names to the cluster machines.

The Kubernetes API server, which runs on each master node after a successful cluster installation, must be able to resolve the node names of the cluster machines. If the API servers and worker nodes are in different zones, you can configure a default DNS search zone to allow the API server to resolve the node names. Another supported approach is to always refer to hosts by their fully-qualified domain names in both the node objects and all DNS requests.

You must configure the network connectivity between machines to allow cluster components to communicate. Each machine must be able to resolve the host names of all other machines in the cluster.

Table 1.6. All machines to all machines

Protocol	Port	Description
ICMP	N/A	Network reachability tests

Protocol	Port	Description
TCP	9000-9999	Host level services, including the node exporter on ports 9100-9101 and the Cluster Version Operator on port 9099 .
	10250-10259	The default ports that Kubernetes reserves
	10256	openshift-sdn
UDP	4789	VXLAN and GENEVE
	6081	VXLAN and GENEVE
	9000-9999	Host level services, including the node exporter on ports 9100-9101 .
TCP/UDP	30000-32767	Kubernetes NodePort

Table 1.7. All machines to control plane

Protocol	Port	Description
TCP	2379-2380	etcd server, peer, and metrics ports
	6443	Kubernetes API

Network topology requirements

The infrastructure that you provision for your cluster must meet the following network topology requirements.




IMPORTANT

OpenShift Container Platform requires all nodes to have internet access to pull images for platform containers and provide telemetry data to Red Hat.

Load balancers

Before you install OpenShift Container Platform, you must provision two load balancers that meet the following requirements:

1. **API load balancer.** Provides a common endpoint for users, both human and machine, to interact with and configure the platform. Configure the following conditions:
 - Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
 - A stateless load balancing algorithm. The options vary based on the load balancer implementation.

**NOTE**

Session persistence is not required for the API load balancer to function properly.

Configure the following ports on both the front and back of the load balancers:

Table 1.8. API load balancer

Port	Back-end machines (pool members)	Internal	External	Description
6443	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane. You must configure the /readyz endpoint for the API server health check probe.	X	X	Kubernetes API server
22623	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane.	X		Machine Config server

**NOTE**

The load balancer must be configured to take a maximum of 30 seconds from the time the API server turns off the **/readyz** endpoint to the removal of the API server instance from the pool. Within the time frame after **/readyz** returns an error or becomes healthy, the endpoint must have been removed or added. Probing every 5 or 10 seconds, with two successful requests to become healthy and three to become unhealthy, are well-tested values.

2. **Application Ingress load balancer.** Provides an Ingress point for application traffic flowing in from outside the cluster. Configure the following conditions:

- Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
- A connection-based or session-based persistence is recommended, based on the options available and types of applications that will be hosted on the platform.

Configure the following ports on both the front and back of the load balancers:

Table 1.9. Application Ingress load balancer

Port	Back-end machines (pool members)	Internal	External	Description
443	The machines that run the Ingress router pods, compute, or worker, by default.	X	X	HTTPS traffic

Port	Back-end machines (pool members)	Internal	External	Description
80	The machines that run the Ingress router pods, compute, or worker by default.	X	X	HTTP traffic

TIP

If the true IP address of the client can be seen by the load balancer, enabling source IP-based session persistence can improve performance for applications that use end-to-end TLS encryption.

**NOTE**

A working configuration for the Ingress router is required for an OpenShift Container Platform cluster. You must configure the Ingress router after the control plane initializes.

1.2.4.2. User-provisioned DNS requirements

The following DNS records are required for an OpenShift Container Platform cluster that uses user-provisioned infrastructure. In each record, **<cluster_name>** is the cluster name and **<base_domain>** is the cluster base domain that you specify in the **install-config.yaml** file. A complete DNS record takes the form: **<component>.<cluster_name>.<base_domain>..**

Table 1.10. Required DNS records

Component	Record	Description
Kubernetes API	api.<cluster_name>.<base_domain>..	This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.

Component	Record	Description
	api-int.<cluster_name>.<base_domain>.	<p>This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable from all the nodes within the cluster.</p> <div data-bbox="1038 517 1145 987" style="background-color: black; width: 66px; height: 210px; margin-bottom: 10px;"></div> <p>IMPORTANT</p> <p>The API server must be able to resolve the worker nodes by the host names that are recorded in Kubernetes. If it cannot resolve the node names, proxied API calls can fail, and you cannot retrieve logs from Pods.</p>
Routes	*.apps.<cluster_name>.<base_domain>.	<p>A wildcard DNS A/AAAA or CNAME record that points to the load balancer that targets the machines that run the Ingress router pods, which are the worker nodes by default. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.</p>

Component	Record	Description
etcd	etcd-<code><index></code>.<code><cluster_name></code>.<code><base_domain></code>.	OpenShift Container Platform requires DNS A/AAAA records for each etcd instance to point to the control plane machines that host the instances. The etcd instances are differentiated by <code><index></code> values, which start with 0 and end with n-1 , where n is the number of control plane machines in the cluster. The DNS record must resolve to an unicast IPv4 address for the control plane machine, and the records must be resolvable from all the nodes in the cluster.
	_etcd-server-ssl._tcp.<code><cluster_name></code>.<code><base_domain></code>.	For each control plane machine, OpenShift Container Platform also requires a SRV DNS record for etcd server on that machine with priority 0 , weight 10 and port 2380 . A cluster that uses three control plane machines requires the following records: <pre> # _service._proto.name. TTL class SRV priority weight port target. _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 0.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 1.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 2.<cluster_name>. <base_domain> </pre>

1.2.5. Generating an SSH private key and adding it to the agent


If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



NOTE

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's `~/.ssh/authorized_keys` list.



NOTE

You must use a local key, not one that you configured with platform-specific approaches such as [AWS key pairs](#).

Procedure

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N "" \
-f <path>/<file_name> 1
```

- 1 Specify the path and file name, such as `~/.ssh/id_rsa`, of the SSH key. Do not specify an existing SSH key, as it will be overwritten.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1
Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```

- 1 Specify the path and file name for your SSH private key, such as `~/.ssh/id_rsa`

Next steps

- When you install OpenShift Container Platform, provide the SSH public key to the installation program.

1.2.6. Obtaining the installation program


Before you install OpenShift Container Platform, download the installation file on a local computer.

Prerequisites

- You must install the cluster from a computer that uses Linux or macOS.
- You need 500 MB of local disk space to download the installation program.


Procedure

1. Access the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.
2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.



IMPORTANT

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.



IMPORTANT

Deleting the files created by the installation program does not remove your cluster, even if the cluster failed during installation. You must complete the OpenShift Container Platform uninstallation procedures outlined for your specific cloud provider to remove your cluster entirely.

3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:

```
$ tar xvf <installation_program>.tar.gz
```

4. From the [Pull Secret](#) page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a **.txt** file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

1.2.7. Installing the CLI by downloading the binary

You can install the OpenShift CLI (**oc**) in order to interact with OpenShift Container Platform from a command-line interface. You can install **oc** on Linux, Windows, or macOS.



IMPORTANT

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

1.2.7.1. Installing the CLI on Linux

You can install the OpenShift CLI (**oc**) binary on Linux by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.
2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **Linux** from the drop-down menu and click **Download command-line tools**.
4. Unpack the archive:

```
$ tar xvzf <file>
```

5. Place the **oc** binary in a directory that is on your **PATH**.
To check your **PATH**, execute the following command:

```
$ echo $PATH
```

After you install the CLI, it is available using the **oc** command:

```
$ oc <command>
```

1.2.7.2. Installing the CLI on Windows

You can install the OpenShift CLI (**oc**) binary on Windows by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.
2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **Windows** from the drop-down menu and click **Download command-line tools**.
4. Unzip the archive with a ZIP program.
5. Move the **oc** binary to a directory that is on your **PATH**.
To check your **PATH**, open the command prompt and execute the following command:

```
C:\> path
```

After you install the CLI, it is available using the **oc** command:

```
C:\> oc <command>
```

1.2.7.3. Installing the CLI on macOS

You can install the OpenShift CLI (**oc**) binary on macOS by using the following procedure.

Procedure

1. Navigate to the [Infrastructure Provider](#) page on the Red Hat OpenShift Cluster Manager site.

2. Select your infrastructure provider, and, if applicable, your installation type.
3. In the **Command-line interface** section, select **MacOS** from the drop-down menu and click **Download command-line tools**.
4. Unpack and unzip the archive.
5. Move the **oc** binary to a directory on your PATH.
To check your **PATH**, open a terminal and execute the following command:

```
$ echo $PATH
```

After you install the CLI, it is available using the **oc** command:

```
$ oc <command>
```

1.2.8. Manually creating the installation configuration file

For installations of OpenShift Container Platform that use user-provisioned infrastructure, you must manually generate your installation configuration file.


Prerequisites

- Obtain the OpenShift Container Platform installation program and the access token for your cluster.

Procedure

1. Create an installation directory to store your required installation assets in:

```
$ mkdir <installation_directory>
```



IMPORTANT

You must create a directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.


2. Customize the following **install-config.yaml** file template and save it in the **<installation_directory>**.



NOTE

You must name this configuration file **install-config.yaml**.

3. Back up the **install-config.yaml** file so that you can use it to install multiple clusters.



IMPORTANT

The **install-config.yaml** file is consumed during the next step of the installation process. You must back it up now.

1.2.8.1. Sample **install-config.yaml** file for bare metal

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.

```

apiVersion: v1
baseDomain: example.com 1
compute:
- hyperthreading: Enabled 2 3
  name: worker
  replicas: 0 4
controlPlane:
  hyperthreading: Enabled 5 6
  name: master 7
  replicas: 3 8
metadata:
  name: test 9
networking:
  clusterNetwork:
  - cidr: 10.128.0.0/14 10
    hostPrefix: 23 11
  networkType: OpenShiftSDN
  serviceNetwork: 12
  - 172.30.0.0/16
platform:
  none: {} 13
fips: false 14
pullSecret: '{"auths": ...}' 15
sshKey: 'ssh-ed25519 AAAA...' 16

```


- 1 The base domain of the cluster. All DNS records must be sub-domains of this base and include the cluster name.
- 2 5 The **controlPlane** section is a single mapping, but the compute section is a sequence of mappings. To meet the requirements of the different data structures, the first line of the **compute** section must begin with a hyphen, -, and the first line of the **controlPlane** section must not. Although both sections currently define a single machine pool, it is possible that future versions of OpenShift Container Platform will support defining multiple compute pools during installation. Only one control plane pool is used.
- 3 6 7 Whether to enable or disable simultaneous multithreading, or **hyperthreading**. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores. You can disable it by setting the parameter value to **Disabled**. If you disable simultaneous multithreading in some cluster machines, you must disable it in all cluster machines.



IMPORTANT

If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.

- 4 You must set the value of the **replicas** parameter to **0**. This parameter controls the number of workers that the cluster creates and manages for you, which are functions that the cluster does not perform when you use user-provisioned infrastructure. You must manually deploy worker machines for the cluster to use before you finish installing OpenShift Container Platform.
- 8 The number of control plane machines that you add to the cluster. Because the cluster uses this values as the number of etcd endpoints in the cluster, the value must match the number of control plane machines that you deploy.
- 9 The cluster name that you specified in your DNS records.
- 10 A block of IP addresses from which Pod IP addresses are allocated. This block must not overlap with existing physical networks. These IP addresses are used for the Pod network. If you need to access the Pods from an external network, you must configure load balancers and routers to manage the traffic.
- 11 The subnet prefix length to assign to each individual node. For example, if **hostPrefix** is set to **23**, then each node is assigned a **/23** subnet out of the given **cidr**, which allows for 510 ($2^{(32 - 23)} - 2$) pod IPs addresses. If you are required to provide access to nodes from an external network, configure load balancers and routers to manage the traffic.
- 12 The IP address pool to use for service IP addresses. You can enter only one IP address pool. If you need to access the services from an external network, configure load balancers and routers to manage the traffic.
- 13 You must set the platform to **none**. You cannot provide additional platform configuration variables for bare metal infrastructure.
- 14 Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the cryptography modules that are provided with RHCOS instead.
- 15 The pull secret that you obtained from the [Pull Secret](#) page on the Red Hat OpenShift Cluster Manager site. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.
- 16 The public portion of the default SSH key for the **core** user in Red Hat Enterprise Linux CoreOS (RHCOS).



NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

1.2.8.2. Network configuration parameters

You can modify your cluster network configuration parameters in the **install-config.yaml** configuration file. The following table describes the parameters.

**NOTE**


You cannot modify these parameters in the **install-config.yaml** file after installation.

Table 1.11. Required network parameters

Parameter	Description	Value
networking.net workType	The default Container Network Interface (CNI) network provider plug-in to deploy. The OpenShiftSDN plug-in is the only plug-in supported in OpenShift Container Platform 4.3.	The default value is OpenShiftSDN .
networking.clus terNetwork.cidr	A block of IP addresses from which Pod IP addresses are allocated. The OpenShiftSDN network plug-in supports multiple cluster networks. The address blocks for multiple cluster networks must not overlap. Select address pools large enough to fit your anticipated workload.	An IP address allocation in CIDR format. The default value is 10.128.0.0/14 .
networking.clus terNetwork.host Prefix	The subnet prefix length to assign to each individual node. For example, if hostPrefix is set to 23 , then each node is assigned a /23 subnet out of the given cidr , allowing for 510 ($2^{(32 - 23)} - 2$) Pod IP addresses.	A subnet prefix. The default value is 23 .
networking.serv iceNetwork[]	A block of IP addresses for services. OpenShiftSDN allows only one serviceNetwork block. The address block must not overlap with any other network block.	An IP address allocation in CIDR format. The default value is 172.30.0.0/16 .
networking.mac hineCIDR	A block of IP addresses used by the OpenShift Container Platform installation program while installing the cluster. The address block must not overlap with any other network block.	An IP address allocation in CIDR format. The default value is 10.0.0.0/16 .

1.2.9. Modifying advanced network configuration parameters

You can modify the advanced network configuration parameters only before you install the cluster. Advanced configuration customization lets you integrate your cluster into your existing network environment by specifying an MTU or VXLAN port, by allowing customization of [kube-proxy](#) settings, and by specifying a different **mode** for the **openshiftSDNConfig** parameter.

**IMPORTANT**

Modifying the OpenShift Container Platform manifest files directly is not supported.

Prerequisites

- Create the **install-config.yaml** file and complete any modifications to it.

- Create the Ignition config files for your cluster.

Procedure

1. Use the following command to create manifests:

```
$ ./openshift-install create manifests --dir=<installation_directory> 1
```

- 1** For **<installation_directory>**, specify the name of the directory that contains the **install-config.yaml** file for your cluster.

2. Modify the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** Kubernetes manifest file to prevent Pods from being scheduled on the control plane machines:
 - a. Open the **manifests/cluster-scheduler-02-config.yml** file.
 - b. Locate the **mastersSchedulable** parameter and set its value to **False**.
 - c. Save and exit the file.



NOTE

Currently, due to a [Kubernetes limitation](#), router Pods running on control plane machines will not be reachable by the ingress load balancer.

3. Create a file that is named **cluster-network-03-config.yml** in the **<installation_directory>/manifests/** directory:

```
$ touch <installation_directory>/manifests/cluster-network-03-config.yml 1
```

- 1** For **<installation_directory>**, specify the directory name that contains the **manifests/** directory for your cluster.

After creating the file, several network configuration files are in the **manifests/** directory, as shown:

```
$ ls <installation_directory>/manifests/cluster-network-*
```

Example output

```
cluster-network-01-crd.yml
cluster-network-02-config.yml
cluster-network-03-config.yml
```

4. Open the **cluster-network-03-config.yml** file in an editor and enter a CR that describes the Operator configuration you want:

```
apiVersion: operator.openshift.io/v1
kind: Network
metadata:
  name: cluster
spec: 1
```

```

clusterNetwork:
- cidr: 10.128.0.0/14
  hostPrefix: 23
serviceNetwork:
- 172.30.0.0/16
defaultNetwork:
type: OpenShiftSDN
openshiftSDNConfig:
mode: NetworkPolicy
mtu: 1450
vxlanPort: 4789

```

- 1 The parameters for the **spec** parameter are only an example. Specify your configuration for the Cluster Network Operator in the CR.

The CNO provides default values for the parameters in the CR, so you must specify only the parameters that you want to change.

5. Save the **cluster-network-03-config.yml** file and quit the text editor.
6. Optional: Back up the **manifests/cluster-network-03-config.yml** file. The installation program deletes the **manifests/** directory when creating the cluster.

1.2.10. Cluster Network Operator configuration

The configuration for the cluster network is specified as part of the Cluster Network Operator (CNO) configuration and stored in a CR object that is named **cluster**. The CR specifies the parameters for the **Network** API in the **operator.openshift.io** API group.

You can specify the cluster network configuration for your OpenShift Container Platform cluster by setting the parameter values for the **defaultNetwork** parameter in the CNO CR. The following CR displays the default configuration for the CNO and explains both the parameters you can configure and the valid parameter values:

Cluster Network Operator CR

```

apiVersion: operator.openshift.io/v1
kind: Network
metadata:
name: cluster
spec:
clusterNetwork: 1
- cidr: 10.128.0.0/14
  hostPrefix: 23
serviceNetwork: 2
- 172.30.0.0/16
defaultNetwork: 3
...
kubeProxyConfig: 4
iptablesSyncPeriod: 30s 5
proxyArguments:
iptables-min-sync-period: 6
- 0s

```

- 1 2 Specified in the **install-config.yaml** file.
- 3 Configures the default Container Network Interface (CNI) network provider for the cluster network.
- 4 The parameters for this object specify the **kube-proxy** configuration. If you do not specify the parameter values, the Cluster Network Operator applies the displayed default parameter values. If you are using the OVN-Kubernetes default CNI network provider, the kube-proxy configuration has no effect.
- 5 The refresh period for **iptables** rules. The default value is **30s**. Valid suffixes include **s**, **m**, and **h** and are described in the [Go time package](#) documentation.



NOTE

Because of performance improvements introduced in OpenShift Container Platform 4.3 and greater, adjusting the **iptablesSyncPeriod** parameter is no longer necessary.

- 6 The minimum duration before refreshing **iptables** rules. This parameter ensures that the refresh does not happen too frequently. Valid suffixes include **s**, **m**, and **h** and are described in the [Go time package](#).

1.2.10.1. Configuration parameters for the OpenShift SDN default CNI network provider

The following YAML object describes the configuration parameters for the OpenShift SDN default Container Network Interface (CNI) network provider.

```
defaultNetwork:
  type: OpenShiftSDN 1
  openshiftSDNConfig: 2
    mode: NetworkPolicy 3
    mtu: 1450 4
    vxlanPort: 4789 5
```

- 1 Specified in the **install-config.yaml** file.
- 2 Specify only if you want to override part of the OpenShift SDN configuration.
- 3 Configures the network isolation mode for OpenShift SDN. The allowed values are **Multitenant**, **Subnet**, or **NetworkPolicy**. The default value is **NetworkPolicy**.
- 4 The maximum transmission unit (MTU) for the VXLAN overlay network. This value is normally configured automatically, but if the nodes in your cluster do not all use the same MTU, then you must set this explicitly to 50 less than the smallest node MTU value.
- 5 The port to use for all VXLAN packets. The default value is **4789**. If you are running in a virtualized environment with existing nodes that are part of another VXLAN network, then you might be required to change this. For example, when running an OpenShift SDN overlay on top of VMware NSX-T, you must select an alternate port for VXLAN, since both SDNs use the same default VXLAN port number.

On Amazon Web Services (AWS), you can select an alternate port for the VXLAN between port **9000** and port **9999**.

1.2.10.2. Cluster Network Operator example configuration


A complete CR object for the CNO is displayed in the following example:

Cluster Network Operator example CR

```
apiVersion: operator.openshift.io/v1
kind: Network
metadata:
  name: cluster
spec:
  clusterNetwork:
    - cidr: 10.128.0.0/14
      hostPrefix: 23
  serviceNetwork:
    - 172.30.0.0/16
  defaultNetwork:
    type: OpenShiftSDN
    openshiftSDNConfig:
      mode: NetworkPolicy
      mtu: 1450
      vxlanPort: 4789
  kubeProxyConfig:
    iptablesSyncPeriod: 30s
    proxyArguments:
      iptables-min-sync-period:
        - 0s
```

1.2.11. Creating the Ignition config files

Because you must manually start the cluster machines, you must generate the Ignition config files that the cluster needs to make its machines.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must complete your cluster installation and keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

Prerequisites


- Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

Procedure

1. Obtain the Ignition config files:

```
$ ./openshift-install create ignition-configs --dir=<installation_directory> 1
```


- 1 For **<installation_directory>**, specify the directory name to store the files that the installation program creates.



IMPORTANT

If you created an **install-config.yaml** file, specify the directory that contains it. Otherwise, specify an empty directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

The following files are generated in the directory:



1.2.12. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines

Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. Follow either the steps to use an ISO image or network PXE booting to create the machines.

1.2.12.1. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines using an ISO image


Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. You can use an ISO image to create the machines.

Prerequisites

- Obtain the Ignition config files for your cluster.
- Have access to an HTTP server that you can access from your computer and that the machines that you create can access.

Procedure

1. Upload the control plane, compute, and bootstrap Ignition config files that the installation program created to your HTTP server. Note the URLs of these files.
2. Obtain the RHCOS images that are required for your preferred method of installing operating system instances from the [Product Downloads](#) page on the Red Hat customer portal or the [RHCOS image mirror](#) page.



IMPORTANT

The RHCOS images might not change with every release of OpenShift Container Platform. You must download images with the highest version that is less than or equal to the OpenShift Container Platform version that you install. Use the image versions that match your OpenShift Container Platform version if they are available.

You must download the ISO file and the RAW disk file. Those file names resemble the following examples:

- ISO: **rhcos-<version>-installer.<architecture>.iso**
 - Compressed metal RAW: **rhcos-<version>-metal.<architecture>.raw.gz**
3. Upload either the RAW RHCOS image file to your HTTP server and note its URL.
 4. Use the ISO to start the RHCOS installation. Use one of the following installation options:
 - Burn the ISO image to a disk and boot it directly.
 - Use ISO redirection via a LOM interface.
 5. After the instance boots, press the **TAB** or **E** key to edit the kernel command line.
 6. Add the parameters to the kernel command line:

```
coreos.inst=yes
coreos.inst.install_dev=sda 1
coreos.inst.image_url=<image_URL> 2
coreos.inst.ignition_url=http://example.com/config.ign 3
ip=<dhcp or static IP address> 4 5
```

- 1 Specify the block device of the system to install to.
- 2 Specify the URL of the RAW image that you uploaded to your server.
- 3 Specify the URL of the Ignition config file for this machine type.
- 4 Set **ip=dhcp** or set an individual static IP address (**ip=**) and DNS server (**nameserver=**) on each node. For example, setting **ip=10.10.10.2::10.10.10.254:255.255.255.0:core0.example.com:enp1s0:none nameserver=4.4.4.41** sets:
 - Node's IP address to **10.10.10.2**
 - Gateway address to **10.10.10.254**
 - Netmask to **255.255.255.0**
 - Hostname to **core0.example.com**
 - The DNS server address to **4.4.4.41**
- 5 If you use multiple network interfaces or DNS servers, you can further customize the IP address configuration in the following ways:

- If your system has multiple network interfaces, you can add multiple IP address configurations by specifying multiple **ip=** entries.
 - If your system has multiple network interfaces, you can use a combination of DHCP and static IP configurations. You must specify the interface to use, for example **ip=enp1s0:dhcp ip=10.10.10.2::10.10.10.254:255.255.255.0:core0.example.com:enp2s0:none**.
 - You can provide multiple DNS servers by adding a **nameserver=** entry for each server, such as **nameserver=1.1.1.1 nameserver=8.8.8.8**.
7. Press Enter to complete the installation. After RHCOS installs, the system reboots. After the system reboots, it applies the Ignition config file that you specified.
 8. Continue to create the machines for your cluster.



IMPORTANT

You must create the bootstrap and control plane machines at this time. Because some pods are deployed on compute machines by default, also create at least two compute machines before you install the cluster.

1.2.12.2. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines by PXE or iPXE booting


Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. You can use PXE or iPXE booting to create the machines.

Prerequisites

- Obtain the Ignition config files for your cluster.
- Configure suitable PXE or iPXE infrastructure.
- Have access to an HTTP server that you can access from your computer.

Procedure

1. Upload the master, worker, and bootstrap Ignition config files that the installation program created to your HTTP server. Note the URLs of these files.
2. Obtain the RHCOS ISO image, compressed metal RAW image, **kernel** and **initramfs** files from the [Product Downloads](#) page on the Red Hat customer portal or the [RHCOS image mirror](#) page.



IMPORTANT

The RHCOS images might not change with every release of OpenShift Container Platform. You must download images with the highest version that is less than or equal to the OpenShift Container Platform version that you install. Use the image versions that match your OpenShift Container Platform version if they are available.

The file names contain the OpenShift Container Platform version number. They resemble the following examples:

- ISO: **rhcos-`<version>`-installer.`<architecture>`.iso**
 - Compressed metal RAW image: **rhcos-`<version>`metal.`<architecture>`.raw.gz**
 - **kernel: rhcos-`<version>`-installer-kernel-`<architecture>`**
 - **initramfs: rhcos-`<version>`-installer-initramfs.`<architecture>`.img**
3. Upload the compressed metal RAW image and the **kernel** and **initramfs** files to your HTTP server.
 4. Configure the network boot infrastructure so that the machines boot from their local disks after RHCOS is installed on them.
 5. Configure PXE or iPXE installation for the RHCOS images.
Modify one of the following example menu entries for your environment and verify that the image and Ignition files are properly accessible:

- For PXE:

```

DEFAULT pxeboot
TIMEOUT 20
PROMPT 0
LABEL pxeboot
  KERNEL http://<HTTP_server>/rhcos-<version>-installer-kernel-<architecture> 1
  APPEND ip=dhcp rd.neednet=1 initrd=http://<HTTP_server>/rhcos-<version>-installer-
initramfs.<architecture>.img console=tty0 console=ttyS0 coreos.inst=yes
coreos.inst.install_dev=sda coreos.inst.image_url=http://<HTTP_server>/rhcos-
<version>-metal.<architecture>.raw.gz
coreos.inst.ignition_url=http://<HTTP_server>/bootstrap.ign 2 3

```

- 1** Specify the location of the **kernel** file that you uploaded to your HTTP server.
- 2** If you use multiple NICs, specify a single interface in the **ip** option. For example, to use DHCP on a NIC that is named **eno1**, set **ip=eno1:dhcp**.
- 3** Specify locations of the RHCOS files that you uploaded to your HTTP server. The **initrd** parameter value is the location of the **initramfs** file, the **coreos.inst.image_url** parameter value is the location of the compressed metal RAW image, and the **coreos.inst.ignition_url** parameter value is the location of the bootstrap Ignition config file.

- For iPXE:

```

kernel http://<HTTP_server>/rhcos-<version>-installer-kernel-<architecture> ip=dhcp
rd.neednet=1 initrd=http://<HTTP_server>/rhcos-<version>-installer-initramfs.
<architecture>.img console=tty0 console=ttyS0 coreos.inst=yes
coreos.inst.install_dev=sda coreos.inst.image_url=http://<HTTP_server>/rhcos-
<version>-metal.<architecture>.raw.gz
coreos.inst.ignition_url=http://<HTTP_server>/bootstrap.ign 1 2
initrd http://<HTTP_server>/rhcos-<version>-installer-initramfs.<architecture>.img 3
boot

```

- 1 Specify locations of the RHCOS files that you uploaded to your HTTP server. The **kernel** parameter value is the location of the **kernel** file, the **initrd** parameter value is the location of the **initramfs** file, the **coreos.inst.image_url** parameter value is the location of the compressed metal RAW image, and the **coreos.inst.ignition_url** parameter value is the location of the bootstrap Ignition config file.
- 2 If you use multiple NICs, specify a single interface in the **ip** option. For example, to use DHCP on a NIC that is named **eno1**, set **ip=eno1:dhcp**.
- 3 Specify the location of the **initramfs** file that you uploaded to your HTTP server.

6. Continue to create the machines for your cluster.



IMPORTANT

You must create the bootstrap and control plane machines at this time. Because some pods are deployed on compute machines by default, also create at least two compute machine before you install the cluster.

1.2.13. Creating the cluster

To create the OpenShift Container Platform cluster, you wait for the bootstrap process to complete on the machines that you provisioned by using the Ignition config files that you generated with the installation program.

Prerequisites

- Create the required infrastructure for the cluster.
- You obtained the installation program and generated the Ignition config files for your cluster.
- You used the Ignition config files to create RHCOS machines for your cluster.
- Your machines have direct internet access.

Procedure

1. Monitor the bootstrap process:

```
$ ./openshift-install --dir=<installation_directory> wait-for bootstrap-complete \ 1
--log-level=info 2
INFO Waiting up to 30m0s for the Kubernetes API at https://api.test.example.com...
INFO API v1.16.2 up
INFO Waiting up to 30m0s for bootstrapping to complete...
INFO It is now safe to remove the bootstrap resources
```

- 1 For **<installation_directory>**, specify the path to the directory that you stored the installation files in.
- 2 To view different installation details, specify **warn**, **debug**, or **error** instead of **info**.

The command succeeds when the Kubernetes API server signals that it has been bootstrapped on the control plane machines.

2. After bootstrap process is complete, remove the bootstrap machine from the load balancer.



IMPORTANT

You must remove the bootstrap machine from the load balancer at this point. You can also remove or reformat the machine itself.

1.2.14. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

Prerequisites

- Deploy an OpenShift Container Platform cluster.
- Install the **oc** CLI.

Procedure

1. Export the **kubeadmin** credentials:

```
$ export KUBECONFIG=<installation_directory>/auth/kubeconfig 1
```

- 1** For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

2. Verify you can run **oc** commands successfully using the exported configuration:

```
$ oc whoami
system:admin
```

1.2.15. Approving the CSRs for your machines

When you add machines to a cluster, two pending certificates signing request (CSRs) are generated for each machine that you added. You must confirm that these CSRs are approved or, if necessary, approve them yourself.

Prerequisites

- You added machines to your cluster.

Procedure

1. Confirm that the cluster recognizes the machines:

```
$ oc get nodes

NAME     STATUS    ROLES    AGE   VERSION
master-0 Ready     master   63m   v1.16.2
```

```

master-1 Ready   master 63m v1.16.2
master-2 Ready   master 64m v1.16.2
worker-0 NotReady worker 76s v1.16.2
worker-1 NotReady worker 70s v1.16.2

```

The output lists all of the machines that you created.

- Review the pending certificate signing requests (CSRs) and ensure that you see a client and server request with **Pending** or **Approved** status for each machine that you added to the cluster:

```
$ oc get csr
```

NAME	AGE	REQUESTOR	CONDITION
csr-8b2br	15m	system:serviceaccount:openshift-machine-config-operator:node-bootstrapper	Pending 1
csr-8vnps	15m	system:serviceaccount:openshift-machine-config-operator:node-bootstrapper	Pending
csr-bfd72	5m26s	system:node:ip-10-0-50-126.us-east-2.compute.internal	Pending 2
csr-c57lv	5m26s	system:node:ip-10-0-95-157.us-east-2.compute.internal	Pending
...			

1 A client request CSR.

2 A server request CSR.

In this example, two machines are joining the cluster. You might see more approved CSRs in the list.

- If the CSRs were not approved, after all of the pending CSRs for the machines you added are in **Pending** status, approve the CSRs for your cluster machines:



NOTE

Because the CSRs rotate automatically, approve your CSRs within an hour of adding the machines to the cluster. If you do not approve them within an hour, the certificates will rotate, and more than two certificates will be present for each node. You must approve all of these certificates. After you approve the initial CSRs, the subsequent node client CSRs are automatically approved by the cluster **kube-controller-manager**. You must implement a method of automatically approving the kubelet serving certificate requests.

- To approve them individually, run the following command for each valid CSR:

```
$ oc adm certificate approve <csr_name> 1
```

1 **<csr_name>** is the name of a CSR from the list of current CSRs.

- To approve all pending CSRs, run the following command:

```
$ oc get csr -o go-template='{{range .items}}{{if not .status}}{{.metadata.name}}{\n"}\n{{end}}\n{{end}}' | xargs oc adm certificate approve
```

1.2.16. Initial Operator configuration

After the control plane initializes, you must immediately configure some Operators so that they all become available.

Prerequisites

- Your control plane has initialized.

Procedure

1. Watch the cluster components come online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED	SINCE
authentication	4.3.0	True	False	False	69s
cloud-credential	4.3.0	True	False	False	12m
cluster-autoscaler	4.3.0	True	False	False	11m
console	4.3.0	True	False	False	46s
dns	4.3.0	True	False	False	11m
image-registry	4.3.0	True	False	False	5m26s
ingress	4.3.0	True	False	False	5m36s
kube-apiserver	4.3.0	True	False	False	8m53s
kube-controller-manager	4.3.0	True	False	False	7m24s
kube-scheduler	4.3.0	True	False	False	12m
machine-api	4.3.0	True	False	False	12m
machine-config	4.3.0	True	False	False	7m36s
marketplace	4.3.0	True	False	False	7m54m
monitoring	4.3.0	True	False	False	7h54s
network	4.3.0	True	False	False	5m9s
node-tuning	4.3.0	True	False	False	11m
openshift-apiserver	4.3.0	True	False	False	11m
openshift-controller-manager	4.3.0	True	False	False	5m943s
openshift-samples	4.3.0	True	False	False	3m55s
operator-lifecycle-manager	4.3.0	True	False	False	11m
operator-lifecycle-manager-catalog	4.3.0	True	False	False	11m
service-ca	4.3.0	True	False	False	11m
service-catalog-apiserver	4.3.0	True	False	False	5m26s
service-catalog-controller-manager	4.3.0	True	False	False	5m25s
storage	4.3.0	True	False	False	5m30s

2. Configure the Operators that are not available.

1.2.16.1. Image registry removed during installation

On platforms that do not provide shareable object storage, the OpenShift Image Registry Operator bootstraps itself as **Removed**. This allows **openshift-installer** to complete installations on these platform types.

After installation, you must edit the Image Registry Operator configuration to switch the **ManagementState** from **Removed** to **Managed**.



NOTE

The Prometheus console provides an **ImageRegistryRemoved** alert, for example:

"Image Registry has been removed. **ImageStreamTags**, **BuildConfigs** and **DeploymentConfigs** which reference **ImageStreamTags** may not work as expected. Please configure storage and update the config to **Managed** state by editing `configs.imageregistry.operator.openshift.io`."

1.2.16.2. Image registry storage configuration

The **image-registry** Operator is not initially available for platforms that do not provide default storage. After installation, you must configure your registry to use storage so the Registry Operator is made available.

Instructions for both configuring a PersistentVolume, which is required for production clusters, and for configuring an empty directory as the storage location, which is available for only non-production clusters, are shown.

1.2.17. Completing installation on user-provisioned infrastructure

After you complete the Operator configuration, you can finish installing the cluster on infrastructure that you provide.

Prerequisites

- Your control plane has initialized.
- You have completed the initial Operator configuration.

Procedure

1. Confirm that all the cluster components are online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED	SINCE
authentication	4.3.0	True	False	False	10m
cloud-credential	4.3.0	True	False	False	22m
cluster-autoscaler	4.3.0	True	False	False	21m
console	4.3.0	True	False	False	10m
dns	4.3.0	True	False	False	21m
image-registry	4.3.0	True	False	False	16m
ingress	4.3.0	True	False	False	16m
kube-apiserver	4.3.0	True	False	False	19m
kube-controller-manager	4.3.0	True	False	False	18m
kube-scheduler	4.3.0	True	False	False	22m
machine-api	4.3.0	True	False	False	22m
machine-config	4.3.0	True	False	False	18m
marketplace	4.3.0	True	False	False	18m
monitoring	4.3.0	True	False	False	18m

network	4.3.0	True	False	False	16m
node-tuning	4.3.0	True	False	False	21m
openshift-apiserver	4.3.0	True	False	False	21m
openshift-controller-manager	4.3.0	True	False	False	17m
openshift-samples	4.3.0	True	False	False	14m
operator-lifecycle-manager	4.3.0	True	False	False	21m
operator-lifecycle-manager-catalog	4.3.0	True	False	False	21m
service-ca	4.3.0	True	False	False	21m
service-catalog-apiserver	4.3.0	True	False	False	16m
service-catalog-controller-manager	4.3.0	True	False	False	16m
storage	4.3.0	True	False	False	16m

When all of the cluster Operators are **AVAILABLE**, you can complete the installation.

2. Monitor for cluster completion:

```
$ ./openshift-install --dir=<installation_directory> wait-for install-complete 1
INFO Waiting up to 30m0s for the cluster to initialize...
```

- 1** For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

The command succeeds when the Cluster Version Operator finishes deploying the OpenShift Container Platform cluster from Kubernetes API server.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

3. Confirm that the Kubernetes API server is communicating with the Pods.

- a. To view a list of all Pods, use the following command:

```
$ oc get pods --all-namespaces
```

```

NAMESPACE          NAME                                     READY  STATUS
RESTARTS  AGE
openshift-apiserver-operator  openshift-apiserver-operator-85cb746d55-zqhs8  1/1
Running    1    9m
openshift-apiserver          apiserver-67b9g                                1/1  Running  0
3m
openshift-apiserver          apiserver-ljcmx                                1/1  Running  0
1m
openshift-apiserver          apiserver-z25h4                                1/1  Running  0
2m
openshift-authentication-operator  authentication-operator-69d5d8bf84-vh2n8    1/1
Running    0    5m
...
```

- b. View the logs for a Pod that is listed in the output of the previous command by using the following command:

```
$ oc logs <pod_name> -n <namespace> 1
```

- 1 Specify the Pod name and namespace, as shown in the output of the previous command.

If the Pod logs display, the Kubernetes API server can communicate with the cluster machines.

1.2.18. Next steps

- [Customize your cluster.](#)
- If necessary, you can [opt out of remote health reporting](#) .
- [Set up your registry and configure registry storage](#) .

1.3. INSTALLING A CLUSTER ON BARE METAL IN A RESTRICTED NETWORK

In OpenShift Container Platform version 4.3, you can install a cluster on bare metal infrastructure that you provision in a restricted network.



IMPORTANT

While you might be able to follow this procedure to deploy a cluster on virtualized or cloud environments, you must be aware of additional considerations for non-bare metal platforms. Review the information in the [guidelines for deploying OpenShift Container Platform on non-tested platforms](#) before you attempt to install an OpenShift Container Platform cluster in such an environment.

1.3.1. Prerequisites

- [Create a registry on your mirror host](#) and obtain the **imageContentSources** data for your version of OpenShift Container Platform.



IMPORTANT

Because the installation media is on the mirror host, you can use that computer to complete all installation steps.

- Provision [persistent storage](#) for your cluster. To deploy a private image registry, your storage must provide ReadWriteMany access modes.
- Review details about the [OpenShift Container Platform installation and update](#) processes.
- If you use a firewall and plan to use telemetry, you must [configure the firewall to allow the sites](#) that your cluster requires access to.



NOTE

Be sure to also review this site list if you are configuring a proxy.

1.3.2. About installations in restricted networks

In OpenShift Container Platform 4.3, you can perform an installation that does not require an active connection to the internet to obtain software components. You complete an installation in a restricted network on only infrastructure that you provision, not infrastructure that the installation program provisions, so your platform selection is limited.

If you choose to perform a restricted network installation on a cloud platform, you still require access to its cloud APIs. Some cloud functions, like Amazon Web Service's IAM service, require internet access, so you might still require internet access. Depending on your network, you might require less internet access for an installation on bare metal hardware or on VMware vSphere.

To complete a restricted network installation, you must create a registry that mirrors the contents of the OpenShift Container Platform registry and contains the installation media. You can create this registry on a mirror host, which can access both the internet and your closed network, or by using other methods that meet your restrictions.



IMPORTANT

Restricted network installations always use user-provisioned infrastructure. Because of the complexity of the configuration for user-provisioned installations, consider completing a standard user-provisioned infrastructure installation before you attempt a restricted network installation. Completing this test installation might make it easier to isolate and troubleshoot any issues that might arise during your installation in a restricted network.

1.3.2.1. Additional limits

Clusters in restricted networks have the following additional limitations and restrictions:

- The ClusterVersion status includes an **Unable to retrieve available updates** error.
- By default, you cannot use the contents of the Developer Catalog because you cannot access the required ImageStreamTags.

1.3.3. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to obtain the images that are necessary to install your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the [Red Hat OpenShift Cluster Manager \(OCM\)](#).

Once you confirm that your Red Hat OpenShift Cluster Manager inventory is correct, either maintained automatically by Telemetry or manually using OCM, [use subscription watch](#) to track your OpenShift Container Platform subscriptions at the account or multi-cluster level.

You must have internet access to:

- Access the [Red Hat OpenShift Cluster Manager](#) page to download the installation program and perform subscription management. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster.
- Access [Quay.io](#) to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



IMPORTANT

If your cluster cannot have direct internet access, you can perform a restricted network installation on some types of infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

1.3.4. Machine requirements for a cluster with user-provisioned infrastructure

For a cluster that contains user-provisioned infrastructure, you must deploy all of the required machines.

1.3.4.1. Required machines


The smallest OpenShift Container Platform clusters require the following hosts:

- One temporary bootstrap machine
- Three control plane, or master, machines
- At least two compute machines, which are also known as worker machines



NOTE

The cluster requires the bootstrap machine to deploy the OpenShift Container Platform cluster on the three control plane machines. You can remove the bootstrap machine after you install the cluster.



IMPORTANT

To maintain high availability of your cluster, use separate physical hosts for these cluster machines.

The bootstrap, control plane, and compute machines must use the Red Hat Enterprise Linux CoreOS (RHCOS) as the operating system.

Note that RHCOS is based on Red Hat Enterprise Linux 8 and inherits all of its hardware certifications and requirements. See [Red Hat Enterprise Linux technology capabilities and limits](#) .

1.3.4.2. Network connectivity requirements

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config files from the Machine Config Server. During the initial boot, the machines require either a DHCP server or that static IP addresses be set in order to establish a network connection to download their Ignition config files.

1.3.4.3. Minimum resource requirements

Each cluster machine must meet the following minimum requirements:

Machine	Operating System	vCPU	Virtual RAM	Storage
Bootstrap	RHCOS	4	16 GB	120 GB
Control plane	RHCOS	4	16 GB	120 GB
Compute	RHCOS or RHEL 7.6	2	8 GB	120 GB

1.3.4.4. Certificate signing requests management

Because your cluster has limited access to automatic machine management when you use infrastructure that you provision, you must provide a mechanism for approving cluster certificate signing requests (CSRs) after installation. The **kube-controller-manager** only approves the kubelet client CSRs. The **machine-approver** cannot guarantee the validity of a serving certificate that is requested by using kubelet credentials because it cannot confirm that the correct machine issued the request. You must determine and implement a method of verifying the validity of the kubelet serving certificate requests and approving them.

1.3.5. Creating the user-provisioned infrastructure

Before you deploy an OpenShift Container Platform cluster that uses user-provisioned infrastructure, you must create the underlying infrastructure.

Prerequisites

- Review the [OpenShift Container Platform 4.x Tested Integrations](#) page before you create the supporting infrastructure for your cluster.

Procedure

1. Configure DHCP or set static IP addresses on each node.
2. Provision the required load balancers.
3. Configure the ports for your machines.
4. Configure DNS.
5. Ensure network connectivity.

1.3.5.1. Networking requirements for user-provisioned infrastructure

All the Red Hat Enterprise Linux CoreOS (RHCOS) machines require network in **initramfs** during boot to fetch Ignition config from the Machine Config Server.

During the initial boot, the machines require either a DHCP server or that static IP addresses be set on each host in the cluster in order to establish a network connection, which allows them to download their Ignition config files.

It is recommended to use the DHCP server to manage the machines for the cluster long-term. Ensure that the DHCP server is configured to provide persistent IP addresses and host names to the cluster machines.

The Kubernetes API server, which runs on each master node after a successful cluster installation, must be able to resolve the node names of the cluster machines. If the API servers and worker nodes are in different zones, you can configure a default DNS search zone to allow the API server to resolve the node names. Another supported approach is to always refer to hosts by their fully-qualified domain names in both the node objects and all DNS requests.

You must configure the network connectivity between machines to allow cluster components to communicate. Each machine must be able to resolve the host names of all other machines in the cluster.

Table 1.12. All machines to all machines


Protocol	Port	Description
ICMP	N/A	Network reachability tests
TCP	9000-9999	Host level services, including the node exporter on ports 9100-9101 and the Cluster Version Operator on port 9099 .
	10250-10259	The default ports that Kubernetes reserves
	10256	openshift-sdn
UDP	4789	VXLAN and GENEVE
	6081	VXLAN and GENEVE
	9000-9999	Host level services, including the node exporter on ports 9100-9101 .
TCP/UDP	30000-32767	Kubernetes NodePort

Table 1.13. All machines to control plane

Protocol	Port	Description
TCP	2379-2380	etcd server, peer, and metrics ports
	6443	Kubernetes API

Network topology requirements

The infrastructure that you provision for your cluster must meet the following network topology requirements.



IMPORTANT

OpenShift Container Platform requires all nodes to have internet access to pull images for platform containers and provide telemetry data to Red Hat.

Load balancers

Before you install OpenShift Container Platform, you must provision two load balancers that meet the following requirements:

1. **API load balancer.** Provides a common endpoint for users, both human and machine, to interact with and configure the platform. Configure the following conditions:
 - Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
 - A stateless load balancing algorithm. The options vary based on the load balancer implementation.



NOTE

Session persistence is not required for the API load balancer to function properly.

Configure the following ports on both the front and back of the load balancers:

Table 1.14. API load balancer

Port	Back-end machines (pool members)	Internal	External	Description
6443	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane. You must configure the /readyz endpoint for the API server health check probe.	X	X	Kubernetes API server
22623	Bootstrap and control plane. You remove the bootstrap machine from the load balancer after the bootstrap machine initializes the cluster control plane.	X		Machine Config server



NOTE

The load balancer must be configured to take a maximum of 30 seconds from the time the API server turns off the **/readyz** endpoint to the removal of the API server instance from the pool. Within the time frame after **/readyz** returns an error or becomes healthy, the endpoint must have been removed or added. Probing every 5 or 10 seconds, with two successful requests to become healthy and three to become unhealthy, are well-tested values.

2. **Application Ingress load balancer.** Provides an Ingress point for application traffic flowing in from outside the cluster. Configure the following conditions:
 - Layer 4 load balancing only. This can be referred to as Raw TCP, SSL Passthrough, or SSL Bridge mode.
 - A connection-based or session-based persistence is recommended, based on the options available and types of applications that will be hosted on the platform.


Configure the following ports on both the front and back of the load balancers:

Table 1.15. Application Ingress load balancer

Port	Back-end machines (pool members)	Internal	External	Description
443	The machines that run the Ingress router pods, compute, or worker, by default.	X	X	HTTPS traffic
80	The machines that run the Ingress router pods, compute, or worker by default.	X	X	HTTP traffic

TIP

If the true IP address of the client can be seen by the load balancer, enabling source IP-based session persistence can improve performance for applications that use end-to-end TLS encryption.



NOTE


A working configuration for the Ingress router is required for an OpenShift Container Platform cluster. You must configure the Ingress router after the control plane initializes.

1.3.5.2. User-provisioned DNS requirements

The following DNS records are required for an OpenShift Container Platform cluster that uses user-provisioned infrastructure. In each record, **<cluster_name>** is the cluster name and **<base_domain>** is the cluster base domain that you specify in the **install-config.yaml** file. A complete DNS record takes the form: **<component>.<cluster_name>.<base_domain>..**

Table 1.16. Required DNS records

Component	Record	Description
Kubernetes API	api.<cluster_name>.<base_domain>..	This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.

Component	Record	Description
	api-int.<cluster_name>.<base_domain>.	<p>This DNS A/AAAA or CNAME record must point to the load balancer for the control plane machines. This record must be resolvable from all the nodes within the cluster.</p> <div data-bbox="1040 517 1147 987" style="background-color: black; color: white; padding: 5px; display: inline-block; vertical-align: top;">  </div> <p>IMPORTANT</p> <p>The API server must be able to resolve the worker nodes by the host names that are recorded in Kubernetes. If it cannot resolve the node names, proxied API calls can fail, and you cannot retrieve logs from Pods.</p>
Routes	*.apps.<cluster_name>.<base_domain>.	<p>A wildcard DNS A/AAAA or CNAME record that points to the load balancer that targets the machines that run the Ingress router pods, which are the worker nodes by default. This record must be resolvable by both clients external to the cluster and from all the nodes within the cluster.</p>
etcd	etcd-<index>.<cluster_name>.<base_domain>.	<p>OpenShift Container Platform requires DNS A/AAAA records for each etcd instance to point to the control plane machines that host the instances. The etcd instances are differentiated by <index> values, which start with 0 and end with n-1, where n is the number of control plane machines in the cluster. The DNS record must resolve to an unicast IPv4 address for the control plane machine, and the records must be resolvable from all the nodes in the cluster.</p>

Component	Record	Description
	<code>_etcd-server-ssl._tcp.<cluster_name>.<base_domain>.</code>	<p>For each control plane machine, OpenShift Container Platform also requires a SRV DNS record for etcd server on that machine with priority 0, weight 10 and port 2380. A cluster that uses three control plane machines requires the following records:</p> <pre># _service._proto.name. TTL class SRV priority weight port target. _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 0.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 1.<cluster_name>. <base_domain> _etcd-server-ssl._tcp. <cluster_name>. <base_domain>. 86400 IN SRV 0 10 2380 etcd- 2.<cluster_name>. <base_domain></pre>

1.3.6. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



NOTE

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's `~/.ssh/authorized_keys` list.



NOTE

You must use a local key, not one that you configured with platform-specific approaches such as [AWS key pairs](#).

Procedure

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N "" \
-f <path>/<file_name> 1
```

- 1 Specify the path and file name, such as `~/.ssh/id_rsa`, of the SSH key. Do not specify an existing SSH key, as it will be overwritten.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1
Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```

- 1 Specify the path and file name for your SSH private key, such as `~/.ssh/id_rsa`

Next steps

- When you install OpenShift Container Platform, provide the SSH public key to the installation program. If you install a cluster on infrastructure that you provision, you must provide this key to your cluster's machines.

1.3.7. Manually creating the installation configuration file

For installations of OpenShift Container Platform that use user-provisioned infrastructure, you must manually generate your installation configuration file.


Prerequisites

- Obtain the OpenShift Container Platform installation program and the access token for your cluster.
- Obtain the **imageContentSources** section from the output of the command to mirror the repository.
- Obtain the contents of the certificate for your mirror registry.

Procedure

1. Create an installation directory to store your required installation assets in:

```
$ mkdir <installation_directory>
```



IMPORTANT

You must create a directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.


2. Customize the following **install-config.yaml** file template and save it in the **<installation_directory>**.



NOTE

You must name this configuration file **install-config.yaml**.

- Unless you use a registry that RHCOS trusts by default, such as **docker.io**, you must provide the contents of the certificate for your mirror repository in the **additionalTrustBundle** section. In most cases, you must provide the certificate for your mirror.
 - You must include the **imageContentSources** section from the output of the command to mirror the repository.
3. Back up the **install-config.yaml** file so that you can use it to install multiple clusters.



IMPORTANT

The **install-config.yaml** file is consumed during the next step of the installation process. You must back it up now.

1.3.7.1. Sample install-config.yaml file for bare metal

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.

```
apiVersion: v1
baseDomain: example.com 1
compute:
- hyperthreading: Enabled 2 3
  name: worker
  replicas: 0 4
controlPlane:
  hyperthreading: Enabled 5 6
  name: master 7
  replicas: 3 8
metadata:
  name: test 9
networking:
  clusterNetwork:
  - cidr: 10.128.0.0/14 10
```


manage the traffic.

- 11 The subnet prefix length to assign to each individual node. For example, if **hostPrefix** is set to **23**, then each node is assigned a **/23** subnet out of the given **cidr**, which allows for 510 ($2^{(32 - 23)} - 2$) pod IPs addresses. If you are required to provide access to nodes from an external network, configure load balancers and routers to manage the traffic.
- 12 The IP address pool to use for service IP addresses. You can enter only one IP address pool. If you need to access the services from an external network, configure load balancers and routers to manage the traffic.
- 13 You must set the platform to **none**. You cannot provide additional platform configuration variables for bare metal infrastructure.
- 14 Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the cryptography modules that are provided with RHCOS instead.
- 15 For **<mirror_registry>**, specify the registry domain name, and optionally the port, that your mirror registry uses to serve content. For example **registry.example.com** or **registry.example.com:5000**. For **<credentials>**, specify the base64-encoded user name and password for your mirror registry.
- 16 The public portion of the default SSH key for the **core** user in Red Hat Enterprise Linux CoreOS (RHCOS).



NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- 17 Provide the contents of the certificate file that you used for your mirror registry.
- 18 Provide the **imageContentSources** section from the output of the command to mirror the repository.

1.3.7.2. Configuring the cluster-wide proxy during installation

Production environments can deny direct access to the Internet and instead have an HTTP or HTTPS proxy available. You can configure a new OpenShift Container Platform cluster to use a proxy by configuring the proxy settings in the **install-config.yaml** file.



NOTE

For bare metal installations, if you do not assign node IP addresses from the range that is specified in the **networking.machineCIDR** field in the **install-config.yaml** file, you must include them in the **proxy.noProxy** field.

Prerequisites

- An existing **install-config.yaml** file.

- Review the sites that your cluster requires access to and determine whether any need to bypass the proxy. By default, all cluster egress traffic is proxied, including calls to hosting cloud provider APIs. Add sites to the Proxy object's **spec.noProxy** field to bypass the proxy if necessary.



NOTE


The Proxy object's **status.noProxy** field is populated by default with the instance metadata endpoint (**169.254.169.254**) and with the values of the **networking.machineCIDR**, **networking.clusterNetwork.cidr**, and **networking.serviceNetwork[]** fields from your installation configuration.

Procedure

- Edit your **install-config.yaml** file and add the proxy settings. For example:

```
apiVersion: v1
baseDomain: my.domain.com
proxy:
  httpProxy: http://<username>:<pswd>@<ip>:<port> 1
  httpsProxy: http://<username>:<pswd>@<ip>:<port> 2
  noProxy: example.com 3
  additionalTrustBundle: | 4
    -----BEGIN CERTIFICATE-----
    <MY_TRUSTED_CA_CERT>
    -----END CERTIFICATE-----
  ...
```

- A proxy URL to use for creating HTTP connections outside the cluster. The URL scheme must be **http**. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must not specify an **httpProxy** value.
- A proxy URL to use for creating HTTPS connections outside the cluster. If this field is not specified, then **httpProxy** is used for both HTTP and HTTPS connections. The URL scheme must be **http**; **https** is currently not supported. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must not specify an **httpsProxy** value.
- A comma-separated list of destination domain names, domains, IP addresses, or other network CIDRs to exclude proxying. Preface a domain with **.** to include all subdomains of that domain. Use ***** to bypass proxy for all destinations.
- If provided, the installation program generates a ConfigMap that is named **user-ca-bundle** in the **openshift-config** namespace that contains one or more additional CA certificates that are required for proxying HTTPS connections. The Cluster Network Operator then creates a **trusted-ca-bundle** ConfigMap that merges these contents with the Red Hat Enterprise Linux CoreOS (RHCOS) trust bundle, and this ConfigMap is referenced in the Proxy object's **trustedCA** field. The **additionalTrustBundle** field is required unless the proxy's identity certificate is signed by an authority from the RHCOS trust bundle. If you use an MITM transparent proxy network that does not require additional proxy configuration but requires additional CAs, you must provide the MITM CA certificate.

**NOTE**

The installation program does not support the proxy **readinessEndpoints** field.

2. Save the file and reference it when installing OpenShift Container Platform.


The installation program creates a cluster-wide proxy that is named **cluster** that uses the proxy settings in the provided **install-config.yaml** file. If no proxy settings are provided, a **cluster** Proxy object is still created, but it will have a nil **spec**.

**NOTE**

Only the Proxy object named **cluster** is supported, and no additional proxies can be created.

1.3.8. Creating the Kubernetes manifest and Ignition config files

Because you must modify some cluster definition files and manually start the cluster machines, you must generate the Kubernetes manifest and Ignition config files that the cluster needs to make its machines.

**IMPORTANT**

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must complete your cluster installation and keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

Prerequisites

- Obtain the OpenShift Container Platform installation program. For a restricted network installation, these files are on your mirror host.
- Create the **install-config.yaml** installation configuration file.

Procedure

1. Generate the Kubernetes manifests for the cluster:

```
$ ./openshift-install create manifests --dir=<installation_directory> 1
```

```
INFO Consuming Install Config from target directory
WARNING Making control-plane schedulable by setting MastersSchedulable to true for
Scheduler cluster settings
```

- 1** For **<installation_directory>**, specify the installation directory that contains the **install-config.yaml** file you created.

Because you create your own compute machines later in the installation process, you can safely ignore this warning.

2. Modify the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** Kubernetes manifest file to prevent Pods from being scheduled on the control plane machines:
 - a. Open the **<installation_directory>/manifests/cluster-scheduler-02-config.yml** file.

- b. Locate the **mastersSchedulable** parameter and set its value to **False**.
- c. Save and exit the file.



NOTE

Currently, due to a [Kubernetes limitation](#), router Pods running on control plane machines will not be reachable by the ingress load balancer. This step might not be required in a future minor version of OpenShift Container Platform.

3. Obtain the Ignition config files:

```
$ ./openshift-install create ignition-configs --dir=<installation_directory> 1
```

- 1** For **<installation_directory>**, specify the same installation directory.

The following files are generated in the directory:

```
.
├── auth
│   ├── kubeadmin-password
│   └── kubeconfig
├── bootstrap.ign
├── master.ign
├── metadata.json
└── worker.ign
```

1.3.9. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines

Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. Follow either the steps to use an ISO image or network PXE booting to create the machines.

1.3.9.1. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines using an ISO image


Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. You can use an ISO image to create the machines.

Prerequisites

- Obtain the Ignition config files for your cluster.
- Have access to an HTTP server that you can access from your computer and that the machines that you create can access.

Procedure

1. Upload the control plane, compute, and bootstrap Ignition config files that the installation program created to your HTTP server. Note the URLs of these files.
2. Obtain the RHCOS images that are required for your preferred method of installing operating system instances from the [Product Downloads](#) page on the Red Hat customer portal or the [RHCOS image mirror](#) page.



IMPORTANT

The RHCOS images might not change with every release of OpenShift Container Platform. You must download images with the highest version that is less than or equal to the OpenShift Container Platform version that you install. Use the image versions that match your OpenShift Container Platform version if they are available.

You must download the ISO file and the RAW disk file. Those file names resemble the following examples:

- ISO: **rhcos-<version>-installer.<architecture>.iso**
 - Compressed metal RAW: **rhcos-<version>-metal.<architecture>.raw.gz**
3. Upload either the RAW RHCOS image file to your HTTP server and note its URL.
 4. Use the ISO to start the RHCOS installation. Use one of the following installation options:
 - Burn the ISO image to a disk and boot it directly.
 - Use ISO redirection via a LOM interface.
 5. After the instance boots, press the **TAB** or **E** key to edit the kernel command line.
 6. Add the parameters to the kernel command line:

```
coreos.inst=yes
coreos.inst.install_dev=sda 1
coreos.inst.image_url=<image_URL> 2
coreos.inst.ignition_url=http://example.com/config.ign 3
ip=<dhcp or static IP address> 4 5
```

- 1 Specify the block device of the system to install to.
- 2 Specify the URL of the RAW image that you uploaded to your server.
- 3 Specify the URL of the Ignition config file for this machine type.
- 4 Set **ip=dhcp** or set an individual static IP address (**ip=**) and DNS server (**nameserver=**) on each node. For example, setting **ip=10.10.10.2::10.10.10.254:255.255.255.0:core0.example.com:enp1s0:none nameserver=4.4.4.41** sets:
 - Node's IP address to **10.10.10.2**
 - Gateway address to **10.10.10.254**
 - Netmask to **255.255.255.0**
 - Hostname to **core0.example.com**
 - The DNS server address to **4.4.4.41**
- 5 If you use multiple network interfaces or DNS servers, you can further customize the IP address configuration in the following ways:

- If your system has multiple network interfaces, you can add multiple IP address configurations by specifying multiple **ip=** entries.
 - If your system has multiple network interfaces, you can use a combination of DHCP and static IP configurations. You must specify the interface to use, for example **ip=enp1s0:dhcp ip=10.10.10.2::10.10.10.254:255.255.255.0:core0.example.com:enp2s0:none**.
 - You can provide multiple DNS servers by adding a **nameserver=** entry for each server, such as **nameserver=1.1.1.1 nameserver=8.8.8.8**.
7. Press Enter to complete the installation. After RHCOS installs, the system reboots. After the system reboots, it applies the Ignition config file that you specified.
 8. Continue to create the machines for your cluster.



IMPORTANT

You must create the bootstrap and control plane machines at this time. Because some pods are deployed on compute machines by default, also create at least two compute machines before you install the cluster.

1.3.9.2. Creating Red Hat Enterprise Linux CoreOS (RHCOS) machines by PXE or iPXE booting


Before you install a cluster on bare metal infrastructure that you provision, you must create RHCOS machines for it to use. You can use PXE or iPXE booting to create the machines.

Prerequisites

- Obtain the Ignition config files for your cluster.
- Configure suitable PXE or iPXE infrastructure.
- Have access to an HTTP server that you can access from your computer.

Procedure

1. Upload the master, worker, and bootstrap Ignition config files that the installation program created to your HTTP server. Note the URLs of these files.
2. Obtain the RHCOS ISO image, compressed metal RAW image, **kernel** and **initramfs** files from the [Product Downloads](#) page on the Red Hat customer portal or the [RHCOS image mirror](#) page.



IMPORTANT

The RHCOS images might not change with every release of OpenShift Container Platform. You must download images with the highest version that is less than or equal to the OpenShift Container Platform version that you install. Use the image versions that match your OpenShift Container Platform version if they are available.

The file names contain the OpenShift Container Platform version number. They resemble the following examples:

- ISO: **rhcos-`<version>`-installer.`<architecture>`.iso**
 - Compressed metal RAW image: **rhcos-`<version>`metal.`<architecture>`.raw.gz**
 - **kernel: rhcos-`<version>`-installer-kernel-`<architecture>`**
 - **initramfs: rhcos-`<version>`-installer-initramfs.`<architecture>`.img**
3. Upload the compressed metal RAW image and the **kernel** and **initramfs** files to your HTTP server.
 4. Configure the network boot infrastructure so that the machines boot from their local disks after RHCOS is installed on them.
 5. Configure PXE or iPXE installation for the RHCOS images.
Modify one of the following example menu entries for your environment and verify that the image and Ignition files are properly accessible:

- For PXE:

```

DEFAULT pxeboot
TIMEOUT 20
PROMPT 0
LABEL pxeboot
  KERNEL http://<HTTP_server>/rhcos-<version>-installer-kernel-<architecture> 1
  APPEND ip=dhcp rd.neednet=1 initrd=http://<HTTP_server>/rhcos-<version>-installer-
initramfs.<architecture>.img console=tty0 console=ttyS0 coreos.inst=yes
coreos.inst.install_dev=sda coreos.inst.image_url=http://<HTTP_server>/rhcos-
<version>-metal.<architecture>.raw.gz
coreos.inst.ignition_url=http://<HTTP_server>/bootstrap.ign 2 3

```

- 1** Specify the location of the **kernel** file that you uploaded to your HTTP server.
- 2** If you use multiple NICs, specify a single interface in the **ip** option. For example, to use DHCP on a NIC that is named **eno1**, set **ip=eno1:dhcp**.
- 3** Specify locations of the RHCOS files that you uploaded to your HTTP server. The **initrd** parameter value is the location of the **initramfs** file, the **coreos.inst.image_url** parameter value is the location of the compressed metal RAW image, and the **coreos.inst.ignition_url** parameter value is the location of the bootstrap Ignition config file.

- For iPXE:

```

kernel http://<HTTP_server>/rhcos-<version>-installer-kernel-<architecture> ip=dhcp
rd.neednet=1 initrd=http://<HTTP_server>/rhcos-<version>-installer-initramfs.
<architecture>.img console=tty0 console=ttyS0 coreos.inst=yes
coreos.inst.install_dev=sda coreos.inst.image_url=http://<HTTP_server>/rhcos-
<version>-metal.<architecture>.raw.gz
coreos.inst.ignition_url=http://<HTTP_server>/bootstrap.ign 1 2
initrd http://<HTTP_server>/rhcos-<version>-installer-initramfs.<architecture>.img 3
boot

```

- 1 Specify locations of the RHCOS files that you uploaded to your HTTP server. The **kernel** parameter value is the location of the **kernel** file, the **initrd** parameter value is the location of the **initramfs** file, the **coreos.inst.image_url** parameter value is the location of the compressed metal RAW image, and the **coreos.inst.ignition_url** parameter value is the location of the bootstrap Ignition config file.
- 2 If you use multiple NICs, specify a single interface in the **ip** option. For example, to use DHCP on a NIC that is named **eno1**, set **ip=eno1:dhcp**.
- 3 Specify the location of the **initramfs** file that you uploaded to your HTTP server.

6. Continue to create the machines for your cluster.



IMPORTANT

You must create the bootstrap and control plane machines at this time. Because some pods are deployed on compute machines by default, also create at least two compute machine before you install the cluster.

1.3.10. Creating the cluster

To create the OpenShift Container Platform cluster, you wait for the bootstrap process to complete on the machines that you provisioned by using the Ignition config files that you generated with the installation program.

Prerequisites

- Create the required infrastructure for the cluster.
- You obtained the installation program and generated the Ignition config files for your cluster.
- You used the Ignition config files to create RHCOS machines for your cluster.

Procedure


1. Monitor the bootstrap process:

```
$ ./openshift-install --dir=<installation_directory> wait-for bootstrap-complete \ 1
--log-level=info 2
INFO Waiting up to 30m0s for the Kubernetes API at https://api.test.example.com...
INFO API v1.16.2 up
INFO Waiting up to 30m0s for bootstrapping to complete...
INFO It is now safe to remove the bootstrap resources
```

- 1 For **<installation_directory>**, specify the path to the directory that you stored the installation files in.
- 2 To view different installation details, specify **warn**, **debug**, or **error** instead of **info**.

The command succeeds when the Kubernetes API server signals that it has been bootstrapped on the control plane machines.

2. After bootstrap process is complete, remove the bootstrap machine from the load balancer.



IMPORTANT

You must remove the bootstrap machine from the load balancer at this point. You can also remove or reformat the machine itself.

1.3.11. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

Prerequisites

- Deploy an OpenShift Container Platform cluster.
- Install the **oc** CLI.

Procedure

1. Export the **kubeadmin** credentials:

```
$ export KUBECONFIG=<installation_directory>/auth/kubeconfig 1
```

- 1** For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

2. Verify you can run **oc** commands successfully using the exported configuration:

```
$ oc whoami
system:admin
```

1.3.12. Approving the CSRs for your machines

When you add machines to a cluster, two pending certificates signing request (CSRs) are generated for each machine that you added. You must confirm that these CSRs are approved or, if necessary, approve them yourself.

Prerequisites

- You added machines to your cluster.

Procedure

1. Confirm that the cluster recognizes the machines:

```
$ oc get nodes

NAME     STATUS    ROLES    AGE   VERSION
master-0 Ready     master   63m   v1.16.2
master-1 Ready     master   63m   v1.16.2
```

```

master-2 Ready    master 64m v1.16.2
worker-0 NotReady worker 76s v1.16.2
worker-1 NotReady worker 70s v1.16.2

```

The output lists all of the machines that you created.

- Review the pending certificate signing requests (CSRs) and ensure that you see a client and server request with **Pending** or **Approved** status for each machine that you added to the cluster:

```

$ oc get csr

NAME          AGE    REQUESTOR                                     CONDITION
csr-8b2br    15m    system:serviceaccount:openshift-machine-config-operator:node-
bootstrapper Pending 1
csr-8vnps    15m    system:serviceaccount:openshift-machine-config-operator:node-
bootstrapper Pending
csr-bfd72    5m26s  system:node:ip-10-0-50-126.us-east-2.compute.internal
Pending 2
csr-c57lv    5m26s  system:node:ip-10-0-95-157.us-east-2.compute.internal
Pending
...

```

- A client request CSR.
- A server request CSR.

In this example, two machines are joining the cluster. You might see more approved CSRs in the list.

- If the CSRs were not approved, after all of the pending CSRs for the machines you added are in **Pending** status, approve the CSRs for your cluster machines:



NOTE

Because the CSRs rotate automatically, approve your CSRs within an hour of adding the machines to the cluster. If you do not approve them within an hour, the certificates will rotate, and more than two certificates will be present for each node. You must approve all of these certificates. After you approve the initial CSRs, the subsequent node client CSRs are automatically approved by the cluster **kube-controller-manager**. You must implement a method of automatically approving the kubelet serving certificate requests.

- To approve them individually, run the following command for each valid CSR:

```
$ oc adm certificate approve <csr_name> 1
```

- <csr_name>** is the name of a CSR from the list of current CSRs.

- To approve all pending CSRs, run the following command:

```
$ oc get csr -o go-template='{{range .items}}{{if not .status}}{{.metadata.name}}{"\n"}
{{end}}{{end}}' | xargs oc adm certificate approve
```

-

1.3.13. Initial Operator configuration

After the control plane initializes, you must immediately configure some Operators so that they all become available.

Prerequisites

- Your control plane has initialized.

Procedure

1. Watch the cluster components come online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED	SINCE
authentication	4.3.0	True	False	False	69s
cloud-credential	4.3.0	True	False	False	12m
cluster-autoscaler	4.3.0	True	False	False	11m
console	4.3.0	True	False	False	46s
dns	4.3.0	True	False	False	11m
image-registry	4.3.0	True	False	False	5m26s
ingress	4.3.0	True	False	False	5m36s
kube-apiserver	4.3.0	True	False	False	8m53s
kube-controller-manager	4.3.0	True	False	False	7m24s
kube-scheduler	4.3.0	True	False	False	12m
machine-api	4.3.0	True	False	False	12m
machine-config	4.3.0	True	False	False	7m36s
marketplace	4.3.0	True	False	False	7m54m
monitoring	4.3.0	True	False	False	7h54s
network	4.3.0	True	False	False	5m9s
node-tuning	4.3.0	True	False	False	11m
openshift-apiserver	4.3.0	True	False	False	11m
openshift-controller-manager	4.3.0	True	False	False	5m943s
openshift-samples	4.3.0	True	False	False	3m55s
operator-lifecycle-manager	4.3.0	True	False	False	11m
operator-lifecycle-manager-catalog	4.3.0	True	False	False	11m
service-ca	4.3.0	True	False	False	11m
service-catalog-apiserver	4.3.0	True	False	False	5m26s
service-catalog-controller-manager	4.3.0	True	False	False	5m25s
storage	4.3.0	True	False	False	5m30s

2. Configure the Operators that are not available.

1.3.13.1. Image registry storage configuration

The **image-registry** Operator is not initially available for platforms that do not provide default storage. After installation, you must configure your registry to use storage so the Registry Operator is made available.

Instructions for both configuring a PersistentVolume, which is required for production clusters, and for configuring an empty directory as the storage location, which is available for only non-production clusters, are shown.

1.3.13.1.1. Configuring registry storage for bare metal


As a cluster administrator, following installation you must configure your registry to use storage.

Prerequisites

- Cluster administrator permissions.
- A cluster on bare metal.
- Provision persistent storage for your cluster, such as Red Hat OpenShift Container Storage. To deploy a private image registry, your storage must provide ReadWriteMany access mode.
- Must have "100Gi" capacity.

Procedure

1. To configure your registry to use storage, change the **spec.storage.pvc** in the **configs.imageregistry/cluster** resource.



NOTE

When using shared storage such as NFS, it is strongly recommended to use the **supplementalGroups** strategy, which dictates the allowable supplemental groups for the Security Context, rather than the **fsGroup** ID. Refer to the **NFS Group IDs** documentation for details.

2. Verify you do not have a registry Pod:

```
$ oc get pod -n openshift-image-registry
```



NOTE

- If the storage type is **emptyDIR**, the replica number cannot be greater than **1**.
- If the storage type is **NFS**, you must enable the **no_wdelay** and **root_squash** mount options. For example:

```
# cat /etc/exports
/mnt/data *(rw,sync,no_wdelay,root_squash,insecure,fsid=0)
sh-4.3# exportfs -rv
exporting */mnt/data
```

3. Check the registry configuration:

```
$ oc edit configs.imageregistry.operator.openshift.io

storage:
  pvc:
    claim:
```

Leave the **claim** field blank to allow the automatic creation of an **image-registry-storage** PVC.

4. Check the **clusteroperator** status:

```
$ oc get clusteroperator image-registry
```

1.3.13.1.2. Configuring storage for the image registry in non-production clusters

You must configure storage for the image registry Operator. For non-production clusters, you can set the image registry to an empty directory. If you do so, all images are lost if you restart the registry.

Procedure

- To set the image registry storage to an empty directory:

```
$ oc patch configs.imageregistry.operator.openshift.io cluster --type merge --patch '{"spec": {"storage":{"emptyDir":{}}}'
```



WARNING

Configure this option for only non-production clusters.

If you run this command before the Image Registry Operator initializes its components, the **oc patch** command fails with the following error:

```
Error from server (NotFound): configs.imageregistry.operator.openshift.io "cluster" not found
```

Wait a few minutes and run the command again.

1.3.14. Completing installation on user-provisioned infrastructure

After you complete the Operator configuration, you can finish installing the cluster on infrastructure that you provide.

Prerequisites

- Your control plane has initialized.
- You have completed the initial Operator configuration.

Procedure

1. Confirm that all the cluster components are online:

```
$ watch -n5 oc get clusteroperators
```

NAME	VERSION	AVAILABLE	PROGRESSING	DEGRADED
authentication	4.3.0	True	False	False
cloud-credential	4.3.0	True	False	False

cluster-autoscaler	4.3.0	True	False	False	21m
console	4.3.0	True	False	False	10m
dns	4.3.0	True	False	False	21m
image-registry	4.3.0	True	False	False	16m
ingress	4.3.0	True	False	False	16m
kube-apiserver	4.3.0	True	False	False	19m
kube-controller-manager	4.3.0	True	False	False	18m
kube-scheduler	4.3.0	True	False	False	22m
machine-api	4.3.0	True	False	False	22m
machine-config	4.3.0	True	False	False	18m
marketplace	4.3.0	True	False	False	18m
monitoring	4.3.0	True	False	False	18m
network	4.3.0	True	False	False	16m
node-tuning	4.3.0	True	False	False	21m
openshift-apiserver	4.3.0	True	False	False	21m
openshift-controller-manager	4.3.0	True	False	False	17m
openshift-samples	4.3.0	True	False	False	14m
operator-lifecycle-manager	4.3.0	True	False	False	21m
operator-lifecycle-manager-catalog	4.3.0	True	False	False	21m
service-ca	4.3.0	True	False	False	21m
service-catalog-apiserver	4.3.0	True	False	False	16m
service-catalog-controller-manager	4.3.0	True	False	False	16m
storage	4.3.0	True	False	False	16m

When all of the cluster Operators are **AVAILABLE**, you can complete the installation.

2. Monitor for cluster completion:

```
$ ./openshift-install --dir=<installation_directory> wait-for install-complete 1
INFO Waiting up to 30m0s for the cluster to initialize...
```

- 1 For **<installation_directory>**, specify the path to the directory that you stored the installation files in.

The command succeeds when the Cluster Version Operator finishes deploying the OpenShift Container Platform cluster from Kubernetes API server.



IMPORTANT

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

3. Confirm that the Kubernetes API server is communicating with the Pods.

- a. To view a list of all Pods, use the following command:

```
$ oc get pods --all-namespaces

NAMESPACE          NAME                                     READY  STATUS
RESTARTS  AGE
openshift-apiserver-operator  openshift-apiserver-operator-85cb746d55-zqhs8  1/1
Running      1      9m
```

```
openshift-apiserver      apiserver-67b9g          1/1   Running   0
3m
openshift-apiserver      apiserver-ljcmx          1/1   Running   0
1m
openshift-apiserver      apiserver-z25h4          1/1   Running   0
2m
openshift-authentication-operator authentication-operator-69d5d8bf84-vh2n8 1/1
Running   0      5m
...
```

- b. View the logs for a Pod that is listed in the output of the previous command by using the following command:

```
$ oc logs <pod_name> -n <namespace> 1
```

- 1** Specify the Pod name and namespace, as shown in the output of the previous command.

If the Pod logs display, the Kubernetes API server can communicate with the cluster machines.

4. Register your cluster on the [Cluster registration](#) page.

1.3.15. Next steps

- [Customize your cluster](#).
- If necessary, you can [opt out of remote health reporting](#).