



Red Hat OpenStack Platform 11

Director Installation and Usage

An end-to-end scenario on using Red Hat OpenStack Platform director to create an OpenStack cloud

Red Hat OpenStack Platform 11 Director Installation and Usage

An end-to-end scenario on using Red Hat OpenStack Platform director to create an OpenStack cloud

OpenStack Team
rhos-docs@redhat.com

Legal Notice

Copyright © 2018 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This guide explains how to install Red Hat OpenStack Platform 11 in an enterprise environment using the Red Hat OpenStack Platform director. This includes installing the director, planning your environment, and creating an OpenStack environment with the director.

Table of Contents

CHAPTER 1. INTRODUCTION	6
1.1. UNDERCLOUD	6
1.2. OVERCLOUD	7
1.3. HIGH AVAILABILITY	9
1.4. CEPH STORAGE	9
CHAPTER 2. REQUIREMENTS	11
2.1. ENVIRONMENT REQUIREMENTS	11
2.2. UNDERCLOUD REQUIREMENTS	12
2.2.1. Virtualization Support	12
2.3. NETWORKING REQUIREMENTS	14
2.4. OVERCLOUD REQUIREMENTS	16
2.4.1. Compute Node Requirements	17
2.4.2. Controller Node Requirements	17
2.4.3. Ceph Storage Node Requirements	18
2.4.4. Object Storage Node Requirements	19
2.5. REPOSITORY REQUIREMENTS	19
CHAPTER 3. PLANNING YOUR OVERCLOUD	22
3.1. PLANNING NODE DEPLOYMENT ROLES	22
3.2. PLANNING NETWORKS	23
3.3. PLANNING STORAGE	27
CHAPTER 4. INSTALLING THE UNDERCLOUD	29
4.1. CREATING A DIRECTOR INSTALLATION USER	29
4.2. CREATING DIRECTORIES FOR TEMPLATES AND IMAGES	29
4.3. SETTING THE HOSTNAME FOR THE SYSTEM	29
4.4. REGISTERING YOUR SYSTEM	30
4.5. INSTALLING THE DIRECTOR PACKAGES	31
4.6. CONFIGURING THE DIRECTOR	31
4.7. OBTAINING IMAGES FOR OVERCLOUD NODES	36
4.8. SETTING A NAMESERVER ON THE UNDERCLOUD'S NEUTRON SUBNET	37
4.9. BACKING UP THE UNDERCLOUD	37
4.10. COMPLETING THE UNDERCLOUD CONFIGURATION	37
CHAPTER 5. CONFIGURING A BASIC OVERCLOUD WITH THE CLI TOOLS	38
5.1. REGISTERING NODES FOR THE OVERCLOUD	38
5.2. INSPECTING THE HARDWARE OF NODES	40
5.3. TAGGING NODES INTO PROFILES	41
5.4. DEFINING THE ROOT DISK FOR NODES	43
5.5. CUSTOMIZING THE OVERCLOUD	44
5.6. CREATING THE OVERCLOUD WITH THE CLI TOOLS	45
5.7. INCLUDING ENVIRONMENT FILES IN OVERCLOUD CREATION	49
5.8. MANAGING OVERCLOUD PLANS	51
5.9. VALIDATING OVERCLOUD TEMPLATES AND PLANS	52
5.10. MONITORING THE OVERCLOUD CREATION	53
5.11. ACCESSING THE OVERCLOUD	53
5.12. COMPLETING THE OVERCLOUD CREATION	53
CHAPTER 6. CONFIGURING A BASIC OVERCLOUD WITH THE WEB UI	55
6.1. ACCESSING THE WEB UI	55
6.2. NAVIGATING THE WEB UI	57
6.3. IMPORTING AN OVERCLOUD PLAN IN THE WEB UI	58

6.4. REGISTERING NODES IN THE WEB UI	59
6.5. INSPECTING THE HARDWARE OF NODES IN THE WEB UI	61
6.6. EDITING OVERCLOUD PLAN PARAMETERS IN THE WEB UI	62
6.7. TAGGING NODES INTO ROLES IN THE WEB UI	63
6.8. EDITING NODES IN THE WEB UI	64
6.9. STARTING THE OVERCLOUD CREATION IN THE WEB UI	67
6.10. COMPLETING THE OVERCLOUD CREATION	68
CHAPTER 7. CONFIGURING A BASIC OVERCLOUD USING PRE-PROVISIONED NODES	69
7.1. CREATING A USER FOR CONFIGURING NODES	70
7.2. REGISTERING THE OPERATING SYSTEM FOR NODES	70
7.3. INSTALLING THE USER AGENT ON NODES	71
7.4. CONFIGURING SSL/TLS ACCESS TO THE DIRECTOR	71
7.5. CONFIGURING NETWORKING FOR THE CONTROL PLANE	72
7.6. USING A SEPARATE NETWORK FOR OVERCLOUD NODES	73
7.7. CREATING THE OVERCLOUD WITH PRE-PROVISIONED NODES	75
7.8. POLLING THE METADATA SERVER	77
7.9. MONITORING THE OVERCLOUD CREATION	79
7.10. ACCESSING THE OVERCLOUD	79
7.11. SCALING PRE-PROVISIONED NODES	79
7.12. REMOVING A PRE-PROVISIONED OVERCLOUD	80
7.13. COMPLETING THE OVERCLOUD CREATION	80
CHAPTER 8. PERFORMING TASKS AFTER OVERCLOUD CREATION	81
8.1. CREATING THE OVERCLOUD TENANT NETWORK	81
8.2. CREATING THE OVERCLOUD EXTERNAL NETWORK	81
8.3. CREATING ADDITIONAL FLOATING IP NETWORKS	82
8.4. CREATING THE OVERCLOUD PROVIDER NETWORK	83
8.5. VALIDATING THE OVERCLOUD	83
8.6. MODIFYING THE OVERCLOUD ENVIRONMENT	84
8.7. IMPORTING VIRTUAL MACHINES INTO THE OVERCLOUD	85
8.8. MIGRATING VMS FROM AN OVERCLOUD COMPUTE NODE	85
8.9. RUNNING ANSIBLE AUTOMATION	86
8.10. PROTECTING THE OVERCLOUD FROM REMOVAL	88
8.11. REMOVING THE OVERCLOUD	88
8.12. REVIEW THE TOKEN FLUSH INTERVAL	88
CHAPTER 9. SCALING THE OVERCLOUD	90
9.1. ADDING ADDITIONAL NODES	90
9.2. REMOVING COMPUTE NODES	92
9.3. REPLACING COMPUTE NODES	93
9.4. REPLACING CONTROLLER NODES	94
9.4.1. Preliminary Checks	94
9.4.2. Node Replacement	95
9.4.3. Manual Intervention	97
9.4.4. Finalizing Overcloud Services	102
9.4.5. Finalizing L3 Agent Router Hosting	103
9.4.6. Finalizing Compute Services	103
9.4.7. Conclusion	104
9.5. REPLACING CEPH STORAGE NODES	104
9.6. REPLACING OBJECT STORAGE NODES	104
CHAPTER 10. REBOOTING NODES	106
10.1. REBOOTING THE DIRECTOR	106


10.2. REBOOTING CONTROLLER NODES	106
10.3. REBOOTING CEPH STORAGE NODES	107
10.4. REBOOTING COMPUTE NODES	108
10.5. REBOOTING OBJECT STORAGE NODES	109
CHAPTER 11. TROUBLESHOOTING DIRECTOR ISSUES	110
11.1. TROUBLESHOOTING NODE REGISTRATION	110
11.2. TROUBLESHOOTING HARDWARE INTROSPECTION	110
11.3. TROUBLESHOOTING WORKFLOWS AND EXECUTIONS	112
11.4. TROUBLESHOOTING OVERCLOUD CREATION	113
11.4.1. Orchestration	113
11.4.2. Bare Metal Provisioning	114
11.4.3. Post-Deployment Configuration	115
11.5. TROUBLESHOOTING IP ADDRESS CONFLICTS ON THE PROVISIONING NETWORK	117
11.6. TROUBLESHOOTING "NO VALID HOST FOUND" ERRORS	117
11.7. TROUBLESHOOTING THE OVERCLOUD AFTER CREATION	118
11.7.1. Overcloud Stack Modifications	118
11.7.2. Controller Service Failures	119
11.7.3. Compute Service Failures	119
11.7.4. Ceph Storage Service Failures	120
11.8. TUNING THE UNDERCLOUD	120
11.9. IMPORTANT LOGS FOR UNDERCLOUD AND OVERCLOUD	121
APPENDIX A. SSL/TLS CERTIFICATE CONFIGURATION	123
A.1. INITIALIZING THE SIGNING HOST	123
A.2. CREATING A CERTIFICATE AUTHORITY	123
A.3. ADDING THE CERTIFICATE AUTHORITY TO CLIENTS	123
A.4. CREATING AN SSL/TLS KEY	124
A.5. CREATING AN SSL/TLS CERTIFICATE SIGNING REQUEST	124
A.6. CREATING THE SSL/TLS CERTIFICATE	125
A.7. USING THE CERTIFICATE WITH THE UNDERCLOUD	125
APPENDIX B. POWER MANAGEMENT DRIVERS	127
B.1. DELL REMOTE ACCESS CONTROLLER (DRAC)	127
B.2. INTEGRATED LIGHTS-OUT (ILO)	127
B.3. CISCO UNIFIED COMPUTING SYSTEM (UCS)	128
B.4. FUJITSU INTEGRATED REMOTE MANAGEMENT CONTROLLER (IRMC)	128
B.5. VIRTUAL BARE METAL CONTROLLER (VBMC)	129
B.6. SSH AND VIRSH	131
B.7. FAKE PXE DRIVER	132
APPENDIX C. WHOLE DISK IMAGES	133
C.1. CREATING WHOLE DISK IMAGES	133
C.2. MANUALLY CREATING A WHOLE DISK IMAGE	133
C.3. AUTOMATICALLY CREATING A WHOLE DISK IMAGE	134
C.4. ENCRYPTING VOLUMES ON WHOLE DISK IMAGES	137
C.5. UPLOADING WHOLE DISK IMAGES	140
APPENDIX D. ALTERNATIVE BOOT MODES	141
D.1. STANDARD PXE	141
D.2. UEFI BOOT MODE	141
APPENDIX E. AUTOMATIC PROFILE TAGGING	142
E.1. POLICY FILE SYNTAX	142
E.2. POLICY FILE EXAMPLE	143

E.3. IMPORTING POLICY FILES	145
E.4. AUTOMATIC PROFILE TAGGING PROPERTIES	145
APPENDIX F. SECURITY ENHANCEMENTS	147
F.1. CHANGING THE SSL/TLS CIPHER AND RULES FOR HAPROXY	147

CHAPTER 1. INTRODUCTION

The Red Hat OpenStack Platform director is a toolset for installing and managing a complete OpenStack environment. It is based primarily on the OpenStack project TripleO, which is an abbreviation for "OpenStack-On-OpenStack". This project takes advantage of OpenStack components to install a fully operational OpenStack environment. This includes new OpenStack components that provision and control bare metal systems to use as OpenStack nodes. This provides a simple method for installing a complete Red Hat OpenStack Platform environment that is both lean and robust.

The Red Hat OpenStack Platform director uses two main concepts: an undercloud and an overcloud. The undercloud installs and configures the overcloud. The next few sections outline the concept of each.



1.1. UNDERCLOUD

The undercloud is the main director node. It is a single-system OpenStack installation that includes components for provisioning and managing the OpenStack nodes that form your OpenStack environment (the overcloud). The components that form the undercloud provide the multiple functions:

Environment Planning

The undercloud provides planning functions for users to create and assign certain node roles. The undercloud includes a default set of nodes such as Compute, Controller, and various storage roles, but also provides the ability to use custom roles. In addition, you can select which OpenStack Platform services to include on each node role, which provides a method to model new node types or isolate certain components on their own host.

Bare Metal System Control

The undercloud uses out-of-band management interface, usually Intelligent Platform Management Interface (IPMI), of each node for power management control and a PXE-based service to discover hardware attributes and install OpenStack to each node. This provides a method to provision bare metal systems as OpenStack nodes. See [Appendix B, Power Management Drivers](#) for a full list of power management drivers.

Orchestration

The undercloud provides a set of YAML templates that acts as a set of plans for your environment. The undercloud imports these plans and follows their instructions to create the resulting OpenStack environment. The plans also include hooks that allow you to incorporate your own customizations as certain points in the environment creation process.

Command Line Tools and a Web UI

The Red Hat OpenStack Platform director performs these undercloud functions through a terminal-based command line interface or a web-based user interface.

Undercloud Components

The undercloud uses OpenStack components as its base tool set. This includes the following components:

- OpenStack Identity (keystone) - Provides authentication and authorization for the director's components.
- OpenStack Bare Metal (ironic) and OpenStack Compute (nova) - Manages bare metal nodes.
- OpenStack Networking (neutron) and Open vSwitch - Controls networking for bare metal nodes.
- OpenStack Image Service (glance) - Stores images that are written to bare metal machines.
- OpenStack Orchestration (heat) and Puppet - Provides orchestration of nodes and configuration of nodes after the director writes the overcloud image to disk.
- OpenStack Telemetry (ceilometer) - Performs monitoring and data collection. This also includes:
 - OpenStack Telemetry Metrics (gnocchi) - Provides a time series database for metrics.
 - OpenStack Telemetry Alarming (aodh) - Provides an alarming component for monitoring.
 - OpenStack Telemetry Event Storage (panko) - Provides event storage for monitoring.
- OpenStack Workflow Service (mistral) - Provides a set of workflows for certain director-specific actions, such as importing and deploying plans.
- OpenStack Messaging Service (zaqar) - Provides a messaging service for the OpenStack Workflow Service.
- OpenStack Object Storage (swift) - Provides object storage for various OpenStack Platform components, including:
 - Image storage for OpenStack Image Service
 - Introspection data for OpenStack Bare Metal
 - Deployment plans for OpenStack Workflow Service

1.2. OVERCLOUD

The overcloud is the resulting Red Hat OpenStack Platform environment created using the undercloud. This includes different nodes roles which you define based on the OpenStack Platform environment you aim to create. The undercloud includes a default set of overcloud node roles, which include:

Controller

Nodes that provide administration, networking, and high availability for the OpenStack environment. An ideal OpenStack environment recommends three of these nodes together in a high availability cluster.

A default Controller node contains the following components:

- OpenStack Dashboard (horizon)
- OpenStack Identity (keystone)
- OpenStack Compute (nova) API
- OpenStack Networking (neutron)
- OpenStack Image Service (glance)
- OpenStack Block Storage (cinder)
- OpenStack Object Storage (swift)
- OpenStack Orchestration (heat)
- OpenStack Telemetry (ceilometer)
- OpenStack Telemetry Metrics (gnocchi)
- OpenStack Telemetry Alarming (aodh)
- OpenStack Clustering (sahara)
- OpenStack Shared File Systems (manila)
- OpenStack Bare Metal (ironic)
- MariaDB
- Open vSwitch
- Pacemaker and Galera for high availability services.

Compute

These nodes provide computing resources for the OpenStack environment. You can add more Compute nodes to scale out your environment over time. A default Compute node contains the following components:

- OpenStack Compute (nova)
- KVM/QEMU
- OpenStack Telemetry (ceilometer) agent
- Open vSwitch

Storage

Nodes that provide storage for the OpenStack environment. This includes nodes for:

- Ceph Storage nodes - Used to form storage clusters. Each node contains a Ceph Object Storage Daemon (OSD). In addition, the director installs Ceph Monitor onto the Controller nodes in situations where it deploys Ceph Storage nodes.
- Block storage (cinder) - Used as external block storage for HA Controller nodes. This node contains the following components:

- OpenStack Block Storage (cinder) volume
- OpenStack Telemetry (ceilometer) agent
- Open vSwitch.
- Object storage (swift) - These nodes provide a external storage layer for OpenStack Swift. The Controller nodes access these nodes through the Swift proxy. This node contains the following components:
 - OpenStack Object Storage (swift) storage
 - OpenStack Telemetry (ceilometer) agent
 - Open vSwitch.

1.3. HIGH AVAILABILITY

The Red Hat OpenStack Platform director uses a Controller node cluster to provide high availability services to your OpenStack Platform environment. The director installs a duplicate set of components on each Controller node and manages them together as a single service. This type of cluster configuration provides a fallback in the event of operational failures on a single Controller node; this provides OpenStack users with a certain degree of continuous operation.

The OpenStack Platform director uses some key pieces of software to manage components on the Controller node:

- Pacemaker - Pacemaker is a cluster resource manager. Pacemaker manages and monitors the availability of OpenStack components across all nodes in the cluster.
- HAProxy - Provides load balancing and proxy services to the cluster.
- Galera - Replicates the Red Hat OpenStack Platform database across the cluster.
- Memcached - Provides database caching.



NOTE

Red Hat OpenStack Platform director automatically configures the bulk of high availability on Controller nodes. However, the nodes require some manual configuration to enable power management controls. This guide includes these instructions.

1.4. CEPH STORAGE

It is common for large organizations using OpenStack to serve thousands of clients or more. Each OpenStack client is likely to have their own unique needs when consuming block storage resources. Deploying glance (images), cinder (volumes) and/or nova (Compute) on a single node can become impossible to manage in large deployments with thousands of clients. Scaling OpenStack externally resolves this challenge.

However, there is also a practical requirement to virtualize the storage layer with a solution like Red Hat Ceph Storage so that you can scale the Red Hat OpenStack Platform storage layer from tens of terabytes to petabytes (or even exabytes) of storage. Red Hat Ceph Storage provides this storage virtualization layer with high availability and high performance while running on commodity hardware. While virtualization might seem like it comes with a performance penalty, Ceph stripes block device

images as objects across the cluster; this means large Ceph Block Device images have better performance than a standalone disk. Ceph Block devices also support caching, copy-on-write cloning, and copy-on-read cloning for enhanced performance.

See [Red Hat Ceph Storage](#) for additional information about Red Hat Ceph Storage.

CHAPTER 2. REQUIREMENTS

This chapter outlines the main requirements for setting up an environment to provision Red Hat OpenStack Platform using the director. This includes the requirements for setting up the director, accessing it, and the hardware requirements for hosts that the director provisions for OpenStack services.



NOTE

Prior to deploying Red Hat OpenStack Platform, it is important to consider the characteristics of the available deployment methods. For more information, refer to the [Installing and Managing Red Hat OpenStack Platform](#).

2.1. ENVIRONMENT REQUIREMENTS

Minimum Requirements:

- 1 host machine for the Red Hat OpenStack Platform director
- 1 host machine for a Red Hat OpenStack Platform Compute node
- 1 host machine for a Red Hat OpenStack Platform Controller node

Recommended Requirements:

- 1 host machine for the Red Hat OpenStack Platform director
- 3 host machines for Red Hat OpenStack Platform Compute nodes
- 3 host machines for Red Hat OpenStack Platform Controller nodes in a cluster
- 3 host machines for Red Hat Ceph Storage nodes in a cluster

Note the following:

- It is recommended to use bare metal systems for all nodes. At minimum, the Compute nodes require bare metal systems.
- All overcloud bare metal systems require an Intelligent Platform Management Interface (IPMI). This is because the director controls the power management.
- Set the each node's internal BIOS clock to UTC. This prevents issues with future-dated file timestamps when **hwclock** synchronizes the BIOS clock before applying the timezone offset.



WARNING

Do not upgrade to the Red Hat Enterprise Linux 7.3 kernel without also upgrading from Open vSwitch (OVS) 2.4.0 to OVS 2.5.0. If only the kernel is upgraded, then OVS will stop functioning.

2.2. UNDERCLOUD REQUIREMENTS


The undercloud system hosting the director provides provisioning and management for all nodes in the overcloud.

- An 8-core 64-bit x86 processor with support for the Intel 64 or AMD64 CPU extensions.
- A minimum of 16 GB of RAM.
- A minimum of 40 GB of available disk space on the root disk. Make sure to leave at least 10 GB free space before attempting an overcloud deployment or update. This free space accommodates image conversion and caching during the node provisioning process.
- A minimum of 2 x 1 Gbps Network Interface Cards. However, it is recommended to use a 10 Gbps interface for Provisioning network traffic, especially if provisioning a large number of nodes in your overcloud environment.
- Red Hat Enterprise Linux 7.3 installed as the host operating system.
- SELinux is enabled on the host.

2.2.1. Virtualization Support

Red Hat only supports a virtualized undercloud on the following platforms:

Platform	Notes
Kernel-based Virtual Machine (KVM)	Hosted by Red Hat Enterprise Linux 5, 6, and 7 as listed on certified hypervisors
Red Hat Enterprise Virtualization	Hosted by Red Hat Enterprise Virtualization 3.0, 3.1, 3.2, 3.3, 3.4, 3.5, 3.6, and 4.0 as listed on certified hypervisors
Microsoft Hyper-V	Hosted by versions of Hyper-V as listed on the Red Hat Customer Portal Certification Catalogue .
VMware ESX and ESXi	Hosted by versions of ESX and ESXi as listed on the Red Hat Customer Portal Certification Catalogue .



IMPORTANT

Red Hat OpenStack Platform director 11 requires the latest version of Red Hat Enterprise Linux as the host operating system. This means your virtualization platform must also support the underlying Red Hat Enterprise Linux version.

Virtual Machine Requirements

Resource requirements for a virtual undercloud are similar to those of a bare metal undercloud. You should consider the various tuning options when provisioning such as network model, guest CPU capabilities, storage backend, storage format, and caching mode.

Network Considerations

Note the following network considerations for your virtualized undercloud:

Power Management

The undercloud VM requires access to the overcloud nodes' power management devices. This is the IP address set for the **pm_addr** parameter when registering nodes.

Provisioning network

The NIC used for the provisioning (**ctlplane**) network requires the ability to broadcast and serve DHCP requests to the NICs of the overcloud's bare metal nodes. As a recommendation, create a bridge that connects the VM's NIC to the same network as the bare metal NICs.



NOTE

A common problem occurs when the hypervisor technology blocks the undercloud from transmitting traffic from an unknown address. - If using Red Hat Enterprise Virtualization, disable **anti-mac-spoofing** to prevent this. - If using VMware ESX or ESXi, allow forged transmits to prevent this.

Example Architecture

This is just an example of a basic undercloud virtualization architecture using a KVM server. It is intended as a foundation you can build on depending on your network and resource requirements.

The KVM host uses two Linux bridges:

br-ex (eth0)

- Provides outside access to the undercloud
- DHCP server on outside network assigns network configuration to undercloud using the virtual NIC (eth0)
- Provides access for the undercloud to access the power management interfaces for the bare metal servers

br-ctlplane (eth1)

- Connects to the same network as the bare metal overcloud nodes
- Undercloud fulfills DHCP and PXE boot requests through virtual NIC (eth1)
- Bare metal servers for the overcloud boot through PXE over this network

The KVM host requires the following packages:

```
$ yum install libvirt-client libvirt-daemon qemu-kvm libvirt-daemon-
driver-qemu libvirt-daemon-kvm virt-install bridge-utils rsync
```

The following command creates the undercloud virtual machine on the KVM host and create two virtual NICs that connect to the respective bridges:

```
$ virt-install --name undercloud --memory=16384 --vcpus=4 --location
/var/lib/libvirt/images/rhel-server-7.3-x86_64-dvd.iso --disk size=100 --
network bridge=br-ex --network bridge=br-ctlplane --graphics=vnc --hvm --
os-variant=rhel7
```

This starts a **libvirt** domain. Connect to it with **virt-manager** and walk through the install process. Alternatively, you can perform an unattended installation using the following options to include a kickstart file:

```
--initrd-inject=/root/ks.cfg --extra-args "ks=file:/ks.cfg"
```

Once installation completes, SSH into the instance as the **root** user and follow the instructions in [Chapter 4, Installing the Undercloud](#)

Backups

To back up a virtualized undercloud, there are multiple solutions:

- **Option 1:** Follow the instructions in the [Back Up and Restore the Director Undercloud](#) Guide.
- **Option 2:** Shut down the undercloud and take a copy of the undercloud virtual machine storage backing.
- **Option 3:** Take a snapshot of the undercloud VM if your hypervisor supports live or atomic snapshots.

If using a KVM server, use the following procedure to take a snapshot:

1. Make sure **qemu-guest-agent** is running on the undercloud guest VM.
2. Create a live snapshot of the running VM:

```
$ virsh snapshot-create-as --domain undercloud --disk-only --atomic --quiesce
```

1. Take a copy of the (now read-only) QCOW backing file

```
$ rsync --sparse -avh --progress /var/lib/libvirt/images/undercloud.qcow2 1.qcow2
```

1. Merge the QCOW overlay file into the backing file and switch the undercloud VM back to using the original file:

```
$ virsh blockcommit undercloud vda --active --verbose --pivot
```

2.3. NETWORKING REQUIREMENTS

The undercloud host requires at least two networks:

- **Provisioning network** - Provides DHCP and PXE boot functions to help discover bare metal systems for use in the overcloud. Typically, this network must use a native VLAN on a trunked interface so that the director serves PXE boot and DHCP requests. Some server hardware BIOSes support PXE boot from a VLAN, but the BIOS must also support translating that VLAN into a native VLAN after booting, otherwise the undercloud will not be reachable. Currently, only a small subset of server hardware fully supports this feature. This is also the network you use to control power management through Intelligent Platform Management Interface (IPMI) on all overcloud nodes.

- External Network - A separate network for external access to the overcloud and undercloud. The interface connecting to this network requires a routable IP address, either defined statically, or dynamically through an external DHCP service.

This represents the minimum number of networks required. However, the director can isolate other Red Hat OpenStack Platform network traffic into other networks. Red Hat OpenStack Platform supports both physical interfaces and tagged VLANs for network isolation.

Note the following:

- Typical minimal overcloud network configuration can include:
 - Single NIC configuration - One NIC for the Provisioning network on the native VLAN and tagged VLANs that use subnets for the different overcloud network types.
 - Dual NIC configuration - One NIC for the Provisioning network and the other NIC for the External network.
 - Dual NIC configuration - One NIC for the Provisioning network on the native VLAN and the other NIC for tagged VLANs that use subnets for the different overcloud network types.
 - Multiple NIC configuration - Each NIC uses a subnet for a different overcloud network type.
- Additional physical NICs can be used for isolating individual networks, creating bonded interfaces, or for delegating tagged VLAN traffic.
- If using VLANs to isolate your network traffic types, use a switch that supports 802.1Q standards to provide tagged VLANs.
- During the overcloud creation, you will refer to NICs using a single name across all overcloud machines. Ideally, you should use the same NIC on each overcloud node for each respective network to avoid confusion. For example, use the primary NIC for the Provisioning network and the secondary NIC for the OpenStack services.
- Make sure the Provisioning network NIC is not the same NIC used for remote connectivity on the director machine. The director installation creates a bridge using the Provisioning NIC, which drops any remote connections. Use the External NIC for remote connections to the director system.
- The Provisioning network requires an IP range that fits your environment size. Use the following guidelines to determine the total number of IP addresses to include in this range:
 - Include at least one IP address per node connected to the Provisioning network.
 - If planning a high availability configuration, include an extra IP address for the virtual IP of the cluster.
 - Include additional IP addresses within the range for scaling the environment.



NOTE

Duplicate IP addresses should be avoided on the Provisioning network. For more information, see [Section 3.2, “Planning Networks”](#).

**NOTE**

For more information on planning your IP address usage, for example, for storage, provider, and tenant networks, see [the Networking Guide](#).

- Set all overcloud systems to PXE boot off the Provisioning NIC, and disable PXE boot on the External NIC (and any other NICs on the system). Also ensure that the Provisioning NIC has PXE boot at the top of the boot order, ahead of hard disks and CD/DVD drives.
- All overcloud bare metal systems require a supported power management interface, such as an Intelligent Platform Management Interface (IPMI). This allows the director to control the power management of each node.
- Make a note of the following details for each overcloud system: the MAC address of the Provisioning NIC, the IP address of the IPMI NIC, IPMI username, and IPMI password. This information will be useful later when setting up the overcloud nodes.
- If an instance needs to be accessible from the external internet, you can allocate a floating IP address from a public network and associate it with an instance. The instance still retains its private IP but network traffic uses NAT to traverse through to the floating IP address. Note that a floating IP address can only be assigned to a single instance rather than multiple private IP addresses. However, the floating IP address is reserved only for use by a single tenant, allowing the tenant to associate or disassociate with a particular instance as required. This configuration exposes your infrastructure to the external internet. As a result, you might need to check that you are following suitable security practices.
- To mitigate the risk of network loops in Open vSwitch, only a single interface or a single bond may be a member of a given bridge. If you require multiple bonds or interfaces, you can configure multiple bridges.
- It is recommended to use DNS hostname resolution so that your overcloud nodes can connect to external services, such as the Red Hat Content Delivery Network and network time servers.

IMPORTANT

Your OpenStack Platform implementation is only as secure as its environment. Follow good security principles in your networking environment to ensure that network access is properly controlled. For example:

- Use network segmentation to mitigate network movement and isolate sensitive data; a flat network is much less secure.
- Restrict services access and ports to a minimum.
- Ensure proper firewall rules and password usage.
- Ensure that SELinux is enabled.

For details on securing your system, see:

- [Red Hat Enterprise Linux 7 Security Guide](#)
- [Red Hat Enterprise Linux 7 SELinux User's and Administrator's Guide](#)

2.4. OVERCLOUD REQUIREMENTS

The following sections detail the requirements for individual systems and nodes in the overcloud installation.



NOTE

Booting an overcloud node from the SAN (FC-AL, FCoE, iSCSI) is not yet supported.

2.4.1. Compute Node Requirements

Compute nodes are responsible for running virtual machine instances after they are launched. Compute nodes must support hardware virtualization. Compute nodes must also have enough memory and disk space to support the requirements of the virtual machine instances they host.

Processor

64-bit x86 processor with support for the Intel 64 or AMD64 CPU extensions, and the AMD-V or Intel VT hardware virtualization extensions enabled. It is recommended this processor has a minimum of 4 cores.

Memory

A minimum of 6 GB of RAM. + Add additional RAM to this requirement based on the amount of memory that you intend to make available to virtual machine instances.

Disk Space

A minimum of 40 GB of available disk space.

Network Interface Cards

A minimum of one 1 Gbps Network Interface Cards, although it is recommended to use at least two NICs in a production environment. Use additional network interface cards for bonded interfaces or to delegate tagged VLAN traffic.

Power Management

Each Controller node requires a supported power management interface, such as an Intelligent Platform Management Interface (IPMI) functionality, on the server's motherboard.

2.4.2. Controller Node Requirements

Controller nodes are responsible for hosting the core services in a RHEL OpenStack Platform environment, such as the Horizon dashboard, the back-end database server, Keystone authentication, and High Availability services.

Processor

64-bit x86 processor with support for the Intel 64 or AMD64 CPU extensions.

Memory

Minimum amount of memory is 32 GB. However, the amount of recommended memory depends on the number of vCPUs (which is based on CPU cores multiplied by hyper-threading value). Use the following calculations as guidance:

- **Controller RAM minimum calculation:**
 - Use 1.5 GB of memory per vCPU. For example, a machine with 48 vCPUs should have 72 GB of RAM.
- **Controller RAM recommended calculation:**
 - Use 3 GB of memory per vCPU. For example, a machine with 48 vCPUs should have 144 GB of RAM

For more information on measuring memory requirements, see ["Red Hat OpenStack Platform Hardware Requirements for Highly Available Controllers"](#) on the Red Hat Customer Portal.

Disk Storage and Layout

By default, the Telemetry (**gnocchi**) and Object Storage (**swift**) services are both installed on the Controller, with both configured to use the root disk. These defaults are suitable for deploying small overclouds built on commodity hardware; such environments are typical of proof-of-concept and test environments. These defaults also allow the deployment of overclouds with minimal planning but offer little in terms of workload capacity and performance.

In an enterprise environment, however, this could cause a significant bottleneck, as Telemetry accesses storage constantly. This results in heavy disk I/O usage, which severely impacts the performance of all other Controller services. In this type of environment, you need to plan your overcloud and configure it accordingly.

Red Hat provides several configuration recommendations for both Telemetry and Object Storage. See [Deployment Recommendations for Specific Red Hat OpenStack Platform Services](#) for details.

Network Interface Cards

A minimum of 2 x 1 Gbps Network Interface Cards. Use additional network interface cards for bonded interfaces or to delegate tagged VLAN traffic.

Power Management

Each Controller node requires a supported power management interface, such as an Intelligent Platform Management Interface (IPMI) functionality, on the server's motherboard.

2.4.3. Ceph Storage Node Requirements

Ceph Storage nodes are responsible for providing object storage in a RHEL OpenStack Platform environment.

Processor

64-bit x86 processor with support for the Intel 64 or AMD64 CPU extensions.

Memory

Memory requirements depend on the amount of storage space. Ideally, use at minimum 1 GB of memory per 1 TB of hard disk space.

Disk Space

Storage requirements depends on the amount of memory. Ideally, use at minimum 1 GB of memory per 1 TB of hard disk space.

Disk Layout

The recommended Red Hat Ceph Storage node configuration requires at least three or more disks in a layout similar to the following:

- **/dev/sda** - The root disk. The director copies the main Overcloud image to the disk.
- **/dev/sdb** - The journal disk. This disk divides into partitions for Ceph OSD journals. For example, **/dev/sdb1**, **/dev/sdb2**, **/dev/sdb3**, and onward. The journal disk is usually a solid state drive (SSD) to aid with system performance.
- **/dev/sdc** and onward - The OSD disks. Use as many disks as necessary for your storage requirements.

Network Interface Cards

A minimum of one 1 Gbps Network Interface Cards, although it is recommended to use at least two NICs in a production environment. Use additional network interface cards for bonded interfaces or to delegate tagged VLAN traffic. It is recommended to use a 10 Gbps interface for storage node, especially if creating an OpenStack Platform environment that serves a high volume of traffic.

Power Management

Each Controller node requires a supported power management interface, such as an Intelligent Platform Management Interface (IPMI) functionality, on the server's motherboard.

See the [Red Hat Ceph Storage for the Overcloud](#) guide for more information about installing an overcloud with a Ceph Storage cluster.

2.4.4. Object Storage Node Requirements

Object Storage nodes provides an object storage layer for the overcloud. The Object Storage proxy is installed on Controller nodes. The storage layer will require bare metal nodes with multiple number of disks per node.

Processor

64-bit x86 processor with support for the Intel 64 or AMD64 CPU extensions.

Memory

Memory requirements depend on the amount of storage space. Ideally, use at minimum 1 GB of memory per 1 TB of hard disk space. For optimal performance, it is recommended to use 2 GB per 1 TB of hard disk space, especially for small file (less 100GB) workloads.

Disk Space

Storage requirements depends on the capacity needed for the workload. It is recommended to use SSD drives to store the account and container data. The capacity ratio of account and container data to objects is of about 1 per cent. For example, for every 100TB of hard drive capacity, provide 1TB of SSD capacity for account and container data.

However, this depends on the type of stored data. If STORING mostly small objects, provide more SSD space. For large objects (videos, backups), use less SSD space.

Disk Layout

The recommended node configuration requires a disk layout similar to the following:

- **/dev/sda** - The root disk. The director copies the main overcloud image to the disk.
- **/dev/sdb** - Used for account data.
- **/dev/sdc** - Used for container data.
- **/dev/sdd** and onward - The object server disks. Use as many disks as necessary for your storage requirements.

Network Interface Cards

A minimum of 2 x 1 Gbps Network Interface Cards. Use additional network interface cards for bonded interfaces or to delegate tagged VLAN traffic.

Power Management

Each Controller node requires a supported power management interface, such as an Intelligent Platform Management Interface (IPMI) functionality, on the server's motherboard.

2.5. REPOSITORY REQUIREMENTS

Both the undercloud and overcloud require access to Red Hat repositories either through the Red Hat Content Delivery Network, or through Red Hat Satellite 5 or 6. If using a Red Hat Satellite Server, synchronize the required repositories to your OpenStack Platform environment. Use the following list of CDN channel names as a guide:



WARNING

Do not upgrade to the Red Hat Enterprise Linux 7.3 kernel without also upgrading from Open vSwitch (OVS) 2.4.0 to OVS 2.5.0. If only the kernel is upgraded, then OVS will stop functioning.

Table 2.1. OpenStack Platform Repositories

Name	Repository	Description of Requirement
Red Hat Enterprise Linux 7 Server (RPMs)	rhel-7-server-rpms	Base operating system repository.
Red Hat Enterprise Linux 7 Server - Extras (RPMs)	rhel-7-server-extras-rpms	Contains Red Hat OpenStack Platform dependencies.
Red Hat Enterprise Linux 7 Server - RH Common (RPMs)	rhel-7-server-rh-common-rpms	Contains tools for deploying and configuring Red Hat OpenStack Platform.
Red Hat Satellite Tools for RHEL 7 Server RPMs x86_64	rhel-7-server-satellite-tools-6.2-rpms	Tools for managing hosts with Red Hat Satellite 6.
Red Hat Enterprise Linux High Availability (for RHEL 7 Server) (RPMs)	rhel-ha-for-rhel-7-server-rpms	High availability tools for Red Hat Enterprise Linux. Used for Controller node high availability.
Red Hat Enterprise Linux OpenStack Platform 11 for RHEL 7 (RPMs)	rhel-7-server-openstack-11-rpms	Core Red Hat OpenStack Platform repository. Also contains packages for Red Hat OpenStack Platform director.
Red Hat Ceph Storage OSD 2 for Red Hat Enterprise Linux 7 Server (RPMs)	rhel-7-server-rhceph-2-osd-rpms	(For Ceph Storage Nodes) Repository for Ceph Storage Object Storage daemon. Installed on Ceph Storage nodes.

Red Hat Ceph Storage MON 2 for Red Hat Enterprise Linux 7 Server (RPMs)	rhel-7-server-rhceph-2-mon-rpms	(For Ceph Storage Nodes) Repository for Ceph Storage Monitor daemon. Installed on Controller nodes in OpenStack environments using Ceph Storage nodes.
Red Hat Ceph Storage Tools 2 for Red Hat Enterprise Linux 7 Server (RPMs)	rhel-7-server-rhceph-2-tools-rpms	Provides tools for nodes to communicate with the Ceph Storage cluster. This repository should be enabled for all nodes when deploying an overcloud with a Ceph Storage cluster.

**NOTE**

To configure repositories for your Red Hat OpenStack Platform environment in an offline network, see "[Configuring Red Hat OpenStack Platform Director in an Offline Environment](#)" on the Red Hat Customer Portal.

CHAPTER 3. PLANNING YOUR OVERCLOUD

The following section provides some guidelines on planning various aspects of your Red Hat OpenStack Platform environment. This includes defining node roles, planning your network topology, and storage.

3.1. PLANNING NODE DEPLOYMENT ROLES

The director provides multiple default node types for building your overcloud. These node types are:

Controller

Provides key services for controlling your environment. This includes the dashboard (horizon), authentication (keystone), image storage (glance), networking (neutron), orchestration (heat), and high availability services. A Red Hat OpenStack Platform environment requires three Controller nodes for a highly available environment.



NOTE

Environments with one node can be used for testing purposes. Environments with two nodes or more than three nodes are not supported.

Compute

A physical server that acts as a hypervisor, and provides the processing capabilities required for running virtual machines in the environment. A basic Red Hat OpenStack Platform environment requires at least one Compute node.

Ceph Storage

A host that provides Red Hat Ceph Storage. Additional Ceph Storage hosts scale into a cluster. This deployment role is optional.

Swift Storage

A host that provides external object storage for OpenStack's swift service. This deployment role is optional.

The following table provides some example of different overclouds and defines the node types for each scenario.

Table 3.1. Node Deployment Roles for Scenarios

	Controller	Compute	Ceph Storage	Swift Storage	Total
Small overcloud	3	1	-	-	4
Medium overcloud	3	3	-	-	6
Medium overcloud with additional Object storage	3	3	-	3	9

Medium overcloud with Ceph Storage cluster	3	3	3	-	9
--	---	---	---	---	---

In addition, consider whether to split individual services into custom roles. For more information on the composable roles architecture, see [Chapter 8. Composable Roles and Services](#) in the *Advanced Overcloud Customization* guide.

3.2. PLANNING NETWORKS

It is important to plan your environment's networking topology and subnets so that you can properly map roles and services to correctly communicate with each other. Red Hat OpenStack Platform uses the neutron networking service, which operates autonomously and manages software-based networks, static and floating IP addresses, and DHCP. The director deploys this service on each Controller node in an overcloud environment.

Red Hat OpenStack Platform maps the different services onto separate network traffic types, which are assigned to the various subnets in your environments. These network traffic types include:

Table 3.2. Network Type Assignments

Network Type	Description	Used By
IPMI	Network used for power management of nodes. This network is predefined before the installation of the undercloud.	All nodes
Provisioning / Control Plane	The director uses this network traffic type to deploy new nodes over PXE boot and orchestrate the installation of OpenStack Platform on the overcloud bare metal servers. This network is predefined before the installation of the undercloud.	All nodes
Internal API	The Internal API network is used for communication between the OpenStack services using API communication, RPC messages, and database communication.	Controller, Compute, Cinder Storage, Swift Storage

Tenant	Neutron provides each tenant with their own networks using either VLAN segregation (where each tenant network is a network VLAN), or tunneling (through VXLAN or GRE). Network traffic is isolated within each tenant network. Each tenant network has an IP subnet associated with it, and network namespaces means that multiple tenant networks can use the same address range without causing conflicts.	Controller, Compute
Storage	Block Storage, NFS, iSCSI, and others. Ideally, this would be isolated to an entirely separate switch fabric for performance reasons.	All nodes
Storage Management	OpenStack Object Storage (swift) uses this network to synchronize data objects between participating replica nodes. The proxy service acts as the intermediary interface between user requests and the underlying storage layer. The proxy receives incoming requests and locates the necessary replica to retrieve the requested data. Services that use a Ceph backend connect over the Storage Management network, since they do not interact with Ceph directly but rather use the frontend service. Note that the RBD driver is an exception, as this traffic connects directly to Ceph.	Controller, Ceph Storage, Cinder Storage, Swift Storage
External	Hosts the OpenStack Dashboard (horizon) for graphical system management, the public APIs for OpenStack services, and performs SNAT for incoming traffic destined for instances. If the external network uses private IP addresses (as per RFC-1918), then further NAT must be performed for traffic originating from the internet.	Controller and undercloud

Floating IP	Allows incoming traffic to reach instances using 1-to-1 IP address mapping between the floating IP address, and the IP address actually assigned to the instance in the tenant network. If hosting the Floating IPs on a VLAN separate from External, you can trunk the Floating IP VLAN to the Controller nodes and add the VLAN through Neutron after overcloud creation. This provides a means to create multiple Floating IP networks attached to multiple bridges. The VLANs are trunked but are not configured as interfaces. Instead, neutron creates an OVS port with the VLAN segmentation ID on the chosen bridge for each Floating IP network.	Controller
Management	Provides access for system administration functions such as SSH access, DNS traffic, and NTP traffic. This network also acts as a gateway for non-Controller nodes	All nodes

In a typical Red Hat OpenStack Platform installation, the number of network types often exceeds the number of physical network links. In order to connect all the networks to the proper hosts, the overcloud uses VLAN tagging to deliver more than one network per interface. Most of the networks are isolated subnets but some require a Layer 3 gateway to provide routing for Internet access or infrastructure network connectivity.



NOTE

It is recommended that you deploy a project network (tunneled with GRE or VXLAN) even if you intend to use a neutron VLAN mode (with tunneling disabled) at deployment time. This requires minor customization at deployment time and leaves the option available to use tunnel networks as utility networks or virtualization networks in the future. You still create Tenant networks using VLANs, but you can also create VXLAN tunnels for special-use networks without consuming tenant VLANs. It is possible to add VXLAN capability to a deployment with a Tenant VLAN, but it is not possible to add a Tenant VLAN to an existing overcloud without causing disruption.


The director provides a method for mapping six of these traffic types to certain subnets or VLANs. These traffic types include:

- Internal API
- Storage

- Storage Management
- Tenant Networks
- External
- Management

Any unassigned networks are automatically assigned to the same subnet as the Provisioning network.

The diagram below provides an example of a network topology where the networks are isolated on separate VLANs. Each overcloud node uses two interfaces (**nic2** and **nic3**) in a bond to deliver these networks over their respective VLANs. Meanwhile, each overcloud node communicates with the undercloud over the Provisioning network through a native VLAN using **nic1**.



OPENSTACK_364029_0715

The following table provides examples of network traffic mappings different network layouts:

Table 3.3. Network Mappings

	Mappings	Total Interfaces	Total VLANs
Flat Network with External Access	Network 1 - Provisioning, Internal API, Storage, Storage Management, Tenant Networks Network 2 - External, Floating IP (mapped after overcloud creation)	2	2
Isolated Networks	Network 1 - Provisioning Network 2 - Internal API Network 3 - Tenant Networks Network 4 - Storage Network 5 - Storage Management Network 6 - Storage Management Network 7 - External, Floating IP (mapped after overcloud creation)	3 (includes 2 bonded interfaces)	7

3.3. PLANNING STORAGE



NOTE

Using LVM on a guest instance that uses a backend cinder-volume of any driver or backend type results in issues with performance and volume visibility and availability. These issues can be mitigated using a LVM filter. For more information, please refer to [section 2.1 Back Ends](#) in the *Storage Guide* and KCS article 3213311, "[Using LVM on a cinder volume exposes the data to the compute host.](#)"

The director provides different storage options for the overcloud environment. This includes:

Ceph Storage Nodes

The director creates a set of scalable storage nodes using Red Hat Ceph Storage. The overcloud uses these nodes for:

- **Images** - Glance manages images for VMs. Images are immutable. OpenStack treats images as binary blobs and downloads them accordingly. You can use glance to store images in a Ceph Block Device.

- **Volumes** - Cinder volumes are block devices. OpenStack uses volumes to boot VMs, or to attach volumes to running VMs. OpenStack manages volumes using Cinder services. You can use Cinder to boot a VM using a copy-on-write clone of an image.
- **Guest Disks** - Guest disks are guest operating system disks. By default, when you boot a virtual machine with nova, its disk appears as a file on the filesystem of the hypervisor (usually under `/var/lib/nova/instances/<uuid>/`). It is possible to boot every virtual machine inside Ceph directly without using cinder, which is advantageous because it allows you to perform maintenance operations easily with the live-migration process. Additionally, if your hypervisor dies it is also convenient to trigger **nova evacuate** and run the virtual machine elsewhere almost seamlessly.



IMPORTANT

If you want to boot virtual machines in Ceph (ephemeral backend or boot from volume), the glance image format must be **RAW** format. Ceph does not support other image formats such as QCOW2 or VMDK for hosting a virtual machine disk.

See [Red Hat Ceph Storage Architecture Guide](#) for additional information.

Swift Storage Nodes

The director creates an external object storage node. This is useful in situations where you need to scale or replace controller nodes in your overcloud environment but need to retain object storage outside of a high availability cluster.

CHAPTER 4. INSTALLING THE UNDERCLOUD

The first step to creating your Red Hat OpenStack Platform environment is to install the director on the undercloud system. This involves a few prerequisite steps to enable the necessary subscriptions and repositories.

4.1. CREATING A DIRECTOR INSTALLATION USER

The director installation process requires a non-root user to execute commands. Use the following commands to create the user named **stack** and set a password:

```
[root@director ~]# useradd stack
[root@director ~]# passwd stack # specify a password
```

Disable password requirements for this user when using **sudo**:

```
[root@director ~]# echo "stack ALL=(root) NOPASSWD:ALL" | tee -a
/etc/sudoers.d/stack
[root@director ~]# chmod 0440 /etc/sudoers.d/stack
```

Switch to the new **stack** user:

```
[root@director ~]# su - stack
[stack@director ~]$
```

Continue the director installation as the **stack** user.

4.2. CREATING DIRECTORIES FOR TEMPLATES AND IMAGES

The director uses system images and Heat templates to create the overcloud environment. To keep these files organized, we recommend creating directories for images and templates:

```
$ mkdir ~/images
$ mkdir ~/templates
```

Other sections in this guide use these two directories to store certain files.

4.3. SETTING THE HOSTNAME FOR THE SYSTEM

The director requires a fully qualified domain name for its installation and configuration process. This means you may need to set the hostname of your director's host. Check the hostname of your host:

```
$ hostname # Checks the base hostname
$ hostname -f # Checks the long hostname (FQDN)
```

If either commands do not report the correct hostname or report an error, use **hostnamectl** to set a hostname:

```
$ sudo hostnamectl set-hostname manager.example.com
$ sudo hostnamectl set-hostname --transient manager.example.com
```

The director also requires an entry for the system's hostname and base name in `/etc/hosts`. For example, if the system is named `manager.example.com`, then `/etc/hosts` requires an entry like:

```
127.0.0.1    manager.example.com manager localhost localhost.localdomain
localhost4  localhost4.localdomain4
```

4.4. REGISTERING YOUR SYSTEM

To install the Red Hat OpenStack Platform director, first register the host system using Red Hat Subscription Manager, and subscribe to the required channels.

1. Register your system with the Content Delivery Network, entering your Customer Portal user name and password when prompted:

```
$ sudo subscription-manager register
```

2. Find the entitlement pool ID for Red Hat OpenStack Platform director. For example:

```
$ sudo subscription-manager list --available --all --
matches="*OpenStack*"
Subscription Name:   Name of SKU
Provides:            Red Hat Single Sign-On
                    Red Hat Enterprise Linux Workstation
                    Red Hat CloudForms
                    Red Hat OpenStack
                    Red Hat Software Collections (for RHEL
Workstation)
                    Red Hat Virtualization
SKU:                 SKU-Number
Contract:            Contract-Number
Pool ID:              Valid-Pool-Number-123456
Provides Management: Yes
Available:            1
Suggested:            1
Service Level:        Support-level
Service Type:         Service-Type
Subscription Type:     Sub-type
Ends:                 End-date
System Type:          Physical
```

3. Locate the **Pool ID** value and attach the Red Hat OpenStack Platform 11 entitlement:

```
$ sudo subscription-manager attach --pool=Valid-Pool-Number-123456
```

4. Disable all default repositories, and then enable the required Red Hat Enterprise Linux repositories:

```
$ sudo subscription-manager repos --disable=*
$ sudo subscription-manager repos --enable=rhel-7-server-rpms --
enable=rhel-7-server-extras-rpms --enable=rhel-7-server-rh-common-
rpms --enable=rhel-ha-for-rhel-7-server-rpms --enable=rhel-7-server-
openstack-11-rpms
```

These repositories contain packages the director installation requires.



IMPORTANT

Only enable the repositories listed in [Section 2.5, “Repository Requirements”](#). Additional repositories can cause package and software conflicts. Do not enable any additional repositories.

Perform an update on your system to make sure you have the latest base system packages:

```
$ sudo yum update -y
$ sudo reboot
```

The system is now ready for the director installation.

4.5. INSTALLING THE DIRECTOR PACKAGES

Use the following command to install the required command line tools for director installation and configuration:

```
$ sudo yum install -y python-tripleoclient
```

This installs all packages required for the director installation.

4.6. CONFIGURING THE DIRECTOR

The director installation process requires certain settings to determine your network configurations. The settings are stored in a template located in the **stack** user’s home directory as **undercloud.conf**.

Red Hat provides a basic template to help determine the required settings for your installation. Copy this template to the **stack** user’s home directory:

```
$ cp /usr/share/instack-undercloud/undercloud.conf.sample
~/undercloud.conf
```

The **undercloud.conf** file contains settings to configure your undercloud. If you omit or comment out a parameter, the undercloud installation uses the default value.

The template contains two sections: **[DEFAULT]** and **[auth]**. The **[DEFAULT]** section contains the following parameters:

undercloud_hostname


Defines the fully qualified host name for the undercloud. If set, the undercloud installation configures all system host name settings. If left unset, the undercloud uses the current host name, but the user must configure all system host name settings appropriately.

local_ip

The IP address defined for the director’s Provisioning NIC. This is also the IP address the director uses for its DHCP and PXE boot services. Leave this value as the default **192.168.24.1/24** unless you are using a different subnet for the Provisioning network, for example, if it conflicts with an existing IP address or subnet in your environment.

network_gateway

The gateway for the overcloud instances. This is the undercloud host, which forwards traffic to the External network. Leave this as the default **192.168.24.1** unless you are either using a different IP address for the director or want to directly use an external gateway.



NOTE

The director's configuration script also automatically enables IP forwarding using the relevant **sysctl** kernel parameter.

undercloud_public_host

The IP address defined for the director's Public API when using SSL/TLS. This is an IP address for accessing the director endpoints externally over SSL/TLS. The director configuration attaches this IP address to its software bridge as a routed IP address, which uses the **/32** netmask.

undercloud_admin_host

The IP address defined for the director's Admin API when using SSL/TLS. This is an IP address for administration endpoint access over SSL/TLS. The director configuration attaches this IP address to its software bridge as a routed IP address, which uses the **/32** netmask.

undercloud_nameservers

A list of DNS nameservers to use for the undercloud hostname resolution.

undercloud_ntp_servers

A list of network time protocol servers to help synchronize the undercloud's date and time.

undercloud_service_certificate

The location and filename of the certificate for OpenStack SSL/TLS communication. Ideally, you obtain this certificate from a trusted certificate authority. Otherwise generate your own self-signed certificate using the guidelines in [Appendix A, SSL/TLS Certificate Configuration](#). These guidelines also contain instructions on setting the SELinux context for your certificate, whether self-signed or from an authority.

generate_service_certificate

Defines whether to generate an SSL/TLS certificate during the undercloud installation, which is used for the **undercloud_service_certificate** parameter. The undercloud installation saves the resulting certificate **/etc/pki/tls/certs/undercloud-[undercloud_public_vip].pem**. The CA defined in the **certificate_generation_ca** parameter signs this certificate.

certificate_generation_ca

The **certmonger** nickname of the CA that signs the requested certificate. Only use this option if you have set the **generate_service_certificate** parameter. If you select the **local** CA, certmonger extracts the local CA certificate to **/etc/pki/ca-trust/source/anchors/cm-local-ca.pem** and adds it to the trust chain.

service_principal

The Kerberos principal for the service using the certificate. Only use this if your CA requires a Kerberos principal, such as in FreeIPA.

local_interface

The chosen interface for the director's Provisioning NIC. This is also the device the director uses for its DHCP and PXE boot services. Change this value to your chosen device. To see which device is connected, use the **ip addr** command. For example, this is the result of an **ip addr** command:

```
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast
state UP qlen 1000
    link/ether 52:54:00:75:24:09 brd ff:ff:ff:ff:ff:ff
```

```

    inet 192.168.122.178/24 brd 192.168.122.255 scope global dynamic
eth0
    valid_lft 3462sec preferred_lft 3462sec
    inet6 fe80::5054:ff:fe75:2409/64 scope link
    valid_lft forever preferred_lft forever
3: eth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noop state
DOWN
    link/ether 42:0b:c2:a5:c1:26 brd ff:ff:ff:ff:ff:ff

```

In this example, the External NIC uses **eth0** and the Provisioning NIC uses **eth1**, which is currently not configured. In this case, set the **local_interface** to **eth1**. The configuration script attaches this interface to a custom bridge defined with the **inspection_interface** parameter.

local_mtu

MTU to use for the **local_interface**.

network_cidr

The network that the director uses to manage overcloud instances. This is the Provisioning network, which the undercloud's **neutron** service manages. Leave this as the default **192.168.24.0/24** unless you are using a different subnet for the Provisioning network.

masquerade_network

Defines the network that will masquerade for external access. This provides the Provisioning network with a degree of network address translation (NAT) so that it has external access through the director. Leave this as the default (**192.168.24.0/24**) unless you are using a different subnet for the Provisioning network.

dhcp_start; dhcp_end

The start and end of the DHCP allocation range for overcloud nodes. Ensure this range contains enough IP addresses to allocate your nodes.

hieradata_override

Path to **hieradata** override file. If set, the undercloud installation copies this file under **/etc/puppet/hieradata** and sets it as the first file in the hierarchy. Use this to provide custom configuration to services beyond the **undercloud.conf** parameters.

net_config_override

Path to network configuration override template. If set, the undercloud uses a JSON format template to configure the networking with **os-net-config**. This ignores the network parameters set in **undercloud.conf**. See **/usr/share/instack-undercloud/templates/net-config.json.template** for an example.

inspection_interface

The bridge the director uses for node introspection. This is custom bridge that the director configuration creates. The **LOCAL_INTERFACE** attaches to this bridge. Leave this as the default **br-ctlplane**.

inspection_iprange

A range of IP address that the director's introspection service uses during the PXE boot and provisioning process. Use comma-separated values to define the start and end of this range. For example, **192.168.24.100, 192.168.24.120**. Make sure this range contains enough IP addresses for your nodes and does not conflict with the range for **dhcp_start** and **dhcp_end**.

inspection_extras

Defines whether to enable extra hardware collection during the inspection process. Requires **python-hardware** or **python-hardware-detect** package on the introspection image.

inspection_runbench

Runs a set of benchmarks during node introspection. Set to **true** to enable. This option is necessary if you intend to perform benchmark analysis when inspecting the hardware of registered nodes. See [Section 5.2, “Inspecting the Hardware of Nodes”](#) for more details.

inspection_enable_uefi

Defines whether to support introspection of nodes with UEFI-only firmware. For more information, see [Appendix D, *Alternative Boot Modes*](#).

enable_node_discovery

Automatically enroll any unknown node that PXE-boots the introspection ramdisk. New nodes use the **fake_pxe** driver as a default but you can set **discovery_default_driver** to override. You can also use introspection rules to specify driver information for newly enrolled nodes.

discovery_default_driver

Sets the default driver for automatically enrolled nodes. Requires **enable_node_discovery** enabled and you must include the driver in the **enabled_drivers** list. See [Appendix B, *Power Management Drivers*](#) for a list of supported drivers.

undercloud_debug

Sets the log level of undercloud services to **DEBUG**. Set this value to **true** to enable.

undercloud_update_packages

Defines whether to update packages during the undercloud installation.

enable_tempest

Defines whether to install the validation tools. The default is set to **false**, but you can enable using **true**.

enable_telemetry

Defines whether to install OpenStack Telemetry services (ceilometer, aodh, panko, gnocchi) in the undercloud. In Red Hat OpenStack Platform 11, the metrics backend for telemetry is provided by gnocchi. Setting **enable_telemetry** parameter to **true** will install and set up telemetry services automatically. The default value is **false**, which disables telemetry on the undercloud. This parameter is required if using other products that consume metrics data, such as Red Hat CloudForms.

enable_ui

Defines Whether to install the director’s web UI. This allows you to perform overcloud planning and deployments through a graphical web interface. For more information, see [Chapter 6, *Configuring a Basic Overcloud with the Web UI*](#). Note that the UI is only available with SSL/TLS enabled using either the **undercloud_service_certificate** or **generate_service_certificate**.

enable_validations

Defines whether to install the requirements to run validations.

enable_legacy_ceilometer_api

Defines whether to enable legacy OpenStack Telemetry service (Ceilometer) API in the Undercloud. Note the legacy API is deprecated and will be removed in a future release. Please use the newer components installed with **enable_telemetry**.

enable_novajoin

Defines whether to install the **novajoin** metadata service in the Undercloud.

ipa_otp

Defines the one time password to register the Undercloud node to an IPA server. This is required when **enable_novajoin** is enabled.

ipxe_enabled

Defines whether to use iPXE or standard PXE. The default is **true**, which enables iPXE. Set to **false** to set to standard PXE. For more information, see [Appendix D, *Alternative Boot Modes*](#).

scheduler_max_attempts

Maximum number of times the scheduler attempts to deploy an instance. Keep this greater or equal to the number of bare metal nodes you expect to deploy at once to work around potential race condition when scheduling.

clean_nodes

Defines whether to wipe the hard drive between deployments and after introspection. Enabling cleaning will increase the node enrollment and instance tear-down time, and it will not be possible to restore an overcloud after deletion.

enabled_drivers

A list of bare metal drivers to enable for the undercloud. See [Appendix B, *Power Management Drivers*](#) for a list of supported drivers.

The **[auth]** section contains the following parameters:

**undercloud_db_password; undercloud_admin_token; undercloud_admin_password;
undercloud_glance_password; etc**

The remaining parameters are the access details for all of the director's services. No change is required for the values. The director's configuration script automatically generates these values if blank in **undercloud.conf**. You can retrieve all values after the configuration script completes.



IMPORTANT

The configuration file examples for these parameters use **<None>** as a placeholder value. Setting these values to **<None>** leads to a deployment error.

Modify the values for these parameters to suit your network. When complete, save the file and run the following command:

```
$ openstack undercloud install
```

This launches the director's configuration script. The director installs additional packages and configures its services to suit the settings in the **undercloud.conf**. This script takes several minutes to complete.

The configuration script generates two files when complete:

- **undercloud-passwords.conf** - A list of all passwords for the director's services.
- **stackrc** - A set of initialization variables to help you access the director's command line tools.

The configuration also starts all OpenStack Platform services automatically. Check the enabled services using the following command:

```
$ sudo systemctl list-units openstack-*
```

To initialize the **stack** user to use the command line tools, run the following command:

```
$ source ~/stackrc
```

You can now use the director's command line tools.

4.7. OBTAINING IMAGES FOR OVERCLOUD NODES

The director requires several disk images for provisioning overcloud nodes. This includes:

- An introspection kernel and ramdisk - Used for bare metal system introspection over PXE boot.
- A deployment kernel and ramdisk - Used for system provisioning and deployment.
- An overcloud kernel, ramdisk, and full image - A base overcloud system that is written to the node's hard disk.

Obtain these images from the **rhosp-director-images** and **rhosp-director-images-ipa** packages:

```
$ sudo yum install rhosp-director-images rhosp-director-images-ipa
```

Extract the archives to the **images** directory on the **stack** user's home (**/home/stack/images**):

```
$ cd ~/images
$ for i in /usr/share/rhosp-director-images/overcloud-full-latest-11.0.tar
/usr/share/rhosp-director-images/ironic-python-agent-latest-11.0.tar; do
tar -xvf $i; done
```

Import these images into the director:

```
$ openstack overcloud image upload --image-path /home/stack/images/
```

This uploads the following images into the director: **bm-deploy-kernel**, **bm-deploy-ramdisk**, **overcloud-full**, **overcloud-full-initrd**, **overcloud-full-vmlinuz**. These are the images for deployment and the overcloud. The script also installs the introspection images on the director's PXE server.

View a list of the images in the CLI:

```
$ openstack image list
+-----+-----+
| ID                                     | Name                               |
+-----+-----+
| 765a46af-4417-4592-91e5-a300ead3faf6 | bm-deploy-ramdisk                 |
| 09b40e3d-0382-4925-a356-3a4b4f36b514 | bm-deploy-kernel                  |
| ef793cd0-e65c-456a-a675-63cd57610bd5 | overcloud-full                    |
| 9a51a6cb-4670-40de-b64b-b70f4dd44152 | overcloud-full-initrd             |
| 4f7e33f4-d617-47c1-b36f-cbe90f132e5d | overcloud-full-vmlinuz            |
+-----+-----+
```

This list will not show the introspection PXE images. The director copies these files to **/httpboot**.

```
[stack@host1 ~]$ ls -l /httpboot
total 341460
-rwxr-xr-x. 1 root          root          5153184 Mar 31 06:58
agent.kernel
-rw-r--r--. 1 root          root          344491465 Mar 31 06:59
```

```
agent.ramdisk
-rw-r--r--. 1 ironic-inspector ironic-inspector 337 Mar 31 06:23
inspector.ipxe
```

**NOTE**

The default **overcloud-full.qcow2** image is a flat partition image. However, you can also import and use whole disk images. See [Appendix C, *Whole Disk Images*](#) for more information.

4.8. SETTING A NAMESERVER ON THE UNDERCLOUD'S NEUTRON SUBNET

If you intend for the overcloud to resolve external hostnames, such as **cdn.redhat.com**, it is recommended to set a nameserver on the overcloud nodes. For a standard overcloud without network isolation, the nameserver is defined using the undercloud's **neutron** subnet. Use the following commands to define nameservers for the environment:

```
$ openstack subnet list
$ openstack subnet set --dns-nameserver [nameserver1-ip] --dns-nameserver
[nameserver2-ip] [subnet-uuid]
```

View the subnet to verify the nameserver:

```
$ openstack subnet show [subnet-uuid]
+-----+-----+
| Field                | Value                                |
+-----+-----+
| ...                  |                                     |
| dns_nameservers      | 8.8.8.8                             |
| ...                  |                                     |
+-----+-----+
```

**IMPORTANT**

If you aim to isolate service traffic onto separate networks, the overcloud nodes use the **DnsServer** parameter in your network environment files.

4.9. BACKING UP THE UNDERCLOUD

Red Hat provides a process to back up important data from the undercloud host and the Red Hat OpenStack Platform director. For more information about undercloud backups, see the ["Back Up and Restore the Director Undercloud"](#) guide.

4.10. COMPLETING THE UNDERCLOUD CONFIGURATION

This completes the undercloud configuration. The next chapter explores basic overcloud configuration, including registering nodes, inspecting them, and then tagging them into various node roles.

CHAPTER 5. CONFIGURING A BASIC OVERCLOUD WITH THE CLI TOOLS

This chapter provides the basic configuration steps for an OpenStack Platform environment using the CLI tools. An overcloud with a basic configuration contains no custom features. However, you can add advanced configuration options to this basic overcloud and customize it to your specifications using the instructions in the [Advanced Overcloud Customization](#) guide.

For the examples in this chapter, all nodes in this chapter are bare metal systems using IPMI for power management. For more supported power management types and their options, see [Appendix B, Power Management Drivers](#).

Workflow

1. Create a node definition template and register blank nodes in the director.
2. Inspect hardware of all nodes.
3. Tag nodes into roles.
4. Define additional node properties.

Requirements

- The director node created in [Chapter 4, Installing the Undercloud](#)
- A set of bare metal machines for your nodes. The number of node required depends on the type of overcloud you intend to create (see [Section 3.1, “Planning Node Deployment Roles”](#) for information on overcloud roles). These machines also must comply with the requirements set for each node type. For these requirements, see [Section 2.4, “Overcloud Requirements”](#). These nodes do not require an operating system. The director copies a Red Hat Enterprise Linux 7 image to each node.
- One network connection for our Provisioning network, which is configured as a native VLAN. All nodes must connect to this network and comply with the requirements set in [Section 2.3, “Networking Requirements”](#). For the examples in this chapter, we use 192.168.24.0/24 as the Provisioning subnet with the following IP address assignments:

Table 5.1. Provisioning Network IP Assignments

Node Name	IP Address	MAC Address	IPMI IP Address
Director	192.168.24.1	aa:aa:aa:aa:aa:aa	None required
Controller	DHCP defined	bb:bb:bb:bb:bb:bb	192.168.24.205
Compute	DHCP defined	cc:cc:cc:cc:cc:cc	192.168.24.206

- All other network types use the Provisioning network for OpenStack services. However, you can create additional networks for other network traffic types.

5.1. REGISTERING NODES FOR THE OVERCLOUD

The director requires a node definition template, which you create manually. This file (**instackenv.json**) uses the JSON format file, and contains the hardware and power management details for your nodes. For example, a template for registering two nodes might look like this:

```
{
  "nodes": [
    {
      "mac": [
        "bb:bb:bb:bb:bb:bb"
      ],
      "name": "node01",
      "cpu": "4",
      "memory": "6144",
      "disk": "40",
      "arch": "x86_64",
      "pm_type": "pxe_ipmitool",
      "pm_user": "admin",
      "pm_password": "p@55w0rd!",
      "pm_addr": "192.168.24.205"
    },
    {
      "mac": [
        "cc:cc:cc:cc:cc:cc"
      ],
      "name": "node02",
      "cpu": "4",
      "memory": "6144",
      "disk": "40",
      "arch": "x86_64",
      "pm_type": "pxe_ipmitool",
      "pm_user": "admin",
      "pm_password": "p@55w0rd!",
      "pm_addr": "192.168.24.206"
    }
  ]
}
```

This template uses the following attributes:

name

The logical name for the node.

pm_type

The power management driver to use. This example uses the IPMI driver (**pxe_ipmitool**), which is the preferred driver for power management.

pm_user; pm_password

The IPMI username and password.

pm_addr

The IP address of the IPMI device.

mac

(Optional) A list of MAC addresses for the network interfaces on the node. Use only the MAC address for the Provisioning NIC of each system.

cpu

(Optional) The number of CPUs on the node.

memory

(Optional) The amount of memory in MB.

disk

(Optional) The size of the hard disk in GB.

arch

(Optional) The system architecture.



NOTE

IPMI is the preferred supported power management driver. For more supported power management types and their options, see [Appendix B, Power Management Drivers](#). If these power management drivers do not work as expected, use IPMI for your power management.

After creating the template, save the file to the **stack** user's home directory (**/home/stack/instackenv.json**), then import it into the director using the following command:

```
$ openstack overcloud node import ~/instackenv.json
```

This imports the template and registers each node from the template into the director.

After the node registration and configuration completes, view a list of these nodes in the CLI:

```
$ openstack baremetal node list
```

5.2. INSPECTING THE HARDWARE OF NODES

The director can run an introspection process on each node. This process causes each node to boot an introspection agent over PXE. This agent collects hardware data from the node and sends it back to the director. The director then stores this introspection data in the OpenStack Object Storage (swift) service running on the director. The director uses hardware information for various purposes such as profile tagging, benchmarking, and manual root disk assignment.



NOTE

You can also create policy files to automatically tag nodes into profiles immediately after introspection. For more information on creating policy files and including them in the introspection process, see [Appendix E, Automatic Profile Tagging](#). Alternatively, you can manually tag nodes into profiles as per the instructions in [Section 5.3, "Tagging Nodes into Profiles"](#).


Run the following command to inspect the hardware attributes of each node:

```
$ openstack overcloud node introspect --all-manageable --provide
```

- The **--all-manageable** option introspects only nodes in a managed state. In this example, it is all of them.
- The **--provide** option resets all nodes to an **active** state after introspection.

Monitor the progress of the introspection using the following command in a separate terminal window:

```
$ sudo journalctl -l -u openstack-ironic-inspector -u openstack-ironic-inspector-dnsmasq -u openstack-ironic-conductor -f
```



IMPORTANT

Make sure this process runs to completion. This process usually takes 15 minutes for bare metal nodes.

After the introspection completes, all nodes change to an **active** state.

Performing Individual Node Introspection

To perform a single introspection on an **active** node, set the node to management mode and perform the introspection:

```
$ openstack baremetal node manage [NODE UUID]
$ openstack overcloud node introspect [NODE UUID] --provide
```

After the introspection completes, the nodes changes to an **active** state.

Performing Node Introspection after Initial Introspection

After an initial introspection, all nodes should enter an **active** state due to the **--provide** option. To perform introspection on all nodes after the initial introspection, set all nodes to a **manageable** state and run the bulk introspection command

```
$ for node in $(openstack baremetal node list --fields uuid -f value) ; do
openstack baremetal node manage $node ; done
$ openstack overcloud node introspect --all-manageable --provide
```

After the introspection completes, all nodes change to an **active** state.

5.3. TAGGING NODES INTO PROFILES

After registering and inspecting the hardware of each node, you will tag them into specific profiles. These profile tags match your nodes to flavors, and in turn the flavors are assigned to a deployment role. The following example shows the relationship across roles, flavors, profiles, and nodes for Controller nodes:

Type	Description
Role	The Controller role defines how to configure controller nodes.
Flavor	The control flavor defines the hardware profile for nodes to use as controllers. You assign this flavor to the Controller role so the director can decide which nodes to use.

Type	Description
Profile	The control profile is a tag you apply to the control flavor. This defines the nodes that belong to the flavor.
Node	You also apply the control profile tag to individual nodes, which groups them to the control flavor and, as a result, the director configures them using the Controller role.

Default profile flavors **compute**, **control**, **swift-storage**, **ceph-storage**, and **block-storage** are created during undercloud installation and are usable without modification in most environments.



NOTE

For a large number of nodes, use automatic profile tagging. See [Appendix E, Automatic Profile Tagging](#) for more details.

To tag a node into a specific profile, add a **profile** option to the **properties/capabilities** parameter for each node. For example, to tag your nodes to use Controller and Compute profiles respectively, use the following commands:

```
$ openstack baremetal node set --property
capabilities='profile:compute,boot_option:local' 58c3d07e-24f2-48a7-bbb6-
6843f0e8ee13
$ openstack baremetal node set --property
capabilities='profile:control,boot_option:local' 1a4e30da-b6dc-499d-ba87-
0bd8a3819bc0
```

The addition of the **profile:compute** and **profile:control** options tag the two nodes into each respective profiles.

These commands also set the **boot_option:local** parameter, which defines how each node boots. Depending on your hardware, you might also need to add the **boot_mode** parameter to **uefi** so that nodes boot using UEFI instead of the default BIOS mode. For more information, see [Section D.2, “UEFI Boot Mode”](#).

After completing node tagging, check the assigned profiles or possible profiles:

```
$ openstack overcloud profiles list
```

Custom Role Profiles

If using custom roles, you might need to create additional flavors and profiles to accommodate these new roles. For example, to create a new flavor for a Networker role, run the following command:

```
$ openstack flavor create --id auto --ram 4096 --disk 40 --vcpus 1
networker
$ openstack flavor set --property "cpu_arch"="x86_64" --property
"capabilities:boot_option"="local" --property
"capabilities:profile"="networker" networker
```

Assign nodes with this new profile:

```
$ openstack baremetal node set --property
capabilities='profile:networker,boot_option:local' dad05b82-0c74-40bf-
9d12-193184bfc72d
```

5.4. DEFINING THE ROOT DISK FOR NODES

Some nodes might use multiple disks. This means the director needs to identify the disk to use for the root disk during provisioning. There are several properties you can use to help the director identify the root disk:

- **model** (String): Device identifier.
- **vendor** (String): Device vendor.
- **serial** (String): Disk serial number.
- **hctl** (String): Host:Channel:Target:Lun for SCSI.
- **size** (Integer): Size of the device in GB.
- **wwn** (String): Unique storage identifier.
- **wwn_with_extension** (String): Unique storage identifier with the vendor extension appended.
- **wwn_vendor_extension** (String): Unique vendor storage identifier.
- **rotational** (Boolean): True for a rotational device (HDD), otherwise false (SSD).
- **name** (String): The name of the device, for example: /dev/sdb1 Only use this for devices with persistent names.

In this example, you specify the drive to deploy the overcloud image using the serial number of the disk to determine the root device.

Check the disk information from each node's hardware introspection. The following command displays the disk information from a node:

```
$ openstack baremetal introspection data save 1a4e30da-b6dc-499d-ba87-
0bd8a3819bc0 | jq ".inventory.disks"
```

For example, the data for one node might show three disks:

```
[
  {
    "size": 299439751168,
    "rotational": true,
    "vendor": "DELL",
    "name": "/dev/sda",
    "wwn_vendor_extension": "0x1ea4dcc412a9632b",
    "wwn_with_extension": "0x61866da04f3807001ea4dcc412a9632b",
    "model": "PERC H330 Mini",
    "wwn": "0x61866da04f380700",
    "serial": "61866da04f3807001ea4dcc412a9632b"
```

```

    }
    {
      "size": 299439751168,
      "rotational": true,
      "vendor": "DELL",
      "name": "/dev/sdb",
      "wwn_vendor_extension": "0x1ea4e13c12e36ad6",
      "wwn_with_extension": "0x61866da04f380d001ea4e13c12e36ad6",
      "model": "PERC H330 Mini",
      "wwn": "0x61866da04f380d00",
      "serial": "61866da04f380d001ea4e13c12e36ad6"
    }
    {
      "size": 299439751168,
      "rotational": true,
      "vendor": "DELL",
      "name": "/dev/sdc",
      "wwn_vendor_extension": "0x1ea4e31e121cfb45",
      "wwn_with_extension": "0x61866da04f37fc001ea4e31e121cfb45",
      "model": "PERC H330 Mini",
      "wwn": "0x61866da04f37fc00",
      "serial": "61866da04f37fc001ea4e31e121cfb45"
    }
  ]

```

For this example, set the root device to disk 2, which has **61866da04f380d001ea4e13c12e36ad6** as the serial number. This requires a change to the **root_device** parameter for the node definition:


```
$ openstack baremetal node set --property root_device='{ "serial":
"61866da04f380d001ea4e13c12e36ad6"}' 1a4e30da-b6dc-499d-ba87-0bd8a3819bc0
```

This helps the director identify the specific disk to use as the root disk. When we initiate our overcloud creation, the director provisions this node and writes the overcloud image to this disk.



NOTE

Make sure to configure the BIOS of each node to include booting from the chosen root disk. The recommended boot order is network boot, then root disk boot.



IMPORTANT

Do not use **name** to set the root disk as this value can change when the node boots.

5.5. CUSTOMIZING THE OVERCLOUD

The undercloud includes a set of Heat templates that acts as a plan for your overcloud creation. You can customize advanced features for your overcloud using the [Advanced Overcloud Customization](#) guide.

Otherwise, you can continue and deploy a basic overcloud. See [Section 5.6, “Creating the Overcloud with the CLI Tools”](#) for more information.



IMPORTANT

A basic overcloud uses local LVM storage for block storage, which is not a supported configuration. It is recommended to use an external storage solution for block storage.

5.6. CREATING THE OVERCLOUD WITH THE CLI TOOLS

The final stage in creating your OpenStack environment is to run the **openstack overcloud deploy** command to create it. Before running this command, you should familiarize yourself with key options and how to include custom environment files. The following section discusses the **openstack overcloud deploy** command and the options associated with it.



WARNING

Do not run **openstack overcloud deploy** as a background process. The overcloud creation might hang in mid-deployment if started as a background process.

Setting Overcloud Parameters

The following table lists the additional parameters when using the **openstack overcloud deploy** command.

Table 5.2. Deployment Parameters

Parameter	Description
--templates [TEMPLATES]	The directory containing the Heat templates to deploy. If blank, the command uses the default template location at /usr/share/openstack-tripleo-heat-templates/
--stack STACK	The name of the stack to create or update
-t [TIMEOUT], --timeout [TIMEOUT]	Deployment timeout in minutes
--libvirt-type [LIBVIRT_TYPE]	Virtualization type to use for hypervisors
--ntp-server [NTP_SERVER]	Network Time Protocol (NTP) server to use to synchronize time. You can also specify multiple NTP servers in a comma-separated list, for example: --ntp-server 0.centos.pool.org,1.centos.pool.org . For a high availability cluster deployment, it is essential that your controllers are consistently referring to the same time source. Note that a typical environment might already have a designated NTP time source with established practices.

Parameter	Description
--no-proxy [NO_PROXY]	Defines custom values for the environment variable <code>no_proxy</code> , which excludes certain hostnames from proxy communication.
--overcloud-ssh-user OVERCLOUD_SSH_USER	Defines the SSH user to access the overcloud nodes. Normally SSH access occurs through the heat-admin user.
-e [EXTRA HEAT TEMPLATE], --extra-template [EXTRA HEAT TEMPLATE]	Extra environment files to pass to the overcloud deployment. Can be specified more than once. Note that the order of environment files passed to the openstack overcloud deploy command is important. For example, parameters from each sequential environment file override the same parameters from earlier environment files.
--environment-directory	The directory containing environment files to include in deployment. The command processes these environment files in numerical, then alphabetical order.
--validation-errors-nonfatal	The overcloud creation process performs a set of pre-deployment checks. This option exits if any non-fatal errors occur from the pre-deployment checks. It is advisable to use this option as any errors can cause your deployment to fail.
--validation-warnings-fatal	The overcloud creation process performs a set of pre-deployment checks. This option exits if any non-critical warnings occur from the pre-deployment checks.
--dry-run	Performs validation check on the overcloud but does not actually create the overcloud.
--skip-postconfig	Skip the overcloud post-deployment configuration.
--force-postconfig	Force the overcloud post-deployment configuration.
--answers-file ANSWERS_FILE	Path to a YAML file with arguments and parameters.
--rhel-reg	Register overcloud nodes to the Customer Portal or Satellite 6.
--reg-method	Registration method to use for the overcloud nodes. satellite for Red Hat Satellite 6 or Red Hat Satellite 5, portal for Customer Portal.

Parameter	Description
--reg-org [REG_ORG]	Organization to use for registration.
--reg-force	Register the system even if it is already registered.
--reg-sat-url [REG_SAT_URL]	The base URL of the Satellite server to register overcloud nodes. Use the Satellite's HTTP URL and not the HTTPS URL for this parameter. For example, use http://satellite.example.com and not https://satellite.example.com . The overcloud creation process uses this URL to determine whether the server is a Red Hat Satellite 5 or Red Hat Satellite 6 server. If a Red Hat Satellite 6 server, the overcloud obtains the katello-ca-consumer-latest.noarch.rpm file, registers with subscription-manager , and installs katello-agent . If a Red Hat Satellite 5 server, the overcloud obtains the RHN-ORG-TRUSTED-SSL-CERT file and registers with rhnreg_ks .
--reg-activation-key [REG_ACTIVATION_KEY]	Activation key to use for registration.

Some command line parameters are outdated or deprecated in favor of using Heat template parameters, which you include in the **parameter_defaults** section on an environment file. The following table maps deprecated parameters to their Heat Template equivalents.

Table 5.3. Mapping Deprecated CLI Parameters to Heat Template Parameters

Parameter	Description	Heat Template Parameter
--control-scale	The number of Controller nodes to scale out	ControllerCount
--compute-scale	The number of Compute nodes to scale out	ComputeCount
--ceph-storage-scale	The number of Ceph Storage nodes to scale out	CephStorageCount
--block-storage-scale	The number of Cinder nodes to scale out	BlockStorageCount
--swift-storage-scale	The number of Swift nodes to scale out	ObjectStorageCount
--control-flavor	The flavor to use for Controller nodes	OvercloudControlFlavor

Parameter	Description	Heat Template Parameter
--compute-flavor	The flavor to use for Compute nodes	OvercloudComputeFlavor
--ceph-storage-flavor	The flavor to use for Ceph Storage nodes	OvercloudCephStorageFlavor
--block-storage-flavor	The flavor to use for Cinder nodes	OvercloudBlockStorageFlavor
--swift-storage-flavor	The flavor to use for Swift storage nodes	OvercloudSwiftStorageFlavor
--neutron-flat-networks	Defines the flat networks to configure in neutron plugins. Defaults to "datacentre" to permit external network creation	NeutronFlatNetworks
--neutron-physical-bridge	An Open vSwitch bridge to create on each hypervisor. This defaults to "br-ex". Typically, this should not need to be changed	HypervisorNeutronPhysicalBridge
--neutron-bridge-mappings	The logical to physical bridge mappings to use. Defaults to mapping the external bridge on hosts (br-ex) to a physical name (datacentre). You would use this for the default floating network	NeutronBridgeMappings
--neutron-public-interface	Defines the interface to bridge onto br-ex for network nodes	NeutronPublicInterface
--neutron-network-type	The tenant network type for Neutron	NeutronNetworkType
--neutron-tunnel-types	The tunnel types for the Neutron tenant network. To specify multiple values, use a comma separated string	NeutronTunnelTypes
--neutron-tunnel-id-ranges	Ranges of GRE tunnel IDs to make available for tenant network allocation	NeutronTunnelIdRanges
--neutron-vni-ranges	Ranges of VXLAN VNI IDs to make available for tenant network allocation	NeutronVniRanges

Parameter	Description	Heat Template Parameter
--neutron-network-vlan-ranges	The Neutron ML2 and Open vSwitch VLAN mapping range to support. Defaults to permitting any VLAN on the <i>datacentre</i> physical network	NeutronNetworkVLANRanges
--neutron-mechanism-drivers	The mechanism drivers for the neutron tenant network. Defaults to "openvswitch". To specify multiple values, use a comma-separated string	NeutronMechanismDrivers
--neutron-disable-tunneling	Disables tunneling in case you aim to use a VLAN segmented network or flat network with Neutron	No parameter mapping.
--validation-errors-fatal	The overcloud creation process performs a set of pre-deployment checks. This option exits if any fatal errors occur from the pre-deployment checks. It is advisable to use this option as any errors can cause your deployment to fail.	No parameter mapping

These parameters are scheduled for removal in a future version of Red Hat OpenStack Platform.



NOTE

Run the following command for a full list of options:

```
$ openstack help overcloud deploy
```

5.7. INCLUDING ENVIRONMENT FILES IN OVERCLOUD CREATION

The **-e** includes an environment file to customize your overcloud. You can include as many environment files as necessary. However, the order of the environment files is important as the parameters and resources defined in subsequent environment files take precedence. Use the following list as an example of the environment file order:

- The amount of nodes per each role and their flavors. It is vital to include this information for overcloud creation.
- Any network isolation files, starting with the initialization file (**environments/network-isolation.yaml**) from the heat template collection, then your custom NIC configuration file, and finally any additional network configurations.
- Any external load balancing environment files.
- Any storage environment files such as Ceph Storage, NFS, iSCSI, etc.

- Any environment files for Red Hat CDN or Satellite registration.
- Any other custom environment files.

Any environment files added to the overcloud using the **-e** option become part of your overcloud's stack definition. The following command is an example of how to start the overcloud creation with custom environment files included:

```
$ openstack overcloud deploy --templates \
  -e ~/templates/node-info.yaml \
  -e /usr/share/openstack-tripleo-heat-templates/environments/network-
isolation.yaml \
  -e ~/templates/network-environment.yaml \
  -e ~/templates/storage-environment.yaml \
  --ntp-server pool.ntp.org \
```

This command contains the following additional options:

- **--templates** - Creates the overcloud using the Heat template collection in **/usr/share/openstack-tripleo-heat-templates**.
- **-e ~/templates/node-info.yaml** - The **-e** option adds an additional environment file to the overcloud deployment. In this case, it is a custom environment file that defines how many nodes and which flavors to use for each role. For example:

```
parameter_defaults:
  OvercloudControlFlavor: control
  OvercloudComputeFlavor: compute
  OvercloudCephStorageFlavor: ceph-storage
  ControllerCount: 3
  ComputeCount: 3
  CephStorageCount: 3
```

- **-e /usr/share/openstack-tripleo-heat-templates/environments/network-isolation.yaml** - The **-e** option adds an additional environment file to the overcloud deployment. In this case, it is an environment file that initializes network isolation configuration.
- **-e ~/templates/network-environment.yaml** - The **-e** option adds an additional environment file to the overcloud deployment. In this case, it is a network environment file that contains customization for network isolation.
- **-e ~/templates/storage-environment.yaml** - The **-e** option adds an additional environment file to the overcloud deployment. In this case, it is a custom environment file that initializes our storage configuration.
- **--ntp-server pool.ntp.org** - Use an NTP server for time synchronization. This is useful for keeping the Controller node cluster in synchronization.

The director requires these environment files for re-deployment and post-deployment functions in [Chapter 8, Performing Tasks after Overcloud Creation](#). Failure to include these files can result in damage to your overcloud.

If you aim to later modify the overcloud configuration, you should:

1. Modify parameters in the custom environment files and Heat templates

2. Run the **openstack overcloud deploy** command again with the same environment files

Do not edit the overcloud configuration directly as such manual configuration gets overridden by the director's configuration when updating the overcloud stack with the director.

Including an Environment File Directory

You can add a whole directory containing environment files using the **--environment-directory** option. The deployment command processes the environment files in this directory in numerical, then alphabetical order. If using this method, it is recommended to use filenames with a numerical prefix to order how they are processed. For example:

```
$ ls -1 ~/templates
00-node-info.yaml
10-network-isolation.yaml
20-network-environment.yaml
30-storage-environment.yaml
40-rhel-registration.yaml
```

Run the following deployment command to include the directory:

```
$ openstack overcloud deploy --templates --environment-directory
~/templates
```

Using an Answers File

An answers file is a YAML format file that simplifies the inclusion of templates and environment files. The answers file uses the following parameters:

templates

The core Heat template collection to use. This acts as a substitute for the **--templates** command line option.

environments

A list of environment files to include. This acts as a substitute for the **--environment-file (-e)** command line option.

For example, an answers file might contain the following:

```
templates: /usr/share/openstack-tripleo-heat-templates/
environments:
  - ~/templates/00-node-info.yaml
  - ~/templates/10-network-isolation.yaml
  - ~/templates/20-network-environment.yaml
  - ~/templates/30-storage-environment.yaml
  - ~/templates/40-rhel-registration.yaml
```

Run the following deployment command to include the answers file:

```
$ openstack overcloud deploy --answers-file ~/answers.yaml
```

5.8. MANAGING OVERCLOUD PLANS

As an alternative to using the **openstack overcloud deploy** command, the director can also manage imported plans.

To create a new plan, run the following command as the **stack** user:

```
$ openstack overcloud plan create --templates /usr/share/openstack-tripleo-heat-templates my-overcloud
```

This creates a plan from the core Heat template collection in **/usr/share/openstack-tripleo-heat-templates**. The director names the plan based on your input. In this example, it is **my-overcloud**. The director uses this name as a label for the object storage container, the workflow environment, and overcloud stack names.

Add parameters from environment files using the following command:

```
$ openstack overcloud parameters set my-overcloud ~/templates/my-environment.yaml
```

Deploy your plans using the following command:

```
$ openstack overcloud plan deploy my-overcloud
```

Delete existing plans using the following command:

```
$ openstack overcloud plan delete my-overcloud
```



NOTE

The **openstack overcloud deploy** command essentially uses all of these commands to remove the existing plan, upload a new plan with environment files, and deploy the plan.

5.9. VALIDATING OVERCLOUD TEMPLATES AND PLANS

Before executing an overcloud creation or stack update, validate your Heat templates and environment files for any errors.

Creating a Rendered Template

The core Heat templates for the overcloud are in a Jinja2 format. To validate your templates, render a version without Jinja2 formatting using the following commands:

```
$ openstack overcloud plan create --templates /usr/share/openstack-tripleo-heat-templates overcloud-validation
$ mkdir ~/overcloud-validation
$ cd ~/overcloud-validation
$ swift download overcloud-validation
```

Use the rendered template in **~/overcloud-validation** for the validation tests that follow.

Validating Template Syntax

Use the following command to validate the template syntax:

```
$ openstack orchestration template validate --show-nested --template
~/overcloud-validation/overcloud.yaml -e ~/overcloud-validation/overcloud-
resource-registry-puppet.yaml -e [ENVIRONMENT FILE] -e [ENVIRONMENT FILE]
```



NOTE

The validation requires the **overcloud-resource-registry-puppet.yaml** environment file to include overcloud-specific resources. Add any additional environment files to this command with **-e** option. Also include the **--show-nested** option to resolve parameters from nested templates.

This command identifies any syntax errors in the template. If the template syntax validates successfully, the output shows a preview of the resulting overcloud template.

5.10. MONITORING THE OVERCLOUD CREATION

The overcloud creation process begins and the director provisions your nodes. This process takes some time to complete. To view the status of the overcloud creation, open a separate terminal as the **stack** user and run:

```
$ source ~/stackrc
$ openstack stack list --nested
```

The **openstack stack list --nested** command shows the current stage of the overcloud creation.

5.11. ACCESSING THE OVERCLOUD

The director generates a script to configure and help authenticate interactions with your overcloud from the director host. The director saves this file, **overcloudrc**, in your **stack** user's home director. Run the following command to use this file:

```
$ source ~/overcloudrc
```

This loads the necessary environment variables to interact with your overcloud from the director host's CLI. To return to interacting with the director's host, run the following command:

```
$ source ~/stackrc
```

Each node in the overcloud also contains a user called **heat-admin**. The **stack** user has SSH access to this user on each node. To access a node over SSH, find the IP address of the desired node:

```
$ nova list
```

Then connect to the node using the **heat-admin** user and the node's IP address:

```
$ ssh heat-admin@192.168.24.23
```

5.12. COMPLETING THE OVERCLOUD CREATION

This concludes the creation of the overcloud using the command line tools. For post-creation functions, see [Chapter 8, *Performing Tasks after Overcloud Creation*](#).

CHAPTER 6. CONFIGURING A BASIC OVERCLOUD WITH THE WEB UI

This chapter provides the basic configuration steps for an OpenStack Platform environment using the web UI. An overcloud with a basic configuration contains no custom features. However, you can add advanced configuration options to this basic overcloud and customize it to your specifications using the instructions in the [Advanced Overcloud Customization](#) guide.

For the examples in this chapter, all nodes in this chapter are bare metal systems using IPMI for power management. For more supported power management types and their options, see [Appendix B, Power Management Drivers](#).

Workflow

1. Register blank nodes using a node definition template and manual registration.
2. Inspect hardware of all nodes.
3. Upload an overcloud plan to the director.
4. Assign nodes into roles.

Requirements

- The director node created in [Chapter 4, Installing the Undercloud](#) with the UI enabled
- A set of bare metal machines for your nodes. The number of node required depends on the type of overcloud you intend to create (see [Section 3.1, “Planning Node Deployment Roles”](#) for information on overcloud roles). These machines also must comply with the requirements set for each node type. For these requirements, see [Section 2.4, “Overcloud Requirements”](#). These nodes do not require an operating system. The director copies a Red Hat Enterprise Linux 7 image to each node.
- One network connection for our Provisioning network, which is configured as a native VLAN. All nodes must connect to this network and comply with the requirements set in [Section 2.3, “Networking Requirements”](#).
- All other network types use the Provisioning network for OpenStack services. However, you can create additional networks for other network traffic types.

6.1. ACCESSING THE WEB UI

Users access the director's web UI through SSL. For example, if the IP address of your undercloud is 192.168.24.1, then the address to access the UI is **https://192.168.24.1**. The web UI initially presents a login screen with fields for the following:

- **Username** - The administration user for the director. The default is **admin**.
- **Password** - The password for the administration user. Run **sudo hiera admin_password** as the **stack** user on the undercloud host terminal to find out the password.

When logging in to the UI, the UI accesses the OpenStack Identity Public API and obtains the endpoints for the other Public API services. These services include

Component	UI Purpose
OpenStack Identity (keystone)	For authentication to the UI and for endpoint discovery of other services.
OpenStack Orchestration (heat)	For the status of the deployment.
OpenStack Bare Metal (ironic)	For control of nodes.
OpenStack Object Storage (swift)	For storage of the Heat template collection or plan used for the overcloud creation.
OpenStack Workflow (mistral)	To access and execute director tasks.
OpenStack Messaging (zaqar)	A websocket-based service to find the status of certain tasks.

The UI interacts directly with these Public APIs, which is why your client system requires access to their endpoints. The director exposes these endpoints through SSL/TLS encrypted paths on the Public VIP (**undercloud_public_host** in your **undercloud.conf** file). Each path corresponds to the service. For example, **https://192.168.24.2:443/keystone** maps to the OpenStack Identity Public API.

If you aim to change the endpoints or use a different IP for endpoint access, the director UI reads settings from the **/var/www/openstack-tripleo-ui/dist/tripleo_ui_config.js** file. This file uses the following parameters:

Parameter	Description
keystone	The Public API for the OpenStack Identity (keystone) service. The UI automatically discovers the endpoints for the other services through this service, which means you only need to define this parameter. However, you can define custom URLs for the other endpoints if necessary.
heat	The Public API for the OpenStack Orchestration (heat) service.
ironic	The Public API for the OpenStack Bare Metal (ironic) service.
swift	The Public API for the OpenStack Object Storage (swift) service.
mistral	The Public API for the OpenStack Workflow (mistral) service.
zaqar-websocket	The websocket for the OpenStack Messaging (zaqar) service.

Parameter	Description
zaqar_default_queue	The messaging queue to use for the OpenStack Messaging (zaqar) service. The default is tripleo .

The following is an example `tripleo_ui_config.js` file where **192.168.24.2** is the Public VIP for the undercloud:

```
window.tripleOUiConfig = {
  'keystone': 'https://192.168.24.2:443/keystone/v2.0',
  'heat': 'https://192.168.24.2:443/heat/v1/(tenant_id)s',
  'ironic': 'https://192.168.24.2:443/ironic',
  'mistral': 'https://192.168.24.2:443/mistral/v2',
  'swift': 'https://192.168.24.2:443/swift/v1/AUTH_%(tenant_id)s',
  'zaqar-websocket': 'wss://192.168.24.2:443/zaqar',
  "zaqar_default_queue": "tripleo"
};
```

6.2. NAVIGATING THE WEB UI

The UI provides three main sections:

Deployment Plan

A menu item at the top of the UI. This page acts as the main UI section and allows you to define the plan to use for your overcloud creation, the nodes to assign to each role, and the status of the current overcloud. This section also provides a deployment workflow to guide you through each step of the overcloud creation process, including setting deployment parameters and assigning your nodes to roles.

overcloud [Manage Deployments](#)

The screenshot displays the 'Deployment Plan' section of the OpenStack Web UI. It features a vertical progress bar on the left with four numbered steps:

- 1 Prepare Hardware**: Includes a button labeled '+ Register Nodes'.
- 2 Specify Deployment Configuration**: Includes the text 'Base resources configuration, user-environment.yaml' and a link 'Edit Configuration'.
- 3 Configure Roles and Assign Nodes**: Shows '6 Nodes available to assign' and a grid of five role cards:
 - Block Storage**: 0 Nodes assigned, Assign Nodes button.
 - Controller**: 0 Nodes assigned, Assign Nodes button.
 - Compute**: 0 Nodes assigned, Assign Nodes button.
 - Object Storage**: 0 Nodes assigned, Assign Nodes button.
 - Ceph Storage**: 0 Nodes assigned, Assign Nodes button.
- 4 Deploy**: Includes a button labeled 'Validate and Deploy'.

Nodes

A menu item at the top of the UI. This page acts as a node configuration section and provides methods for registering new nodes and introspecting registered nodes. This section also defines the nodes available for deployment, the nodes currently deployed, and nodes in maintenance.

Nodes

[Refresh Results](#) [+ Register Nodes](#)

Registered 8

Deployed 0

Maintenance 0

Filter

Showing 8 of 8 items

Introspect Nodes

Provide Nodes

Delete Nodes

	MAC Address(es)	Name	Role	CPU Arch.	CPU (cores)	Disk (GB)	Memory (MB)	Power State	Provision State
<input type="checkbox"/>	52:54:00:ec:52:50	node01	Not assigned	x86_64	1	49	4096	power off	available
<input type="checkbox"/>	52:54:00:62:22:24	node02	Not assigned	x86_64	1	49	4096	power off	available
<input type="checkbox"/>	52:54:00:d7:f9:fa	node03	Not assigned	x86_64	2	99	8192	power off	available
<input type="checkbox"/>	52:54:00:1a:8c:ee	node04	Not assigned	x86_64	2	99	8192	power off	available
<input type="checkbox"/>	52:54:00:09:b0:ff	node05	Not assigned	x86_64	2	99	8192	power off	available
<input type="checkbox"/>	52:54:00:5a:6c:b9	node06	Not assigned	x86_64	1	49	6144	power off	available
<input type="checkbox"/>	52:54:00:d8:d4:1e	node07	Not assigned	x86_64	1	49	8192	power off	available
<input type="checkbox"/>	52:54:00:b8:fe:fb	node08	Not assigned	x86_64	1	49	4096	power off	available

Validations

A side panel on the right side of the page. This section provides a set of pre-deployment and post-deployment system checks to ensure a successful overcloud creation process. These validation tasks run automatically at certain points in the deployment. However, you can also run them manually. Click the **Play** button for a validation task you want to run. Click the title of each validation task to run it, or click a validation title to view more information about it.



Verify the undercloud fits the RAM requirements

Verify that the undercloud has enough RAM. <https://access.redhat.com/...>

prep

pre-introspection

6.3. IMPORTING AN OVERCLOUD PLAN IN THE WEB UI

The director UI requires a plan before configuring the overcloud. This plan is usually a Heat template collection, like the one on your undercloud at `/usr/share/openstack-tripleo-heat-templates`. In addition, you can customize the plan to suit your hardware and environment requirements. For more information about customizing the overcloud, see the [Advanced Overcloud Customization](#) guide.

The plan displays four main steps to configuring your overcloud:

1. **Prepare Hardware** - Node registration and introspection.
2. **Specify Deployment Configuration** - Configuring overcloud parameters and defining the environment files to include.
3. **Configure Roles and Assign Nodes** - Assign nodes to roles and modify role-specific parameters.
4. **Deploy** - Launch the creation of your overcloud.

The undercloud installation and configuration automatically uploads a plan. You can also import multiple plans in the web UI. Click on **Manage Deployments** on the **Deployment Plan** screen. This displays the current **Plans** table.

Click **Create New Plan** and a window appears asking you for the following information:

- **Plan Name** - A plain text name for the plan. For example **overcloud**.
- **Upload Type** - Choose whether to upload a **Tar Archive (tar.gz)** or a full **Local Folder** (Google Chrome only).
- **Plan Files** - Click browser to choose the plan on your local file system.

If you need to copy the director's Heat template collection to a client machine, archive the files and copy them:

```
$ cd /usr/share/openstack-tripleo-heat-templates/
$ tar -cf ~/overcloud.tar *
$ scp ~/overcloud.tar user@10.0.0.55:~/.
```

Once the director UI uploads the plan, the plan appears in the **Plans** table and you can now configure it. Click on the **Deployment Plan**.

Plans

Showing 1 of 1 items		+ Create New Plan
Name	Actions	
overcloud	Edit	Delete

6.4. REGISTERING NODES IN THE WEB UI

The first step in configuring the overcloud is to register your nodes. Start the node registration process either through:

- Clicking **Register Nodes** under **1 Prepare Hardware** on the **Deployment Plan** screen.
- Clicking **Register Nodes** on the **Nodes** screen.

This displays the **Register Nodes** window.

The director requires a list of nodes for registration, which you can supply using one of two methods:

1. **Uploading a node definition template** - This involves clicking the **Upload from File** button and selecting a file. See [Section 5.1, “Registering Nodes for the Overcloud”](#) for the syntax of the node definition template.
2. **Manually registering each node** - This involves clicking **Add New** and providing a set of details for the node.

The details you need to provide for manual registration include the following:

Name

A plain text name for the node. Use only *RFC3986* unreserved characters.

Driver

The power management driver to use. This example uses the IPMI driver (`pxe_ipmitool`) but other drivers are available. See [Appendix B, Power Management Drivers](#) for available drivers.

IPMI IP Address

The IP address of the IPMI device.

IPMI Username; IPMI Password

The IPMI username and password.

Architecture

(Optional) The system architecture.

CPU count

(Optional) The number of CPUs on the node.

Memory (MB)

(Optional) The amount of memory in MB.

Disk (GB)

(Optional) The size of the hard disk in GB.

NIC MAC Addresses

A list of MAC addresses for the network interfaces on the node. Use only the MAC address for the Provisioning NIC of each system.

**NOTE**

The UI also allows for registration of nodes from a KVM host using the **pxe_ssh** driver. Note that this option is available for testing and evaluation purposes only. It is not recommended for Red Hat OpenStack Platform enterprise environments. For more information, see [Section B.6, “SSH and Virsh”](#).

After entering your node information, click **Register Nodes** at the bottom of the window.

The director registers the nodes. Once complete, you can use the UI to perform introspection on the nodes.

6.5. INSPECTING THE HARDWARE OF NODES IN THE WEB UI

The director UI can run an introspection process on each node. This process causes each node to boot an introspection agent over PXE. This agent collects hardware data from the node and sends it back to the director. The director then stores this introspection data in the OpenStack Object Storage (swift) service running on the director. The director uses hardware information for various purposes such as profile tagging, benchmarking, and manual root disk assignment.

**NOTE**

You can also create policy files to automatically tag nodes into profiles immediately after introspection. For more information on creating policy files and including them in the introspection process, see [Appendix E, *Automatic Profile Tagging*](#). Alternatively, you can tag nodes into profiles through the UI. See [Section 6.7, “Tagging Nodes into Roles in the Web UI”](#) for details on manually tagging nodes.

To start the introspection process:

1. Navigate to the **Nodes** screen
2. Select all nodes you aim to introspect.
3. Click **Introspect Nodes**

**IMPORTANT**

Make sure this process runs to completion. This process usually takes 15 minutes for bare metal nodes.

Once the introspection process completes, select all nodes with the **Provision State** set to **manageable** then click the **Provide Nodes** button. Wait until the **Provision State** changes to **available**.

The nodes are now ready to provision.

6.6. EDITING OVERCLOUD PLAN PARAMETERS IN THE WEB UI

The **Deployment Plan** screen provides a method to customize your uploaded plan. Under **2 Specify Deployment Configuration**, click the **Edit Configuration** link to modify your base overcloud configuration.

A window appears with two main tabs:

Overall Settings

This provides a method to include different features from your overcloud. These features are defined in the plan's **capabilities-map.yaml** file, which each feature using a different environment file. For example, under **Storage** you can select **Storage Environment**, which the plan maps to the **environments/storage-environment.yaml** file and allows you to configure NFS, iSCSI, or Ceph settings for your overcloud. The **Other** tab contains any environment files detected in the plan but not listed in the **capabilities-map.yaml**, which is useful for adding custom environment files included in the plan. Once you have selected the features to include, click **Save**.

Deployment Configuration

Overall Settings

Parameters

Deployment Options

Nova Extensions

Utilities

Base Resources Configuration

Operational Tools

Neutron Plugin Configuration

Other

Overlay Network Configuration

Additional Services

Storage

High Availability

Enables configuration of an Overcloud controller with Pacemaker

☐ Pacemaker

Enable configuration of an Overcloud controller with Pacemaker

Pacemaker options

☐ Pacemaker No Restart

Docker RDO

Docker container with heat agents for containerized compute node

☐ Docker RDO

Enable TLS

☐ TLS

Use this option to pass in certificates for SSL deployments. For these values to take effect, one of the TLS endpoints environments must also be used.

TLS Endpoints

☐ SSL-enabled deployment with DNS name as public endpoint

Use this environment when deploying an SSL-enabled overcloud where the public endpoint is a DNS name.

☐ SSL-enabled deployment with IP address as public endpoint

Use this environment when deploying an SSL-enabled overcloud where the public endpoint is an IP address.

External load balancer

Enable external load balancer

☐ External load balancer IPv6
 ☐ External load balancer IPv4

Save Changes

Cancel

Parameters

This includes various base-level and environment file parameters for your overcloud. For example, you can change the node count for each role in this section. If you aim to use three controller nodes, change the **ControllerCount** to 3. Once you have modified your base-level parameters, click **Save**.

Deployment Configuration
✕

Overall Settings
Parameters

BlockStorageCount

Number of BlockStorage nodes to deploy

BlockStorageHostnameFormat

Format for BlockStorage node hostnames Note %index% is translated into the index of the node, e.g 0/1/2 etc and %stackname% is replaced with the stack name e.g overcloud

BlockStorageRemovalPolicies

BlockStorageSchedulerHints

BlockStorageServices

OS::TripleO::Services::CACerts,OS::TripleO::Services::BlockStorageCinderVolume,OS::TripleO::Services::Kernel,OS::TripleO::Services::Ntp,OS::TripleO::Services::Timezone,OS::TripleO::Services::Snmp,OS::TripleO::Services::TripleoPackages,OS::TripleO::Services::TripleoFirewall,OS::TripleO::Services::SensuClient,OS::TripleO::Services::FluentdClient,OS::TripleO::Services::VipHosts

CephStorageCount

CephStorageHostnameFormat

6.7. TAGGING NODES INTO ROLES IN THE WEB UI

After registering and inspecting the hardware of each node, you tag them into specific profiles. These profiles match your nodes to a specific flavor and deployment role.

To assign nodes to a role, scroll to the **3 Configure Roles and Assign Nodes** section on the **Deployment Plan** screen. Click **Assign Nodes** for a chosen role. A window appears that allows you to select the nodes to assign to the role. Once you have selected the role's nodes, click **Assign/Unassign Selected Nodes**.

Assign Nodes to Controller Role ✕

Showing 8 of 8 items
Assign/Unassign Selected Nodes

	MAC Address(es)	Name	Role	CPU Arch.	CPU (cores)	Disk (GB)	Memory (MB)	Power State	Provision State
<input type="checkbox"/>	52:54:00:b8:fe:fb	node08	Not assigned	x86_64	1	49	4096	power off	available
<input type="checkbox"/>	52:54:00:1a:8c:ee	node04	Not assigned	x86_64	2	99	8192	power off	available
<input type="checkbox"/>	52:54:00:5a:6c:b9	node06	Not assigned	x86_64	1	49	6144	power off	available
<input type="checkbox"/>	52:54:00:d7:f9:fa	node03	Not assigned	x86_64	2	99	8192	power off	available
<input type="checkbox"/>	52:54:00:ec:52:50	node01	Not assigned	x86_64	1	49	4096	power off	available
<input type="checkbox"/>	52:54:00:09:b0:ff	node05	Not assigned	x86_64	2	99	8192	power off	available
<input type="checkbox"/>	52:54:00:d8:d4:1e	node07	Not assigned	x86_64	1	49	8192	power off	available
<input type="checkbox"/>	52:54:00:62:22:24	node02	Not assigned	x86_64	1	49	4096	power off	available


Done

Once these nodes are assigned to the role, click **Done** to return to the **Deployment Plan** screen.

Complete this task for each role you want in your overcloud.

6.8. EDITING NODES IN THE WEB UI

Each node role provides a method for configuring role-specific parameters. Scroll to **3 Configure Roles and Assign Nodes** roles on the **Deployment Plan** screen. Click the **Edit Role Parameters** icon (pencil icon) next to the role name.



A window appears that shows two main tabs:

Parameters

This includes various role specific parameters. For example, if you are editing the controller role, you can change the default flavor for the role using the **OvercloudControlFlavor** parameter. Once you have modified your role specific parameters, click **Save Changes**.

Controller Role

Parameters

Services

Network Configuration

SoftwareConfigTransport

POLL_TEMP_URL

How the server should receive the metadata required for software configuration.

EndpointMap

{}

Mapping of service endpoint -> protocol. Typically set via parameter_defaults in the resource registry.

HostnameMap

{}

Optional mapping to override hostnames

ConfigCommand

os-refresh-config --timeout 14400

Command which will be run whenever configuration data changes

KeyName

default

Name of an existing Nova key pair to enable SSH access to the instances

NetworkDeploymentActions

CREATE

Heat action when to apply network configuration changes

ControllerSchedulerHints

{}

Optional scheduler hints to pass to nova

Services

This defines the service-specific parameters for the chosen role. The left panel shows a list of services that you select and modify. For example, to change the time zone, click the **OS::TripleO::Services::Timezone** service and change the **TimeZone** parameter to your desired time zone. Once you have modified your service-specific parameters, click **Save Changes**.

Controller Role

Parameters

Services

Network Configuration

OS::TripleO::Services::NeutronCorePlugin
OS::TripleO::Services::SwiftRingBuilder
OS::TripleO::Services::CeilometerCollector
OS::TripleO::Services::NovaApi
OS::TripleO::Services::GnocchiStatsd
OS::TripleO::Services::AodhNotifier
OS::TripleO::Services::Timezone
OS::TripleO::Services::NovaScheduler
OS::TripleO::Services::NeutronDhcpAgent
OS::TripleO::Services::CinderApi
OS::TripleO::Services::NeutronMetadataAgent
OS::TripleO::Services::SwiftProxy
OS::TripleO::Services::TripleoFirewall
OS::TripleO::Services::NovaMetadata
OS::TripleO::Services::CeilometerAgentNotification

TimeZone
UTC

The timezone to be set on the overcloud.

DefaultPasswords
{}

EndpointMap
{}

Mapping of service endpoint -> protocol. Typically set via parameter_defaults in the resource registry.

ServiceNetMap
{}

Mapping of service_name -> network name. Typically set via parameter_defaults in the resource registry. This mapping overrides those in ServiceNetMapDefaults.

Network Configuration

This allows you to define an IP address or subnet range for various networks in your overcloud.

Controller Role

Parameters

Services

Network Configuration

Software Config to drive os-net-config for a simple bridge.

TenantIpSubnet

IP address/subnet on the tenant network

ManagementIpSubnet

IP address/subnet on the management network

ExternalIpSubnet

IP address/subnet on the external network

StorageIpSubnet

IP address/subnet on the storage network

StorageMgmtIpSubnet

IP address/subnet on the storage mgmt network

ControlPlaneIp

IP address/subnet on the ctlplane network

InternalApiIpSubnet

IP address/subnet on the internal API network



IMPORTANT

Although the role's service parameters appear in the UI, some services might be disabled by default. You can enable these services through the instructions in [Section 6.6, “Editing Overcloud Plan Parameters in the Web UI”](#). See also the *Composable Roles* section of the [Advanced Overcloud Customization](#) guide for information on enabling these services.

6.9. STARTING THE OVERCLOUD CREATION IN THE WEB UI

Once the overcloud plan is configured, you can start the overcloud deployment. This involves scrolling to the **4 Deploy** section and clicking **Validate and Deploy**.



If you have not run or passed all the validations for the undercloud, a warning message appears. Make sure that your undercloud host satisfies the requirements before running a deployment.



Deploy Plan overcloud

Summary: Base resources configuration, user-environment.yaml



Not all pre-deployment validations have passed

It is highly recommended that you resolve all validation issues before continuing.

Are you sure you want to deploy this plan?



When you are ready to deploy, click **Deploy**.

The UI regularly monitors the progress of the overcloud's creation and display a progress bar indicating the current percentage of progress. The **View detailed information** link displays a log of the current OpenStack Orchestration stacks in your overcloud.

Plan overcloud deployment
×

Deployment in progress
31%

Resources

Filter
Showing 52 of 52 items

Name	Status	Updated Time
MysqlRootPassword	CREATE_COMPLETE	2016-11-24T07:00:08Z
PcsdPassword	CREATE_COMPLETE	2016-11-24T07:00:08Z
VipMap	CREATE_COMPLETE	2016-11-24T07:00:08Z
RabbitCookie	CREATE_COMPLETE	2016-11-24T07:00:08Z
Controller	INIT_COMPLETE	2016-11-24T07:00:08Z
ObjectStorage	INIT_COMPLETE	2016-11-24T07:00:08Z
ObjectStorageIplListMap	INIT_COMPLETE	2016-11-24T07:00:08Z
ControllerIplListMap	INIT_COMPLETE	2016-11-24T07:00:08Z
BlockStorageServiceChain	CREATE_IN_PROGRESS	2016-11-24T07:00:08Z
ComputeHostsDeployment	INIT_COMPLETE	2016-11-24T07:00:08Z
RedisVirtualIP	CREATE_COMPLETE	2016-11-24T07:00:08Z
StorageVirtualIP	CREATE_COMPLETE	2016-11-24T07:00:08Z

Wait until the overcloud deployment completes.

After the overcloud creation process completes, the **4 Deploy** section displays the current overcloud status and the following details:

- **IP address** - The IP address for accessing your overcloud.
- **Password** - The password for the OpenStack **admin** user on the overcloud.

Use this information to access your overcloud.

✓
Deployment succeeded
Stack CREATE completed successfully

Overcloud information:

- Overcloud IP address:
- Username: admin
- Password:

🗑 Delete Deployment

6.10. COMPLETING THE OVERCLOUD CREATION


This concludes the creation of the overcloud through the director's UI. For post-creation functions, see [Chapter 8, Performing Tasks after Overcloud Creation](#).

CHAPTER 7. CONFIGURING A BASIC OVERCLOUD USING PRE-PROVISIONED NODES

This chapter provides the basic configuration steps for using pre-provisioned nodes to configure an OpenStack Platform environment. This scenario differs from the standard overcloud creation scenarios in multiple ways:

- You can provision nodes using an external tool and let the director control the overcloud configuration only.
- You can use nodes without relying on the director's provisioning methods. This is useful if creating an overcloud without power management control or using networks with DHCP/PXE boot restrictions.
- The director does not use OpenStack Compute (nova), OpenStack Bare Metal (ironic), or OpenStack Image (glance) for managing nodes.
- Pre-provisioned nodes use a custom partitioning layout.

This scenario provides basic configuration with no custom features. However, you can add advanced configuration options to this basic overcloud and customize it to your specifications using the instructions in the [Advanced Overcloud Customization](#) guide.



IMPORTANT

Mixing pre-provisioned nodes with director-provisioned nodes in an overcloud is not supported.

Requirements

- The director node created in [Chapter 4, *Installing the Undercloud*](#).
- A set of bare metal machines for your nodes. The number of nodes required depends on the type of overcloud you intend to create (see [Section 3.1, “Planning Node Deployment Roles”](#) for information on overcloud roles). These machines also must comply with the requirements set for each node type. For these requirements, see [Section 2.4, “Overcloud Requirements”](#). These nodes require a Red Hat Enterprise Linux 7.3 operating system.
- One network connection for managing the pre-provisioned nodes. This scenario requires uninterrupted SSH access to the nodes for orchestration agent configuration.
- One network connection for the Control Plane network. There are two main scenarios for this network:
 - Using the Provisioning Network as the Control Plane, which is the default scenario. This network is usually a layer-3 (L3) routable network connection from the pre-provisioned nodes to the director. The examples for this scenario use following IP address assignments:

Table 7.1. Provisioning Network IP Assignments

Node Name	IP Address
Director	192.168.24.1

Node Name	IP Address
Controller	192.168.24.2
Compute	192.168.24.3

- Using a separate network. In situations where the director's Provisioning network is a private non-routable network, you can define IP addresses for the nodes from any subnet and communicate with the director over the Public API endpoint. There are certain caveats to this scenario, which this chapter examines later in [Section 7.6, "Using a Separate Network for Overcloud Nodes"](#).
- All other network types in this example also use the Control Plane network for OpenStack services. However, you can create additional networks for other network traffic types.

7.1. CREATING A USER FOR CONFIGURING NODES

At a later stage in this process, the director requires SSH access to the overcloud nodes as the **stack** user.

- On each overcloud node, create the user named **stack** and set a password on each node. For example, use the following on the Controller node:

```
[root@controller ~]# useradd stack
[root@controller ~]# passwd stack # specify a password
```

- Disable password requirements for this user when using **sudo**:

```
[root@controller ~]# echo "stack ALL=(root) NOPASSWD:ALL" | tee -a
/etc/sudoers.d/stack
[root@controller ~]# chmod 0440 /etc/sudoers.d/stack
```

- Once you have created and configured the **stack** user on all pre-provisioned nodes, copy the **stack** user's public SSH key from the director node to each overcloud node. For example, to copy the director's public SSH key to the Controller node:

```
[stack@director ~]$ ssh-copy-id stack@192.168.24.2
```

7.2. REGISTERING THE OPERATING SYSTEM FOR NODES

Each node requires access to a Red Hat subscription. The following procedure shows how to register each node to the Red Hat Content Delivery Network. Perform these steps on each node:

- Run the registration command and enter your Customer Portal user name and password when prompted:

```
[root@controller ~]# sudo subscription-manager register
```

- Find the entitlement pool for the Red Hat OpenStack Platform 11.


```
[root@controller ~]# sudo subscription-manager list --available --all --matches="*OpenStack*"
```

3. Use the pool ID located in the previous step to attach the Red Hat OpenStack Platform 11 entitlements:

```
[root@controller ~]# sudo subscription-manager attach --pool=pool_id
```

4. Disable all default repositories, and then enable the required Red Hat Enterprise Linux repositories:

```
[root@controller ~]# sudo subscription-manager repos --disable=*
[root@controller ~]# sudo subscription-manager repos --enable=rhel-7-server-rpms --enable=rhel-7-server-extras-rpms --enable=rhel-7-server-rh-common-rpms --enable=rhel-ha-for-rhel-7-server-rpms --enable=rhel-7-server-openstack-11-rpms --enable=rhel-7-server-rhceph-2-osd-rpms --enable=rhel-7-server-rhceph-2-mon-rpms --enable=rhel-7-server-rhceph-2-tools-rpms
```



IMPORTANT

Only enable the repositories listed in [Section 2.5, “Repository Requirements”](#). Additional repositories can cause package and software conflicts. Do not enable any additional repositories.

5. Update your system to ensure sure you have the latest base system packages:

```
[root@controller ~]# sudo yum update -y
[root@controller ~]# sudo reboot
```

The node is now ready to use for your overcloud.

7.3. INSTALLING THE USER AGENT ON NODES

Each pre-provisioned node uses the OpenStack Orchestration (heat) agent to communicate with the director. The agent on each node polls the director and obtains metadata tailored to each node. This metadata allows the agent to configure each node.

Install the initial packages for the orchestration agent on each node:

```
[root@controller ~]# sudo yum -y install python-heat-agent*
```

7.4. CONFIGURING SSL/TLS ACCESS TO THE DIRECTOR

If the director uses SSL/TLS, the pre-provisioned nodes require the certificate authority file used to sign the director's SSL/TLS certificates. If using your own certificate authority, perform the following on each overcloud node:

1. Copy the certificate authority file to the `/etc/pki/ca-trust/source/anchors/` directory on each pre-provisioned node.
2. Run the following command on each overcloud node:

```
[root@controller ~]# sudo update-ca-trust extract
```

This ensures the overcloud nodes can access the director's Public API over SSL/TLS.

7.5. CONFIGURING NETWORKING FOR THE CONTROL PLANE

The pre-provisioned overcloud nodes obtain metadata from the director using standard HTTP requests. This means all overcloud nodes require L3 access to either:

- The director's Control Plane network, which is the subnet defined with the **network_cidr** parameter from your **undercloud.conf** file. The nodes either requires direct access to this subnet or routable access to the subnet.
- The director's Public API endpoint, specified as the **undercloud_public_host** parameter from your **undercloud.conf** file. This option is available if either you do not have an L3 route to the Control Plane or you aim to use SSL/TLS communication when polling the director for metadata. See [Section 7.6, "Using a Separate Network for Overcloud Nodes"](#) for additional steps for configuring your overcloud nodes to use the Public API endpoint.

The director uses a Control Plane network to manage and configure a standard overcloud. For an overcloud with pre-provisioned nodes, your network configuration might require some modification to accommodate how the director communicates with the pre-provisioned nodes.

Using Network Isolation

Network isolation allows you to group services to use specific networks, including the Control Plane. There are multiple network isolation strategies contained in the [The Advanced Overcloud Customization](#) guide. In addition, you can also define specific IP addresses for nodes on the control plane. For more information on isolation networks and creating predictable node placement strategies, see the following sections in the *Advanced Overcloud Customizations* guide:

- ["Isolating Networks"](#)
- ["Controlling Node Placement"](#)



NOTE

If using network isolation, make sure your NIC templates do not include the NIC used for undercloud access. These template can reconfigure the NIC, which can lead to connectivity and configuration problems during deployment.

Assigning IP Addresses

If not using network isolation, you can use a single Control Plane network to manage all services. This requires manual configuration of the Control Plane NIC on each node to use an IP address within the Control Plane network range. If using the director's Provisioning network as the Control Plane, make sure the chosen overcloud IP addresses fall outside of the DHCP ranges for both provisioning (**dhcp_start** and **dhcp_end**) and introspection (**inspection_iprange**).

During standard overcloud creation, the director creates OpenStack Networking (neutron) ports to automatically assigns IP addresses to the overcloud nodes on the Provisioning / Control Plane network. However, this can cause the director to assign different IP addresses to the ones manually configured for each node. In this situation, use a predictable IP address strategy to force the director to use the pre-provisioned IP assignments on the Control Plane.

An example of a predictable IP strategy is to use an environment file (**ctlplane-assignments.yaml**) with the following IP assignments:

```
resource_registry:
  OS::TripleO::DeployedServer::ControlPlanePort: /usr/share/openstack-
    tripleo-heat-templates/deployed-server/deployed-neutron-port.yaml

parameter_defaults:
  DeployedServerPortMap:
    controller-ctlplane:
      fixed_ips:
        - ip_address: 192.168.24.2
      subnets:
        - cidr: 24
    compute-ctlplane:
      fixed_ips:
        - ip_address: 192.168.24.3
      subnets:
        - cidr: 24
```

In this example, the **OS::TripleO::DeployedServer::ControlPlanePort** resource passes a set of parameters to the director and defines the IP assignments of our pre-provisioned nodes. The **DeployedServerPortMap** parameter defines the IP addresses and subnet CIDRs that correspond to each overcloud node. The mapping defines:

1. The name of the assignment, which follows the format **<node_hostname>-<network>**
2. The IP assignments, which use the following parameter patterns:
 - **fixed_ips/ip_address** - Defines the fixed IP addresses for the control plane. Use multiple **ip_address** parameters in a list to define multiple IP addresses.
 - **subnets/cidr** - Defines the CIDR value for the subnet.

A later step in this chapter uses the resulting environment file (**ctlplane-assignments.yaml**) as part of the **openstack overcloud deploy** command.

7.6. USING A SEPARATE NETWORK FOR OVERCLOUD NODES

By default, the director uses the Provisioning network as the overcloud Control Plane. However, if this network is isolated and non-routable, nodes cannot communicate with the director's Internal API during configuration. In this situation, you might need to define a separate network for the nodes and configure them to communicate with the director over the Public API.

There are several requirements for this scenario:

- The overcloud nodes must accommodate the basic network configuration from [Section 7.5, “Configuring Networking for the Control Plane”](#).
- You must enable SSL/TLS on the director for Public API endpoint usage. For more information, see [Section 4.6, “Configuring the Director”](#) and [Appendix A, SSL/TLS Certificate Configuration](#).
- You must define an accessible fully qualified domain name (FQDN) for director. This FQDN must resolve to a routable IP address for the director. Use the **undercloud_public_host** parameter in the **undercloud.conf** file to set this FQDN.

The examples in this section use IP address assignments that differ from the main scenario:

Table 7.2. Provisioning Network IP Assignments

Node Name	IP Address or FQDN
Director (Internal API)	192.168.24.1 (Provisioning Network and Control Plane)
Director (Public API)	10.1.1.1 / director.example.com
Overcloud Virtual IP	192.168.100.1
Controller	192.168.100.2
Compute	192.168.100.3

The following sections provide additional configuration for situations that require a separate network for overcloud nodes.

Orchestration Configuration

With SSL/TLS communication enabled on the undercloud, the director provides a Public API endpoint for most services. However, OpenStack Orchestration (heat) uses the internal endpoint as a default provider for metadata. This means the undercloud requires some modification so overcloud nodes can access OpenStack Orchestration on public endpoints. This modification involves changing some Puppet hieradata on the director.

The **hieradata_override** in your **undercloud.conf** allows you to specify additional Puppet hieradata for undercloud configuration. Use the following steps to modify hieradata relevant to OpenStack Orchestration:

1. If you are not using a **hieradata_override** file already, create a new one. This example uses one located at **/home/stack/hieradata.yaml**.
2. Include the following hieradata in **/home/stack/hieradata.yaml**:

```
heat_clients_endpoint_type: public
heat::engine::default_deployment_signal_transport: TEMP_URL_SIGNAL
```

This changes the endpoint type from the default **internal** to **public** and changes the signaling method to use TempURLs from OpenStack Object Storage (swift).

3. In your **undercloud.conf**, set the **hieradata_override** parameter to the path of the hieradata file:

```
hieradata_override = /home/stack/hieradata.yaml
```

4. Rerun the **openstack overcloud install** command to implement the new configuration options.

This switches the orchestration metadata server to use URLs on the director's Public API.

IP Address Assignments

The method for IP assignments is similar to [Section 7.5, “Configuring Networking for the Control Plane”](#). However, since the Control Plane is not routable from the deployed servers, you use the **DeployedServerPortMap** parameter to assign IP addresses from your chosen overcloud node subnet, including the virtual IP address to access the Control Plane. The following is a modified version of the **ctlplane-assignments.yaml** environment file from [Section 7.5, “Configuring Networking for the Control Plane”](#) that accommodates this network architecture:

```
resource_registry:
  OS::TripleO::DeployedServer::ControlPlanePort: /usr/share/openstack-
tripleo-heat-templates/deployed-server/deployed-neutron-port.yaml
  OS::TripleO::Network::Ports::ControlPlaneVipPort: /usr/share/openstack-
tripleo-heat-templates/deployed-server/deployed-neutron-port.yaml
  OS::TripleO::Network::Ports::RedisVipPort: /usr/share/openstack-tripleo-
heat-templates/network/ports/noop.yaml ❶

parameter_defaults:
  NeutronPublicInterface: eth1
  EC2MetadataIp: 192.168.100.1 ❷
  ControlPlaneDefaultRoute: 192.168.100.1
  DeployedServerPortMap:
    control_virtual_ip:
      fixed_ips:
        - ip_address: 192.168.100.1
      subnets:
        - cidr: 24
    controller0-ctlplane:
      fixed_ips:
        - ip_address: 192.168.100.2
      subnets:
        - cidr: 24
    compute0-ctlplane:
      fixed_ips:
        - ip_address: 192.168.100.3
      subnets:
        - cidr: 24
```

- ❶ The **RedisVipPort** resource is mapped to **network/ports/noop.yaml**. This mapping is because the default Redis VIP address comes from the Control Plane. In this situation, we use a **noop** to disable this Control Plane mapping.
- ❷ The **EC2MetadataIp** and **ControlPlaneDefaultRoute** parameters are set to the value of the Control Plane virtual IP address. The default NIC configuration templates require these parameters and you must set them to use a pingable IP address to pass the validations performed during deployment. Alternatively, customize the NIC configuration so they do not require these parameters.

7.7. CREATING THE OVERCLOUD WITH PRE-PROVISIONED NODES

The overcloud deployment uses the standard CLI methods from [Section 5.6, “Creating the Overcloud with the CLI Tools”](#). For pre-provisioned nodes, the deployment command requires some additional options and environment files from the core Heat template collection:

- **--disable-validations** - Disables basic CLI validations for services not used with pre-provisioned infrastructure.
- **environments/deployed-server-environment.yaml** - Main environment file for creating and configuring pre-provisioned infrastructure. This environment file substitutes the **OS::Nova::Server** resources with **OS::Heat::DeployedServer** resources.
- **environments/deployed-server-bootstrap-environment-rhel.yaml** - Environment file to execute a bootstrap script on the pre-provisioned servers. This script installs additional packages and provides basic configuration for overcloud nodes.
- **environments/deployed-server-pacemaker-environment.yaml** - Environment file for Pacemaker configuration on pre-provisioned Controller nodes. The namespace for the resources registered in this file use the Controller role name from **deployed-server/deployed-server-roles-data.yaml**, which is **ControllerDeployedServer** by default.
- **deployed-server/deployed-server-roles-data.yaml** - An example custom roles file. This file replicates the default **roles_data.yaml** but also includes the **disable_constraints: True** parameter for each role. This parameter disables orchestration constraints in the generated role templates. These constraints are for services not used with pre-provisioned infrastructure.
If using your own custom roles file, make sure to include the **disable_constraints: True** parameter with each role. For example:

```
- name: ControllerDeployedServer
  disable_constraints: True
  CountDefault: 1
  ServicesDefault:
    - OS::TripleO::Services::CACerts
    - OS::TripleO::Services::CephMon
    - OS::TripleO::Services::CephExternal
    - OS::TripleO::Services::CephRgw
    ...
```

The following is an example overcloud deployment command with the environment files specific to the pre-provisioned architecture:

```
[stack@director ~]$ source ~/stackrc
[stack@director ~]$ openstack overcloud deploy \
  [other arguments] \
  --disable-validations \
  -e /usr/share/openstack-tripleo-heat-templates/environments/deployed-
server-environment.yaml \
  -e /usr/share/openstack-tripleo-heat-templates/environments/deployed-
server-bootstrap-environment-rhel.yaml \
  -e /usr/share/openstack-tripleo-heat-templates/environments/deployed-
server-pacemaker-environment.yaml \
  -r /usr/share/openstack-tripleo-heat-templates/deployed-server/deployed-
server-roles-data.yaml
```


This begins the overcloud configuration. However, the deployment stack pauses when the overcloud node resources enter the **CREATE_IN_PROGRESS** stage:

```
2017-01-14 13:25:13Z [overcloud.Compute.0.Compute]: CREATE_IN_PROGRESS
state changed
2017-01-14 13:25:14Z [overcloud.Controller.0.Controller]:
CREATE_IN_PROGRESS state changed
```

This pause is due to the director waiting for the orchestration agent on the overcloud nodes to poll the metadata server. The next section shows how to configure nodes to start polling the metadata server.

7.8. POLLING THE METADATA SERVER

The deployment is now in progress but paused at a **CREATE_IN_PROGRESS** stage. The next step is to configure the orchestration agent on the overcloud nodes to poll the metadata server on the director. There are two ways to accomplish this:



IMPORTANT

Only use automatic configuration for the initial deployment. Do not use automatic configuration if scaling up your nodes.

Automatic Configuration

The director's core Heat template collection contains a script that performs automatic configuration of the Heat agent on the overcloud nodes. The script requires you to source the **stackrc** file as the **stack** user to authenticate with the director and query the orchestration service:

```
[stack@director ~]$ source ~/stackrc
```

In addition, the script also requires some additional environment variables to define the nodes roles and their IP addresses. These environment variables are:

OVERCLOUD_ROLES

A space-separated list of roles to configure. These roles correlate to roles defined in your roles data file.

[ROLE]_hosts

Each role requires an environment variable with a space-separated list of IP addresses for nodes in the role.

The following commands demonstrate how to set these environment variables:

```
[stack@director ~]$ export OVERCLOUD_ROLES="ControllerDeployedServer
ComputeDeployedServer"
[stack@director ~]$ export ControllerDeployedServer_hosts="192.168.100.2"
[stack@director ~]$ export ComputeDeployedServer_hosts="192.168.100.3"
```

Run the script to configure the orchestration agent on each overcloud node:

```
[stack@director ~]$ /usr/share/openstack-tripleo-heat-templates/deployed-
server/scripts/get-occ-config.sh
```

**NOTE**

The script accesses the pre-provisioned nodes over SSH using the same user executing the script. In this case, the script authenticates with the **stack** user.

The script accomplishes the following:

- Queries the director's orchestration services for the metadata URL for each node.
- Accesses the node and configures the agent on each node with its specific metadata URL.
- Restarts the orchestration agent service.

Once the script completes, the overcloud nodes start polling orchestration service on the director. The stack deployment continues.

Manual configuration

If you prefer to manually configure the orchestration agent on the pre-provisioned nodes, use the following command to query the orchestration service on the director for each node's metadata URL:

```
[stack@director ~]$ source ~/stackrc
[stack@director ~]$ for STACK in $(openstack stack resource list -n5 --
filter name=deployed-server -c stack_name -f value overcloud) ; do
STACKID=$(echo $STACK | cut -d '-' -f2,4 --output-delimiter " "); echo "==
Metadata URL for $STACKID ==" ; openstack stack resource metadata $STACK
deployed-server | jq -r '["os-collect-config"].request.metadata_url' ;
echo ; done
```

This displays the stack name and metadata URL for each node:

```
== Metadata URL for ControllerDeployedServer 0 ==
http://192.168.24.1:8080/v1/AUTH_6fce4e6019264a5b8283e7125f05b764/ov-
edServer-ts6lr4tm5p44-deployed-server-td42md2tap4g/43d302fa-d4c2-40df-
b3ac-624d6075ef27?
temp_url_sig=58313e577a93de8f8d2367f8ce92dd7be7aac3a1&temp_url_expires=214
7483586

== Metadata URL for ComputeDeployedServer 0 ==
http://192.168.24.1:8080/v1/AUTH_6fce4e6019264a5b8283e7125f05b764/ov-
edServer-wdpk7upmz3eh-deployed-server-ghv7ptfikz2j/0a43e94b-fe02-427b-
9bfe-71d2b7bb3126?
temp_url_sig=8a50d8ed6502969f0063e79bb32592f4203a136e&temp_url_expires=214
7483586
```

On each overcloud node:

1. Remove the existing **os-collect-config.conf** template. This ensures the agent does not override our manual changes:

```
$ sudo /bin/rm -f /usr/libexec/os-apply-config/templates/etc/os-
collect-config.conf
```

2. Configure the **/etc/os-collect-config.conf** file to use the corresponding metadata URL. For example, the Controller node uses the following:

```
[DEFAULT]
collectors=request
command=os-refresh-config
polling_interval=30

[request]
metadata_url=http://192.168.24.1:8080/v1/AUTH_6fce4e6019264a5b8283e7
125f05b764/ov-edServer-ts6lr4tm5p44-deployed-server-
td42md2tap4g/43d302fa-d4c2-40df-b3ac-624d6075ef27?
temp_url_sig=58313e577a93de8f8d2367f8ce92dd7be7aac3a1&temp_url_expir
es=2147483586
```

3. Save the file.
4. Restart the **os-collect-config** service:

```
[stack@controller ~]$ sudo systemctl restart os-collect-config
```

After you have configured and restarted them, the orchestration agents poll the director's orchestration service for overcloud configuration. The deployment stack continues its creation and the stack for each node eventually changes to **CREATE_COMPLETE**.

7.9. MONITORING THE OVERCLOUD CREATION

The overcloud configuration process begins. This process takes some time to complete. To view the status of the overcloud creation, open a separate terminal as the **stack** user and run:

```
$ source ~/stackrc
$ heat stack-list --show-nested
```

The **heat stack-list --show-nested** command shows the current stage of the overcloud creation.

7.10. ACCESSING THE OVERCLOUD

The director generates a script to configure and help authenticate interactions with your overcloud from the director host. The director saves this file, **overcloudrc**, in your **stack** user's home director. Run the following command to use this file:

```
$ source ~/overcloudrc
```

This loads the necessary environment variables to interact with your overcloud from the CLI on the director node. To return to interacting with the director node, run:

```
$ source ~/stackrc
```

7.11. SCALING PRE-PROVISIONED NODES

The process for scaling pre-provisioned nodes is similar to the standard scaling procedures in [Chapter 9, *Scaling the Overcloud*](#). However, the process for adding new pre-provisioned nodes differs since pre-provisioned nodes do not use the standard registration and management process from OpenStack Bare Metal (ironic) and OpenStack Compute (nova).

Scaling Up Pre-Provisioned Nodes

When scaling up the overcloud with pre-provisioned nodes, you need to configure the orchestration agent on each node to correspond to the director's node count.

The general process for scaling up the nodes is:

1. Prepare the new pre-provisioned nodes as per the [Requirements](#).
2. Scale up the nodes. See [Chapter 9, *Scaling the Overcloud*](#) for these instructions.
3. After executing the deployment command, wait until the director creates the new node resources. Manually configure the pre-provisioned nodes to poll the director's orchestration server metadata URL as per the instructions in [Section 7.8, "Polling the Metadata Server"](#).

Scaling Down Pre-Provisioned Nodes

When scaling down the overcloud with pre-provisioned nodes, follow the scale down instructions as normal as shown in [Chapter 9, *Scaling the Overcloud*](#).

Once you have removed overcloud nodes from the stack, power off these nodes. Under a standard deployment, the bare metal services on the director control this function. However, with pre-provisioned nodes, you should either manually shutdown these nodes or use the power management control for each physical system. If you do not power off the nodes after removing them from the stack, they might remain operational and reconnect as part of the overcloud environment.

After powering down the removed nodes, reprovision them back to a base operating system configuration so that they do not unintentionally join the overcloud in the future



NOTE

Do not attempt to reuse nodes previously removed from the overcloud without first reprovisioning them with a fresh base operating system. The scale down process only removes the node from the overcloud stack and does not uninstall any packages.

7.12. REMOVING A PRE-PROVISIONED OVERCLOUD

Removing an entire overcloud that uses pre-provisioned nodes uses the same procedure as a standard overcloud. See [Section 8.11, "Removing the Overcloud"](#) for more details.

After removing the overcloud, power off all nodes and reprovision them back to a base operating system configuration.



NOTE

Do not attempt to reuse nodes previously removed from the overcloud without first reprovisioning them with a fresh base operating system. The removal process only deletes the overcloud stack and does not uninstall any packages.

7.13. COMPLETING THE OVERCLOUD CREATION

This concludes the creation of the overcloud using pre-provisioned nodes. For post-creation functions, see [Chapter 8, *Performing Tasks after Overcloud Creation*](#).

CHAPTER 8. PERFORMING TASKS AFTER OVERCLOUD CREATION

This chapter explores some of the functions you perform after creating your overcloud of choice.

8.1. CREATING THE OVERCLOUD TENANT NETWORK

The overcloud requires a Tenant network for instances. Source the **overcloud** and create an initial Tenant network in Neutron. For example:

```
$ source ~/overcloudrc
$ openstack network create default
$ openstack subnet create default --network default --gateway 172.20.1.1 -
-subnet-range 172.20.0.0/16
```

This creates a basic Neutron network called **default**. The overcloud automatically assigns IP addresses from this network using an internal DHCP mechanism.

Confirm the created network:

```
$ openstack network list
+-----+-----+-----+
| id | name | subnets |
+-----+-----+-----+
| 95fadaa1-5dda-4777... | default | 7e060813-35c5-462c-a56a-1c6f8f4f332f |
+-----+-----+-----+
```

8.2. CREATING THE OVERCLOUD EXTERNAL NETWORK

You need to create the External network on the overcloud so that you can assign floating IP addresses to instances.

Using a Native VLAN

This procedure assumes a dedicated interface or native VLAN for the External network.

Source the **overcloud** and create an External network in Neutron. For example:

```
$ source ~/overcloudrc
$ openstack network create public --external --provider-network-type flat
--provider-physical-network datacentre
$ openstack subnet create public --network public --dhcp --allocation-pool
start=10.1.1.51,end=10.1.1.250 --gateway 10.1.1.1 --subnet-range
10.1.1.0/24
```

In this example, you create a network with the name **public**. The overcloud requires this specific name for the default floating IP pool. This is also important for the validation tests in [Section 8.5, “Validating the Overcloud”](#).

This command also maps the network to the **datacentre** physical network. As a default, **datacentre** maps to the **br-ex** bridge. Leave this option as the default unless you have used custom neutron settings during the overcloud creation.

Using a Non-Native VLAN

If not using the native VLAN, assign the network to a VLAN using the following commands:

```
$ source ~/overcloudrc
$ openstack network create public --external --provider-network-type vlan
--provider-physical-network datacentre --provider-segment 104
$ openstack subnet create public --network public --dhcp --allocation-pool
start=10.1.1.51,end=10.1.1.250 --gateway 10.1.1.1 --subnet-range
10.1.1.0/24
```

The **provider:segmentation_id** value defines the VLAN to use. In this case, you can use 104.

Confirm the created network:

```
$ openstack network list
+-----+-----+-----+
| id                  | name          | subnets |
+-----+-----+-----+
| d474fe1f-222d-4e32... | public        | 01c5f621-1e0f-4b9d-9c30-7dc59592a52f |
+-----+-----+-----+
```

8.3. CREATING ADDITIONAL FLOATING IP NETWORKS

Floating IP networks can use any bridge, not just **br-ex**, as long as you meet the following conditions:

- **NeutronExternalNetworkBridge** is set to **''** in your network environment file.
- You have mapped the additional bridge during deployment. For example, to map a new bridge called **br-floating** to the **floating** physical network:

```
$ source ~/stackrc
$ openstack overcloud deploy --templates -e /usr/share/openstack-tripleo-heat-templates/environments/network-isolation.yaml -e
~/templates/network-environment.yaml --neutron-bridge-mappings
datacentre:br-ex,floating:br-floating
```

Create the Floating IP network after creating the overcloud:

```
$ source ~/overcloudrc
$ openstack network create ext-net --external --provider-physical-network
floating --provider-network-type vlan --provider-segment 105
$ openstack subnet create ext-subnet --network ext-net --dhcp --
allocation-pool start=10.1.2.51,end=10.1.2.250 --gateway 10.1.2.1 --
subnet-range 10.1.2.0/24
```

8.4. CREATING THE OVERCLOUD PROVIDER NETWORK

A provider network is a network attached physically to a network existing outside of the deployed overcloud. This can be an existing infrastructure network or a network that provides external access directly to instances through routing instead of floating IPs.

When creating a provider network, you associate it with a physical network, which uses a bridge mapping. This is similar to floating IP network creation. You add the provider network to both the Controller and the Compute nodes because the Compute nodes attach VM virtual network interfaces directly to the attached network interface.

For example, if the desired provider network is a VLAN on the br-ex bridge, use the following command to add a provider network on VLAN 201:

```
$ source ~/overcloudrc
$ openstack network create provider_network --provider-physical-network
datacentre --provider-network-type vlan --provider-segment 201 --share
```

This command creates a shared network. It is also possible to specify a tenant instead of specifying **--share**. That network will only be available to the specified tenant. If you mark a provider network as external, only the operator may create ports on that network.

Add a subnet to a provider network if you want neutron to provide DHCP services to the tenant instances:

```
$ source ~/overcloudrc
$ openstack subnet create provider-subnet --network provider_network --
dhcp --allocation-pool start=10.9.101.50,end=10.9.101.100 --gateway
10.9.101.254 --subnet-range 10.9.101.0/24
```

Other networks might require access externally through the provider network. In this situation, create a new router so that other networks can route traffic through the provider network:

```
$ openstack router create external
$ openstack router set --external-gateway provider_network external
```

Attach other networks to this router. For example, if you had a subnet called **subnet1**, you can attach it to the router with the following commands:

```
$ openstack router add subnet external subnet1
```

This adds **subnet1** to the routing table and allows traffic using **subnet1** to route to the provider network.

8.5. VALIDATING THE OVERCLOUD

The overcloud uses the OpenStack Integration Test Suite (tempest) tool set to conduct a series of integration tests. This section provides information on preparations for running the integration tests. For full instruction on using the OpenStack Integration Test Suite, see the [OpenStack Integration Test Suite Guide](#).

Before Running the Integration Test Suite

If running this test from the undercloud, ensure that the undercloud host has access to the overcloud's Internal API network. For example, add a temporary VLAN on the undercloud host to access the Internal API network (ID: 201) using the 172.16.0.201/24 address:

```
$ source ~/stackrc
$ sudo ovs-vsctl add-port br-ctlplane vlan201 tag=201 -- set interface
vlan201 type=internal
$ sudo ip l set dev vlan201 up; sudo ip addr add 172.16.0.201/24 dev
vlan201
```

Before running the OpenStack Integration Test Suite, check that the **heat_stack_owner** role exists in your overcloud:

```
$ source ~/overcloudrc
$ openstack role list
+-----+-----+
| ID                                     | Name               |
+-----+-----+
| 6226a517204846d1a26d15aae1af208f | swiftoperator      |
| 7c7eb03955e545dd86bbfeb73692738b | heat_stack_owner   |
+-----+-----+
```

If the role does not exist, create it:

```
$ openstack role create heat_stack_owner
```

After Running the Integration Test Suite

After completing the validation, remove any temporary connections to the overcloud's Internal API. In this example, use the following commands to remove the previously created VLAN on the undercloud:

```
$ source ~/stackrc
$ sudo ovs-vsctl del-port vlan201
```

8.6. MODIFYING THE OVERCLOUD ENVIRONMENT

Sometimes you might intend to modify the overcloud to add additional features, or change the way it operates. To modify the overcloud, make modifications to your custom environment files and Heat templates, then rerun the **openstack overcloud deploy** command from your initial overcloud creation. For example, if you created an overcloud using [Section 5.6, “Creating the Overcloud with the CLI Tools”](#), you would rerun the following command:

```
$ source ~/stackrc
$ openstack overcloud deploy --templates \
  -e ~/templates/node-info.yaml \
  -e /usr/share/openstack-tripleo-heat-templates/environments/network-
isolation.yaml \
  -e ~/templates/network-environment.yaml \
  -e ~/templates/storage-environment.yaml \
  --ntp-server pool.ntp.org
```

The director checks the **overcloud** stack in heat, and then updates each item in the stack with the environment files and heat templates. It does not recreate the overcloud, but rather changes the existing overcloud.

If you aim to include a new environment file, add it to the **openstack overcloud deploy** command with a **-e** option. For example:

```
$ source ~/stackrc
$ openstack overcloud deploy --templates \
  -e ~/templates/new-environment.yaml \
  -e /usr/share/openstack-tripleo-heat-templates/environments/network-
isolation.yaml \
  -e ~/templates/network-environment.yaml \
  -e ~/templates/storage-environment.yaml \
  -e ~/templates/node-info.yaml \
  --ntp-server pool.ntp.org
```

This includes the new parameters and resources from the environment file into the stack.



IMPORTANT

It is advisable not to make manual modifications to the overcloud's configuration as the director might overwrite these modifications later.

8.7. IMPORTING VIRTUAL MACHINES INTO THE OVERCLOUD

Use the following procedure if you have an existing OpenStack environment and aim to migrate its virtual machines to your Red Hat OpenStack Platform environment.

Create a new image by taking a snapshot of a running server and download the image.

```
$ openstack server image create instance_name --name image_name
$ openstack image save image_name --file exported_vm.qcow2
```

Upload the exported image into the overcloud and launch a new instance.

```
$ openstack image create imported_image --file exported_vm.qcow2 --disk-
format qcow2 --container-format bare
$ openstack server create imported_instance --key-name default --flavor
m1.demo --image imported_image --nic net-id=net_id
```



IMPORTANT

Each VM disk has to be copied from the existing OpenStack environment and into the new Red Hat OpenStack Platform. Snapshots using QCOW will lose their original layering system.

8.8. MIGRATING VMS FROM AN OVERCLOUD COMPUTE NODE

In some situations, you might perform maintenance on an overcloud Compute node. To prevent downtime, migrate the VMs on the Compute node to another Compute node in the overcloud.

The director configures all Compute nodes to provide secure migration. All Compute nodes also require

a shared SSH key to provide each host's **nova** user with access to other Compute nodes during the migration process. The director creates this key using the **OS::TripleO::Services::NovaCompute** composable service. This composable service is one of the main services included on all Compute roles by default (see "[Composable Services and Custom Roles](#)" in *Advanced Overcloud Customization*).

To migrate an instance:

1. From the undercloud, select a Compute Node to reboot and disable it:

```
$ source ~/overcloudrc
$ openstack compute service list
$ openstack compute service set [hostname] nova-compute --disable
```

2. List all instances on the Compute node:

```
$ openstack server list --host [hostname] --all-projects
```

3. Migrate each instance from the disabled host. Use one of the following commands:

- a. Migrate the instance to a specific host of your choice:

```
$ openstack server migrate [instance-id] --live [target-host] --wait
```

- b. Let **nova-scheduler** automatically select the target host:

```
$ nova live-migration [instance-id]
```



NOTE

The **nova** command might cause some deprecation warnings, which are safe to ignore.

4. Wait until migration completes.
5. Confirm the instance has migrated from the Compute node:

```
$ openstack server list --host [hostname] --all-projects
```

6. Repeat this step until you have migrated all instances from the Compute Node.

This migrates all instances from a Compute node. You can now perform maintenance on the node without any instance downtime. To return the Compute node to an enabled state, run the following command:

```
$ source ~/overcloudrc
$ openstack compute service set [hostname] nova-compute --enable
```

8.9. RUNNING ANSIBLE AUTOMATION

The director provides the ability to run Ansible-based automation on your OpenStack Platform environment. The director uses the **tripleo-ansible-inventory** command to generate a dynamic inventory of nodes in your environment.



IMPORTANT

The dynamic inventory tool only includes the undercloud and the default **controller** and **compute** overcloud nodes. Other roles are not supported.

To view a dynamic inventory of nodes, run the **tripleo-ansible-inventory** command after sourcing **stackrc**:

```
$ source ~/stackrc
$ tripleo-ansible-inventory --list
```

The **--list** option provides details on all hosts.

This outputs the dynamic inventory in a JSON format:

```
{
  "overcloud": {
    "children": ["controller", "compute"],
    "vars": {
      "ansible_ssh_user": "heat-admin"
    }
  },
  "controller": ["192.168.24.2"],
  "undercloud": {
    "hosts": ["localhost"],
    "vars": {
      "overcloud_horizon_url": "http://192.168.24.4:80/dashboard",
      "overcloud_admin_password": "abcdefghijklmnopqrstuvwxyz12345678",
      "ansible_connection": "local"
    }
  },
  "compute": ["192.168.24.3"]
}
```

To execute Ansible playbooks on your environment, run the **ansible** command and include the full path of the dynamic inventory tool using the **-i** option. For example:

```
ansible [HOSTS] -i /bin/tripleo-ansible-inventory [OTHER OPTIONS]
```

- Exchange **[HOSTS]** for the type of hosts to use. For example:
 - **controller** for all Controller nodes
 - **compute** for all Compute nodes
 - **overcloud** for all overcloud child nodes i.e. **controller** and **compute**
 - **undercloud** for the undercloud
 - **"*"** for all nodes
- Exchange **[OTHER OPTIONS]** for the additional Ansible options. Some useful options include:
 - **--ssh-extra-args='-o StrictHostKeyChecking=no'** to bypasses confirmation on host key checking.
 - **-u [USER]** to change the SSH user that executes the Ansible automation. The default SSH user for the overcloud is automatically defined using the **ansible_ssh_user** parameter in the dynamic inventory. The **-u** option overrides this parameter.
 - **-m [MODULE]** to use a specific Ansible module. The default is **command**, which executes Linux commands.

- **-a [MODULE_ARGS]** to define arguments for the chosen module.



IMPORTANT

Ansible automation on the overcloud falls outside the standard overcloud stack. This means subsequent execution of the **openstack overcloud deploy** command might override Ansible-based configuration for OpenStack Platform services on overcloud nodes.

8.10. PROTECTING THE OVERCLOUD FROM REMOVAL

To avoid accidental removal of the overcloud with the **heat stack-delete overcloud** command, Heat contains a set of policies to restrict certain actions. Edit the `/etc/heat/policy.json` and find the following parameter:

```
"stacks:delete": "rule:deny_stack_user"
```

Change it to:

```
"stacks:delete": "rule:deny_everybody"
```

Save the file.

This prevents removal of the overcloud with the **heat** client. To allow removal of the overcloud, revert the policy to the original value.

8.11. REMOVING THE OVERCLOUD

The whole overcloud can be removed when desired.

Delete any existing overcloud:

```
$ source ~/stackrc
$ openstack overcloud delete overcloud
```

Confirm the deletion of the overcloud:

```
$ openstack stack list
```

Deletion takes a few minutes.

Once the removal completes, follow the standard steps in the deployment scenarios to recreate your overcloud.

8.12. REVIEW THE TOKEN FLUSH INTERVAL

The Identity Service (keystone) uses a token-based system for access control against the other OpenStack services. After a certain period, the database will accumulate a large number of unused tokens; a default cron job flushes the token table every day. It is recommended that you monitor your environment and adjust the token flush interval as needed.

For the overcloud, you can adjust the interval using the **KeystoneCronToken** values. For more information, see the [Overcloud Parameters](#) guide.

CHAPTER 9. SCALING THE OVERCLOUD



WARNING

Do not use **openstack server delete** to remove nodes from the overcloud. Read the procedures defined in this section to properly remove and replace nodes.

There might be situations where you need to add or remove nodes after the creation of the overcloud. For example, you might need to add more Compute nodes to the overcloud. This situation requires updating the overcloud.

Use the following table to determine support for scaling each node type:

Table 9.1. Scale Support for Each Node Type

Node Type	Scale Up?	Scale Down?	Notes
Controller	N	N	
Compute	Y	Y	
Ceph Storage Nodes	Y	N	You must have at least 1 Ceph Storage node from the initial overcloud creation.
Block Storage Nodes	N	N	
Object Storage Nodes	Y	Y	Requires manual ring management, which is described in Section 9.6 , “Replacing Object Storage Nodes”.



IMPORTANT

Make sure to leave at least 10 GB free space before scaling the overcloud. This free space accommodates image conversion and caching during the node provisioning process.

9.1. ADDING ADDITIONAL NODES

To add more nodes to the director’s node pool, create a new JSON file (for example, **newnodes.json**) containing the new node details to register:

```
{
  "nodes": [
```

```

{
  "mac": [
    "dd:dd:dd:dd:dd:dd"
  ],
  "cpu": "4",
  "memory": "6144",
  "disk": "40",
  "arch": "x86_64",
  "pm_type": "pxe_ipmitool",
  "pm_user": "admin",
  "pm_password": "p@55w0rd!",
  "pm_addr": "192.168.24.207"
},
{
  "mac": [
    "ee:ee:ee:ee:ee:ee"
  ],
  "cpu": "4",
  "memory": "6144",
  "disk": "40",
  "arch": "x86_64",
  "pm_type": "pxe_ipmitool",
  "pm_user": "admin",
  "pm_password": "p@55w0rd!",
  "pm_addr": "192.168.24.208"
}
]
}

```

See [Section 5.1, “Registering Nodes for the Overcloud”](#) for an explanation of these parameters.

Run the following command to register these nodes:

```
$ openstack baremetal import --json newnodes.json
```

After registering the new nodes, launch the introspection process for them. Use the following commands for each new node:

```
$ openstack baremetal node manage [NODE UUID]
$ openstack overcloud node introspect [NODE UUID] --provide
```

This detects and benchmarks the hardware properties of the nodes.

After the introspection process completes, tag each new node for its desired role. For example, for a Compute node, use the following command:

```
$ openstack baremetal node set --property
capabilities='profile:compute,boot_option:local' [NODE UUID]
```

Set the boot images to use during the deployment. Find the UUIDs for the **bm-deploy-kernel** and **bm-deploy-ramdisk** images:

```
$ openstack image list
+-----+-----+
| ID                                     | Name                                     |
+-----+-----+
```

```
+-----+-----+
| 09b40e3d-0382-4925-a356-3a4b4f36b514 | bm-deploy-kernel |
| 765a46af-4417-4592-91e5-a300ead3faf6 | bm-deploy-ramdisk |
| ef793cd0-e65c-456a-a675-63cd57610bd5 | overcloud-full |
| 9a51a6cb-4670-40de-b64b-b70f4dd44152 | overcloud-full-initrd |
| 4f7e33f4-d617-47c1-b36f-cbe90f132e5d | overcloud-full-vmlinuz |
+-----+-----+
```

Set these UUIDs for the new node's **deploy_kernel** and **deploy_ramdisk** settings:

```
$ openstack baremetal node set --driver-info deploy_kernel='09b40e3d-0382-4925-a356-3a4b4f36b514' [NODE UUID]
$ openstack baremetal node set --driver-info deploy_ramdisk='765a46af-4417-4592-91e5-a300ead3faf6' [NODE UUID]
```

Scaling the overcloud requires running the **openstack overcloud deploy** again with the desired number of nodes for a role. For example, to scale to 5 Compute nodes:

```
$ openstack overcloud deploy --templates --compute-scale 5 [OTHER_OPTIONS]
```

This updates the entire overcloud stack. Note that this only updates the stack. It does not delete the overcloud and replace the stack.



IMPORTANT

Make sure to include all environment files and options from your initial overcloud creation. This includes the same scale parameters for non-Compute nodes.

9.2. REMOVING COMPUTE NODES

There might be situations where you need to remove Compute nodes from the overcloud. For example, you might need to replace a problematic Compute node.



IMPORTANT

Before removing a Compute node from the overcloud, migrate the workload from the node to other Compute nodes. See [Section 8.8, “Migrating VMs from an Overcloud Compute Node”](#) for more details.

Next, disable the node's Compute service on the overcloud. This stops the node from scheduling new instances.

```
$ source ~/stack/overcloudrc
$ openstack compute service list
$ openstack compute service set [hostname] nova-compute --disable
$ source ~/stack/stackrc
```

Removing overcloud nodes requires an update to the **overcloud** stack in the director using the local template files. First identify the UUID of the overcloud stack:

```
$ openstack stack list
```

Identify the UUIDs of the nodes to delete:

```
$ openstack server list
```

Run the following command to delete the nodes from the stack and update the plan accordingly:

```
$ openstack overcloud node delete --stack [STACK_UUID] --templates -e  
[ENVIRONMENT_FILE] [NODE1_UUID] [NODE2_UUID] [NODE3_UUID]
```



IMPORTANT

If you passed any extra environment files when you created the overcloud, pass them here again using the **-e** or **--environment-file** option to avoid making undesired manual changes to the overcloud.



IMPORTANT

Make sure the **openstack overcloud node delete** command runs to completion before you continue. Use the **openstack stack list** command and check the **overcloud** stack has reached an **UPDATE_COMPLETE** status.

Finally, remove the node's Compute service:

```
$ source ~/stack/overcloudrc  
$ openstack compute service list  
$ openstack compute service delete [service-id]  
$ source ~/stack/stackrc
```

And remove the node's Open vSwitch agent:

```
$ source ~/stack/overcloudrc  
$ openstack network agent list  
$ openstack network agent delete [openvswitch-agent-id]  
$ source ~/stack/stackrc
```

You are now free to remove the node from the overcloud and re-provision it for other purposes.

9.3. REPLACING COMPUTE NODES

If a Compute node fails, you can replace the node with a working one. Replacing a Compute node uses the following process:

- Migrate workload off the existing Compute node and shutdown the node. See [Section 8.8, “Migrating VMs from an Overcloud Compute Node”](#) for this process.
- Remove the Compute node from the overcloud. See [Section 9.2, “Removing Compute Nodes”](#) for this process.
- Scale out the overcloud with a new Compute node. See [Section 9.1, “Adding Additional Nodes”](#) for this process.

This process ensures that a node can be replaced without affecting the availability of any instances.

9.4. REPLACING CONTROLLER NODES

In certain circumstances a Controller node in a high availability cluster might fail. In these situations, you must remove the node from the cluster and replace it with a new Controller node. This also includes ensuring the node connects to the other nodes in the cluster.

This section provides instructions on how to replace a Controller node. The process involves running the **openstack overcloud deploy** command to update the overcloud with a request to replace a controller node. Note that this process is not completely automatic; during the overcloud stack update process, the **openstack overcloud deploy** command will at some point report a failure and halt the overcloud stack update. At this point, the process requires some manual intervention. Then the **openstack overcloud deploy** process can continue.



IMPORTANT

The following procedure only applies to high availability environments. Do not use this procedure if only using one Controller node.

9.4.1. Preliminary Checks

Before attempting to replace an overcloud Controller node, it is important to check the current state of your Red Hat OpenStack Platform environment. Checking the current state can help avoid complications during the Controller replacement process. Use the following list of preliminary checks to determine if it is safe to perform a Controller node replacement. Run all commands for these checks on the undercloud.

1. Check the current status of the **overcloud** stack on the undercloud:

```
$ source stackrc
$ openstack stack list --nested
```

The **overcloud** stack and its subsequent child stacks should have either a **CREATE_COMPLETE** or **UPDATE_COMPLETE**.

2. Perform a backup of the undercloud databases:

```
$ mkdir /home/stack/backup
$ sudo mysqldump --all-databases --quick --single-transaction | gzip
> /home/stack/backup/dump_db_undercloud.sql.gz
```

3. Check your undercloud contains 10 GB free storage to accommodate for image caching and conversion when provisioning the new node.
4. Check the status of Pacemaker on the running Controller nodes. For example, if 192.168.0.47 is the IP address of a running Controller node, use the following command to get the Pacemaker status:

```
$ ssh heat-admin@192.168.0.47 'sudo pcs status'
```

The output should show all services running on the existing nodes and stopped on the failed node.

5. Check the following parameters on each node of the overcloud's MariaDB cluster:

- **wsrep_local_state_comment**: **Synced**

- **wsrep_cluster_size: 2**

Use the following command to check these parameters on each running Controller node (respectively using 192.168.0.47 and 192.168.0.46 for IP addresses):

```
$ for i in 192.168.0.47 192.168.0.46 ; do echo "**** $i ****" ; ssh
heat-admin@$i "sudo mysql --exec=\"SHOW STATUS LIKE
'wsrep_local_state_comment'\"; sudo mysql --exec=\"SHOW STATUS
LIKE 'wsrep_cluster_size'\"; done
```

6. Check the RabbitMQ status. For example, if 192.168.0.47 is the IP address of a running Controller node, use the following command to get the status

```
$ ssh heat-admin@192.168.0.47 "sudo rabbitmqctl cluster_status"
```

The **running_nodes** key should only show the two available nodes and not the failed node.

7. Disable fencing, if enabled. For example, if 192.168.0.47 is the IP address of a running Controller node, use the following command to disable fencing:

```
$ ssh heat-admin@192.168.0.47 "sudo pcs property set stonith-
enabled=false"
```

Check the fencing status with the following command:

```
$ ssh heat-admin@192.168.0.47 "sudo pcs property show stonith-
enabled"
```

8. Check the **nova-compute** service on the director node:

```
$ sudo systemctl status openstack-nova-compute
$ openstack hypervisor list
```

The output should show all non-maintenance mode nodes as **up**.

9. Make sure all undercloud services are running:

```
$ sudo systemctl -t service
```

9.4.2. Node Replacement

Identify the index of the node to remove. The node index is the suffix on the instance name from **nova list** output.

```
[stack@director ~]$ openstack server list
+-----+-----+
| ID                                          | Name                               |
+-----+-----+
| 861408be-4027-4f53-87a6-cd3cf206ba7a     | overcloud-compute-0              |
| 0966e9ae-f553-447a-9929-c4232432f718     | overcloud-compute-1              |
| 9c08fa65-b38c-4b2e-bd47-33870bffa06c7    | overcloud-compute-2              |
| a7f0f5e1-e7ce-4513-ad2b-81146bc8c5af     | overcloud-controller-0           |
+-----+-----+
```

```
| cfefaf60-8311-4bc3-9416-6a824a40a9ae | overcloud-controller-1 |
| 97a055d4-aefd-481c-82b7-4a5f384036d2 | overcloud-controller-2 |
+-----+-----+
```

In this example, the aim is to remove the **overcloud-controller-1** node and replace it with **overcloud-controller-3**. First, set the node into maintenance mode so the director does not reprovision the failed node. Correlate the instance ID from **nova list** with the node ID from **openstack baremetal node list**

```
[stack@director ~]$ openstack baremetal node list
+-----+-----+-----+-----+
| UUID                                     | Name | Instance UUID |
+-----+-----+-----+-----+
| 36404147-7c8a-41e6-8c72-a6e90afc7584 | None | 7bee57cf-4a58-4eaf-b851-2a8bf6620e48 |
| 91eb9ac5-7d52-453c-a017-c0e3d823efd0 | None | None |
| 75b25e9a-948d-424a-9b3b-f0ef70a6eacf | None | None |
| 038727da-6a5c-425f-bd45-fda2f4bd145b | None | 763bfec2-9354-466a-ae65-2401c13e07e5 |
| dc2292e6-4056-46e0-8848-d6e96df1f55d | None | 2017b481-706f-44e1-852a-2ee857c303c4 |
| c7eadcea-e377-4392-9fc3-cf2b02b7ec29 | None | 5f73c7d7-4826-49a5-b6be-8bfd558f3b41 |
| da3a8d19-8a59-4e9d-923a-6a336fe10284 | None | cfefaf60-8311-4bc3-9416-6a824a40a9ae |
| 807cb6ce-6b94-4cd1-9969-5c47560c2eee | None | c07c13e6-a845-4791-9628-260110829c3a |
+-----+-----+-----+-----+
```

Set the node into maintenance mode:

```
[stack@director ~]$ openstack baremetal node maintenance set da3a8d19-8a59-4e9d-923a-6a336fe10284
```

Tag the new node with the **control** profile.

```
[stack@director ~]$ openstack baremetal node set --property
capabilities='profile:control,boot_option:local' 75b25e9a-948d-424a-9b3b-f0ef70a6eacf
```

The overcloud's database must continue running during the replacement procedure. To ensure Pacemaker does not stop Galera during this procedure, select a running Controller node and run the following command on the undercloud using the Controller node's IP address:

```
[stack@director ~]$ ssh heat-admin@192.168.0.47 "sudo pcs resource
unmanage galera"
```

Create a YAML file (`~/templates/remove-controller.yaml`) that defines the node index to remove:

```
parameters:
  ControllerRemovalPolicies:
    [{'resource_list': ['1']}]
```

NOTE

You can speed up the replacement process by reducing the number for tries for settle in Corosync. Include the **CorosyncSettleTries** parameter in the `~/templates/remove-controller.yaml` environment file:

```
parameter_defaults:
  CorosyncSettleTries: 5
```

After identifying the node index, redeploy the overcloud and include the **remove-controller.yaml** environment file:

```
[stack@director ~]$ openstack overcloud deploy --templates --control-scale
3 -e ~/templates/remove-controller.yaml [OTHER OPTIONS]
```

If you passed any extra environment files or options when you created the overcloud, pass them again here to avoid making undesired changes to the overcloud.

However, note that the **-e ~/templates/remove-controller.yaml** is only required once in this instance.

The director removes the old node, creates a new one, and updates the overcloud stack. You can check the status of the overcloud stack with the following command:

```
[stack@director ~]$ openstack stack list --nested
```

9.4.3. Manual Intervention

During the **ControllerNodesPostDeployment** stage, the overcloud stack update halts with an **UPDATE_FAILED** error at **ControllerDeployment_Step1**. This is because some Puppet modules do not support nodes replacement. This point in the process requires some manual intervention. Follow these configuration steps:

1. Get a list of IP addresses for the Controller nodes. For example:

```
[stack@director ~]$ openstack server list
... +-----+ ... +-----+
... | Name                | ... | Networks                |
... +-----+ ... +-----+
... | overcloud-compute-0  | ... | ctlplane=192.168.0.44   |
... | overcloud-controller-0 | ... | ctlplane=192.168.0.47   |
... | overcloud-controller-2 | ... | ctlplane=192.168.0.46   |
... | overcloud-controller-3 | ... | ctlplane=192.168.0.48   |
... +-----+ ... +-----+
```

2. Check the **nodeid** value of the removed node in the **/etc/corosync/corosync.conf** file on an existing node. For example, the existing node is **overcloud-controller-0** at 192.168.0.47:

```
[stack@director ~]$ ssh heat-admin@192.168.0.47 "sudo cat /etc/corosync/corosync.conf"
```

This displays a **nodelist** that contains the ID for the removed node (**overcloud-controller-1**):

```
nodelist {
  node {
    ring0_addr: overcloud-controller-0
    nodeid: 1
  }
  node {
    ring0_addr: overcloud-controller-1
    nodeid: 2
  }
  node {
    ring0_addr: overcloud-controller-2
    nodeid: 3
  }
}
```

Note the **nodeid** value of the removed node for later. In this example, it is 2.

3. Delete the failed node from the Corosync configuration on each node and restart Corosync. For this example, log into **overcloud-controller-0** and **overcloud-controller-2** and run the following commands:

```
[stack@director] ssh heat-admin@192.168.0.47 "sudo pcs cluster localnode remove overcloud-controller-1"
[stack@director] ssh heat-admin@192.168.0.47 "sudo pcs cluster reload corosync"
[stack@director] ssh heat-admin@192.168.0.46 "sudo pcs cluster localnode remove overcloud-controller-1"
[stack@director] ssh heat-admin@192.168.0.46 "sudo pcs cluster reload corosync"
```

4. Log into one of the remaining nodes and delete the node from the cluster with the **crm_node** command:

```
[stack@director] ssh heat-admin@192.168.0.47
[heat-admin@overcloud-controller-0 ~]$ sudo crm_node -R overcloud-controller-1 --force
```

Stay logged into this node.

5. Delete the failed node from the RabbitMQ cluster:

```
[heat-admin@overcloud-controller-0 ~]$ sudo rabbitmqctl forget_cluster_node rabbit@overcloud-controller-1
```

6. Delete the failed node from MongoDB. First, find the IP address for the node's Internal API connection.

```
[heat-admin@overcloud-controller-0 ~]$ sudo netstat -tulnp | grep
27017
tcp          0      0 192.168.0.47:27017    0.0.0.0:*
LISTEN      13415/mongod
```

Check that the node is the **primary** replica set:

```
[root@overcloud-controller-0 ~]# echo "db.isMaster()" | mongo --host
192.168.0.47:27017
MongoDB shell version: 2.6.11
connecting to: 192.168.0.47:27017/echo
{
  "setName" : "tripleo",
  "setVersion" : 1,
  "ismaster" : true,
  "secondary" : false,
  "hosts" : [
    "192.168.0.47:27017",
    "192.168.0.46:27017",
    "192.168.0.45:27017"
  ],
  "primary" : "192.168.0.47:27017",
  "me" : "192.168.0.47:27017",
  "electionId" : ObjectId("575919933ea8637676159d28"),
  "maxBsonObjectSize" : 16777216,
  "maxMessageSizeBytes" : 48000000,
  "maxWriteBatchSize" : 1000,
  "localTime" : ISODate("2016-06-09T09:02:43.340Z"),
  "maxWireVersion" : 2,
  "minWireVersion" : 0,
  "ok" : 1
}
bye
```

This should indicate if the current node is the primary. If not, use the IP address of the node indicated in the **primary** key.

Connect to MongoDB on the primary node:

```
[heat-admin@overcloud-controller-0 ~]$ mongo --host 192.168.0.47
MongoDB shell version: 2.6.9
connecting to: 192.168.0.47:27017/test
Welcome to the MongoDB shell.
For interactive help, type "help".
For more comprehensive documentation, see
http://docs.mongodb.org/
Questions? Try the support group
http://groups.google.com/group/mongodb-user
tripleo:PRIMARY>
```

Check the status of the MongoDB cluster:

```
tripleo:PRIMARY> rs.status()
```

Identify the node using the **_id** key and remove the failed node using the **name** key. In this case, we remove Node 1, which has **192.168.0.45:27017** for **name**:

```
tripleo:PRIMARY> rs.remove('192.168.0.45:27017')
```

IMPORTANT

You must run the command against the **PRIMARY** replica set. If you see the following message:

```
"replSetReconfig command must be sent to the current
replica set primary."
```

Relog into MongoDB on the node designated as **PRIMARY**.

NOTE

The following output is normal when removing the failed node's replica set:

```
2016-05-07T03:57:19.541+0000 DBClientCursor::init call()
failed
2016-05-07T03:57:19.543+0000 Error: error doing query:
failed at src/mongo/shell/query.js:81
2016-05-07T03:57:19.545+0000 trying reconnect to
192.168.0.47:27017 (192.168.0.47) failed
2016-05-07T03:57:19.547+0000 reconnect 192.168.0.47:27017
(192.168.0.47) ok
```

Exit MongoDB:

```
tripleo:PRIMARY> exit
```

- Update list of nodes in the Galera cluster:

```
[heat-admin@overcloud-controller-0 ~]$ sudo pcs resource update
galera wsrep_cluster_address=gcomm://overcloud-controller-
0,overcloud-controller-3,overcloud-controller-2
```

- Configure the Galera cluster check on the new node. Copy the **/etc/sysconfig/clustercheck** from the existing node to the same location on the new node.
- Configure the **root** user's Galera access on the new node. Copy the **/root/.my.cnf** from the existing node to the same location on the new node.
- Add the new node to the cluster:

```
[heat-admin@overcloud-controller-0 ~]$ sudo pcs cluster node add
overcloud-controller-3
```

11. Check the `/etc/corosync/corosync.conf` file on each node. If the **nodeid** of the new node is the same as the removed node, update the value to a new nodeid value. For example, the `/etc/corosync/corosync.conf` file contains an entry for the new node (**overcloud-controller-3**):

```

nodelist {
  node {
    ring0_addr: overcloud-controller-0
    nodeid: 1
  }
  node {
    ring0_addr: overcloud-controller-2
    nodeid: 3
  }
  node {
    ring0_addr: overcloud-controller-3
    nodeid: 2
  }
}

```

Note that in this example, the new node uses the same **nodeid** of the removed node. Update this value to a unused node ID value. For example:

```

node {
  ring0_addr: overcloud-controller-3
  nodeid: 4
}

```

Update this **nodeid** value on each Controller node's `/etc/corosync/corosync.conf` file, including the new node.

12. Restart the Corosync service on the existing nodes only. For example, on **overcloud-controller-0**:

```

[heat-admin@overcloud-controller-0 ~]$ sudo pcs cluster reload
corosync

```

And on **overcloud-controller-2**:

```

[heat-admin@overcloud-controller-2 ~]$ sudo pcs cluster reload
corosync

```

Do not run this command on the new node.

13. Start the new Controller node:

```

[heat-admin@overcloud-controller-0 ~]$ sudo pcs cluster start
overcloud-controller-3

```

14. Restart the Galera cluster and return it to Pacemaker management:

```

[heat-admin@overcloud-controller-0 ~]$ sudo pcs resource cleanup
galera
[heat-admin@overcloud-controller-0 ~]$ sudo pcs resource manage

```

galera

15. Enable and restart some services through Pacemaker. The cluster is currently in maintenance mode and you will need to temporarily disable it to enable the service. For example:

```
[heat-admin@overcloud-controller-3 ~]$ sudo pcs property set
maintenance-mode=false --wait
```

16. Wait until the Galera service starts on all nodes.

```
[heat-admin@overcloud-controller-3 ~]$ sudo pcs status | grep galera
-A1
Master/Slave Set: galera-master [galera]
Masters: [ overcloud-controller-0 overcloud-controller-2 overcloud-
controller-3 ]
```

If need be, perform a **cleanup** on the new node:

```
[heat-admin@overcloud-controller-3 ~]$ sudo pcs resource cleanup
galera --node overcloud-controller-3
```

17. Switch the cluster back into maintenance mode:

```
[heat-admin@overcloud-controller-3 ~]$ sudo pcs property set
maintenance-mode=true --wait
```

The manual configuration is complete. Re-run the overcloud deployment command to continue the stack update:

```
[stack@director ~]$ openstack overcloud deploy --templates --control-scale
3 [OTHER OPTIONS]
```



IMPORTANT

If you passed any extra environment files or options when you created the overcloud, pass them again here to avoid making undesired changes to the overcloud. However, note that the **remove-controller.yaml** file is no longer needed.

9.4.4. Finalizing Overcloud Services

After the overcloud stack update completes, some final configuration is required. Log in to one of the Controller nodes and refresh any stopped services in Pacemaker:

```
[heat-admin@overcloud-controller-0 ~]$ for i in `sudo pcs status|grep -B2
Stop |grep -v "Stop\|Start"|awk -F"[" '\/\[/ {print
substr($NF,0,length($NF)-1)}'`; do echo $i; sudo pcs resource cleanup $i;
done
```

Perform a final status check to make sure services are running correctly:

```
[heat-admin@overcloud-controller-0 ~]$ sudo pcs status
```

**NOTE**

If any services have failed, use the **pcs resource cleanup** command to restart them after resolving them.

Exit to the director

```
[heat-admin@overcloud-controller-0 ~]$ exit
```

9.4.5. Finalizing L3 Agent Router Hosting

Source the **overcloudrc** file so that you can interact with the overcloud. Check your routers to make sure the L3 agents are properly hosting the routers in your overcloud environment. In this example, we use a router with the name **r1**:

```
[stack@director ~]$ source ~/overcloudrc
[stack@director ~]$ neutron l3-agent-list-hosting-router r1
```

This list might still show the old node instead of the new node. To replace it, list the L3 network agents in your environment:

```
[stack@director ~]$ neutron agent-list | grep "neutron-l3-agent"
```

Identify the UUID for the agents on the new node and the old node. Add the router to the agent on the new node and remove the router from old node. For example:

```
[stack@director ~]$ neutron l3-agent-router-add fd6b3d6e-7d8c-4e1a-831a-4ec1c9ebb965 r1
[stack@director ~]$ neutron l3-agent-router-remove b40020af-c6dd-4f7a-b426-eba7bac9dbc2 r1
```

Perform a final check on the router and make all are active:

```
[stack@director ~]$ neutron l3-agent-list-hosting-router r1
```

Delete the existing Neutron agents that point to old Controller node. For example:

```
[stack@director ~]$ neutron agent-list -F id -F host | grep overcloud-controller-1
| ddae8e46-3e8e-4a1b-a8b3-c87f13c294eb | overcloud-controller-1.localdomain |
[stack@director ~]$ neutron agent-delete ddae8e46-3e8e-4a1b-a8b3-c87f13c294eb
```

9.4.6. Finalizing Compute Services

Compute services for the removed node still exist in the overcloud and require removal. Source the **overcloudrc** file so that you can interact with the overcloud. Check the compute services for the removed node:

```
[stack@director ~]$ source ~/overcloudrc
[stack@director ~]$ nova service-list | grep "overcloud-controller-
```

```
1.localdomain"
```

Remove the compute services for the node. For example, if the **nova-scheduler** service for **overcloud-controller-1.localdomain** has an ID of 5, run the following command:

```
[stack@director ~]$ nova service-delete 5
```

Perform this task for each service of the removed node.

Check the **openstack-nova-consoleauth** service on the new node.


```
[stack@director ~]$ nova service-list | grep consoleauth
```

If the service is not running, log into a Controller node and restart the service:

```
[stack@director] ssh heat-admin@192.168.0.47
[heat-admin@overcloud-controller-0 ~]$ pcs resource restart openstack-
nova-consoleauth
```

9.4.7. Conclusion

The failed Controller node and its related services are now replaced with a new node.



IMPORTANT

If you disabled automatic ring building for Object Storage, like in [Section 9.6, “Replacing Object Storage Nodes”](#), you need to manually build the Object Storage ring files for the new node. See [Section 9.6, “Replacing Object Storage Nodes”](#) for more information on manually building ring files.

9.5. REPLACING CEPH STORAGE NODES

The director provides a method to replace Ceph Storage nodes in a director-created cluster. You can find these instructions in the [Red Hat Ceph Storage for the Overcloud](#).

9.6. REPLACING OBJECT STORAGE NODES

This section describes how to replace Object Storage nodes while maintaining the integrity of the cluster. In this example, we have a two-node Object Storage cluster where the node **overcloud-objectstorage-1** needs to be replaced. Our aim is to add one more node, then remove **overcloud-objectstorage-1** (effectively replacing it).

1. Create an environment file called `~/templates/swift-upscale.yaml` with the following content:

```
parameter_defaults:
  ObjectStorageCount: 3
```

The **ObjectStorageCount** defines how many Object Storage nodes in our environment. In this situation, we scale from 2 to 3 nodes.

2. Include the **swift-upscale.yaml** file with the rest of your overcloud’s environment files (`ENVIRONMENT_FILES`) as part of the **openstack overcloud deploy**:

```
$ openstack overcloud deploy --templates ENVIRONMENT_FILES -e swift-
upscale.yaml
```



NOTE

Add **swift-upscale.yaml** to the end of the environment file list so its parameters supersede previous environment file parameters.

After redeployment completes, the overcloud now contains an additional Object Storage node.

3. Data now needs to be replicated to the new node. Before removing a node (in this case, **overcloud-objectstorage-1**) you should wait for a *replication pass* to finish on the new node. You can check the replication pass progress in **/var/log/swift/swift.log**. When the pass finishes, the Object Storage service should log entries similar to the following:

```
Mar 29 08:49:05 localhost object-server: Object replication
complete.
Mar 29 08:49:11 localhost container-server: Replication run OVER
Mar 29 08:49:13 localhost account-server: Replication run OVER
```

4. To remove the old node from the ring, reduce the **ObjectStorageCount** in **swift-upscale.yaml** to omit the old ring. In this case, we reduce it to 2:

```
parameter_defaults:
  ObjectStorageCount: 2
```

5. Create a new environment file named **remove-object-node.yaml**. This file will identify and remove the specified Object Storage node. The following content specifies the removal of **overcloud-objectstorage-1**:

```
parameter_defaults:
  ObjectStorageRemovalPolicies:
    [{'resource_list': ['1']}]
```

6. Include both environment files with the deployment command:

```
$ openstack overcloud deploy --templates ENVIRONMENT_FILES -e swift-
upscale.yaml -e remove-object-node.yaml ...
```

The director deletes the Object Storage node from the overcloud and updates the rest of the nodes on the overcloud to accommodate the node removal.

CHAPTER 10. REBOOTING NODES

Some situations require a reboot of nodes in the undercloud and overcloud. The following procedures show how to reboot different node types. Be aware of the following notes:

- If rebooting all nodes in one role, it is advisable to reboot each node individually. This helps retain services for that role during the reboot.
- If rebooting all nodes in your OpenStack Platform environment, use the following list to guide the reboot order:

Recommended Node Reboot Order

1. Reboot the director
2. Reboot Controller nodes
3. Reboot Ceph Storage nodes
4. Reboot Compute nodes
5. Reboot object Storage nodes

10.1. REBOOTING THE DIRECTOR

To reboot the director node, follow this process:

1. Reboot the node:

```
$ sudo reboot
```

2. Wait until the node boots.

When the node boots, check the status of all services:

```
$ sudo systemctl list-units "openstack*" "neutron*" "openvswitch"
```



NOTE

It might take approximately 10 minutes for the **openstack-nova-compute** to become active after a reboot.

Verify the existence of your Overcloud and its nodes:

```
$ source ~/stackrc
$ openstack server list
$ openstack baremetal node list
$ openstack stack list
```

10.2. REBOOTING CONTROLLER NODES

To reboot the Controller nodes, follow this process:

1. Select a node to reboot. Log into it and reboot it:

```
$ sudo reboot
```

The remaining Controller Nodes in the cluster retain the high availability services during the reboot.

2. Wait until the node boots.
3. Log into the node and check the cluster status:

```
$ sudo pcs status
```

The node rejoins the cluster.



NOTE

If any services fail after the reboot, run `sudo pcs resource cleanup`, which cleans the errors and sets the state of each resource to **Started**. If any errors persist, contact Red Hat and request guidance and assistance.

4. Check all **systemd** services on the Controller Node are active:

```
$ sudo systemctl list-units "openstack*" "neutron*" "openvswitch"
```

5. Log out of the node, select the next Controller Node to reboot, and repeat this procedure until you have rebooted all Controller Nodes.

10.3. REBOOTING CEPH STORAGE NODES

To reboot the Ceph Storage nodes, follow this process:

1. Log into a Ceph MON or Controller node and disable Ceph Storage cluster rebalancing temporarily:

```
$ sudo ceph osd set noout
$ sudo ceph osd set norebalance
```

2. Select the first Ceph Storage node to reboot and log into it.
3. Reboot the node:

```
$ sudo reboot
```

4. Wait until the node boots.
5. Log into the node and check the cluster status:

```
$ sudo ceph -s
```

Check that the **pgmap** reports all **pgs** as normal (**active+clean**).

6. Log out of the node, reboot the next node, and check its status. Repeat this process until you have rebooted all Ceph storage nodes.
7. When complete, log into a Ceph MON or Controller node and enable cluster rebalancing again:

```
$ sudo ceph osd unset noout
$ sudo ceph osd unset norebalance
```

8. Perform a final status check to verify the cluster reports **HEALTH_OK**:

```
$ sudo ceph status
```

10.4. REBOOTING COMPUTE NODES

Reboot each Compute node individually and ensure zero downtime of instances in your OpenStack Platform environment. This involves the following workflow:

1. Select a Compute node to reboot
2. Migrate its instances to another Compute node
3. Reboot the empty Compute node

List all Compute nodes and their UUIDs:

```
$ nova list | grep "compute"
```

Select a Compute node to reboot and first migrate its instances using the following process:

1. From the undercloud, select a Compute Node to reboot and disable it:

```
$ source ~/overcloudrc
$ openstack compute service list
$ openstack compute service set [hostname] nova-compute --disable
```

2. List all instances on the Compute node:

```
$ openstack server list --host [hostname] --all-projects
```

3. Migrate each instance from the disabled host. Use one of the following commands:

- a. Migrate the instance to a specific host of your choice:

```
$ openstack server migrate [instance-id] --live [target-host] --
wait
```

- b. Let **nova-scheduler** automatically select the target host:

```
$ nova live-migration [instance-id]
```


**NOTE**

The **nova** command might cause some deprecation warnings, which are safe to ignore.

4. Wait until migration completes.
5. Confirm the instance has migrated from the Compute node:

```
$ openstack server list --host [hostname] --all-projects
```

6. Repeat this step until you have migrated all instances from the Compute Node.

**IMPORTANT**

For full instructions on configuring and migrating instances, see [Section 8.8, “Migrating VMs from an Openstack Compute Node”](#).

Reboot the Compute node using the following process

1. Log into the Compute Node and reboot it:

```
$ sudo reboot
```

2. Wait until the node boots.
3. Enable the Compute Node again:

```
$ source ~/overcloudrc
$ openstack compute service set [hostname] nova-compute --enable
```

4. Check whether the Compute node is enabled:

```
$ openstack compute service list
```

10.5. REBOOTING OBJECT STORAGE NODES

To reboot the Object Storage nodes, follow this process:

1. Select a Object Storage node to reboot. Log into it and reboot it:

```
$ sudo reboot
```

2. Wait until the node boots.
3. Log into the node and check the status:

```
$ sudo systemctl list-units "openstack-swift*"
```

4. Log out of the node and repeat this process on the next Object Storage node.

CHAPTER 11. TROUBLESHOOTING DIRECTOR ISSUES

An error can occur at certain stages of the director's processes. This section provides some information for diagnosing common problems.

Note the common logs for the director's components:

- The **/var/log** directory contains logs for many common OpenStack Platform components as well as logs for standard Red Hat Enterprise Linux applications.
- The **journald** service provides logs for various components. Note that **ironic** uses two units: **openstack-ironic-api** and **openstack-ironic-conductor**. Likewise, **ironic-inspector** uses two units as well: **openstack-ironic-inspector** and **openstack-ironic-inspector-dnsmasq**. Use both units for each respective component. For example:

```
$ sudo journalctl -u openstack-ironic-inspector -u openstack-ironic-inspector-dnsmasq
```

- **ironic-inspector** also stores the ramdisk logs in **/var/log/ironic-inspector/ramdisk/** as gz-compressed tar files. Filenames contain date, time, and the IPMI address of the node. Use these logs for diagnosing introspection issues.

11.1. TROUBLESHOOTING NODE REGISTRATION

Issues with node registration usually arise from issues with incorrect node details. In this case, use **ironic** to fix problems with node data registered. Here are a few examples:

Find out the assigned port UUID:

```
$ ironic node-port-list [NODE UUID]
```

Update the MAC address:

```
$ ironic port-update [PORT UUID] replace address=[NEW MAC]
```

Run the following command:

```
$ ironic node-update [NODE UUID] replace driver_info/ipmi_address=[NEW IPMI ADDRESS]
```

11.2. TROUBLESHOOTING HARDWARE INTROSPECTION

The introspection process must run to completion. However, **ironic**'s Discovery daemon (**ironic-inspector**) times out after a default 1 hour period if the discovery ramdisk provides no response. Sometimes this might indicate a bug in the discovery ramdisk but usually it happens due to an environment misconfiguration, particularly BIOS boot settings.

Here are some common scenarios where environment misconfiguration occurs and advice on how to diagnose and resolve them.

Errors with Starting Node Introspection

Normally the introspection process uses the **baremetal introspection**, which acts as an umbrella

command for ironic's services. However, if running the introspection directly with **ironic-inspector**, it might fail to discover nodes in the AVAILABLE state, which is meant for deployment and not for discovery. Change the node status to the MANAGEABLE state before discovery:

```
$ ironic node-set-provision-state [NODE UUID] manage
```

Then, when discovery completes, change back to AVAILABLE before provisioning:

```
$ ironic node-set-provision-state [NODE UUID] provide
```

Stopping the Discovery Process

Stop the introspection process:

```
$ openstack baremetal introspection abort [NODE UUID]
```

You can also wait until the process times out. If necessary, change the **timeout** setting in **/etc/ironic-inspector/inspector.conf** to another period in minutes.

Accessing the Introspection Ramdisk

The introspection ramdisk uses a dynamic login element. This means you can provide either a temporary password or an SSH key to access the node during introspection debugging. Use the following process to set up ramdisk access:


1. Provide a temporary password to the **openssl passwd -1** command to generate an MD5 hash. For example:

```
$ openssl passwd -1 mytestpassword
$1$enjRSyIw$/fYUpJwr6abFy/d.koRgQ/
```

2. Edit the **/httpboot/inspector.ipxe** file, find the line starting with **kernel**, and append the **rootpwd** parameter and the MD5 hash. For example:

```
kernel http://192.2.0.1:8088/agent.kernel ipa-inspection-callback-
url=http://192.168.0.1:5050/v1/continue ipa-inspection-
collectors=default,extra-hardware,logs
systemd.journald.forward_to_console=yes BOOTIF=${mac} ipa-debug=1
ipa-inspection-benchmarks=cpu,mem,disk
rootpwd="$1$enjRSyIw$/fYUpJwr6abFy/d.koRgQ/" selinux=0
```

Alternatively, you can append the **sshkey** parameter with your public SSH key.



NOTE

Quotation marks are required for both the **rootpwd** and **sshkey** parameters.

3. Start the introspection and find the IP address from either the **arp** command or the DHCP logs:

```
$ arp
$ sudo journalctl -u openstack-ironic-inspector-dnsmasq
```

4. SSH as a root user with the temporary password or the SSH key.

```
$ ssh root@192.168.24.105
```

Checking Introspection Storage

The director uses OpenStack Object Storage (swift) to save the hardware data obtained during the introspection process. If this service is not running, the introspection can fail. Check all services related to OpenStack Object Storage to ensure the service is running:

```
$ sudo systemctl list-units openstack-swift*
```

11.3. TROUBLESHOOTING WORKFLOWS AND EXECUTIONS

The OpenStack Workflow (mistral) service groups multiple OpenStack tasks into workflows. Red Hat OpenStack Platform uses a set of these workflow to perform common functions across the CLI and web UI. This includes bare metal node control, validations, plan management, and overcloud deployment.

For example, when running the **openstack overcloud deploy** command, the OpenStack Workflow service executes two workflows. The first one uploads the deployment plan:

```
Removing the current plan files
Uploading new plan files
Started Mistral Workflow. Execution ID: aef1e8c6-a862-42de-8bce-
073744ed5e6b
Plan updated
```

The second one starts the overcloud deployment:

```
Deploying templates in the directory /tmp/tripleoclient-LhRlHX/tripleo-
heat-templates
Started Mistral Workflow. Execution ID: 97b64abe-d8fc-414a-837a-
1380631c764d
2016-11-28 06:29:26Z [overcloud]: CREATE_IN_PROGRESS Stack CREATE started
2016-11-28 06:29:26Z [overcloud.Networks]: CREATE_IN_PROGRESS state
changed
2016-11-28 06:29:26Z [overcloud.HeatAuthEncryptionKey]: CREATE_IN_PROGRESS
state changed
2016-11-28 06:29:26Z [overcloud.ServiceNetMap]: CREATE_IN_PROGRESS state
changed
...
```

Workflow Objects

OpenStack Workflow uses the following objects to keep track of the workflow:

Actions

A particular instruction that OpenStack performs once an associated task runs. Examples include running shell scripts or performing HTTP requests. Some OpenStack components have in-built actions that OpenStack Workflow uses.

Tasks

Defines the action to run and the result of running the action. These tasks usually have actions or other workflows associated with them. Once a task completes, the workflow directs to another task, usually depending on whether the task succeeded or failed.

Workflows

A set of tasks grouped together and executed in a specific order.

Executions

Defines a particular action, task, or workflow running.

Workflow Error Diagnosis

OpenStack Workflow also provides robust logging of executions, which help you identify issues with certain command failures. For example, if a workflow execution fails, you can identify the point of failure. List the workflow executions that have the failed state **ERROR**:

```
$ mistral execution-list | grep "ERROR"
```

Get the UUID of the failed workflow execution (for example, 3c87a885-0d37-4af8-a471-1b392264a7f5) and view the execution and its output:

```
$ mistral execution-get 3c87a885-0d37-4af8-a471-1b392264a7f5
$ mistral execution-get-output 3c87a885-0d37-4af8-a471-1b392264a7f5
```

This provides information about the failed task in the execution. The **mistral execution-get** also displays the workflow used for the execution (for example, **tripleo.plan_management.v1.update_deployment_plan**). You can view the full workflow definition using the following command:

```
$ mistral execution-get-definition
tripleo.plan_management.v1.update_deployment_plan
```

This is useful for identifying where in the workflow a particular task occurs.

You can also view action executions and their results using a similar command syntax:

```
$ mistral action-execution-list
$ mistral action-execution-get b59245bf-7183-4fcf-9508-c83ec1a26908
$ mistral action-execution-get-output b59245bf-7183-4fcf-9508-c83ec1a26908
```

This is useful for identifying a specific action causing issues.

11.4. TROUBLESHOOTING OVERCLOUD CREATION

There are three layers where the deployment can fail:

- Orchestration (heat and nova services)
- Bare Metal Provisioning (ironic service)
- Post-Deployment Configuration (Puppet)

If an overcloud deployment has failed at any of these levels, use the OpenStack clients and service log files to diagnose the failed deployment.

11.4.1. Orchestration

In most cases, Heat shows the failed overcloud stack after the overcloud creation fails:

```
$ heat stack-list
+-----+-----+-----+-----+
| id                | stack_name | stack_status      | creation_time
+-----+-----+-----+-----+
| 7e88af95-535c-4a55... | overcloud  | CREATE_FAILED     | 2015-04-06T17:57:16Z |
```

If the stack list is empty, this indicates an issue with the initial Heat setup. Check your Heat templates and configuration options, and check for any error messages that presented after running **openstack overcloud deploy**.

11.4.2. Bare Metal Provisioning

Check **ironic** to see all registered nodes and their current status:

```
$ ironic node-list
+-----+-----+-----+-----+-----+-----+
| UUID      | Name | Instance UUID | Power State | Provision State | Maintenance |
+-----+-----+-----+-----+-----+-----+
| f1e261... | None | None          | power off   | available       | False
| f0b8c1... | None | None          | power off   | available       | False
```

Here are some common issues that arise from the provisioning process.

- Review the Provision State and Maintenance columns in the resulting table. Check for the following:
 - An empty table, or fewer nodes than you expect
 - Maintenance is set to True
 - Provision State is set to **manageable**. This usually indicates an issue with the registration or discovery processes. For example, if Maintenance sets itself to True automatically, the nodes are usually using the wrong power management credentials.
- If Provision State is **available**, then the problem occurred before bare metal deployment has even started.
- If Provision State is **active** and Power State is **power on**, the bare metal deployment has finished successfully. This means that the problem occurred during the post-deployment configuration step.

- If Provision State is **wait call-back** for a node, the bare metal provisioning process has not yet finished for this node. Wait until this status changes, otherwise, connect to the virtual console of the failed node and check the output.
- If Provision State is **error** or **deploy failed**, then bare metal provisioning has failed for this node. Check the bare metal node's details:

```
$ ironic node-show [NODE UUID]
```

Look for **last_error** field, which contains error description. If the error message is vague, you can use logs to clarify it:

```
$ sudo journalctl -u openstack-ironic-conductor -u openstack-ironic-api
```

- If you see **wait timeout error** and the node Power State is **power on**, connect to the virtual console of the failed node and check the output.

11.4.3. Post-Deployment Configuration

Many things can occur during the configuration stage. For example, a particular Puppet module could fail to complete due to an issue with the setup. This section provides a process to diagnose such issues.

List all the resources from the overcloud stack to see which one failed:

```
$ heat resource-list overcloud
```

This shows a table of all resources and their states. Look for any resources with a **CREATE_FAILED**.

Show the failed resource:

```
$ heat resource-show overcloud [FAILED RESOURCE]
```

Check for any information in the **resource_status_reason** field that can help your diagnosis.

Use the **nova** command to see the IP addresses of the overcloud nodes.

```
$ nova list
```

Log in as the **heat-admin** user to one of the deployed nodes. For example, if the stack's resource list shows the error occurred on a Controller node, log in to a Controller node. The **heat-admin** user has sudo access.

```
$ ssh heat-admin@192.168.24.14
```

Check the **os-collect-config** log for a possible reason for the failure.

```
$ sudo journalctl -u os-collect-config
```

In some cases, nova fails deploying the node in entirety. This situation would be indicated by a failed **OS::Heat::ResourceGroup** for one of the overcloud role types. Use **nova** to see the failure in this case.

```
$ nova list
$ nova show [SERVER ID]
```

The most common error shown will reference the error message **No valid host was found**. See [Section 11.6, “Troubleshooting “No Valid Host Found” Errors”](#) for details on troubleshooting this error. In other cases, look at the following log files for further troubleshooting:

- `/var/log/nova/*`
- `/var/log/heat/*`
- `/var/log/ironic/*`

Use the SOS toolset, which gathers information about system hardware and configuration. Use this information for diagnostic purposes and debugging. SOS is commonly used to help support technicians and developers. SOS is useful on both the undercloud and overcloud. Install the **sos** package:

```
$ sudo yum install sos
```

Generate a report:

```
$ sudo sosreport --all-logs
```

The post-deployment process for Controller nodes uses five main steps for the deployment. This includes:

Table 11.1. Controller Node Configuration Steps

Step	Description
ControllerDeployment_Step1	Initial load balancing software configuration, including Pacemaker, RabbitMQ, Memcached, Redis, and Galera.
ControllerDeployment_Step2	Initial cluster configuration, including Pacemaker configuration, HAProxy, MongoDB, Galera, Ceph Monitor, and database initialization for OpenStack Platform services.
ControllerDeployment_Step3	Initial ring build for OpenStack Object Storage (swift). Configuration of all OpenStack Platform services (nova , neutron , cinder , sahara , ceilometer , heat , horizon , aodh , gnocchi).
ControllerDeployment_Step4	Configure service start up settings in Pacemaker, including constraints to determine service start up order and service start up parameters.
ControllerDeployment_Step5	Initial configuration of projects, roles, and users in OpenStack Identity (keystone).

11.5. TROUBLESHOOTING IP ADDRESS CONFLICTS ON THE PROVISIONING NETWORK

Discovery and deployment tasks will fail if the destination hosts are allocated an IP address which is already in use. To avoid this issue, you can perform a port scan of the Provisioning network to determine whether the discovery IP range and host IP range are free.

Perform the following steps from the undercloud host:

Install **nmap**:

```
# yum install nmap
```

Use **nmap** to scan the IP address range for active addresses. This example scans the 192.168.24.0/24 range, replace this with the IP subnet of the Provisioning network (using CIDR bitmask notation):

```
# nmap -sn 192.168.24.0/24
```

Review the output of the **nmap** scan:

For example, you should see the IP address(es) of the undercloud, and any other hosts that are present on the subnet. If any of the active IP addresses conflict with the IP ranges in `undercloud.conf`, you will need to either change the IP address ranges or free up the IP addresses before introspecting or deploying the overcloud nodes.

```
# nmap -sn 192.168.24.0/24

Starting Nmap 6.40 ( http://nmap.org ) at 2015-10-02 15:14 EDT
Nmap scan report for 192.168.24.1
Host is up (0.00057s latency).
Nmap scan report for 192.168.24.2
Host is up (0.00048s latency).
Nmap scan report for 192.168.24.3
Host is up (0.00045s latency).
Nmap scan report for 192.168.24.5
Host is up (0.00040s latency).
Nmap scan report for 192.168.24.9
Host is up (0.00019s latency).
Nmap done: 256 IP addresses (5 hosts up) scanned in 2.45 seconds
```

11.6. TROUBLESHOOTING "NO VALID HOST FOUND" ERRORS

Sometimes the `/var/log/nova/nova-conductor.log` contains the following error:

```
NoValidHost: No valid host was found. There are not enough hosts
available.
```

This means the nova Scheduler could not find a bare metal node suitable for booting the new instance. This in turn usually means a mismatch between resources that nova expects to find and resources that ironic advertised to nova. Check the following in this case:

1. Make sure introspection succeeds for you. Otherwise check that each node contains the required ironic node properties. For each node:

```
$ ironic node-show [NODE UUID]
```

Check the **properties** JSON field has valid values for keys **cpus**, **cpu_arch**, **memory_mb** and **local_gb**.

2. Check that the nova flavor used does not exceed the ironic node properties above for a required number of nodes:

```
$ nova flavor-show [FLAVOR NAME]
```

3. Check that sufficient nodes are in the **available** state according to **ironic node-list**. Nodes in **manageable** state usually mean a failed introspection.
4. Check the nodes are not in maintenance mode. Use **ironic node-list** to check. A node automatically changing to maintenance mode usually means incorrect power credentials. Check them and then remove maintenance mode:

```
$ ironic node-set-maintenance [NODE UUID] off
```

5. If you're using the Automated Health Check (AHC) tools to perform automatic node tagging, check that you have enough nodes corresponding to each flavor/profile. Check the **capabilities** key in **properties** field for **ironic node-show**. For example, a node tagged for the Compute role should contain **profile:compute**.
6. It takes some time for node information to propagate from ironic to nova after introspection. The director's tool usually accounts for it. However, if you performed some steps manually, there might be a short period of time when nodes are not available to nova. Use the following command to check the total resources in your system.:

```
$ nova hypervisor-stats
```

11.7. TROUBLESHOOTING THE OVERCLOUD AFTER CREATION

After creating your overcloud, you might want to perform certain overcloud operations in the future. For example, you might aim to scale your available nodes, or replace faulty nodes. Certain issues might arise when performing these operations. This section provides some advice to diagnose and troubleshoot failed post-creation operations.

11.7.1. Overcloud Stack Modifications

Problems can occur when modifying the **overcloud** stack through the director. Example of stack modifications include:

- Scaling Nodes
- Removing Nodes
- Replacing Nodes

Modifying the stack is similar to the process of creating the stack, in that the director checks the availability of the requested number of nodes, provisions additional or removes existing nodes, and then applies the Puppet configuration. Here are some guidelines to follow in situations when modifying the **overcloud** stack.

As an initial step, follow the advice set in [Section 11.4.3, “Post-Deployment Configuration”](#). These same steps can help diagnose problems with updating the **overcloud** heat stack. In particular, use the following command to help identify problematic resources:

heat stack-list --show-nested

List all stacks. The **--show-nested** displays all child stacks and their respective parent stacks. This command helps identify the point where a stack failed.

heat resource-list overcloud

List all resources in the **overcloud** stack and their current states. This helps identify which resource is causing failures in the stack. You can trace this resource failure to its respective parameters and configuration in the heat template collection and the Puppet modules.

heat event-list overcloud

List all events related to the **overcloud** stack in chronological order. This includes the initiation, completion, and failure of all resources in the stack. This helps identify points of resource failure.

The next few sections provide advice to diagnose issues on specific node types.

11.7.2. Controller Service Failures

The overcloud Controller nodes contain the bulk of Red Hat OpenStack Platform services. Likewise, you might use multiple Controller nodes in a high availability cluster. If a certain service on a node is faulty, the high availability cluster provides a certain level of failover. However, it then becomes necessary to diagnose the faulty service to ensure your overcloud operates at full capacity.

The Controller nodes use Pacemaker to manage the resources and services in the high availability cluster. The Pacemaker Configuration System (**pcs**) command is a tool that manages a Pacemaker cluster. Run this command on a Controller node in the cluster to perform configuration and monitoring functions. Here are few commands to help troubleshoot overcloud services on a high availability cluster:

pcs status

Provides a status overview of the entire cluster including enabled resources, failed resources, and online nodes.

pcs resource show

Shows a list of resources, and their respective nodes.

pcs resource disable [resource]

Stop a particular resource.

pcs resource enable [resource]

Start a particular resource.

pcs cluster standby [node]

Place a node in standby mode. The node is no longer available in the cluster. This is useful for performing maintenance on a specific node without affecting the cluster.

pcs cluster unstandby [node]

Remove a node from standby mode. The node becomes available in the cluster again.

Use these Pacemaker commands to identify the faulty component and/or node. After identifying the component, view the respective component log file in **/var/log/**.

11.7.3. Compute Service Failures

Compute nodes use the Compute service to perform hypervisor-based operations. This means the main diagnosis for Compute nodes revolves around this service. For example:

- View the status of the service using the following **systemd** function:

```
$ sudo systemctl status openstack-nova-compute.service
```

Likewise, view the **systemd** journal for the service using the following command:

```
$ sudo journalctl -u openstack-nova-compute.service
```

- The primary log file for Compute nodes is **/var/log/nova/nova-compute.log**. If issues occur with Compute node communication, this log file is usually a good place to start a diagnosis.
- If performing maintenance on the Compute node, migrate the existing instances from the host to an operational Compute node, then disable the node. See [Section 8.8, “Migrating VMs from an Overcloud Compute Node”](#) for more information on node migrations.

11.7.4. Ceph Storage Service Failures

For any issues that occur with Red Hat Ceph Storage clusters, see [Chapter 10. Logging and Debugging](#) in the Red Hat Ceph Storage Configuration Guide. This section provides information on diagnosing logs for all Ceph storage services.

11.8. TUNING THE UNDERCLOUD

The advice in this section aims to help increase the performance of your undercloud. Implement the recommendations as necessary.

- The Identity Service (keystone) uses a token-based system for access control against the other OpenStack services. After a certain period, the database will accumulate a large number of unused tokens; a default cronjob flushes the token table every day. It is recommended that you monitor your environment and adjust the token flush interval as needed. For the undercloud, you can adjust the interval using **crontab -u keystone -e**. Note that this is a temporary change and that **openstack undercloud update** will reset this cronjob back to its default.
- Heat stores a copy of all template files in its database's **raw_template** table each time you run **openstack overcloud deploy**. The **raw_template** table retains all past templates and grows in size. To remove unused templates in the **raw_templates** table, create a daily cronjob that clears unused templates that exist in the database for longer than a day:

```
0 04 * * * /bin/heat-manage purge_deleted -g days 1
```

- The **openstack-heat-engine** and **openstack-heat-api** services might consume too many resources at times. If so, set **max_resources_per_stack=-1** in **/etc/heat/heat.conf** and restart the heat services:

```
$ sudo systemctl restart openstack-heat-engine openstack-heat-api
```

- Sometimes the director might not have enough resources to perform concurrent node provisioning. The default is 10 nodes at the same time. To reduce the number of concurrent nodes, set the **max_concurrent_builds** parameter in **/etc/nova/nova.conf** to a value

less than 10 and restart the nova services:

```
$ sudo systemctl restart openstack-nova-api openstack-nova-scheduler
```

- Edit the `/etc/my.cnf.d/server.cnf` file. Some recommended values to tune include:

max_connections

Number of simultaneous connections to the database. The recommended value is 4096.

innodb_additional_mem_pool_size

The size in bytes of a memory pool the database uses to store data dictionary information and other internal data structures. The default is usually 8M and an ideal value is 20M for the undercloud.

innodb_buffer_pool_size

The size in bytes of the buffer pool, the memory area where the database caches table and index data. The default is usually 128M and an ideal value is 1000M for the undercloud.

innodb_flush_log_at_trx_commit

Controls the balance between strict ACID compliance for commit operations, and higher performance that is possible when commit-related I/O operations are rearranged and done in batches. Set to 1.

innodb_lock_wait_timeout

The length of time in seconds a database transaction waits for a row lock before giving up. Set to 50.

innodb_max_purge_lag

This variable controls how to delay INSERT, UPDATE, and DELETE operations when purge operations are lagging. Set to 10000.

innodb_thread_concurrency

The limit of concurrent operating system threads. Ideally, provide at least two threads for each CPU and disk resource. For example, if using a quad-core CPU and a single disk, use 10 threads.

- Ensure that heat has enough workers to perform an overcloud creation. Usually, this depends on how many CPUs the undercloud has. To manually set the number of workers, edit the `/etc/heat/heat.conf` file, set the **num_engine_workers** parameter to the number of workers you need (ideally 4), and restart the heat engine:

```
$ sudo systemctl restart openstack-heat-engine
```

11.9. IMPORTANT LOGS FOR UNDERCLOUD AND OVERCLOUD

Use the following logs to find out information about the undercloud and overcloud when troubleshooting.

Table 11.2. Important Logs for the Undercloud

Information	Log Location
OpenStack Compute log	<code>/var/log/nova/nova-compute.log</code>
OpenStack Compute API interactions	<code>/var/log/nova/nova-api.log</code>

Information	Log Location
OpenStack Compute Conductor log	<code>/var/log/nova/nova-conductor.log</code>
OpenStack Orchestration log	<code>heat-engine.log</code>
OpenStack Orchestration API interactions	<code>heat-api.log</code>
OpenStack Orchestration CloudFormations log	<code>/var/log/heat/heat-api-cfn.log</code>
OpenStack Bare Metal Conductor log	<code>ironic-conductor.log</code>
OpenStack Bare Metal API interactions	<code>ironic-api.log</code>
Introspection	<code>/var/log/ironic-inspector/ironic-inspector.log</code>
OpenStack Workflow Engine log	<code>/var/log/mistral/engine.log</code>
OpenStack Workflow Executor log	<code>/var/log/mistral/executor.log</code>
OpenStack Workflow API interactions	<code>/var/log/mistral/api.log</code>

Table 11.3. Important Logs for the Overcloud

Information	Log Location
Cloud-Init Log	<code>/var/log/cloud-init.log</code>
Overcloud Configuration (Summary of Last Puppet Run)	<code>/var/lib/puppet/state/last_run_summary.yaml</code>
Overcloud Configuration (Report from Last Puppet Run)	<code>/var/lib/puppet/state/last_run_report.yaml</code>
Overcloud Configuration (All Puppet Reports)	<code>/var/lib/puppet/reports/overcloud-*/*</code>
Overcloud Configuration (stdout from each Puppet Run)	<code>/var/run/heat-config/deployed/*-stdout.log</code>
Overcloud Configuration (stderr from each Puppet Run)	<code>/var/run/heat-config/deployed/*-stderr.log</code>
High availability log	<code>/var/log/pacemaker.log</code>

APPENDIX A. SSL/TLS CERTIFICATE CONFIGURATION

You can configure the undercloud to use SSL/TLS for communication over public endpoints. However, if using a SSL certificate with your own certificate authority, the certificate requires the configuration steps in the following section.



NOTE

For overcloud SSL/TLS certificate creation, see ["Enabling SSL/TLS on the Overcloud"](#) in the *Advanced Overcloud Customization* guide.

A.1. INITIALIZING THE SIGNING HOST

The signing host is the host that generates new certificates and signs them with a certificate authority. If you have never created SSL certificates on the chosen signing host, you might need to initialize the host so that it can sign new certificates.

The `/etc/pki/CA/index.txt` file stores records of all signed certificates. Check if this file exists. If it does not exist, create an empty file:

```
$ sudo touch /etc/pki/CA/index.txt
```

The `/etc/pki/CA/serial` file identifies the next serial number to use for the next certificate to sign. Check if this file exists. If it does not exist, create a new file with a new starting value:

```
$ sudo echo '1000' | sudo tee /etc/pki/CA/serial
```

A.2. CREATING A CERTIFICATE AUTHORITY

Normally you sign your SSL/TLS certificates with an external certificate authority. In some situations, you might aim to use your own certificate authority. For example, you might aim to have an internal-only certificate authority.

For example, generate a key and certificate pair to act as the certificate authority:

```
$ openssl genrsa -out ca.key.pem 4096
$ openssl req -key ca.key.pem -new -x509 -days 7300 -extensions v3_ca -
out ca.crt.pem
```

The `openssl req` command asks for certain details about your authority. Enter these details.

This creates a certificate authority file called `ca.crt.pem`.

A.3. ADDING THE CERTIFICATE AUTHORITY TO CLIENTS

For any external clients aiming to communicate using SSL/TLS, copy the certificate authority file to each client that requires access your Red Hat OpenStack Platform environment. Once copied to the client, run the following command on the client to add it to the certificate authority trust bundle:

```
$ sudo cp ca.crt.pem /etc/pki/ca-trust/source/anchors/
$ sudo update-ca-trust extract
```

A.4. CREATING AN SSL/TLS KEY

Run the following commands to generate the SSL/TLS key (**server.key.pem**), which we use at different points to generate our undercloud or overcloud certificates:

```
$ openssl genrsa -out server.key.pem 2048
```

A.5. CREATING AN SSL/TLS CERTIFICATE SIGNING REQUEST

This next procedure creates a certificate signing request for either the undercloud or overcloud.

Copy the default OpenSSL configuration file for customization.

```
$ cp /etc/pki/tls/openssl.cnf .
```

Edit the custom **openssl.cnf** file and set SSL parameters to use for the director. An example of the types of parameters to modify include:

```
[req]
distinguished_name = req_distinguished_name
req_extensions = v3_req

[req_distinguished_name]
countryName = Country Name (2 letter code)
countryName_default = AU
stateOrProvinceName = State or Province Name (full name)
stateOrProvinceName_default = Queensland
localityName = Locality Name (eg, city)
localityName_default = Brisbane
organizationalUnitName = Organizational Unit Name (eg, section)
organizationalUnitName_default = Red Hat
commonName = Common Name
commonName_default = 192.168.0.1
commonName_max = 64

[ v3_req ]
# Extensions to add to a certificate request
basicConstraints = CA:FALSE
keyUsage = nonRepudiation, digitalSignature, keyEncipherment
subjectAltName = @alt_names

[alt_names]
IP.1 = 192.168.0.1
DNS.1 = instack.localdomain
DNS.2 = vip.localdomain
DNS.3 = 192.168.0.1
```

Set the **commonName_default** to one of the following:

- If using an IP address to access over SSL/TLS, use the **undercloud_public_vip** parameter in **undercloud.conf**.
- If using a fully qualified domain name to access over SSL/TLS, use the domain name instead.

Edit the **alt_names** section to include the following entries:

- **IP** - A list of IP addresses for clients to access the director over SSL.
- **DNS** - A list of domain names for clients to access the director over SSL. Also include the Public API IP address as a DNS entry at the end of the **alt_names** section.

For more information about **openssl.cnf**, run **man openssl.cnf**.

Run the following command to generate certificate signing request (**server.csr.pem**):

```
$ openssl req -config openssl.cnf -key server.key.pem -new -out
server.csr.pem
```

Make sure to include the SSL/TLS key you created in [Section A.4, “Creating an SSL/TLS Key”](#) for the **-key** option.

Use the **server.csr.pem** file to create the SSL/TLS certificate in the next section.

A.6. CREATING THE SSL/TLS CERTIFICATE

The following command creates a certificate for your undercloud or overcloud:

```
$ sudo openssl ca -config openssl.cnf -extensions v3_req -days 3650 -in
server.csr.pem -out server.crt.pem -cert ca.crt.pem -keyfile ca.key.pem
```

This command uses:

- The configuration file specifying the v3 extensions. Include this as the **-config** option.
- The certificate signing request from [Section A.5, “Creating an SSL/TLS Certificate Signing Request”](#) to generate the certificate and sign it through a certificate authority. Include this as the **-in** option.
- The certificate authority you created in [Section A.2, “Creating a Certificate Authority”](#), which signs the certificate. Include this as the **-cert** option.
- The certificate authority private key you created in [Section A.2, “Creating a Certificate Authority”](#). Include this as the **-keyfile** option.

This results in a certificate named **server.crt.pem**. Use this certificate in conjunction with the SSL/TLS key from [Section A.4, “Creating an SSL/TLS Key”](#) to enable SSL/TLS.

A.7. USING THE CERTIFICATE WITH THE UNDERCLOUD

Run the following command to combine the certificate and key together:

```
$ cat server.crt.pem server.key.pem > undercloud.pem
```

This creates a **undercloud.pem** file. You specify the location of this file for the **undercloud_service_certificate** option in your **undercloud.conf** file. This file also requires a special SELinux context so that the HAProxy tool can read it. Use the following example as a guide:

```
$ sudo mkdir /etc/pki/instack-certs
$ sudo cp ~/undercloud.pem /etc/pki/instack-certs/.
$ sudo semanage fcontext -a -t etc_t "/etc/pki/instack-certs(/.*)"?"
$ sudo restorecon -R /etc/pki/instack-certs
```

Add the **undercloud.pem** file location to the **undercloud_service_certificate** option in the **undercloud.conf** file. For example:

```
undercloud_service_certificate = /etc/pki/instack-certs/undercloud.pem
```

In addition, make sure to add your certificate authority from [Section A.2, “Creating a Certificate Authority”](#) to the undercloud’s list of trusted Certificate Authorities so that different services within the undercloud have access to the certificate authority:

```
$ sudo cp ca.crt.pem /etc/pki/ca-trust/source/anchors/
$ sudo update-ca-trust extract
```

Continue installing the undercloud as per the instructions in [Section 4.6, “Configuring the Director”](#).

APPENDIX B. POWER MANAGEMENT DRIVERS

Although IPMI is the main method the director uses for power management control, the director also supports other power management types. This appendix provides a list of the supported power management features. Use these power management settings for [Section 5.1, “Registering Nodes for the Overcloud”](#).

B.1. DELL REMOTE ACCESS CONTROLLER (DRAC)

DRAC is an interface that provides out-of-band remote management features including power management and server monitoring.

pm_type

Set this option to **pxe_drac**.

pm_user; pm_password

The DRAC username and password.

pm_addr

The IP address of the DRAC host.

- To enable this driver, add **pxe_drac** to the **enabled_drivers** option in your **undercloud.conf** file, then rerun **openstack undercloud install** command.

B.2. INTEGRATED LIGHTS-OUT (ILO)

iLO from Hewlett-Packard is an interface that provides out-of-band remote management features including power management and server monitoring.

pm_type

Set this option to **pxe_ilo**.

pm_user; pm_password

The iLO username and password.

pm_addr

The IP address of the iLO interface.

- To enable this driver, add **pxe_ilo** to the **enabled_drivers** option in your **undercloud.conf** file, then rerun **openstack undercloud install** command.
- The director also requires an additional set of utilities for iLo. Install the **python-proliantutils** package and restart the **openstack-ironic-conductor** service:

```
$ sudo yum install python-proliantutils
$ sudo systemctl restart openstack-ironic-conductor.service
```

- HP nodes must a 2015 firmware version for successful introspection. The director has been successfully tested with nodes using firmware version 1.85 (May 13 2015).
- Using a shared iLO port is not supported.

B.3. CISCO UNIFIED COMPUTING SYSTEM (UCS)

UCS from Cisco is a data center platform that unites compute, network, storage access, and virtualization resources. This driver focuses on the power management for bare metal systems connected to the UCS.

pm_type

Set this option to **pxe_ucs**.

pm_user; pm_password

The UCS username and password.

pm_addr

The IP address of the UCS interface.

pm_service_profile

The UCS service profile to use. Usually takes the format of **org-root/ls-[service_profile_name]**. For example:


```
"pm_service_profile": "org-root/ls-Nova-1"
```

- To enable this driver, add **pxe_ucs** to the **enabled_drivers** option in your **undercloud.conf** file, then rerun **openstack undercloud install** command.
- The director also requires an additional set of utilities for UCS. Install the **python-UcsSdk** package and restart the **openstack-ironic-conductor** service:

```
$ sudo yum install python-UcsSdk
$ sudo systemctl restart openstack-ironic-conductor.service
```

B.4. FUJITSU INTEGRATED REMOTE MANAGEMENT CONTROLLER (iRMC)

Fujitsu's iRMC is a Baseboard Management Controller (BMC) with integrated LAN connection and extended functionality. This driver focuses on the power management for bare metal systems connected to the iRMC.



IMPORTANT

iRMC S4 or higher is required.

pm_type

Set this option to **pxe_irmc**.

pm_user; pm_password

The username and password for the iRMC interface.

pm_addr

The IP address of the iRMC interface.

pm_port (Optional)

The port to use for iRMC operations. The default is 443.

pm_auth_method (Optional)

The authentication method for iRMC operations. Use either **basic** or **digest**. The default is **basic**

pm_client_timeout (Optional)

Timeout (in seconds) for iRMC operations. The default is 60 seconds.

pm_sensor_method (Optional)

Sensor data retrieval method. Use either **ipmitool** or **sccs**. The default is **ipmitool**.

- To enable this driver, add **pxe_irmc** to the **enabled_drivers** option in your **undercloud.conf** file, then rerun **openstack undercloud install** command.
- The director also requires an additional set of utilities if you enabled SCCI as the sensor method. Install the **python-scciclient** package and restart the **openstack-ironic-conductor** service:

```
$ yum install python-scciclient
$ sudo systemctl restart openstack-ironic-conductor.service
```

B.5. VIRTUAL BARE METAL CONTROLLER (VBMC)

The director can use virtual machines as nodes on a KVM host. It controls their power management through emulated IPMI devices. This allows you to use the standard IPMI parameters from [Section 5.1, “Registering Nodes for the Overcloud”](#) but for virtual nodes.

This power management method supersedes the method in [Section B.6, “SSH and Virsh”](#), which is now deprecated.



IMPORTANT

This option uses virtual machines instead of bare metal nodes. This means it is available for testing and evaluation purposes only. It is not recommended for Red Hat OpenStack Platform enterprise environments.

Configuring the KVM Host

On the KVM host, enable the OpenStack Platform repository and install the **python-virtualbmc** package:

```
$ sudo subscription-manager repos --enable=rhel-7-server-openstack-11-rpms
$ sudo yum install -y python-virtualbmc
```

Create a virtual bare metal controller (BMC) for each virtual machine using the **vbmc** command. For example, if you aim to create a BMC for virtual machines named **Node01** and **Node02**, run the following commands:

```
$ vbmc add Node01 --port 6230 --username admin --password p455w0rd!
$ vbmc add Node02 --port 6231 --username admin --password p455w0rd!
```

This defines the port to access each BMC and sets each BMC’s authentication details.

**NOTE**

Use a different port for each virtual machine. Port numbers lower than 1025 require root privileges in the system.

Start each BMC with the following commands:

```
$ vbmc start Node01
$ vbmc start Node02
```

**NOTE**

You must repeat this step after rebooting the KVM host.

Registering Nodes

Use the following parameters in your node registration file (`/home/stack/instackenv.json`):

pm_type

Set this option to **pxe_ipmitool**.

pm_user; pm_password

The IPMI username and password for the node's virtual BMC device.

pm_addr

The IP address of the KVM host that contains the node.

pm_port

The port to access the specific node on the KVM host.

mac

A list of MAC addresses for the network interfaces on the node. Use only the MAC address for the Provisioning NIC of each system.

For example:

```
{
  "nodes": [
    {
      "pm_type": "pxe_ipmitool",
      "mac": [
        "aa:aa:aa:aa:aa:aa"
      ],
      "pm_user": "admin",
      "pm_password": "p455w0rd!",
      "pm_addr": "192.168.0.1",
      "pm_port": "6230",
      "name": "Node01"
    },
    {
      "pm_type": "pxe_ipmitool",
      "mac": [
        "bb:bb:bb:bb:bb:bb"
      ],
      "pm_user": "admin",
```

```

        "pm_password": "p455w0rd!",
        "pm_addr": "192.168.0.1",
        "pm_port": "6231",
        "name": "Node02"
    }
]
}

```

Migrating Existing Nodes

You can migrate existing nodes from using the deprecated **pxe_ssh** driver to using the new virtual BMC method. The following command is an example that sets a node to use the **pxe_ipmitool** driver and its parameters:


```

openstack baremetal node set Node01 \
  --driver pxe_ipmitool \
  --driver-info ipmi_address=192.168.0.1 \
  --driver-info ipmi_port=6230 \
  --driver-info ipmi_username="admin" \
  --driver-info ipmi_password="p455w0rd!"

```

B.6. SSH AND VIRSH

The director can access a KVM host running **libvirt** through SSH and use virtual machines as nodes. The director uses **virsh** to control the power management of these nodes.



IMPORTANT

This option is deprecated in favor of the method in [Section B.5, “Virtual Bare Metal Controller \(VBMC\)”](#). If you continue to use this deprecated driver, note that it is only available for testing and evaluation purposes only. It is not recommended for Red Hat OpenStack Platform enterprise environments.

pm_type

Set this option to **pxe_ssh**.

pm_user; pm_password

The SSH username and contents of the SSH private key. If using the CLI tools to register your nodes, the private key must be on one line with new lines replaced with escape characters (**\n**). For example:

```

-----BEGIN RSA PRIVATE KEY-----\nMIIIEogIBAAKCAQEA .... kk+WXt9Y=\n-----
END RSA PRIVATE KEY-----

```

Add the SSH public key to the libvirt server's **authorized_keys** collection.

pm_addr

The IP address of the virsh host.

- The server hosting libvirt requires an SSH key pair with the public key set as the **pm_password** attribute.
- Ensure the chosen **pm_user** has full access to the libvirt environment.

B.7. FAKE PXE DRIVER

This driver provides a method to use bare metal devices without power management. This means the director does not control the registered bare metal devices and as such require manual control of power at certain points in the introspect and deployment processes.



IMPORTANT

This option is available for testing and evaluation purposes only. It is not recommended for Red Hat OpenStack Platform enterprise environments.

pm_type

Set this option to **fake_pxe**.

- This driver does not use any authentication details because it does not control power management.
- To enable this driver, add **fake_pxe** to the **enabled_drivers** option in your **undercloud.conf** file, then rerun **openstack undercloud install** command.
- When performing introspection on nodes, manually power the nodes after running the **openstack baremetal introspection bulk start** command.
- When performing overcloud deployment, check the node status with the **ironic node-list** command. Wait until the node status changes from **deploying** to **deploy wait-callback** and then manually power the nodes.
- After the overcloud provisioning process completes, reboot the nodes. To check the completion of provisioning, check the node status with the **ironic node-list** command, wait until the node status changes to **active**, then manually reboot all overcloud nodes.

APPENDIX C. WHOLE DISK IMAGES

The main overcloud image is a flat partition image. This means it contains no partitioning information or bootloader on the images itself. The director uses a separate kernel and ramdisk when booting and creates a basic partitioning layout when writing the overcloud image to disk. However, you can create a whole disk image, which includes a partitioning layout and bootloader.

C.1. CREATING WHOLE DISK IMAGES

Creating a whole disk image from the **overcloud-full.qcow2** flat partition image involves the following steps:

1. Open the **overcloud-full** flat partition as a base for our whole disk image.
2. Create a new whole disk image with the desired size. This example uses a 10 GB image.
3. Create partitions and volumes on the whole disk image. Create as many partitions and volumes necessary for your desired whole disk image. This example creates an isolated partition for **boot** and logical volumes for the other content in the filesystem.
4. Create the initial filesystems on the partitions and volumes.
5. Mount flat partition filesystem and copy content to the right partitions on the whole disk image.
6. Generate the **fstab** content and save it to **/etc/fstab** on the whole disk image.
7. Unmount all the filesystems.
8. Mount the partitions on the whole disk image only. Start with the root partition mounted at **/** and mount the other partition in their respective directories.
9. Install the bootloader using shell commands to execute **grub2-install** and **grub2-mkconfig** on the whole disk image. This installs the **grub2** bootloader in the whole disk image.
10. Update **dracut** to provide support for logical volume management
11. Unmount all the filesystems and close the image

C.2. MANUALLY CREATING A WHOLE DISK IMAGE

A recommended tool for creating images is **guestfish**, which you install using the following command:

```
$ sudo yum install -y guestfish
```

Once installed, run the **guestfish** interactive shell:

```
$ guestfish
```

```
Welcome to guestfish, the guest filesystem shell for
editing virtual machine filesystems and disk images.
```

```
Type: 'help' for help on commands
      'man' to read the manual
```

```
'quit' to quit the shell

><fs>
```

For more information on using **guestfish** see ["The Guestfish Shell"](#) in the *Virtualization Deployment and Administration Guide* for Red Hat Enterprise Linux 7.

C.3. AUTOMATICALLY CREATING A WHOLE DISK IMAGE

The following Python script uses the **guestfish** library to automatically generate the whole disk image.

```
#!/usr/bin/env python
import guestfs
import os

# remove old generated drive
try:
    os.unlink("/home/stack/images/overcloud-full-partitioned.qcow2")
except:
    pass

g = guestfs.GuestFS(python_return_dict=True)

# import old and new images
print("Creating new repartitioned image")
g.add_drive_opts("/home/stack/images/overcloud-full.qcow2",
format="qcow2", readonly=1)
g.disk_create("/home/stack/images/overcloud-full-partitioned.qcow2",
"qcow2", 10.2 * 1024 * 1024 * 1024) #10.2G
g.add_drive_opts("/home/stack/images/overcloud-full-partitioned.qcow2",
format="qcow2", readonly=0)
g.launch()

# create the partitions for new image
print("Creating the initial partitions")
g.part_init("/dev/sdb", "mbr")
g.part_add("/dev/sdb", "primary", 2048, 616448)
g.part_add("/dev/sdb", "primary", 616449, -1)

g.pvcreate("/dev/sdb2")
g.vgcreate("vg", ['/dev/sdb2', ])
g.lvcreate("var", "vg", 5 * 1024)
g.lvcreate("tmp", "vg", 500)
g.lvcreate("swap", "vg", 250)
g.lvcreate("home", "vg", 100)
g.lvcreate("root", "vg", 4 * 1024)
g.part_set_bootable("/dev/sdb", 1, True)

# add filesystems to volumes
print("Adding filesystems")
ids = {}
keys = [ 'var', 'tmp', 'swap', 'home', 'root' ]
volumes = ['/dev/vg/var', '/dev/vg/tmp', '/dev/vg/swap', '/dev/vg/home',
'/dev/vg/root']
swap_volume = volumes[2]
```

```

count = 0
for volume in volumes:
    if count!=2:
        g.mkfs('ext4', volume)
        ids[keys[count]] = g.vfs_uuid(volume)
    count +=1

# create filesystem on boot and swap
g.mkfs('ext4', '/dev/sdb1')
g.mkswap_opts(volumes[2])
ids['swap'] = g.vfs_uuid(volumes[2])

# mount drives and copy content
print("Start copying content")
g.mkmountpoint('/old')
g.mkmountpoint('/root')
g.mkmountpoint('/boot')
g.mkmountpoint('/home')
g.mkmountpoint('/var')
g.mount('/dev/sda', '/old')

g.mount('/dev/sdb1', '/boot')
g.mount(volumes[4], '/root')
g.mount(volumes[3], '/home')
g.mount(volumes[0], '/var')

# copy content to root
results = g.ls('/old/')
for result in results:
    if result not in ('boot', 'home', 'tmp', 'var'):
        print("Copying %s to root" % result)
        g.cp_a('/old/%s' % result, '/root/')

# copy extra content
folders_to_copy = ['boot', 'home', 'var']
for folder in folders_to_copy:
    results = g.ls('/old/%s/' % folder)
    for result in results:
        print("Copying %s to %s" % (result, folder))
        g.cp_a('/old/%s/%s' % (folder, result),
            '/%s/' % folder)

# create /etc/fstab file
print("Generating fstab content")
fstab_content = """
UUID={boot_id} /boot ext4 defaults 0 2
UUID={root_id} / ext4 defaults 0 1
UUID={swap_id} none swap sw 0 0
UUID={tmp_id} /tmp ext4 defaults 0 2
UUID={home_id} /home ext4 defaults 0 2
UUID={var_id} /var ext4 defaults 0 2
""".format(
    boot_id=g.vfs_uuid('/dev/sdb1'),
    root_id=ids['root'],
    swap_id=ids['swap'],

```

```

    tmp_id=ids['tmp'],
    home_id=ids['home'],
    var_id=ids['var'])

g.write('/root/etc/fstab', fstab_content)

# unmount filesystems
g.umount('/root')
g.umount('/boot')
g.umount('/old')
g.umount('/var')

# mount in the right directories to install bootloader
print("Installing bootloader")
g.mount(volumes[4], '/')
g.mkdir('/boot')
g.mkdir('/var')
g.mount('/dev/sdb1', '/boot')
g.mount(volumes[0], '/var')

# do a selinux relabel
g.selinux_relabel('/etc/selinux/targeted/contexts/files/file_contexts',
'/', force=True)
g.selinux_relabel('/etc/selinux/targeted/contexts/files/file_contexts',
'/var', force=True)

g.sh('grub2-install --target=i386-pc /dev/sdb')
g.sh('grub2-mkconfig -o /boot/grub2/grub.cfg')

# create dracut.conf file
dracut_content = ""
add_dracutmodules+="lvm crypt"
""
g.write('/etc/dracut.conf', dracut_content)

# update initramfs to include lvm and crypt
kernels = g.ls('/lib/modules')
for kernel in kernels:
    print("Updating dracut to include modules in kernel %s" % kernel)
    g.sh('dracut -f /boot/initramfs-%s.img %s --force' % (kernel, kernel))
g.umount('/boot')
g.umount('/var')
g.umount('/')

# close images
print("Finishing image")
g.shutdown()
g.close()

```

Save this script as a executable file on the undercloud and run it as the **stack** user:

```
$ ./whole-disk-image.py
```

This automatically creates the whole disk image from the flat partition image. Once the whole disk image creation completes, replace the old **overcloud-full.qcow2** image:

-

```
$ mv ~/images/overcloud-full.qcow2 ~/images/overcloud-full-old.qcow2
$ cp ~/images/overcloud-full-partitioned.qcow2 ~/images/overcloud-
full.qcow2
```

You can now upload the whole disk image along with your other images.

C.4. ENCRYPTING VOLUMES ON WHOLE DISK IMAGES

You can also use **guestfish** to encrypt volumes on your whole disk image. This requires using the **luks-format** subcommand, which erases the current volume and creates an encrypted volume.

The following Python script is a modified version of the script in [Section C.3, “Automatically Creating a Whole Disk Image”](#). This new script encrypts the **home** volume:

```
#!/usr/bin/env python
import binascii
import guestfs
import os

# remove old generated drive
try:
    os.unlink("/tmp/overcloud-full-partitioned.qcow2")
except:
    pass

g = guestfs.GuestFS(python_return_dict=True)

# import old and new images
print("Creating new repartitioned image")
g.add_drive_opts("/tmp/overcloud-full.qcow2", format="qcow2", readonly=1)
g.disk_create("/tmp/overcloud-full-partitioned.qcow2", "qcow2", 10 * 1024
* 1024 * 1024) #10G
g.add_drive_opts("/tmp/overcloud-full-partitioned.qcow2", format="qcow2",
readonly=0)
g.launch()

# create the partitions for new image
print("Creating the initial partitions")
g.part_init("/dev/sdb", "mbr")
g.part_add("/dev/sdb", "primary", 2048, 616448)
g.part_add("/dev/sdb", "primary", 616449, -1)

g.pvcreate("/dev/sdb2")
g.vgcreate("vg", ['/dev/sdb2', ])
g.lvcreate("var", "vg", 4400)
g.lvcreate("tmp", "vg", 500)
g.lvcreate("swap", "vg", 250)
g.lvcreate("home", "vg", 100)
g.lvcreate("root", "vg", 4000)
g.part_set_bootable("/dev/sdb", 1, True)

# encrypt home partition and write keys
print("Encrypting volume")
random_content = binascii.b2a_hex(os.urandom(1024))
g.luks_format('/dev/vg/home', random_content, 0)
```

```

# open the encrypted volume
volumes = ['/dev/vg/var', '/dev/vg/tmp', '/dev/vg/swap',
            '/dev/mapper/encryptedhome', '/dev/vg/root']

g.luks_open('/dev/vg/home', random_content, 'encryptedhome')
g.vgscan()
g.vg_activate_all(True)

# add filesystems to volumes
print("Adding filesystems")
ids = {}
keys = [ 'var', 'tmp', 'swap', 'home', 'root' ]
swap_volume = volumes[2]

count = 0
for volume in volumes:
    if count!=2:
        g.mkfs('ext4', volume)
        if keys[count] == 'home':
            ids['home'] = g.vfs_uuid('/dev/vg/home')
        else:
            ids[keys[count]] = g.vfs_uuid(volume)
        count +=1

# create filesystem on boot and swap
g.mkfs('ext4', '/dev/sdb1')
g.mkswap_opts(volumes[2])
ids['swap'] = g.vfs_uuid(volumes[2])

# mount drives and copy content
print("Start copying content")
g.mkmountpoint('/old')
g.mkmountpoint('/root')
g.mkmountpoint('/boot')
g.mkmountpoint('/home')
g.mkmountpoint('/var')
g.mount('/dev/sda', '/old')

g.mount('/dev/sdb1', '/boot')
g.mount(volumes[4], '/root')
g.mount(volumes[3], '/home')
g.mount(volumes[0], '/var')

# copy content to root
results = g.ls('/old/')
for result in results:
    if result not in ('boot', 'home', 'tmp', 'var'):
        print("Copying %s to root" % result)
        g.cp_a('/old/%s' % result, '/root/')

# copy extra content
folders_to_copy = ['boot', 'home', 'var']
for folder in folders_to_copy:
    results = g.ls('/old/%s/' % folder)
    for result in results:

```

```

    print("Copying %s to %s" % (result, folder))
    g.cp_a('/old/%s/%s' % (folder, result),
          '/%s/' % folder)

# write keyfile for encrypted volume
g.write('/root/root/home_keyfile', random_content)
g.chmod(0400, '/root/root/home_keyfile')

# generate mapper for encrypted home
mapper = """
home UUID={home_id} /root/home_keyfile
""".format(home_id=ids['home'])
g.write('/root/etc/crypttab', mapper)

# create /etc/fstab file
print("Generating fstab content")
fstab_content = """
UUID={boot_id} /boot ext4 defaults 1 2
UUID={root_id} / ext4 defaults 1 1
UUID={swap_id} none swap sw 0 0
UUID={tmp_id} /tmp ext4 defaults 1 2
UUID={var_id} /var ext4 defaults 1 2
/dev/mapper/home /home ext4 defaults 1 2
""".format(
    boot_id=g.vfs_uuid('/dev/sdb1'),
    root_id=ids['root'],
    swap_id=ids['swap'],
    tmp_id=ids['tmp'],
    home_id=ids['home'],
    var_id=ids['var'])

g.write('/root/etc/fstab', fstab_content)

# umount filesystems
g.umount('/root')
g.umount('/boot')
g.umount('/old')
g.umount('/var')
g.umount('/home')

# close encrypted volume
g.luks_close('/dev/mapper/cryptedhome')

# mount in the right directories to install bootloader
print("Installing bootloader")
g.mount(volumes[4], '/')
g.mkdir('/boot')
g.mkdir('/var')
g.mount('/dev/sdb1', '/boot')
g.mount(volumes[0], '/var')

# add rd.auto=1 on grub parameters
g.sh('sed -i "s/*.GRUB_CMDLINE_LINUX.*/GRUB_CMDLINE_LINUX=\\\\"console=tty0
crashkernel=auto rd.auto=1\\\\" /etc/default/grub')

g.sh('grub2-install --target=i386-pc /dev/sdb')

```

```

g.sh('grub2-mkconfig -o /boot/grub2/grub.cfg')

# create dracut.conf file
dracut_content = ""
add_dracutmodules+="lvm crypt"
""
g.write('/etc/dracut.conf', dracut_content)

# update initramfs to include lvm and crypt
kernels = g.ls('/lib/modules')
for kernel in kernels:
    print("Updating dracut to include modules in kernel %s" % kernel)
    g.sh('dracut -f /boot/initramfs-%s.img %s --force' % (kernel, kernel))

# do a selinux relabel
g.selinux_relabel('/etc/selinux/targeted/contexts/files/file_contexts',
'/', force=True)
g.selinux_relabel('/etc/selinux/targeted/contexts/files/file_contexts',
'/var', force=True)

g.umount('/boot')
g.umount('/var')
g.umount('/')

# close images
print("Finishing image")
g.shutdown()
g.close()

```

This script also:

- Creates a key (**random_content**)
- Saves the encryption key at **/root/home_keyfile**
- Generates a **crypttab** file to automatically decrypt the volume using the **/root/home_keyfile**

Use this script as an example to create encrypted volumes as part of your whole disk image creation process.

C.5. UPLOADING WHOLE DISK IMAGES

To upload a whole disk image, use the **--whole-disk-image** option with the image upload command. For example:

```

$ openstack overcloud image upload --whole-disk --image-path
/home/stack/images

```

This command uploads the images from **/home/stack/images** but treats the **overcloud-full.qcow2** file as a whole disk image. This means you must rename the desired whole disk image to **overcloud-full.qcow2** before running the image upload command.

APPENDIX D. ALTERNATIVE BOOT MODES

The default boot mode for nodes is BIOS over iPXE. The following sections outline some alternative boot modes for the director to use when provisioning and inspecting nodes.

D.1. STANDARD PXE

The iPXE boot process uses HTTP to boot the introspection and deployment images. Older systems might only support a standard PXE boot, which boots over TFTP.

To change from iPXE to PXE, edit the **undercloud.conf** file on the director host and set **ipxe_enabled** to **False**:

```
ipxe_enabled = False
```

Save this file and run the undercloud installation:

```
$ openstack undercloud install
```

For more information on this process, see the article ["Changing from iPXE to PXE in Red Hat OpenStack Platform director"](#).

D.2. UEFI BOOT MODE

The default boot mode is the legacy BIOS mode. Newer systems might require UEFI boot mode instead of the legacy BIOS mode. In this situation, set the following in your **undercloud.conf** file:

```
ipxe_enabled = True
inspection_enable_uefi = True
```

Save this file and run the undercloud installation:

```
$ openstack undercloud install
```

Set the boot mode to **uefi** for each registered node. For example, to add or replace the existing **boot_mode** parameters in the **capabilities** property:

```
$ NODE=<NODE NAME OR ID> ; openstack baremetal node set --property
capabilities="boot_mode:uefi,${openstack baremetal node show $NODE -f json
-c properties | jq -r '.properties.capabilities' | sed 's/boot_mode:
[^,]*,//g'})" $NODE
```



NOTE

Check that you have retained the **profile** and **boot_option** capabilities with this command.

In addition, set the boot mode to **uefi** for each flavor. For example:

```
$ openstack flavor set --property capabilities:boot_mode='uefi' control
```

APPENDIX E. AUTOMATIC PROFILE TAGGING

The introspection process performs a series of benchmark tests. The director saves the data from these tests. You can create a set of policies that use this data in various ways. For example:

- The policies can identify and isolate underperforming or unstable nodes from use in the overcloud.
- The policies can define whether to automatically tag nodes into specific profiles.

E.1. POLICY FILE SYNTAX

Policy files use a JSON format that contains a set of rules. Each rule defines a *description*, a *condition*, and an *action*.

Description

This is a plain text description of the rule.

Example:

```
"description": "A new rule for my node tagging policy"
```

Conditions

A condition defines an evaluation using the following key-value pattern:

field

Defines the field to evaluate. For field types, see [Section E.4, “Automatic Profile Tagging Properties”](#)

op

Defines the operation to use for the evaluation. This includes the following:

- **eq** - Equal to
- **ne** - Not equal to
- **lt** - Less than
- **gt** - Greater than
- **le** - Less than or equal to
- **ge** - Greater than or equal to
- **in-net** - Checks that an IP address is in a given network
- **matches** - Requires a full match against a given regular expression
- **contains** - Requires a value to contain a given regular expression;
- **is-empty** - Checks that field is empty.

invert

Boolean value to define whether to invert the result of the evaluation.

multiple

Defines the evaluation to use if multiple results exist. This includes:

- **any** - Requires any result to match
- **all** - Requires all results to match
- **first** - Requires the first result to match

value

Defines the value in the evaluation. If the field and operation result in the value, the condition return a true result. If not, the condition returns false.

Example:

```
"conditions": [
  {
    "field": "local_gb",
    "op": "ge",
    "value": 1024
  }
],
```

Actions

An action is performed if the condition returns as true. It uses the **action** key and additional keys depending on the value of **action**:

- **fail** - Fails the introspection. Requires a **message** parameter for the failure message.
- **set-attribute** - Sets an attribute on an Ironi node. Requires a **path** field, which is the path to an Ironi attribute (e.g. **/driver_info/ipmi_address**), and a **value** to set.
- **set-capability** - Sets a capability on an Ironi node. Requires **name** and **value** fields, which are the name and the value for a new capability accordingly. The existing value for this same capability is replaced. For example, use this to define node profiles.
- **extend-attribute** - The same as **set-attribute** but treats the existing value as a list and appends value to it. If the optional **unique** parameter is set to True, nothing is added if the given value is already in a list.

Example:

```
"actions": [
  {
    "action": "set-capability",
    "name": "profile",
    "value": "swift-storage"
  }
]
```

E.2. POLICY FILE EXAMPLE

The following is an example JSON file (**rules.json**) with the introspection rules to apply:

```
[
  {
    "description": "Fail introspection for unexpected nodes",
    "conditions": [
      {
        "op": "lt",
        "field": "memory_mb",
        "value": 4096
      }
    ],
    "actions": [
      {
        "action": "fail",
        "message": "Memory too low, expected at least 4 GiB"
      }
    ]
  },
  {
    "description": "Assign profile for object storage",
    "conditions": [
      {
        "op": "ge",
        "field": "local_gb",
        "value": 1024
      }
    ],
    "actions": [
      {
        "action": "set-capability",
        "name": "profile",
        "value": "swift-storage"
      }
    ]
  },
  {
    "description": "Assign possible profiles for compute and controller",
    "conditions": [
      {
        "op": "lt",
        "field": "local_gb",
        "value": 1024
      },
      {
        "op": "ge",
        "field": "local_gb",
        "value": 40
      }
    ],
    "actions": [
      {
        "action": "set-capability",
        "name": "compute_profile",
        "value": "1"
      },
      {
        "action": "set-capability",
```

```

        "name": "control_profile",
        "value": "1"
      },
      {
        "action": "set-capability",
        "name": "profile",
        "value": null
      }
    ]
  }
]

```

This example consists of three rules:

- Fail introspection if memory is lower than 4096 MiB. Such rules can be applied to exclude nodes that should not become part of your cloud.
- Nodes with a hard drive size 1 TiB and bigger are assigned the swift-storage profile unconditionally.
- Nodes with a hard drive less than 1 TiB but more than 40 GiB can be either Compute or Controller nodes. We assign two capabilities (**compute_profile** and **control_profile**) so that the **openstack overcloud profiles match** command can later make the final choice. For that to work, we remove the existing profile capability, otherwise it will have priority.

Other nodes are not changed.



NOTE

Using introspection rules to assign the **profile** capability always overrides the existing value. However, **[PROFILE]_profile** capabilities are ignored for nodes with an existing profile capability.

E.3. IMPORTING POLICY FILES

Import the policy file into the director with the following command:

```
$ openstack baremetal introspection rule import rules.json
```

Then run the introspection process.

```
$ openstack baremetal introspection bulk start
```

After introspection completes, check the nodes and their assigned profiles:

```
$ openstack overcloud profiles list
```

If you made a mistake in introspection rules, you can delete them all:

```
$ openstack baremetal introspection rule purge
```

E.4. AUTOMATIC PROFILE TAGGING PROPERTIES

Automatic Profile Tagging evaluates the following node properties for the **field** attribute for each condition:

Property	Description
memory_mb	The amount of memory for the node in MB.
cpus	The total number of cores for the node's CPUs.
cpu_arch	The architecture of the node's CPUs.
local_gb	The total storage space of the node's root disk. See Section 5.4, "Defining the Root Disk for Nodes" for more information about setting the root disk for a node.

APPENDIX F. SECURITY ENHANCEMENTS

The following sections provide some suggestions to harden the security of your undercloud.

F.1. CHANGING THE SSL/TLS CIPHER AND RULES FOR HAPROXY

If you enabled SSL/TLS in the undercloud (see [Section 4.6, “Configuring the Director”](#)), you might want to harden the SSL/TLS ciphers and rules used with the HAProxy configuration. This helps avoid SSL/TLS vulnerabilities, such as the [POODLE vulnerability](#).

Set the following hieradata using the **hieradata_override** undercloud configuration option:

tripleo::haproxy::ssl_cipher_suite

The cipher suite to use in HAProxy.

tripleo::haproxy::ssl_options

The SSL/TLS rules to use in HAProxy.

For example, you might aim to use the following cipher and rules:

- Cipher: **ECDHE-ECDSA-CHACHA20-POLY1305:ECDHE-RSA-CHACHA20-POLY1305:ECDHE-ECDSA-AES128-GCM-SHA256:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-ECDSA-AES256-GCM-SHA384:ECDHE-RSA-AES256-GCM-SHA384:DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-ECDSA-AES128-SHA256:ECDHE-RSA-AES128-SHA256:ECDHE-ECDSA-AES128-SHA:ECDHE-RSA-AES256-SHA384:ECDHE-RSA-AES128-SHA:ECDHE-ECDSA-AES256-SHA384:ECDHE-ECDSA-AES256-SHA:ECDHE-RSA-AES256-SHA:DHE-RSA-AES128-SHA256:DHE-RSA-AES128-SHA:DHE-RSA-AES256-SHA256:DHE-RSA-AES256-SHA:ECDHE-ECDSA-DES-CBC3-SHA:ECDHE-RSA-DES-CBC3-SHA:EDH-RSA-DES-CBC3-SHA:AES128-GCM-SHA256:AES256-GCM-SHA384:AES128-SHA256:AES256-SHA256:AES128-SHA:AES256-SHA:DES-CBC3-SHA:!DSS**
- Rules: **no-sslsv3 no-tls-tickets**

Create a hieradata override file (**haproxy-hiera-overrides.yaml**) with the following content:

```
tripleo::haproxy::ssl_cipher_suite: ECDHE-ECDSA-CHACHA20-POLY1305:ECDHE-RSA-CHACHA20-POLY1305:ECDHE-ECDSA-AES128-GCM-SHA256:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-ECDSA-AES256-GCM-SHA384:ECDHE-RSA-AES256-GCM-SHA384:DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-ECDSA-AES128-SHA256:ECDHE-RSA-AES128-SHA256:ECDHE-ECDSA-AES128-SHA:ECDHE-RSA-AES256-SHA384:ECDHE-RSA-AES128-SHA:ECDHE-ECDSA-AES256-SHA384:ECDHE-ECDSA-AES256-SHA:ECDHE-RSA-AES256-SHA:DHE-RSA-AES128-SHA256:DHE-RSA-AES128-SHA:DHE-RSA-AES256-SHA256:DHE-RSA-AES256-SHA:ECDHE-ECDSA-DES-CBC3-SHA:ECDHE-RSA-DES-CBC3-SHA:EDH-RSA-DES-CBC3-SHA:AES128-GCM-SHA256:AES256-GCM-SHA384:AES128-SHA256:AES256-SHA256:AES128-SHA:AES256-SHA:DES-CBC3-SHA:!DSS
tripleo::haproxy::ssl_options: no-sslsv3 no-tls-tickets
```



NOTE

The cipher collection is one continuous line.

Set the **hieradata_override** parameter in the **undercloud.conf** file to use the hieradata override file you created before running **openstack undercloud install**:

```
[DEFAULT]
```

```
...
```

```
hieradata_override = haproxy-hiera-overrides.yaml
```

```
...
```