



# OpenShift Container Platform 4.11

## Storage

Configuring and managing storage in OpenShift Container Platform



# OpenShift Container Platform 4.11 Storage

---

Configuring and managing storage in OpenShift Container Platform

## Legal Notice

Copyright © 2024 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux<sup>®</sup> is the registered trademark of Linus Torvalds in the United States and other countries.

Java<sup>®</sup> is a registered trademark of Oracle and/or its affiliates.

XFS<sup>®</sup> is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL<sup>®</sup> is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js<sup>®</sup> is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack<sup>®</sup> Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## Abstract

This document provides instructions for configuring persistent volumes from various storage back ends and managing dynamic allocation from Pods.

## Table of Contents

<b>CHAPTER 1. OPENSIFT CONTAINER PLATFORM STORAGE OVERVIEW .....</b>	<b>7</b>
1.1. GLOSSARY OF COMMON TERMS FOR OPENSIFT CONTAINER PLATFORM STORAGE	7
1.2. STORAGE TYPES	9
1.2.1. Ephemeral storage	9
1.2.2. Persistent storage	9
1.3. CONTAINER STORAGE INTERFACE (CSI)	9
1.4. DYNAMIC PROVISIONING	9
 <b>CHAPTER 2. UNDERSTANDING EPHEMERAL STORAGE .....</b>	 <b>11</b>
2.1. OVERVIEW	11
2.2. TYPES OF EPHEMERAL STORAGE	11
Root	11
Runtime	11
2.3. EPHEMERAL STORAGE MANAGEMENT	11
2.4. MONITORING EPHEMERAL STORAGE	11
 <b>CHAPTER 3. UNDERSTANDING PERSISTENT STORAGE .....</b>	 <b>13</b>
3.1. PERSISTENT STORAGE OVERVIEW	13
3.2. LIFECYCLE OF A VOLUME AND CLAIM	13
3.2.1. Provision storage	13
3.2.2. Bind claims	13
3.2.3. Use pods and claimed PVs	14
3.2.4. Storage Object in Use Protection	14
3.2.5. Release a persistent volume	14
3.2.6. Reclaim policy for persistent volumes	14
3.2.7. Reclaiming a persistent volume manually	15
3.2.8. Changing the reclaim policy of a persistent volume	15
3.3. PERSISTENT VOLUMES	16
3.3.1. Types of PVs	17
3.3.2. Capacity	17
3.3.3. Access modes	17
3.3.4. Phase	20
3.3.4.1. Mount options	20
3.4. PERSISTENT VOLUME CLAIMS	21
3.4.1. Storage classes	22
3.4.2. Access modes	22
3.4.3. Resources	22
3.4.4. Claims as volumes	22
3.5. BLOCK VOLUME SUPPORT	23
3.5.1. Block volume examples	24
3.6. USING FSGROUP TO REDUCE POD TIMEOUTS	26
 <b>CHAPTER 4. CONFIGURING PERSISTENT STORAGE .....</b>	 <b>28</b>
4.1. PERSISTENT STORAGE USING AWS ELASTIC BLOCK STORE	28
4.1.1. Creating the EBS storage class	28
4.1.2. Creating the persistent volume claim	28
4.1.3. Volume format	29
4.1.4. Maximum number of EBS volumes on a node	29
4.1.5. Encrypting container persistent volumes on AWS with a KMS key	29
4.1.6. Additional resources	31
4.2. PERSISTENT STORAGE USING AZURE	31
4.2.1. Creating the Azure storage class	31

4.2.2. Creating the persistent volume claim	32
4.2.3. Volume format	33
4.2.4. Machine sets that deploy machines with ultra disks using PVCs	33
4.2.4.1. Creating machines with ultra disks by using machine sets	33
4.2.4.2. Troubleshooting resources for machine sets that enable ultra disks	36
4.2.4.2.1. Unable to mount a persistent volume claim backed by an ultra disk	36
4.3. PERSISTENT STORAGE USING AZURE FILE	37
4.3.1. Create the Azure File share persistent volume claim	37
4.3.2. Mount the Azure File share in a pod	39
4.4. PERSISTENT STORAGE USING CINDER	39
4.4.1. Manual provisioning with Cinder	40
4.4.1.1. Creating the persistent volume	40
4.4.1.2. Persistent volume formatting	41
4.4.1.3. Cinder volume security	41
4.5. PERSISTENT STORAGE USING FIBRE CHANNEL	42
4.5.1. Provisioning	43
4.5.1.1. Enforcing disk quotas	44
4.5.1.2. Fibre Channel volume security	44
4.6. PERSISTENT STORAGE USING FLEXVOLUME	44
4.6.1. About FlexVolume drivers	44
4.6.2. FlexVolume driver example	45
4.6.3. Installing FlexVolume drivers	46
4.6.4. Consuming storage using FlexVolume drivers	47
4.7. PERSISTENT STORAGE USING GCE PERSISTENT DISK	48
4.7.1. Creating the GCE storage class	49
4.7.2. Creating the persistent volume claim	49
4.7.3. Volume format	49
4.8. PERSISTENT STORAGE USING HOSTPATH	49
4.8.1. Overview	50
4.8.2. Statically provisioning hostPath volumes	50
4.8.3. Mounting the hostPath share in a privileged pod	51
4.9. PERSISTENT STORAGE USING ISCSI	52
4.9.1. Provisioning	53
4.9.2. Enforcing disk quotas	53
4.9.3. iSCSI volume security	53
4.9.3.1. Challenge Handshake Authentication Protocol (CHAP) configuration	54
4.9.4. iSCSI multipathing	54
4.9.5. iSCSI custom initiator IQN	55
4.10. PERSISTENT STORAGE USING LOCAL VOLUMES	55
4.10.1. Installing the Local Storage Operator	55
4.10.2. Provisioning local volumes by using the Local Storage Operator	58
4.10.3. Provisioning local volumes without the Local Storage Operator	61
4.10.4. Creating the local volume persistent volume claim	63
4.10.5. Attach the local claim	64
4.10.6. Automating discovery and provisioning for local storage devices	65
4.10.7. Using tolerations with Local Storage Operator pods	68
4.10.8. Local Storage Operator Metrics	70
4.10.9. Deleting the Local Storage Operator resources	70
4.10.9.1. Removing a local volume or local volume set	70
4.10.9.2. Uninstalling the Local Storage Operator	71
4.11. PERSISTENT STORAGE USING NFS	72
4.11.1. Provisioning	72
4.11.2. Enforcing disk quotas	74

4.11.3. NFS volume security	74
4.11.3.1. Group IDs	75
4.11.3.2. User IDs	76
4.11.3.3. SELinux	77
4.11.3.4. Export settings	77
4.11.4. Reclaiming resources	78
4.11.5. Additional configuration and troubleshooting	78
4.12. RED HAT OPENSIFT DATA FOUNDATION	79
4.13. PERSISTENT STORAGE USING VMWARE VSPHERE VOLUMES	79
4.13.1. Dynamically provisioning VMware vSphere volumes	80
4.13.2. Prerequisites	80
4.13.2.1. Dynamically provisioning VMware vSphere volumes using the UI	80
4.13.2.2. Dynamically provisioning VMware vSphere volumes using the CLI	81
4.13.3. Statically provisioning VMware vSphere volumes	81
4.13.3.1. Formatting VMware vSphere volumes	83
<b>CHAPTER 5. USING CONTAINER STORAGE INTERFACE (CSI)</b> .....	<b>84</b>
5.1. CONFIGURING CSI VOLUMES	84
5.1.1. CSI Architecture	84
5.1.1.1. External CSI controllers	84
5.1.1.2. CSI driver daemon set	85
5.1.2. CSI drivers supported by OpenShift Container Platform	85
5.1.3. Dynamic provisioning	87
5.1.4. Example using the CSI driver	87
5.2. CSI INLINE EPHEMERAL VOLUMES	88
5.2.1. Overview of CSI inline ephemeral volumes	88
5.2.1.1. Support limitations	88
5.2.2. Embedding a CSI inline ephemeral volume in the pod specification	89
5.3. SHARED RESOURCE CSI DRIVER OPERATOR	90
5.3.1. About CSI	90
5.3.2. Sharing secrets across namespaces	90
5.3.3. Using a SharedSecret instance in a pod	91
5.3.4. Sharing a config map across namespaces	92
5.3.5. Using a SharedConfigMap instance in a pod	93
5.3.6. Additional support limitations for the Shared Resource CSI Driver	95
5.3.7. Additional details about VolumeAttributes on shared resource pod volumes	95
5.3.7.1. The refreshResource attribute	95
5.3.7.2. The refreshResources attribute	96
5.3.7.3. Validation of volumeAttributes before provisioning a shared resource volume for a pod	96
5.3.8. Integration between shared resources, Insights Operator, and OpenShift Container Platform Builds	96
5.4. CSI VOLUME SNAPSHOTS	97
5.4.1. Overview of CSI volume snapshots	97
5.4.2. CSI snapshot controller and sidecar	98
5.4.2.1. External controller	98
5.4.2.2. External sidecar	98
5.4.3. About the CSI Snapshot Controller Operator	98
5.4.3.1. Volume snapshot CRDs	98
5.4.4. Volume snapshot provisioning	99
5.4.4.1. Dynamic provisioning	99
5.4.4.2. Manual provisioning	99
5.4.5. Creating a volume snapshot	99
5.4.6. Deleting a volume snapshot	102
5.4.7. Restoring a volume snapshot	103

5.5. CSI VOLUME CLONING	104
5.5.1. Overview of CSI volume cloning	104
5.5.1.1. Support limitations	104
5.5.2. Provisioning a CSI volume clone	105
5.6. CSI AUTOMATIC MIGRATION	106
5.6.1. Overview	106
5.6.2. Automatic migration of in-tree volumes to CSI	107
5.6.3. Manually enabling CSI automatic migration	108
5.7. ALICLOUD DISK CSI DRIVER OPERATOR	109
5.7.1. Overview	109
5.7.2. About CSI	110
5.8. AWS ELASTIC BLOCK STORE CSI DRIVER OPERATOR	110
5.8.1. Overview	110
5.8.2. About CSI	110
5.9. AWS ELASTIC FILE SERVICE CSI DRIVER OPERATOR	111
5.9.1. Overview	111
5.9.2. About CSI	111
5.9.3. Installing the AWS EFS CSI Driver Operator	112
5.9.4. Configuring AWS EFS CSI Driver Operator with Security Token Service	113
5.9.5. Creating the AWS EFS storage class	115
5.9.5.1. Creating the AWS EFS storage class using the console	115
5.9.5.2. Creating the AWS EFS storage class using the CLI	115
5.9.6. Creating and configuring access to EFS volumes in AWS	116
5.9.7. Dynamic provisioning for AWS EFS	117
5.9.8. Creating static PVs with AWS EFS	118
5.9.9. AWS EFS security	119
5.9.10. AWS EFS troubleshooting	119
5.9.11. Uninstalling the AWS EFS CSI Driver Operator	120
5.9.12. Additional resources	121
5.10. AZURE DISK CSI DRIVER OPERATOR	121
5.10.1. Overview	121
5.10.2. About CSI	121
5.10.3. Creating a storage class with storage account type	122
5.10.4. Machine sets that deploy machines with ultra disks using PVCs	123
5.10.4.1. Creating machines with ultra disks by using machine sets	123
5.10.4.2. Troubleshooting resources for machine sets that enable ultra disks	126
5.10.4.2.1. Unable to mount a persistent volume claim backed by an ultra disk	126
5.10.5. Additional resources	127
5.11. AZURE FILE CSI DRIVER OPERATOR	127
5.11.1. Overview	127
5.11.2. About CSI	127
5.12. AZURE STACK HUB CSI DRIVER OPERATOR	128
5.12.1. Overview	128
5.12.2. About CSI	128
5.12.3. Additional resources	128
5.13. GCP PD CSI DRIVER OPERATOR	128
5.13.1. Overview	128
5.13.2. About CSI	129
5.13.3. GCP PD CSI driver storage class parameters	129
5.13.4. Creating a custom-encrypted persistent volume	130
5.14. IBM VPC BLOCK CSI DRIVER OPERATOR	132
5.14.1. Overview	132
5.14.2. About CSI	132



5.15. OPENSTACK CINDER CSI DRIVER OPERATOR	133
5.15.1. Overview	133
5.15.2. About CSI	133
5.15.3. Making OpenStack Cinder CSI the default storage class	134
5.16. OPENSTACK MANILA CSI DRIVER OPERATOR	135
5.16.1. Overview	135
5.16.2. About CSI	135
5.16.3. Manila CSI Driver Operator limitations	136
5.16.4. Dynamically provisioning Manila CSI volumes	136
5.17. RED HAT VIRTUALIZATION CSI DRIVER OPERATOR	138
5.17.1. Overview	138
5.17.2. About CSI	138
5.17.3. Red Hat Virtualization (RHV) CSI driver storage class	138
5.17.4. Creating a persistent volume on RHV	139
5.18. VMWARE VSPHERE CSI DRIVER OPERATOR	141
5.18.1. Overview	141
5.18.2. About CSI	142
5.18.3. vSphere storage policy	142
5.18.4. ReadWriteMany vSphere volume support	142
5.18.5. VMware vSphere CSI Driver Operator requirements	143
5.18.6. Removing a third-party vSphere CSI Driver Operator	143
5.18.7. Additional resources	144
<b>CHAPTER 6. GENERIC EPHEMERAL VOLUMES</b> .....	<b>145</b>
6.1. OVERVIEW	145
6.2. LIFECYCLE AND PERSISTENT VOLUME CLAIMS	145
6.3. SECURITY	146
6.4. PERSISTENT VOLUME CLAIM NAMING	146
6.5. CREATING GENERIC EPHEMERAL VOLUMES	146
<b>CHAPTER 7. EXPANDING PERSISTENT VOLUMES</b> .....	<b>148</b>
7.1. ENABLING VOLUME EXPANSION SUPPORT	148
7.2. EXPANDING CSI VOLUMES	148
7.3. EXPANDING FLEXVOLUME WITH A SUPPORTED DRIVER	149
7.4. EXPANDING LOCAL VOLUMES	149
7.5. EXPANDING PERSISTENT VOLUME CLAIMS (PVCS) WITH A FILE SYSTEM	150
7.6. RECOVERING FROM FAILURE WHEN EXPANDING VOLUMES	151
<b>CHAPTER 8. DYNAMIC PROVISIONING</b> .....	<b>152</b>
8.1. ABOUT DYNAMIC PROVISIONING	152
8.2. AVAILABLE DYNAMIC PROVISIONING PLUGINS	152
8.3. DEFINING A STORAGE CLASS	153
8.3.1. Basic StorageClass object definition	153
8.3.2. Storage class annotations	154
8.3.3. RHOSP Cinder object definition	155
8.3.4. RHOSP Manila Container Storage Interface (CSI) object definition	155
8.3.5. AWS Elastic Block Store (EBS) object definition	155
8.3.6. Azure Disk object definition	156
8.3.7. Azure File object definition	157
8.3.7.1. Considerations when using Azure File	158
8.3.8. GCE PersistentDisk (gcePD) object definition	159
8.3.9. VMware vSphere object definition	159
8.4. CHANGING THE DEFAULT STORAGE CLASS	160



# CHAPTER 1. OPENSIFT CONTAINER PLATFORM STORAGE OVERVIEW

OpenShift Container Platform supports multiple types of storage, both for on-premise and cloud providers. You can manage container storage for persistent and non-persistent data in an OpenShift Container Platform cluster.

## 1.1. GLOSSARY OF COMMON TERMS FOR OPENSIFT CONTAINER PLATFORM STORAGE

This glossary defines common terms that are used in the storage content.

### Access modes

Volume access modes describe volume capabilities. You can use access modes to match persistent volume claim (PVC) and persistent volume (PV). The following are the examples of access modes:

- ReadWriteOnce (RWO)
- ReadOnlyMany (ROX)
- ReadWriteMany (RWX)
- ReadWriteOncePod (RWOP)

### Cinder

The Block Storage service for Red Hat OpenStack Platform (RHOSP) which manages the administration, security, and scheduling of all volumes.

### Config map

A config map provides a way to inject configuration data into pods. You can reference the data stored in a config map in a volume of type **ConfigMap**. Applications running in a pod can use this data.

### Container Storage Interface (CSI)

An API specification for the management of container storage across different container orchestration (CO) systems.

### Dynamic Provisioning

The framework allows you to create storage volumes on-demand, eliminating the need for cluster administrators to pre-provision persistent storage.

### Ephemeral storage

Pods and containers can require temporary or transient local storage for their operation. The lifetime of this ephemeral storage does not extend beyond the life of the individual pod, and this ephemeral storage cannot be shared across pods.

### Fiber channel

A networking technology that is used to transfer data among data centers, computer servers, switches and storage.

### FlexVolume

FlexVolume is an out-of-tree plugin interface that uses an exec-based model to interface with storage drivers. You must install the FlexVolume driver binaries in a pre-defined volume plugin path on each node and in some cases the control plane nodes.

### fsGroup

The fsGroup defines a file system group ID of a pod.

## iSCSI

Internet Small Computer Systems Interface (iSCSI) is an Internet Protocol-based storage networking standard for linking data storage facilities. An iSCSI volume allows an existing iSCSI (SCSI over IP) volume to be mounted into your Pod.

## hostPath

A hostPath volume in an OpenShift Container Platform cluster mounts a file or directory from the host node's filesystem into your pod.

## KMS key

The Key Management Service (KMS) helps you achieve the required level of encryption of your data across different services. you can use the KMS key to encrypt, decrypt, and re-encrypt data.

## Local volumes

A local volume represents a mounted local storage device such as a disk, partition or directory.

## NFS

A Network File System (NFS) that allows remote hosts to mount file systems over a network and interact with those file systems as though they are mounted locally. This enables system administrators to consolidate resources onto centralized servers on the network.

## OpenShift Data Foundation

A provider of agnostic persistent storage for OpenShift Container Platform supporting file, block, and object storage, either in-house or in hybrid clouds

## Persistent storage

Pods and containers can require permanent storage for their operation. OpenShift Container Platform uses the Kubernetes persistent volume (PV) framework to allow cluster administrators to provision persistent storage for a cluster. Developers can use PVC to request PV resources without having specific knowledge of the underlying storage infrastructure.

## Persistent volumes (PV)

OpenShift Container Platform uses the Kubernetes persistent volume (PV) framework to allow cluster administrators to provision persistent storage for a cluster. Developers can use PVC to request PV resources without having specific knowledge of the underlying storage infrastructure.

## Persistent volume claims (PVCs)

You can use a PVC to mount a PersistentVolume into a Pod. You can access the storage without knowing the details of the cloud environment.

## Pod

One or more containers with shared resources, such as volume and IP addresses, running in your OpenShift Container Platform cluster. A pod is the smallest compute unit defined, deployed, and managed.

## Reclaim policy

A policy that tells the cluster what to do with the volume after it is released. A volume's reclaim policy can be **Retain**, **Recycle**, or **Delete**.

## Role-based access control (RBAC)

Role-based access control (RBAC) is a method of regulating access to computer or network resources based on the roles of individual users within your organization.

## Stateless applications

A stateless application is an application program that does not save client data generated in one session for use in the next session with that client.

## Stateful applications

A stateful application is an application program that saves data to persistent disk storage. A server, client, and applications can use a persistent disk storage. You can use the **Statefulset** object in OpenShift Container Platform to manage the deployment and scaling of a set of Pods, and provides guarantee about the ordering and uniqueness of these Pods.

### Static provisioning

A cluster administrator creates a number of PVs. PVs contain the details of storage. PVs exist in the Kubernetes API and are available for consumption.

### Storage

OpenShift Container Platform supports many types of storage, both for on-premise and cloud providers. You can manage container storage for persistent and non-persistent data in an OpenShift Container Platform cluster.

### Storage class

A storage class provides a way for administrators to describe the classes of storage they offer. Different classes might map to quality of service levels, backup policies, arbitrary policies determined by the cluster administrators.

### VMware vSphere's Virtual Machine Disk (VMDK) volumes

Virtual Machine Disk (VMDK) is a file format that describes containers for virtual hard disk drives that is used in virtual machines.

## 1.2. STORAGE TYPES

OpenShift Container Platform storage is broadly classified into two categories, namely ephemeral storage and persistent storage.

### 1.2.1. Ephemeral storage

Pods and containers are ephemeral or transient in nature and designed for stateless applications. Ephemeral storage allows administrators and developers to better manage the local storage for some of their operations. For more information about ephemeral storage overview, types, and management, see [Understanding ephemeral storage](#).

### 1.2.2. Persistent storage

Stateful applications deployed in containers require persistent storage. OpenShift Container Platform uses a pre-provisioned storage framework called persistent volumes (PV) to allow cluster administrators to provision persistent storage. The data inside these volumes can exist beyond the lifecycle of an individual pod. Developers can use persistent volume claims (PVCs) to request storage requirements. For more information about persistent storage overview, configuration, and lifecycle, see [Understanding persistent storage](#).

## 1.3. CONTAINER STORAGE INTERFACE (CSI)

CSI is an API specification for the management of container storage across different container orchestration (CO) systems. You can manage the storage volumes within the container native environments, without having specific knowledge of the underlying storage infrastructure. With the CSI, storage works uniformly across different container orchestration systems, regardless of the storage vendors you are using. For more information about CSI, see [Using Container Storage Interface \(CSI\)](#).

## 1.4. DYNAMIC PROVISIONING

Dynamic Provisioning allows you to create storage volumes on-demand, eliminating the need for cluster administrators to pre-provision storage. For more information about dynamic provisioning, see [Dynamic provisioning](#).

## CHAPTER 2. UNDERSTANDING EPHEMERAL STORAGE

### 2.1. OVERVIEW

In addition to persistent storage, pods and containers can require ephemeral or transient local storage for their operation. The lifetime of this ephemeral storage does not extend beyond the life of the individual pod, and this ephemeral storage cannot be shared across pods.

Pods use ephemeral local storage for scratch space, caching, and logs. Issues related to the lack of local storage accounting and isolation include the following:

- Pods do not know how much local storage is available to them.
- Pods cannot request guaranteed local storage.
- Local storage is a best effort resource.
- Pods can be evicted due to other pods filling the local storage, after which new pods are not admitted until sufficient storage has been reclaimed.

Unlike persistent volumes, ephemeral storage is unstructured and the space is shared between all pods running on a node, in addition to other uses by the system, the container runtime, and OpenShift Container Platform. The ephemeral storage framework allows pods to specify their transient local storage needs. It also allows OpenShift Container Platform to schedule pods where appropriate, and to protect the node against excessive use of local storage.

While the ephemeral storage framework allows administrators and developers to better manage this local storage, it does not provide any promises related to I/O throughput and latency.

### 2.2. TYPES OF EPHEMERAL STORAGE

Ephemeral local storage is always made available in the primary partition. There are two basic ways of creating the primary partition: **root** and **runtime**.

#### Root

This partition holds the kubelet root directory, **/var/lib/kubelet/** by default, and **/var/log/** directory. This partition can be shared between user pods, the OS, and Kubernetes system daemons. This partition can be consumed by pods through **EmptyDir** volumes, container logs, image layers, and container-writable layers. Kubelet manages shared access and isolation of this partition. This partition is ephemeral, and applications cannot expect any performance SLAs, such as disk IOPS, from this partition.

#### Runtime

This is an optional partition that runtimes can use for overlay file systems. OpenShift Container Platform attempts to identify and provide shared access along with isolation to this partition. Container image layers and writable layers are stored here. If the runtime partition exists, the **root** partition does not hold any image layer or other writable storage.

### 2.3. EPHEMERAL STORAGE MANAGEMENT

Cluster administrators can manage ephemeral storage within a project by setting quotas that define the limit ranges and number of requests for ephemeral storage across all pods in a non-terminal state. Developers can also set requests and limits on this compute resource at the pod and container level.

### 2.4. MONITORING EPHEMERAL STORAGE

You can use **/bin/df** as a tool to monitor ephemeral storage usage on the volume where ephemeral container data is located, which is **/var/lib/kubelet** and **/var/lib/containers**. The available space for only **/var/lib/kubelet** is shown when you use the **df** command if **/var/lib/containers** is placed on a separate disk by the cluster administrator.

To show the human-readable values of used and available space in **/var/lib**, enter the following command:

```
$ df -h /var/lib
```

The output shows the ephemeral storage usage in **/var/lib**:

### Example output

```
Filesystem Size Used Avail Use% Mounted on
/dev/sda1 69G 32G 34G 49% /
```



## CHAPTER 3. UNDERSTANDING PERSISTENT STORAGE

### 3.1. PERSISTENT STORAGE OVERVIEW

Managing storage is a distinct problem from managing compute resources. OpenShift Container Platform uses the Kubernetes persistent volume (PV) framework to allow cluster administrators to provision persistent storage for a cluster. Developers can use persistent volume claims (PVCs) to request PV resources without having specific knowledge of the underlying storage infrastructure.

PVCs are specific to a project, and are created and used by developers as a means to use a PV. PV resources on their own are not scoped to any single project; they can be shared across the entire OpenShift Container Platform cluster and claimed from any project. After a PV is bound to a PVC, that PV can not then be bound to additional PVCs. This has the effect of scoping a bound PV to a single namespace, that of the binding project.

PVs are defined by a **PersistentVolume** API object, which represents a piece of existing storage in the cluster that was either statically provisioned by the cluster administrator or dynamically provisioned using a **StorageClass** object. It is a resource in the cluster just like a node is a cluster resource.

PVs are volume plugins like **Volumes** but have a lifecycle that is independent of any individual pod that uses the PV. PV objects capture the details of the implementation of the storage, be that NFS, iSCSI, or a cloud-provider-specific storage system.



#### IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

PVCs are defined by a **PersistentVolumeClaim** API object, which represents a request for storage by a developer. It is similar to a pod in that pods consume node resources and PVCs consume PV resources. For example, pods can request specific levels of resources, such as CPU and memory, while PVCs can request specific storage capacity and access modes. For example, they can be mounted once read-write or many times read-only.

### 3.2. LIFECYCLE OF A VOLUME AND CLAIM

PVs are resources in the cluster. PVCs are requests for those resources and also act as claim checks to the resource. The interaction between PVs and PVCs have the following lifecycle.

#### 3.2.1. Provision storage

In response to requests from a developer defined in a PVC, a cluster administrator configures one or more dynamic provisioners that provision storage and a matching PV.

Alternatively, a cluster administrator can create a number of PVs in advance that carry the details of the real storage that is available for use. PVs exist in the API and are available for use.

#### 3.2.2. Bind claims

When you create a PVC, you request a specific amount of storage, specify the required access mode, and create a storage class to describe and classify the storage. The control loop in the master watches for new PVCs and binds the new PVC to an appropriate PV. If an appropriate PV does not exist, a provisioner for the storage class creates one.

The size of all PVs might exceed your PVC size. This is especially true with manually provisioned PVs. To minimize the excess, OpenShift Container Platform binds to the smallest PV that matches all other criteria.

Claims remain unbound indefinitely if a matching volume does not exist or can not be created with any available provisioner servicing a storage class. Claims are bound as matching volumes become available. For example, a cluster with many manually provisioned 50Gi volumes would not match a PVC requesting 100Gi. The PVC can be bound when a 100Gi PV is added to the cluster.

### 3.2.3. Use pods and claimed PVs

Pods use claims as volumes. The cluster inspects the claim to find the bound volume and mounts that volume for a pod. For those volumes that support multiple access modes, you must specify which mode applies when you use the claim as a volume in a pod.

Once you have a claim and that claim is bound, the bound PV belongs to you for as long as you need it. You can schedule pods and access claimed PVs by including **persistentVolumeClaim** in the pod's volumes block.



#### NOTE

If you attach persistent volumes that have high file counts to pods, those pods can fail or can take a long time to start. For more information, see [When using Persistent Volumes with high file counts in OpenShift, why do pods fail to start or take an excessive amount of time to achieve "Ready" state?](#)

### 3.2.4. Storage Object in Use Protection

The Storage Object in Use Protection feature ensures that PVCs in active use by a pod and PVs that are bound to PVCs are not removed from the system, as this can result in data loss.

Storage Object in Use Protection is enabled by default.



#### NOTE

A PVC is in active use by a pod when a **Pod** object exists that uses the PVC.

If a user deletes a PVC that is in active use by a pod, the PVC is not removed immediately. PVC removal is postponed until the PVC is no longer actively used by any pods. Also, if a cluster admin deletes a PV that is bound to a PVC, the PV is not removed immediately. PV removal is postponed until the PV is no longer bound to a PVC.

### 3.2.5. Release a persistent volume

When you are finished with a volume, you can delete the PVC object from the API, which allows reclamation of the resource. The volume is considered released when the claim is deleted, but it is not yet available for another claim. The previous claimant's data remains on the volume and must be handled according to policy.

### 3.2.6. Reclaim policy for persistent volumes

The reclaim policy of a persistent volume tells the cluster what to do with the volume after it is released. A volume's reclaim policy can be **Retain**, **Recycle**, or **Delete**.

- **Retain** reclaim policy allows manual reclamation of the resource for those volume plugins that support it.
- **Recycle** reclaim policy recycles the volume back into the pool of unbound persistent volumes once it is released from its claim.



### IMPORTANT

The **Recycle** reclaim policy is deprecated in OpenShift Container Platform 4. Dynamic provisioning is recommended for equivalent and better functionality.

- **Delete** reclaim policy deletes both the **PersistentVolume** object from OpenShift Container Platform and the associated storage asset in external infrastructure, such as AWS EBS or VMware vSphere.



### NOTE

Dynamically provisioned volumes are always deleted.

## 3.2.7. Reclaiming a persistent volume manually

When a persistent volume claim (PVC) is deleted, the persistent volume (PV) still exists and is considered "released". However, the PV is not yet available for another claim because the data of the previous claimant remains on the volume.

### Procedure

To manually reclaim the PV as a cluster administrator:

1. Delete the PV.

```
$ oc delete pv <pv-name>
```

The associated storage asset in the external infrastructure, such as an AWS EBS, GCE PD, Azure Disk, or Cinder volume, still exists after the PV is deleted.

2. Clean up the data on the associated storage asset.
3. Delete the associated storage asset. Alternately, to reuse the same storage asset, create a new PV with the storage asset definition.

The reclaimed PV is now available for use by another PVC.

## 3.2.8. Changing the reclaim policy of a persistent volume

To change the reclaim policy of a persistent volume:

1. List the persistent volumes in your cluster:

```
$ oc get pv
```

### Example output

```
NAME                                CAPACITY  ACCESSMODES  RECLAIMPOLICY  STATUS
```

```

CLAIM          STORAGECLASS  REASON  AGE
pvc-b6efd8da-b7b5-11e6-9d58-0ed433a7dd94  4Gi    RWO    Delete    Bound
default/claim1  manual          10s
pvc-b95650f8-b7b5-11e6-9d58-0ed433a7dd94  4Gi    RWO    Delete    Bound
default/claim2  manual          6s
pvc-bb3ca71d-b7b5-11e6-9d58-0ed433a7dd94  4Gi    RWO    Delete    Bound
default/claim3  manual          3s

```

- Choose one of your persistent volumes and change its reclaim policy:

```
$ oc patch pv <your-pv-name> -p '{"spec":{"persistentVolumeReclaimPolicy":"Retain"}}'
```

- Verify that your chosen persistent volume has the right policy:

```
$ oc get pv
```

### Example output

```

NAME          CAPACITY  ACCESSMODES  RECLAIMPOLICY  STATUS
CLAIM          STORAGECLASS  REASON  AGE
pvc-b6efd8da-b7b5-11e6-9d58-0ed433a7dd94  4Gi    RWO    Delete    Bound
default/claim1  manual          10s
pvc-b95650f8-b7b5-11e6-9d58-0ed433a7dd94  4Gi    RWO    Delete    Bound
default/claim2  manual          6s
pvc-bb3ca71d-b7b5-11e6-9d58-0ed433a7dd94  4Gi    RWO    Retain    Bound
default/claim3  manual          3s

```

In the preceding output, the volume bound to claim **default/claim3** now has a **Retain** reclaim policy. The volume will not be automatically deleted when a user deletes claim **default/claim3**.

## 3.3. PERSISTENT VOLUMES

Each PV contains a **spec** and **status**, which is the specification and status of the volume, for example:

### PersistentVolume object definition example

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 1
spec:
  capacity:
    storage: 5Gi 2
  accessModes:
    - ReadWriteOnce 3
  persistentVolumeReclaimPolicy: Retain 4
  ...
status:
  ...

```

- Name of the persistent volume.

- 2 The amount of storage available to the volume.
- 3 The access mode, defining the read-write and mount permissions.
- 4 The reclaim policy, indicating how the resource should be handled once it is released.

### 3.3.1. Types of PVs

OpenShift Container Platform supports the following persistent volume plugins:

- AliCloud Disk
- AWS Elastic Block Store (EBS)
- AWS Elastic File Store (EFS)
- Azure Disk
- Azure File
- Cinder
- Fibre Channel
- GCE Persistent Disk
- IBM VPC Block
- HostPath
- iSCSI
- Local volume
- NFS
- OpenStack Manila
- Red Hat OpenShift Data Foundation
- VMware vSphere

### 3.3.2. Capacity

Generally, a persistent volume (PV) has a specific storage capacity. This is set by using the **capacity** attribute of the PV.

Currently, storage capacity is the only resource that can be set or requested. Future attributes may include IOPS, throughput, and so on.

### 3.3.3. Access modes

A persistent volume can be mounted on a host in any way supported by the resource provider. Providers have different capabilities and each PV's access modes are set to the specific modes supported by that particular volume. For example, NFS can support multiple read-write clients, but a specific NFS PV

might be exported on the server as read-only. Each PV gets its own set of access modes describing that specific PV's capabilities.

Claims are matched to volumes with similar access modes. The only two matching criteria are access modes and size. A claim's access modes represent a request. Therefore, you might be granted more, but never less. For example, if a claim requests RWO, but the only volume available is an NFS PV (RWO+ROX+RWX), the claim would then match NFS because it supports RWO.


Direct matches are always attempted first. The volume's modes must match or contain more modes than you requested. The size must be greater than or equal to what is expected. If two types of volumes, such as NFS and iSCSI, have the same set of access modes, either of them can match a claim with those modes. There is no ordering between types of volumes and no way to choose one type over another.

All volumes with the same modes are grouped, and then sorted by size, smallest to largest. The binder gets the group with matching modes and iterates over each, in size order, until one size matches.

The following table lists the access modes:

**Table 3.1. Access modes**

Access Mode	CLI abbreviation	Description
ReadWriteOnce	<b>RWO</b>	The volume can be mounted as read-write by a single node.
ReadOnlyMany	<b>ROX</b>	The volume can be mounted as read-only by many nodes.
ReadWriteMany	<b>RWX</b>	The volume can be mounted as read-write by many nodes.



### IMPORTANT

Volume access modes are descriptors of volume capabilities. They are not enforced constraints. The storage provider is responsible for runtime errors resulting from invalid use of the resource.

For example, NFS offers **ReadWriteOnce** access mode. You must mark the claims as **read-only** if you want to use the volume's ROX capability. Errors in the provider show up at runtime as mount errors.

iSCSI and Fibre Channel volumes do not currently have any fencing mechanisms. You must ensure the volumes are only used by one node at a time. In certain situations, such as draining a node, the volumes can be used simultaneously by two nodes. Before draining the node, first ensure the pods that use these volumes are deleted.

**Table 3.2. Supported access modes for PVs**

Volume plugin	ReadWriteOnce [1]	ReadOnlyMany	ReadWriteMany
AliCloud Disk	■	-	-
AWS EBS [2]	■	-	-

Volume plugin	ReadWriteOnce [1]	ReadOnlyMany	ReadWriteMany
AWS EFS	■	■	■
Azure File	■	■	■
Azure Disk	■	-	-
Cinder	■	-	-
Fibre Channel	■	■	■ [3]
GCE Persistent Disk	■	-	-
HostPath	■	-	-
IBM VPC Disk	■	-	-
iSCSI	■	■	■ [3]
Local volume	■	-	-
NFS	■	■	■
OpenStack Manila	-	-	■
Red Hat OpenShift Data Foundation	■	-	■
VMware vSphere	■	-	■ [4]

1. ReadWriteOnce (RWO) volumes cannot be mounted on multiple nodes. If a node fails, the system does not allow the attached RWO volume to be mounted on a new node because it is already assigned to the failed node. If you encounter a multi-attach error message as a result, force delete the pod on a shutdown or crashed node to avoid data loss in critical workloads, such as when dynamic persistent volumes are attached.
2. Use a recreate deployment strategy for pods that rely on AWS EBS.

3. Only raw block volumes support the ReadWriteMany (RWX) access mode for Fibre Channel and iSCSI. For more information, see "Block volume support".
4. If the underlying vSphere environment supports the vSAN file service, then the vSphere Container Storage Interface (CSI) Driver Operator installed by OpenShift Container Platform supports provisioning of ReadWriteMany (RWX) volumes. If you do not have vSAN file service configured, and you request RWX, the volume fails to get created and an error is logged. For more information, see "Using Container Storage Interface" → "VMware vSphere CSI Driver Operator".

### 3.3.4. Phase

Volumes can be found in one of the following phases:

**Table 3.3. Volume phases**

Phase	Description
Available	A free resource not yet bound to a claim.
Bound	The volume is bound to a claim.
Released	The claim was deleted, but the resource is not yet reclaimed by the cluster.
Failed	The volume has failed its automatic reclamation.

You can view the name of the PVC bound to the PV by running:

```
$ oc get pv <pv-claim>
```

#### 3.3.4.1. Mount options

You can specify mount options while mounting a PV by using the attribute **mountOptions**.

For example:

#### Mount options example

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  mountOptions: 1
    - nfsvers=4.1
  nfs:
    path: /tmp
```



```

server: 172.17.0.2
persistentVolumeReclaimPolicy: Retain
claimRef:
  name: claim1
  namespace: default

```

- 1 Specified mount options are used while mounting the PV to the disk.

The following PV types support mount options:

- AWS Elastic Block Store (EBS)
- Azure Disk
- Azure File
- Cinder
- GCE Persistent Disk
- iSCSI
- Local volume
- NFS
- Red Hat OpenShift Data Foundation (Ceph RBD only)
- VMware vSphere



#### NOTE

Fibre Channel and HostPath PVs do not support mount options.

#### Additional resources

- [ReadWriteMany vSphere volume support](#)

## 3.4. PERSISTENT VOLUME CLAIMS

Each **PersistentVolumeClaim** object contains a **spec** and **status**, which is the specification and status of the persistent volume claim (PVC), for example:

#### PersistentVolumeClaim object definition example

```

kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: myclaim 1
spec:
  accessModes:
    - ReadWriteOnce 2
resources:
  requests:

```

```

storage: 8Gi 3
storageClassName: gold 4
status:
...
```

- 1** Name of the PVC
- 2** The access mode, defining the read-write and mount permissions
- 3** The amount of storage available to the PVC
- 4** Name of the **StorageClass** required by the claim

### 3.4.1. Storage classes

Claims can optionally request a specific storage class by specifying the storage class's name in the **storageClassName** attribute. Only PVs of the requested class, ones with the same **storageClassName** as the PVC, can be bound to the PVC. The cluster administrator can configure dynamic provisioners to service one or more storage classes. The cluster administrator can create a PV on demand that matches the specifications in the PVC.



#### IMPORTANT

The Cluster Storage Operator might install a default storage class depending on the platform in use. This storage class is owned and controlled by the operator. It cannot be deleted or modified beyond defining annotations and labels. If different behavior is desired, you must define a custom storage class.

The cluster administrator can also set a default storage class for all PVCs. When a default storage class is configured, the PVC must explicitly ask for **StorageClass** or **storageClassName** annotations set to "" to be bound to a PV without a storage class.



#### NOTE

If more than one storage class is marked as default, a PVC can only be created if the **storageClassName** is explicitly specified. Therefore, only one storage class should be set as the default.

### 3.4.2. Access modes

Claims use the same conventions as volumes when requesting storage with specific access modes.

### 3.4.3. Resources

Claims, such as pods, can request specific quantities of a resource. In this case, the request is for storage. The same resource model applies to volumes and claims.

### 3.4.4. Claims as volumes

Pods access storage by using the claim as a volume. Claims must exist in the same namespace as the pod using the claim. The cluster finds the claim in the pod's namespace and uses it to get the **PersistentVolume** backing the claim. The volume is mounted to the host and into the pod, for example:

## Mount volume to the host and into the pod example

```

kind: Pod
apiVersion: v1
metadata:
  name: mypod
spec:
  containers:
  - name: myfrontend
    image: dockerfile/nginx
    volumeMounts:
    - mountPath: "/var/www/html" ❶
      name: mypd ❷
  volumes:
  - name: mypd
    persistentVolumeClaim:
      claimName: myclaim ❸

```

- ❶ Path to mount the volume inside the pod.
- ❷ Name of the volume to mount. Do not mount to the container root, `/`, or any path that is the same in the host and the container. This can corrupt your host system if the container is sufficiently privileged, such as the host `/dev/pts` files. It is safe to mount the host by using `/host`.
- ❸ Name of the PVC, that exists in the same namespace, to use.

## 3.5. BLOCK VOLUME SUPPORT

OpenShift Container Platform can statically provision raw block volumes. These volumes do not have a file system, and can provide performance benefits for applications that either write to the disk directly or implement their own storage service.

Raw block volumes are provisioned by specifying **volumeMode: Block** in the PV and PVC specification.



### IMPORTANT


Pods using raw block volumes must be configured to allow privileged containers.

The following table displays which volume plugins support block volumes.

**Table 3.4. Block volume support**

Volume Plugin	Manually provisioned	Dynamically provisioned	Fully supported
AliCloud Disk	■	■	■
AWS EBS	■	■	■
AWS EFS			

Volume Plugin	Manually provisioned	Dynamically provisioned	Fully supported
Azure Disk	■	■	■
Azure File			
Cinder	■	■	■
Fibre Channel	■		■
GCP	■	■	■
HostPath			
IBM VPC Disk	■	■	■
iSCSI	■		■
Local volume	■		■
NFS			
Red Hat OpenShift Data Foundation	■	■	■
VMware vSphere	■	■	■



## IMPORTANT

Using any of the block volumes that can be provisioned manually, but are not provided as fully supported, is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see [Technology Preview Features Support Scope](#).

### 3.5.1. Block volume examples

#### PV example

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: block-pv
spec:
```

```

capacity:
  storage: 10Gi
accessModes:
  - ReadWriteOnce
volumeMode: Block ❶
persistentVolumeReclaimPolicy: Retain
fc:
  targetWWNs: ["50060e801049cfd1"]
  lun: 0
  readOnly: false

```

- ❶ **volumeMode** must be set to **Block** to indicate that this PV is a raw block volume.

### PVC example

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: block-pvc
spec:
  accessModes:
    - ReadWriteOnce
  volumeMode: Block ❶
  resources:
    requests:
      storage: 10Gi

```

- ❶ **volumeMode** must be set to **Block** to indicate that a raw block PVC is requested.

### Pod specification example

```

apiVersion: v1
kind: Pod
metadata:
  name: pod-with-block-volume
spec:
  containers:
    - name: fc-container
      image: fedora:26
      command: ["/bin/sh", "-c"]
      args: [ "tail -f /dev/null" ]
      volumeDevices: ❶
        - name: data
          devicePath: /dev/xvda ❷
  volumes:
    - name: data
      persistentVolumeClaim:
        claimName: block-pvc ❸

```

- ❶ **volumeDevices**, instead of **volumeMounts**, is used for block devices. Only **PersistentVolumeClaim** sources can be used with raw block volumes.


- 2 **devicePath**, instead of **mountPath**, represents the path to the physical device where the raw block is mapped to the system.
- 3 The volume source must be of type **persistentVolumeClaim** and must match the name of the PVC as expected.

Table 3.5. Accepted values for **volumeMode**

Value	Default
Filesystem	Yes
Block	No

Table 3.6. Binding scenarios for block volumes

PV <b>volumeMode</b>	PVC <b>volumeMode</b>	Binding result
Filesystem	Filesystem	Bind
Unspecified	Unspecified	Bind
Filesystem	Unspecified	Bind
Unspecified	Filesystem	Bind
Block	Block	Bind
Unspecified	Block	No Bind
Block	Unspecified	No Bind
Filesystem	Block	No Bind
Block	Filesystem	No Bind

**IMPORTANT**

Unspecified values result in the default value of **Filesystem**.

### 3.6. USING FSGROUP TO REDUCE POD TIMEOUTS

If a storage volume contains many files (~1,000,000 or greater), you may experience pod timeouts.

This can occur because, by default, OpenShift Container Platform recursively changes ownership and permissions for the contents of each volume to match the **fsGroup** specified in a pod's **securityContext** when that volume is mounted. For large volumes, checking and changing ownership and permissions can

be time consuming, slowing pod startup. You can use the **fsGroupChangePolicy** field inside a **securityContext** to control the way that OpenShift Container Platform checks and manages ownership and permissions for a volume.

**fsGroupChangePolicy** defines behavior for changing ownership and permission of the volume before being exposed inside a pod. This field only applies to volume types that support **fsGroup**-controlled ownership and permissions. This field has two possible values:

- **OnRootMismatch**: Only change permissions and ownership if permission and ownership of root directory does not match with expected permissions of the volume. This can help shorten the time it takes to change ownership and permission of a volume to reduce pod timeouts.
- **Always**: Always change permission and ownership of the volume when a volume is mounted.

### fsGroupChangePolicy example

```
securityContext:
  runAsUser: 1000
  runAsGroup: 3000
  fsGroup: 2000
  fsGroupChangePolicy: "OnRootMismatch" 1
  ...
```

- 1** **OnRootMismatch** specifies skipping recursive permission change, thus helping to avoid pod timeout problems.



#### NOTE

The `fsGroupChangePolicy` field has no effect on ephemeral volume types, such as `secret`, `configMap`, and `emptydir`.

## CHAPTER 4. CONFIGURING PERSISTENT STORAGE

### 4.1. PERSISTENT STORAGE USING AWS ELASTIC BLOCK STORE

OpenShift Container Platform supports AWS Elastic Block Store volumes (EBS). You can provision your OpenShift Container Platform cluster with persistent storage by using [Amazon EC2](#). Some familiarity with Kubernetes and AWS is assumed.

The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. AWS Elastic Block Store volumes can be provisioned dynamically. Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. Persistent volume claims are specific to a project or namespace and can be requested by users. You can define a KMS key to encrypt container-persistent volumes on AWS.



#### IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision AWS EBS storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.



#### IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

For OpenShift Container Platform, automatic migration from AWS EBS in-tree to the Container Storage Interface (CSI) driver is available as a Technology Preview (TP) feature. With migration enabled, volumes provisioned using the existing in-tree driver are automatically migrated to use the AWS EBS CSI driver. For more information, see [CSI automatic migration feature](#).

#### 4.1.1. Creating the EBS storage class

Storage classes are used to differentiate and delineate storage levels and usages. By defining a storage class, users can obtain dynamically provisioned persistent volumes.

#### 4.1.2. Creating the persistent volume claim

##### Prerequisites

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform.

##### Procedure

1. In the OpenShift Container Platform console, click **Storage** → **Persistent Volume Claims**



2. In the persistent volume claims overview, click **Create Persistent Volume Claim**
3. Define the desired options on the page that appears.
  - a. Select the storage class created previously from the drop-down menu.
  - b. Enter a unique name for the storage claim.
  - c. Select the access mode. This determines the read and write access for the created storage claim.
  - d. Define the size of the storage claim.
4. Click **Create** to create the persistent volume claim and generate a persistent volume.

### 4.1.3. Volume format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted AWS volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

### 4.1.4. Maximum number of EBS volumes on a node

By default, OpenShift Container Platform supports a maximum of 39 EBS volumes attached to one node. This limit is consistent with the [AWS volume limits](#). The volume limit depends on the instance type.



#### IMPORTANT

As a cluster administrator, you must use either in-tree or Container Storage Interface (CSI) volumes and their respective storage classes, but never both volume types at the same time. The maximum attached EBS volume number is counted separately for in-tree and CSI volumes.

### 4.1.5. Encrypting container persistent volumes on AWS with a KMS key

Defining a KMS key to encrypt container-persistent volumes on AWS is useful when you have explicit compliance and security guidelines when deploying to AWS.

#### Prerequisites

- Underlying infrastructure must contain storage.
- You must create a customer KMS key on AWS.

#### Procedure

1. Create a storage class:

```
$ cat << EOF | oc create -f -
apiVersion: storage.k8s.io/v1
kind: StorageClass
```

```

metadata:
  name: <storage-class-name> 1
parameters:
  fsType: ext4 2
  encrypted: "true"
  kmsKeyId: keyvalue 3
provisioner: ebs.csi.aws.com
reclaimPolicy: Delete
volumeBindingMode: WaitForFirstConsumer
EOF

```

- 1 Specifies the name of the storage class.
- 2 File system that is created on provisioned volumes.
- 3 Specifies the full Amazon Resource Name (ARN) of the key to use when encrypting the container-persistent volume. If you do not provide any key, but the **encrypted** field is set to **true**, then the default KMS key is used. See [Finding the key ID and key ARN on AWS](#) in the AWS documentation.

2. Create a persistent volume claim (PVC) with the storage class specifying the KMS key:

```

$ cat << EOF | oc create -f -
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: mypvc
spec:
  accessModes:
    - ReadWriteOnce
  volumeMode: Filesystem
  storageClassName: <storage-class-name>
resources:
  requests:
    storage: 1Gi
EOF

```

3. Create workload containers to consume the PVC:

```

$ cat << EOF | oc create -f -
kind: Pod
metadata:
  name: mypod
spec:
  containers:
    - name: httpd
      image: quay.io/centos7/httpd-24-centos7
      ports:
        - containerPort: 80
      volumeMounts:
        - mountPath: /mnt/storage
          name: data
  volumes:
    - name: data

```

```

persistentVolumeClaim:
  claimName: mypvc
EOF

```

#### 4.1.6. Additional resources

- See [AWS Elastic Block Store CSI Driver Operator](#) for information about accessing additional storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

## 4.2. PERSISTENT STORAGE USING AZURE

OpenShift Container Platform supports Microsoft Azure Disk volumes. You can provision your OpenShift Container Platform cluster with persistent storage using Azure. Some familiarity with Kubernetes and Azure is assumed. The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. Azure Disk volumes can be provisioned dynamically. Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. Persistent volume claims are specific to a project or namespace and can be requested by users.



### IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision Azure Disk storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.



### IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

#### Additional resources

- [Microsoft Azure Disk](#)

### 4.2.1. Creating the Azure storage class

Storage classes are used to differentiate and delineate storage levels and usages. By defining a storage class, users can obtain dynamically provisioned persistent volumes.

#### Procedure

1. In the OpenShift Container Platform console, click **Storage** → **Storage Classes**.
2. In the storage class overview, click **Create Storage Class**
3. Define the desired options on the page that appears.

- a. Enter a name to reference the storage class.
- b. Enter an optional description.
- c. Select the reclaim policy.
- d. Select **kubernetes.io/azure-disk** from the drop down list.
  - i. Enter the storage account type. This corresponds to your Azure storage account SKU tier. Valid options are **Premium\_LRS**, **Standard\_LRS**, **StandardSSD\_LRS**, and **UltraSSD\_LRS**.
  - ii. Enter the kind of account. Valid options are **shared**, **dedicated**, and **managed**.



### IMPORTANT

Red Hat only supports the use of **kind: Managed** in the storage class.

With **Shared** and **Dedicated**, Azure creates unmanaged disks, while OpenShift Container Platform creates a managed disk for machine OS (root) disks. But because Azure Disk does not allow the use of both managed and unmanaged disks on a node, unmanaged disks created with **Shared** or **Dedicated** cannot be attached to OpenShift Container Platform nodes.

- e. Enter additional parameters for the storage class as desired.
4. Click **Create** to create the storage class.

### Additional resources

- [Azure Disk Storage Class](#)

## 4.2.2. Creating the persistent volume claim

### Prerequisites

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform.

### Procedure

1. In the OpenShift Container Platform console, click **Storage → Persistent Volume Claims**
2. In the persistent volume claims overview, click **Create Persistent Volume Claim**
3. Define the desired options on the page that appears.
  - a. Select the storage class created previously from the drop-down menu.
  - b. Enter a unique name for the storage claim.
  - c. Select the access mode. This determines the read and write access for the created storage claim.
  - d. Define the size of the storage claim.

4. Click **Create** to create the persistent volume claim and generate a persistent volume.

### 4.2.3. Volume format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted Azure volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

### 4.2.4. Machine sets that deploy machines with ultra disks using PVCs

You can create a machine set running on Azure that deploys machines with ultra disks. Ultra disks are high-performance storage that are intended for use with the most demanding data workloads.

Both the in-tree plugin and CSI driver support using PVCs to enable ultra disks. You can also deploy machines with ultra disks as data disks without creating a PVC.

#### Additional resources

- [Microsoft Azure ultra disks documentation](#)
- [Machine sets that deploy machines on ultra disks using CSI PVCs](#)
- [Machine sets that deploy machines on ultra disks as data disks](#)

#### 4.2.4.1. Creating machines with ultra disks by using machine sets

You can deploy machines with ultra disks on Azure by editing your machine set YAML file.

#### Prerequisites

- Have an existing Microsoft Azure cluster.

#### Procedure

1. Copy an existing Azure **MachineSet** custom resource (CR) and edit it by running the following command:

```
$ oc edit machineset <machine-set-name>
```

where **<machine-set-name>** is the machine set that you want to provision machines with ultra disks.

2. Add the following lines in the positions indicated:

```
apiVersion: machine.openshift.io/v1beta1
kind: MachineSet
...
spec:
...
template:
```

```

...
spec:
  metadata:
    ...
    labels:
      ...
      disk: ultrasssd 1
      ...
  providerSpec:
    value:
      ...
      ultraSSDCapability: Enabled 2
      ...

```

1 Specify a label to use to select a node that is created by this machine set. This procedure uses **disk.ultrasssd** for this value.

2 These lines enable the use of ultra disks.

3. Create a machine set using the updated configuration by running the following command:

```
$ oc create -f <machine-set-name>.yaml
```

4. Create a storage class that contains the following YAML definition:

```

apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: ultra-disk-sc 1
parameters:
  cachingMode: None
  diskIopsReadWrite: "2000" 2
  diskMbpsReadWrite: "320" 3
  kind: managed
  skuName: UltraSSD_LRS
  provisioner: disk.csi.azure.com 4
  reclaimPolicy: Delete
  volumeBindingMode: WaitForFirstConsumer 5

```

1 Specify the name of the storage class. This procedure uses **ultra-disk-sc** for this value.

2 Specify the number of IOPS for the storage class.

3 Specify the throughput in MBps for the storage class.

4 For Azure Kubernetes Service (AKS) version 1.21 or later, use **disk.csi.azure.com**. For earlier versions of AKS, use **kubernetes.io/azure-disk**.

5 Optional: Specify this parameter to wait for the creation of the pod that will use the disk.

5. Create a persistent volume claim (PVC) to reference the **ultra-disk-sc** storage class that contains the following YAML definition:

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: ultra-disk ❶
spec:
  accessModes:
  - ReadWriteOnce
  storageClassName: ultra-disk-sc ❷
resources:
  requests:
    storage: 4Gi ❸

```

- ❶ Specify the name of the PVC. This procedure uses **ultra-disk** for this value.
- ❷ This PVC references the **ultra-disk-sc** storage class.
- ❸ Specify the size for the storage class. The minimum value is **4Gi**.

6. Create a pod that contains the following YAML definition:

```

apiVersion: v1
kind: Pod
metadata:
  name: nginx-ultra
spec:
  nodeSelector:
    disk: ultrasd ❶
  containers:
  - name: nginx-ultra
    image: alpine:latest
    command:
    - "sleep"
    - "infinity"
  volumeMounts:
  - mountPath: "/mnt/azure"
    name: volume
  volumes:
  - name: volume
    persistentVolumeClaim:
      claimName: ultra-disk ❷

```

- ❶ Specify the label of the machine set that enables the use of ultra disks. This procedure uses **disk.ultrasd** for this value.
- ❷ This pod references the **ultra-disk** PVC.

## Verification

1. Validate that the machines are created by running the following command:

```
$ oc get machines
```

The machines should be in the **Running** state.

- For a machine that is running and has a node attached, validate the partition by running the following command:

```
$ oc debug node/<node-name> -- chroot /host lsblk
```

In this command, **oc debug node/<node-name>** starts a debugging shell on the node **<node-name>** and passes a command with **--**. The passed command **chroot /host** provides access to the underlying host OS binaries, and **lsblk** shows the block devices that are attached to the host OS machine.

## Next steps

- To use an ultra disk from within a pod, create workload that uses the mount point. Create a YAML file similar to the following example:

```
apiVersion: v1
kind: Pod
metadata:
  name: ssd-benchmark1
spec:
  containers:
  - name: ssd-benchmark1
    image: nginx
    ports:
    - containerPort: 80
      name: "http-server"
    volumeMounts:
    - name: lun0p1
      mountPath: "/tmp"
  volumes:
  - name: lun0p1
    hostPath:
      path: /var/lib/lun0p1
      type: DirectoryOrCreate
  nodeSelector:
    disktype: ultrasdd
```

### 4.2.4.2. Troubleshooting resources for machine sets that enable ultra disks

Use the information in this section to understand and recover from issues you might encounter.

#### 4.2.4.2.1. Unable to mount a persistent volume claim backed by an ultra disk

If there is an issue mounting a persistent volume claim backed by an ultra disk, the pod becomes stuck in the **ContainerCreating** state and an alert is triggered.

For example, if the **additionalCapabilities.ultraSSDEnabled** parameter is not set on the machine that backs the node that hosts the pod, the following error message appears:

```
StorageAccountType UltraSSD_LRS can be used only when additionalCapabilities.ultraSSDEnabled is set.
```

- To resolve this issue, describe the pod by running the following command:



```
$ oc -n <stuck_pod_namespace> describe pod <stuck_pod_name>
```

## 4.3. PERSISTENT STORAGE USING AZURE FILE

OpenShift Container Platform supports Microsoft Azure File volumes. You can provision your OpenShift Container Platform cluster with persistent storage using Azure. Some familiarity with Kubernetes and Azure is assumed.

The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. You can provision Azure File volumes dynamically.

Persistent volumes are not bound to a single project or namespace, and you can share them across the OpenShift Container Platform cluster. Persistent volume claims are specific to a project or namespace, and can be requested by users for use in applications.



### IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.



### IMPORTANT

Azure File volumes use Server Message Block.



### IMPORTANT

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.

### Additional resources

- [Azure Files](#)

### 4.3.1. Create the Azure File share persistent volume claim

To create the persistent volume claim, you must first define a **Secret** object that contains the Azure account and key. This secret is used in the **PersistentVolume** definition, and will be referenced by the persistent volume claim for use in applications.

### Prerequisites

- An Azure File share exists.
- The credentials to access this share, specifically the storage account and key, are available.

### Procedure

1. Create a **Secret** object that contains the Azure File credentials:

```
$ oc create secret generic <secret-name> --from-literal=azurestorageaccountname=
<storage-account> \ 1
--from-literal=azurestorageaccountkey=<storage-account-key> 2
```

- 1 The Azure File storage account name.
- 2 The Azure File storage account key.

2. Create a **PersistentVolume** object that references the **Secret** object you created:

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
spec:
  capacity:
    storage: "5Gi" 2
  accessModes:
    - "ReadWriteOnce"
  storageClassName: azure-file-sc
  azureFile:
    secretName: <secret-name> 3
    shareName: share-1 4
    readOnly: false
```

- 1 The name of the persistent volume.
- 2 The size of this persistent volume.
- 3 The name of the secret that contains the Azure File share credentials.
- 4 The name of the Azure File share.

3. Create a **PersistentVolumeClaim** object that maps to the persistent volume you created:

```
apiVersion: "v1"
kind: "PersistentVolumeClaim"
metadata:
  name: "claim1" 1
spec:
  accessModes:
    - "ReadWriteOnce"
  resources:
    requests:
      storage: "5Gi" 2
  storageClassName: azure-file-sc 3
  volumeName: "pv0001" 4
```

- 1 The name of the persistent volume claim.

- 2 The size of this persistent volume claim.
- 3 The name of the storage class that is used to provision the persistent volume. Specify the storage class used in the **PersistentVolume** definition.
- 4 The name of the existing **PersistentVolume** object that references the Azure File share.

### 4.3.2. Mount the Azure File share in a pod

After the persistent volume claim has been created, it can be used inside by an application. The following example demonstrates mounting this share inside of a pod.

#### Prerequisites

- A persistent volume claim exists that is mapped to the underlying Azure File share.

#### Procedure

- Create a pod that mounts the existing persistent volume claim:

```

apiVersion: v1
kind: Pod
metadata:
  name: pod-name 1
spec:
  containers:
    ...
    volumeMounts:
      - mountPath: "/data" 2
        name: azure-file-share
  volumes:
    - name: azure-file-share
      persistentVolumeClaim:
        claimName: claim1 3


```

- 1 The name of the pod.
- 2 The path to mount the Azure File share inside the pod. Do not mount to the container root, `/`, or any path that is the same in the host and the container. This can corrupt your host system if the container is sufficiently privileged, such as the host `/dev/pts` files. It is safe to mount the host by using `/host`.
- 3 The name of the **PersistentVolumeClaim** object that has been previously created.

## 4.4. PERSISTENT STORAGE USING CINDER

OpenShift Container Platform supports OpenStack Cinder. Some familiarity with Kubernetes and OpenStack is assumed.

Cinder volumes can be provisioned dynamically. Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. Persistent volume claims are specific to a project or namespace and can be requested by users.



## IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision Cinder storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.

### Additional resources

- For more information about how OpenStack Block Storage provides persistent block storage management for virtual hard drives, see [OpenStack Cinder](#).

## 4.4.1. Manual provisioning with Cinder

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform.

### Prerequisites

- OpenShift Container Platform configured for Red Hat OpenStack Platform (RHOSP)
- Cinder volume ID

### 4.4.1.1. Creating the persistent volume

You must define your persistent volume (PV) in an object definition before creating it in OpenShift Container Platform:


### Procedure

1. Save your object definition to a file.

#### cinder-persistentvolume.yaml

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
spec:
  capacity:
    storage: "5Gi" 2
  accessModes:
    - "ReadWriteOnce"
  cinder: 3
    fsType: "ext3" 4
    volumeID: "f37a03aa-6212-4c62-a805-9ce139fab180" 5
```

- 1 The name of the volume that is used by persistent volume claims or pods.
- 2 The amount of storage allocated to this volume.
- 3 Indicates **cinder** for Red Hat OpenStack Platform (RHOSP) Cinder volumes.
- 4 The file system that is created when the volume is mounted for the first time.
- 5 The Cinder volume to use.



### IMPORTANT

Do not change the **fstype** parameter value after the volume is formatted and provisioned. Changing this value can result in data loss and pod failure.

2. Create the object definition file you saved in the previous step.

```
$ oc create -f cinder-persistentvolume.yaml
```

#### 4.4.1.2. Persistent volume formatting

You can use unformatted Cinder volumes as PVs because OpenShift Container Platform formats them before the first use.

Before OpenShift Container Platform mounts the volume and passes it to a container, the system checks that it contains a file system as specified by the **fsType** parameter in the PV definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

#### 4.4.1.3. Cinder volume security

If you use Cinder PVs in your application, configure security for their deployment configurations.

#### Prerequisites

- An SCC must be created that uses the appropriate **fsGroup** strategy.

#### Procedure

1. Create a service account and add it to the SCC:

```
$ oc create serviceaccount <service_account>
```

```
$ oc adm policy add-scc-to-user <new_scc> -z <service_account> -n <project>
```

2. In your application's deployment configuration, provide the service account name and **securityContext**:

```
apiVersion: v1
kind: ReplicationController
metadata:
  name: frontend-1
```

```

spec:
  replicas: 1 1
  selector: 2
    name: frontend
  template: 3
    metadata:
      labels: 4
        name: frontend 5
    spec:
      containers:
      - image: openshift/hello-openshift
        name: helloworld
        ports:
        - containerPort: 8080
          protocol: TCP
      restartPolicy: Always
      serviceAccountName: <service_account> 6
      securityContext:
        fsGroup: 7777 7

```

- 1** The number of copies of the pod to run.
- 2** The label selector of the pod to run.
- 3** A template for the pod that the controller creates.
- 4** The labels on the pod. They must include labels from the label selector.
- 5** The maximum name length after expanding any parameters is 63 characters.
- 6** Specifies the service account you created.
- 7** Specifies an **fsGroup** for the pods.

## 4.5. PERSISTENT STORAGE USING FIBRE CHANNEL


OpenShift Container Platform supports Fibre Channel, allowing you to provision your OpenShift Container Platform cluster with persistent storage using Fibre channel volumes. Some familiarity with Kubernetes and Fibre Channel is assumed.



### IMPORTANT

Persistent storage using Fibre Channel is not supported on ARM architecture based infrastructures.

The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. Persistent volume claims are specific to a project or namespace and can be requested by users.



## IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

### Additional resources

- [Using Fibre Channel devices](#)

### 4.5.1. Provisioning

To provision Fibre Channel volumes using the **PersistentVolume** API the following must be available:

- The **targetWWNs** (array of Fibre Channel target's World Wide Names).
- A valid LUN number.
- The filesystem type.

A persistent volume and a LUN have a one-to-one mapping between them.

### Prerequisites

- Fibre Channel LUNs must exist in the underlying infrastructure.

### PersistentVolume object definition

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  fc:
    wwids: [scsi-3600508b400105e210000900000490000] 1
    targetWWNs: ['500a0981891b8dc5', '500a0981991b8dc5'] 2
    lun: 2 3
  fsType: ext4
```

- 1** World wide identifiers (WWIDs). Either FC **wwids** or a combination of FC **targetWWNs** and **lun** must be set, but not both simultaneously. The FC WWID identifier is recommended over the WWNs target because it is guaranteed to be unique for every storage device, and independent of the path that is used to access the device. The WWID identifier can be obtained by issuing a SCSI Inquiry to retrieve the Device Identification Vital Product Data (**page 0x83**) or Unit Serial Number (**page 0x80**). FC WWIDs are identified as **/dev/disk/by-id/** to reference the data on the disk, even if the path to the device changes and even when accessing the device from different systems.
- 2** Fibre Channel WWNs are identified as **/dev/disk/by-path/pci-<IDENTIFIER>-fc-0x<WWN>-lun-<LUN#>**, but you do not need to provide any part of the path leading up to the **WWN**, including the **0x**, and anything after, including the **-** (hyphen).
- 3**



## IMPORTANT

Changing the value of the **fstype** parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

### 4.5.1.1. Enforcing disk quotas

Use LUN partitions to enforce disk quotas and size constraints. Each LUN is mapped to a single persistent volume, and unique names must be used for persistent volumes.


Enforcing quotas in this way allows the end user to request persistent storage by a specific amount, such as 10Gi, and be matched with a corresponding volume of equal or greater capacity.

### 4.5.1.2. Fibre Channel volume security

Users request storage with a persistent volume claim. This claim only lives in the user's namespace, and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume across a namespace causes the pod to fail.

Each Fibre Channel LUN must be accessible by all nodes in the cluster.

## 4.6. PERSISTENT STORAGE USING FLEXVOLUME



## IMPORTANT

FlexVolume is a deprecated feature. Deprecated functionality is still included in OpenShift Container Platform and continues to be supported; however, it will be removed in a future release of this product and is not recommended for new deployments.

Out-of-tree Container Storage Interface (CSI) driver is the recommended way to write volume drivers in OpenShift Container Platform. Maintainers of FlexVolume drivers should implement a CSI driver and move users of FlexVolume to CSI. Users of FlexVolume should move their workloads to CSI driver.

For the most recent list of major functionality that has been deprecated or removed within OpenShift Container Platform, refer to the *Deprecated and removed features* section of the OpenShift Container Platform release notes.

OpenShift Container Platform supports FlexVolume, an out-of-tree plugin that uses an executable model to interface with drivers.

To use storage from a back-end that does not have a built-in plugin, you can extend OpenShift Container Platform through FlexVolume drivers and provide persistent storage to applications.

Pods interact with FlexVolume drivers through the **flexvolume** in-tree plugin.

### Additional resources

- [Expanding persistent volumes](#)

### 4.6.1. About FlexVolume drivers



A FlexVolume driver is an executable file that resides in a well-defined directory on all nodes in the cluster. OpenShift Container Platform calls the FlexVolume driver whenever it needs to mount or unmount a volume represented by a **PersistentVolume** object with **flexVolume** as the source.



## IMPORTANT

Attach and detach operations are not supported in OpenShift Container Platform for FlexVolume.

### 4.6.2. FlexVolume driver example

The first command-line argument of the FlexVolume driver is always an operation name. Other parameters are specific to each operation. Most of the operations take a JavaScript Object Notation (JSON) string as a parameter. This parameter is a complete JSON string, and not the name of a file with the JSON data.

The FlexVolume driver contains:

- All **flexVolume.options**.
- Some options from **flexVolume** prefixed by **kubernetes.io/**, such as **fsType** and **readwrite**.
- The content of the referenced secret, if specified, prefixed by **kubernetes.io/secret/**.

#### FlexVolume driver JSON input example

```
{
  "fooServer": "192.168.0.1:1234", 1
  "fooVolumeName": "bar",
  "kubernetes.io/fsType": "ext4", 2
  "kubernetes.io/readwrite": "ro", 3
  "kubernetes.io/secret/<key name>": "<key value>", 4
  "kubernetes.io/secret/<another key name>": "<another key value>",
}
```

- 1 All options from **flexVolume.options**.
- 2 The value of **flexVolume.fsType**.
- 3 **ro/rw** based on **flexVolume.readOnly**.
- 4 All keys and their values from the secret referenced by **flexVolume.secretRef**.

OpenShift Container Platform expects JSON data on standard output of the driver. When not specified, the output describes the result of the operation.

#### FlexVolume driver default output example

```
{
  "status": "<Success/Failure/Not supported>",
  "message": "<Reason for success/failure>"
}
```

Exit code of the driver should be **0** for success and **1** for error.

Operations should be idempotent, which means that the mounting of an already mounted volume should result in a successful operation.

### 4.6.3. Installing FlexVolume drivers

FlexVolume drivers that are used to extend OpenShift Container Platform are executed only on the node. To implement FlexVolumes, a list of operations to call and the installation path are all that is required.

#### Prerequisites

- FlexVolume drivers must implement these operations:

##### **init**

Initializes the driver. It is called during initialization of all nodes.

- Arguments: none
- Executed on: node
- Expected output: default JSON

##### **mount**

Mounts a volume to directory. This can include anything that is necessary to mount the volume, including finding the device and then mounting the device.

- Arguments: **<mount-dir> <json>**
- Executed on: node
- Expected output: default JSON

##### **unmount**

Unmounts a volume from a directory. This can include anything that is necessary to clean up the volume after unmounting.

- Arguments: **<mount-dir>**
- Executed on: node
- Expected output: default JSON

##### **mountdevice**

Mounts a volume's device to a directory where individual pods can then bind mount.

This call-out does not pass "secrets" specified in the FlexVolume spec. If your driver requires secrets, do not implement this call-out.

- Arguments: **<mount-dir> <json>**
- Executed on: node
- Expected output: default JSON

##### **unmountdevice**

Unmounts a volume's device from a directory.

- Arguments: **<mount-dir>**
- Executed on: node
- Expected output: default JSON
  - All other operations should return JSON with **{"status": "Not supported"}** and exit code **1**.

## Procedure

To install the FlexVolume driver:

1. Ensure that the executable file exists on all nodes in the cluster.
2. Place the executable file at the volume plugin path: **/etc/kubernetes/kubelet-plugins/volume/exec/<vendor>~<driver>/<driver>**.

For example, to install the FlexVolume driver for the storage **foo**, place the executable file at: **/etc/kubernetes/kubelet-plugins/volume/exec/openshift.com~foo/foo**.

### 4.6.4. Consuming storage using FlexVolume drivers

Each **PersistentVolume** object in OpenShift Container Platform represents one storage asset in the storage back-end, such as a volume.

## Procedure

- Use the **PersistentVolume** object to reference the installed storage.

### Persistent volume object definition using FlexVolume drivers example

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 1
spec:
  capacity:
    storage: 1Gi 2
  accessModes:
    - ReadWriteOnce
  flexVolume:
    driver: openshift.com/foo 3
    fsType: "ext4" 4
    secretRef: foo-secret 5
    readOnly: true 6
    options: 7
      fooServer: 192.168.0.1:1234
      fooVolumeName: bar

```

- 1 The name of the volume. This is how it is identified through persistent volume claims or from pods. This name can be different from the name of the volume on back-end storage.
- 2 The amount of storage allocated to this volume.

- 3 The name of the driver. This field is mandatory.
- 4 The file system that is present on the volume. This field is optional.
- 5 The reference to a secret. Keys and values from this secret are provided to the FlexVolume driver on invocation. This field is optional.
- 6 The read-only flag. This field is optional.
- 7 The additional options for the FlexVolume driver. In addition to the flags specified by the user in the **options** field, the following flags are also passed to the executable:

```
"fsType": "<FS type>",
"readwrite": "<rw>",
"secret/key1": "<secret1>"
...
"secret/keyN": "<secretN>"
```



#### NOTE

Secrets are passed only to mount or unmount call-outs.

## 4.7. PERSISTENT STORAGE USING GCE PERSISTENT DISK

OpenShift Container Platform supports GCE Persistent Disk volumes (gcePD). You can provision your OpenShift Container Platform cluster with persistent storage using GCE. Some familiarity with Kubernetes and GCE is assumed.

The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.

GCE Persistent Disk volumes can be provisioned dynamically.

Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. Persistent volume claims are specific to a project or namespace and can be requested by users.



#### IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision gcePD storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.



## IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

### Additional resources

- [GCE Persistent Disk](#)

## 4.7.1. Creating the GCE storage class

Storage classes are used to differentiate and delineate storage levels and usages. By defining a storage class, users can obtain dynamically provisioned persistent volumes.

## 4.7.2. Creating the persistent volume claim

### Prerequisites

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform.

### Procedure

1. In the OpenShift Container Platform console, click **Storage → Persistent Volume Claims**
2. In the persistent volume claims overview, click **Create Persistent Volume Claim**
3. Define the desired options on the page that appears.
  - a. Select the storage class created previously from the drop-down menu.
  - b. Enter a unique name for the storage claim.
  - c. Select the access mode. This determines the read and write access for the created storage claim.
  - d. Define the size of the storage claim.
4. Click **Create** to create the persistent volume claim and generate a persistent volume.


## 4.7.3. Volume format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted GCE volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

## 4.8. PERSISTENT STORAGE USING HOSTPATH

A hostPath volume in an OpenShift Container Platform cluster mounts a file or directory from the host node's filesystem into your pod. Most pods will not need a hostPath volume, but it does offer a quick option for testing should an application require it.



## IMPORTANT


The cluster administrator must configure pods to run as privileged. This grants access to pods in the same node.

### 4.8.1. Overview

OpenShift Container Platform supports `hostPath` mounting for development and testing on a single-node cluster.

In a production cluster, you would not use `hostPath`. Instead, a cluster administrator would provision a network resource, such as a GCE Persistent Disk volume, an NFS share, or an Amazon EBS volume. Network resources support the use of storage classes to set up dynamic provisioning.

A `hostPath` volume must be provisioned statically.



## IMPORTANT

Do not mount to the container root, `/`, or any path that is the same in the host and the container. This can corrupt your host system if the container is sufficiently privileged. It is safe to mount the host by using `/host`. The following example shows the `/` directory from the host being mounted into the container at `/host`.

```

apiVersion: v1
kind: Pod
metadata:
  name: test-host-mount
spec:
  containers:
  - image: registry.access.redhat.com/ubi8/ubi
    name: test-container
    command: ['sh', '-c', 'sleep 3600']
    volumeMounts:
    - mountPath: /host
      name: host-slash
  volumes:
  - name: host-slash
    hostPath:
      path: /
      type: "

```

### 4.8.2. Statically provisioning `hostPath` volumes

A pod that uses a `hostPath` volume must be referenced by manual (static) provisioning.

#### Procedure

1. Define the persistent volume (PV). Create a file, `pv.yaml`, with the **PersistentVolume** object definition:

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: task-pv-volume 1

```

```

labels:
  type: local
spec:
  storageClassName: manual 2
  capacity:
    storage: 5Gi
  accessModes:
    - ReadWriteOnce 3
  persistentVolumeReclaimPolicy: Retain
  hostPath:
    path: "/mnt/data" 4

```

- 1** The name of the volume. This name is how it is identified by persistent volume claims or pods.
- 2** Used to bind persistent volume claim requests to this persistent volume.
- 3** The volume can be mounted as **read-write** by a single node.
- 4** The configuration file specifies that the volume is at **/mnt/data** on the cluster's node. Do not mount to the container root, **/**, or any path that is the same in the host and the container. This can corrupt your host system. It is safe to mount the host by using **/host**.

2. Create the PV from the file:

```
$ oc create -f pv.yaml
```

3. Define the persistent volume claim (PVC). Create a file, **pvc.yaml**, with the **PersistentVolumeClaim** object definition:

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: task-pvc-volume
spec:
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 1Gi
  storageClassName: manual

```

4. Create the PVC from the file:

```
$ oc create -f pvc.yaml
```

### 4.8.3. Mounting the hostPath share in a privileged pod

After the persistent volume claim has been created, it can be used inside by an application. The following example demonstrates mounting this share inside of a pod.

#### Prerequisites

- A persistent volume claim exists that is mapped to the underlying hostPath share.

## Procedure

- Create a privileged pod that mounts the existing persistent volume claim:

```

apiVersion: v1
kind: Pod
metadata:
  name: pod-name ❶
spec:
  containers:
    ...
    securityContext:
      privileged: true ❷
    volumeMounts:
      - mountPath: /data ❸
        name: hostpath-privileged
    ...
  securityContext: {}
  volumes:
    - name: hostpath-privileged
      persistentVolumeClaim:
        claimName: task-pvc-volume ❹

```

- ❶ The name of the pod.
- ❷ The pod must run as privileged to access the node's storage.
- ❸ The path to mount the host path share inside the privileged pod. Do not mount to the container root, `/`, or any path that is the same in the host and the container. This can corrupt your host system if the container is sufficiently privileged, such as the host `/dev/pts` files. It is safe to mount the host by using `/host`.
- ❹ The name of the **PersistentVolumeClaim** object that has been previously created.

## 4.9. PERSISTENT STORAGE USING ISCSI

You can provision your OpenShift Container Platform cluster with persistent storage using [iSCSI](#). Some familiarity with Kubernetes and iSCSI is assumed.

The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.



### IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.



**IMPORTANT**

When you use iSCSI on Amazon Web Services, you must update the default security policy to include TCP traffic between nodes on the iSCSI ports. By default, they are ports **860** and **3260**.

**IMPORTANT**

Users must ensure that the iSCSI initiator is already configured on all OpenShift Container Platform nodes by installing the **iscsi-initiator-utils** package and configuring their initiator name in **/etc/iscsi/initiatorname.iscsi**. The **iscsi-initiator-utils** package is already installed on deployments that use Red Hat Enterprise Linux CoreOS (RHCOS).

For more information, see [Managing Storage Devices](#).

### 4.9.1. Provisioning

Verify that the storage exists in the underlying infrastructure before mounting it as a volume in OpenShift Container Platform. All that is required for the iSCSI is the iSCSI target portal, a valid iSCSI Qualified Name (IQN), a valid LUN number, the filesystem type, and the **PersistentVolume** API.

#### PersistentVolume object definition

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi-pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.16.154.81:3260
    iqn: iqn.2014-12.example.server:storage.target00
    lun: 0
    fsType: 'ext4'
```

### 4.9.2. Enforcing disk quotas

Use LUN partitions to enforce disk quotas and size constraints. Each LUN is one persistent volume. Kubernetes enforces unique names for persistent volumes.

Enforcing quotas in this way allows the end user to request persistent storage by a specific amount (for example, **10Gi**) and be matched with a corresponding volume of equal or greater capacity.

### 4.9.3. iSCSI volume security

Users request storage with a **PersistentVolumeClaim** object. This claim only lives in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume claim across a namespace causes the pod to fail.

Each iSCSI LUN must be accessible by all nodes in the cluster.

### 4.9.3.1. Challenge Handshake Authentication Protocol (CHAP) configuration

Optionally, OpenShift Container Platform can use CHAP to authenticate itself to iSCSI targets:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi-pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.0.0.1:3260
    iqn: iqn.2016-04.test.com:storage.target00
    lun: 0
    fsType: ext4
    chapAuthDiscovery: true 1
    chapAuthSession: true 2
    secretRef:
      name: chap-secret 3
```

- 1 Enable CHAP authentication of iSCSI discovery.
- 2 Enable CHAP authentication of iSCSI session.
- 3 Specify name of Secrets object with user name + password. This **Secret** object must be available in all namespaces that can use the referenced volume.

### 4.9.4. iSCSI multipathing

For iSCSI-based storage, you can configure multiple paths by using the same IQN for more than one target portal IP address. Multipathing ensures access to the persistent volume when one or more of the components in a path fail.

To specify multi-paths in the pod specification, use the **portals** field. For example:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi-pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.0.0.1:3260
    portals: ['10.0.2.16:3260', '10.0.2.17:3260', '10.0.2.18:3260'] 1
    iqn: iqn.2016-04.test.com:storage.target00
    lun: 0
    fsType: ext4
    readOnly: false
```

- 1 Add additional target portals using the **portals** field.

### 4.9.5. iSCSI custom initiator IQN

Configure the custom initiator iSCSI Qualified Name (IQN) if the iSCSI targets are restricted to certain IQNs, but the nodes that the iSCSI PVs are attached to are not guaranteed to have these IQNs.

To specify a custom initiator IQN, use **initiatorName** field.

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi-pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.0.0.1:3260
    portals: ['10.0.2.16:3260', '10.0.2.17:3260', '10.0.2.18:3260']
    iqn: iqn.2016-04.test.com:storage.target00
    lun: 0
    initiatorName: iqn.2016-04.test.com:custom.iqn 1
    fsType: ext4
    readOnly: false
```

- 1 Specify the name of the initiator.

## 4.10. PERSISTENT STORAGE USING LOCAL VOLUMES

OpenShift Container Platform can be provisioned with persistent storage by using local volumes. Local persistent volumes allow you to access local storage devices, such as a disk or partition, by using the standard persistent volume claim interface.

Local volumes can be used without manually scheduling pods to nodes because the system is aware of the volume node constraints. However, local volumes are still subject to the availability of the underlying node and are not suitable for all applications.



### NOTE

Local volumes can only be used as a statically created persistent volume.

### 4.10.1. Installing the Local Storage Operator

The Local Storage Operator is not installed in OpenShift Container Platform by default. Use the following procedure to install and configure this Operator to enable local volumes in your cluster.

#### Prerequisites

- Access to the OpenShift Container Platform web console or command-line interface (CLI).

## Procedure

1. Create the **openshift-local-storage** project:

```
$ oc adm new-project openshift-local-storage
```

2. Optional: Allow local storage creation on infrastructure nodes.

You might want to use the Local Storage Operator to create volumes on infrastructure nodes in support of components such as logging and monitoring.

You must adjust the default node selector so that the Local Storage Operator includes the infrastructure nodes, and not just worker nodes.

To block the Local Storage Operator from inheriting the cluster-wide default selector, enter the following command:

```
$ oc annotate namespace openshift-local-storage openshift.io/node-selector=""
```

3. Optional: Allow local storage to run on the management pool of CPUs in single-node deployment.

Use the Local Storage Operator in single-node deployments and allow the use of CPUs that belong to the **management** pool. Perform this step on single-node installations that use management workload partitioning.

To allow Local Storage Operator to run on the management CPU pool, run following commands:

```
$ oc annotate namespace openshift-local-storage  
workload.openshift.io/allowed='management'
```

## From the UI

To install the Local Storage Operator from the web console, follow these steps:

1. Log in to the OpenShift Container Platform web console.
2. Navigate to **Operators** → **OperatorHub**.
3. Type **Local Storage** into the filter box to locate the Local Storage Operator.
4. Click **Install**.
5. On the **Install Operator** page, select **A specific namespace on the cluster**. Select **openshift-local-storage** from the drop-down menu.
6. Adjust the values for **Update Channel** and **Approval Strategy** to the values that you want.
7. Click **Install**.

Once finished, the Local Storage Operator will be listed in the **Installed Operators** section of the web console.

## From the CLI

1. Install the Local Storage Operator from the CLI.

o Create an object YAML file to define an Operator group and subscription for the Local

- a. Create an object YAML file to define an Operator group and subscription for the Local Storage Operator, such as **openshift-local-storage.yaml**:

### Example openshift-local-storage.yaml

```
apiVersion: operators.coreos.com/v1
kind: OperatorGroup
metadata:
  name: local-operator-group
  namespace: openshift-local-storage
spec:
  targetNamespaces:
    - openshift-local-storage
---
apiVersion: operators.coreos.com/v1alpha1
kind: Subscription
metadata:
  name: local-storage-operator
  namespace: openshift-local-storage
spec:
  channel: stable
  installPlanApproval: Automatic ❶
  name: local-storage-operator
  source: redhat-operators
  sourceNamespace: openshift-marketplace
```

- ❶ The user approval policy for an install plan.

2. Create the Local Storage Operator object by entering the following command:

```
$ oc apply -f openshift-local-storage.yaml
```

At this point, the Operator Lifecycle Manager (OLM) is now aware of the Local Storage Operator. A ClusterServiceVersion (CSV) for the Operator should appear in the target namespace, and APIs provided by the Operator should be available for creation.

3. Verify local storage installation by checking that all pods and the Local Storage Operator have been created:
  - a. Check that all the required pods have been created:

```
$ oc -n openshift-local-storage get pods
```

### Example output

```
NAME                                READY STATUS RESTARTS AGE
local-storage-operator-746bf599c9-vlt5t 1/1   Running 0    19m
```

- b. Check the ClusterServiceVersion (CSV) YAML manifest to see that the Local Storage Operator is available in the **openshift-local-storage** project:

```
$ oc get csvs -n openshift-local-storage
```

## Example output

NAME	DISPLAY	VERSION	REPLACES	PHASE
local-storage-operator.4.2.26-202003230335	Local Storage	4.2.26-202003230335		Succeeded

After all checks have passed, the Local Storage Operator is installed successfully.

## 4.10.2. Provisioning local volumes by using the Local Storage Operator


Local volumes cannot be created by dynamic provisioning. Instead, persistent volumes can be created by the Local Storage Operator. The local volume provisioner looks for any file system or block volume devices at the paths specified in the defined resource.

### Prerequisites

- The Local Storage Operator is installed.
- You have a local disk that meets the following conditions:
  - It is attached to a node.
  - It is not mounted.
  - It does not contain partitions.

### Procedure

1. Create the local volume resource. This resource must define the nodes and paths to the local volumes.



#### NOTE

Do not use different storage class names for the same device. Doing so will create multiple persistent volumes (PVs).

### Example: Filesystem

```

apiVersion: "local.storage.openshift.io/v1"
kind: "LocalVolume"
metadata:
  name: "local-disks"
  namespace: "openshift-local-storage" 1
spec:
  nodeSelector: 2
  nodeSelectorTerms:
  - matchExpressions:
    - key: kubernetes.io/hostname
      operator: In
      values:
      - ip-10-0-140-183
      - ip-10-0-158-139
      - ip-10-0-164-33
  storageClassDevices:

```

```

- storageClassName: "local-sc" 3
  volumeMode: Filesystem 4
  fsType: xfs 5
  devicePaths: 6
    - /path/to/device 7

```

- 1 The namespace where the Local Storage Operator is installed.
- 2 Optional: A node selector containing a list of nodes where the local storage volumes are attached. This example uses the node hostnames, obtained from **oc get node**. If a value is not defined, then the Local Storage Operator will attempt to find matching disks on all available nodes.
- 3 The name of the storage class to use when creating persistent volume objects. The Local Storage Operator automatically creates the storage class if it does not exist. Be sure to use a storage class that uniquely identifies this set of local volumes.
- 4 The volume mode, either **Filesystem** or **Block**, that defines the type of local volumes.



#### NOTE

A raw block volume (**volumeMode: Block**) is not formatted with a file system. Use this mode only if any application running on the pod can use raw block devices.

- 5 The file system that is created when the local volume is mounted for the first time.
- 6 The path containing a list of local storage devices to choose from.
- 7 Replace this value with your actual local disks filepath to the **LocalVolume** resource **by-id**, such as **/dev/disk/by-id/wwn**. PVs are created for these local disks when the provisioner is deployed successfully.



#### NOTE

If you are running OpenShift Container Platform on IBM Z with RHEL KVM, you must assign a serial number to your VM disk. Otherwise, the VM disk can not be identified after reboot. You can use the **virsh edit <VM>** command to add the **<serial>mydisk</serial>** definition.

### Example: Block

```

apiVersion: "local.storage.openshift.io/v1"
kind: "LocalVolume"
metadata:
  name: "local-disks"
  namespace: "openshift-local-storage" 1
spec:
  nodeSelector: 2
  nodeSelectorTerms:
    - matchExpressions:
      - key: kubernetes.io/hostname

```

```

operator: In
values:
- ip-10-0-136-143
- ip-10-0-140-255
- ip-10-0-144-180
storageClassDevices:
- storageClassName: "localblock-sc" 3
  volumeMode: Block 4
  devicePaths: 5
  - /path/to/device 6

```

- 1 The namespace where the Local Storage Operator is installed.
- 2 Optional: A node selector containing a list of nodes where the local storage volumes are attached. This example uses the node hostnames, obtained from **oc get node**. If a value is not defined, then the Local Storage Operator will attempt to find matching disks on all available nodes.
- 3 The name of the storage class to use when creating persistent volume objects.
- 4 The volume mode, either **Filesystem** or **Block**, that defines the type of local volumes.
- 5 The path containing a list of local storage devices to choose from.
- 6 Replace this value with your actual local disks filepath to the **LocalVolume** resource **by-id**, such as **dev/disk/by-id/wwn**. PVs are created for these local disks when the provisioner is deployed successfully.



## NOTE

If you are running OpenShift Container Platform on IBM Z with RHEL KVM, you must assign a serial number to your VM disk. Otherwise, the VM disk can not be identified after reboot. You can use the **virsh edit <VM>** command to add the **<serial>mydisk</serial>** definition.

2. Create the local volume resource in your OpenShift Container Platform cluster. Specify the file you just created:

```
$ oc create -f <local-volume>.yaml
```

3. Verify that the provisioner was created and that the corresponding daemon sets were created:

```
$ oc get all -n openshift-local-storage
```

## Example output

```

NAME                                READY STATUS RESTARTS AGE
pod/diskmaker-manager-9wzms         1/1   Running 0      5m43s
pod/diskmaker-manager-jgvjp         1/1   Running 0      5m43s
pod/diskmaker-manager-tbdsj         1/1   Running 0      5m43s
pod/local-storage-operator-7db4bd9f79-t6k87 1/1   Running 0      14m

```

NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)
------	------	------------	-------------	---------



```

AGE
service/local-storage-operator-metrics ClusterIP 172.30.135.36 <none>
8383/TCP,8686/TCP 14m

NAME                DESIRED  CURRENT  READY  UP-TO-DATE  AVAILABLE
NODE SELECTOR  AGE
daemonset.apps/diskmaker-manager 3    3    3    3    3    <none>
5m43s

NAME                READY  UP-TO-DATE  AVAILABLE  AGE
deployment.apps/local-storage-operator 1/1    1    1    14m

NAME                DESIRED  CURRENT  READY  AGE
replicaset.apps/local-storage-operator-7db4bd9f79 1    1    1    14m

```

Note the desired and current number of daemon set processes. A desired count of **0** indicates that the label selectors were invalid.

- Verify that the persistent volumes were created:


```
$ oc get pv
```

#### Example output

```

NAME                CAPACITY  ACCESS MODES  RECLAIM POLICY  STATUS  CLAIM
STORAGECLASS  REASON  AGE
local-pv-1cec77cf  100Gi    RWO           Delete          Available  local-sc  88m
local-pv-2ef7cd2a  100Gi    RWO           Delete          Available  local-sc  82m
local-pv-3fa1c73   100Gi    RWO           Delete          Available  local-sc  48m

```




#### IMPORTANT

Editing the **LocalVolume** object does not change the **fsType** or **volumeMode** of existing persistent volumes because doing so might result in a destructive operation.

### 4.10.3. Provisioning local volumes without the Local Storage Operator

Local volumes cannot be created by dynamic provisioning. Instead, persistent volumes can be created by defining the persistent volume (PV) in an object definition. The local volume provisioner looks for any file system or block volume devices at the paths specified in the defined resource.



#### IMPORTANT

Manual provisioning of PVs includes the risk of potential data leaks across PV reuse when PVCs are deleted. The Local Storage Operator is recommended for automating the life cycle of devices when provisioning local PVs.

#### Prerequisites

- Local disks are attached to the OpenShift Container Platform nodes.

#### Procedure

1. Define the PV. Create a file, such as **example-pv-filesystem.yaml** or **example-pv-block.yaml**, with the **PersistentVolume** object definition. This resource must define the nodes and paths to the local volumes.

**NOTE**

Do not use different storage class names for the same device. Doing so will create multiple PVs.


**example-pv-filesystem.yaml**

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: example-pv-filesystem
spec:
  capacity:
    storage: 100Gi
  volumeMode: Filesystem 1
  accessModes:
  - ReadWriteOnce
  persistentVolumeReclaimPolicy: Delete
  storageClassName: local-storage 2
  local:
    path: /dev/xvdf 3
  nodeAffinity:
    required:
      nodeSelectorTerms:
      - matchExpressions:
        - key: kubernetes.io/hostname
          operator: In
          values:
            - example-node

```

- 1** The volume mode, either **Filesystem** or **Block**, that defines the type of PVs.
- 2** The name of the storage class to use when creating PV resources. Use a storage class that uniquely identifies this set of PVs.
- 3** The path containing a list of local storage devices to choose from, or a directory. You can only specify a directory with **Filesystem volumeMode**.

**NOTE**

A raw block volume (**volumeMode: block**) is not formatted with a file system. Use this mode only if any application running on the pod can use raw block devices.

**example-pv-block.yaml**

```

apiVersion: v1
kind: PersistentVolume

```

```

metadata:
  name: example-pv-block
spec:
  capacity:
    storage: 100Gi
  volumeMode: Block 1
  accessModes:
  - ReadWriteOnce
  persistentVolumeReclaimPolicy: Delete
  storageClassName: local-storage 2
  local:
    path: /dev/xvdf 3
  nodeAffinity:
    required:
      nodeSelectorTerms:
      - matchExpressions:
        - key: kubernetes.io/hostname
          operator: In
          values:
            - example-node

```

- 1** The volume mode, either **Filesystem** or **Block**, that defines the type of PVs.
- 2** The name of the storage class to use when creating PV resources. Be sure to use a storage class that uniquely identifies this set of PVs.
- 3** The path containing a list of local storage devices to choose from.

2. Create the PV resource in your OpenShift Container Platform cluster. Specify the file you just created:

```
$ oc create -f <example-pv>.yaml
```

3. Verify that the local PV was created:

```
$ oc get pv
```

#### Example output

NAME	CAPACITY	ACCESS MODES	RECLAIM POLICY	STATUS	CLAIM
STORAGECLASS	REASON	AGE			
example-pv-filesystem	100Gi	RWO	Delete	Available	local-storage
example-pv1	1Gi	RWO	Delete	Bound	local-storage/pvc1
example-pv2	1Gi	RWO	Delete	Bound	local-storage/pvc2
example-pv3	1Gi	RWO	Delete	Bound	local-storage/pvc3

#### 4.10.4. Creating the local volume persistent volume claim

Local volumes must be statically created as a persistent volume claim (PVC) to be accessed by the pod.

## Prerequisites

- Persistent volumes have been created using the local volume provisioner.

## Procedure

1. Create the PVC using the corresponding storage class:

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: local-pvc-name ❶
spec:
  accessModes:
  - ReadWriteOnce
  volumeMode: Filesystem ❷
resources:
  requests:
    storage: 100Gi ❸
storageClassName: local-sc ❹
```

- ❶ Name of the PVC.
- ❷ The type of the PVC. Defaults to **Filesystem**.
- ❸ The amount of storage available to the PVC.
- ❹ Name of the storage class required by the claim.

2. Create the PVC in the OpenShift Container Platform cluster, specifying the file you just created:

```
$ oc create -f <local-pvc>.yaml
```

### 4.10.5. Attach the local claim

After a local volume has been mapped to a persistent volume claim it can be specified inside of a resource.

## Prerequisites

- A persistent volume claim exists in the same namespace.

## Procedure

1. Include the defined claim in the resource spec. The following example declares the persistent volume claim inside a pod:

```
apiVersion: v1
kind: Pod
spec:
  # ...
  containers:
```

```

volumeMounts:
- name: local-disks 1
  mountPath: /data 2
volumes:
- name: local-disks
  persistentVolumeClaim:
    claimName: local-pvc-name 3
# ...

```

- 1** The name of the volume to mount.
- 2** The path inside the pod where the volume is mounted. Do not mount to the container root, `/`, or any path that is the same in the host and the container. This can corrupt your host system if the container is sufficiently privileged, such as the host `/dev/pts` files. It is safe to mount the host by using `/host`.
- 3** The name of the existing persistent volume claim to use.

2. Create the resource in the OpenShift Container Platform cluster, specifying the file you just created:

```
$ oc create -f <local-pod>.yaml
```

#### 4.10.6. Automating discovery and provisioning for local storage devices

The Local Storage Operator automates local storage discovery and provisioning. With this feature, you can simplify installation when dynamic provisioning is not available during deployment, such as with bare metal, VMware, or AWS store instances with attached devices.



##### IMPORTANT

Automatic discovery and provisioning is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see [Technology Preview Features Support Scope](#).



##### IMPORTANT

Automatic discovery and provisioning is fully supported when used to deploy Red Hat OpenShift Data Foundation on-premise or with platform-agnostic deployment.

Use the following procedure to automatically discover local devices, and to automatically provision local volumes for selected devices.

**WARNING**

Use the **LocalVolumeSet** object with caution. When you automatically provision persistent volumes (PVs) from local disks, the local PVs might claim all devices that match. If you are using a **LocalVolumeSet** object, make sure the Local Storage Operator is the only entity managing local devices on the node. Creating multiple instances of a **LocalVolumeSet** that target a node more than once is not supported.

**Prerequisites**

- You have cluster administrator permissions.
- You have installed the Local Storage Operator.
- You have attached local disks to OpenShift Container Platform nodes.
- You have access to the OpenShift Container Platform web console and the **oc** command-line interface (CLI).

**Procedure**

1. To enable automatic discovery of local devices from the web console:
  - a. In the *Administrator* perspective, navigate to **Operators → Installed Operators** and click on the **Local Volume Discovery** tab.
  - b. Click **Create Local Volume Discovery**.
  - c. Select either **All nodes** or **Select nodes**, depending on whether you want to discover available disks on all or specific nodes.

**NOTE**

Only worker nodes are available, regardless of whether you filter using **All nodes** or **Select nodes**.

- d. Click **Create**.

A local volume discovery instance named **auto-discover-devices** is displayed.

1. To display a continuous list of available devices on a node:
  - a. Log in to the OpenShift Container Platform web console.
  - b. Navigate to **Compute → Nodes**.
  - c. Click the node name that you want to open. The "Node Details" page is displayed.
  - d. Select the **Disks** tab to display the list of the selected devices. The device list updates continuously as local disks are added or removed. You can filter the devices by name, status, type, model, capacity, and mode.

2. To automatically provision local volumes for the discovered devices from the web console:
  - a. Navigate to **Operators** → **Installed Operators** and select **Local Storage** from the list of Operators.
  - b. Select **Local Volume Set** → **Create Local Volume Set**
  - c. Enter a volume set name and a storage class name.
  - d. Choose **All nodes** or **Select nodes** to apply filters accordingly.

**NOTE**

Only worker nodes are available, regardless of whether you filter using **All nodes** or **Select nodes**.

- e. Select the disk type, mode, size, and limit you want to apply to the local volume set, and click **Create**.  
A message displays after several minutes, indicating that the "Operator reconciled successfully."
3. Alternatively, to provision local volumes for the discovered devices from the CLI:
    - a. Create an object YAML file to define the local volume set, such as **local-volume-set.yaml**, as shown in the following example:

```

apiVersion: local.storage.openshift.io/v1alpha1
kind: LocalVolumeSet
metadata:
  name: example-autodetect
spec:
  nodeSelector:
    nodeSelectorTerms:
      - matchExpressions:
          - key: kubernetes.io/hostname
            operator: In
            values:
              - worker-0
              - worker-1
  storageClassName: example-storageclass ❶
  volumeMode: Filesystem
  fsType: ext4
  maxDeviceCount: 10
  deviceInclusionSpec:
    deviceTypes: ❷
      - disk
      - part
    deviceMechanicalProperties:
      - NonRotational
  minSize: 10G
  maxSize: 100G
  models:
    - SAMSUNG
    - Crucial_CT525MX3

```

vendors:

- ATA
- ST2000LM

- 1 Determines the storage class that is created for persistent volumes that are provisioned from discovered devices. The Local Storage Operator automatically creates the storage class if it does not exist. Be sure to use a storage class that uniquely identifies this set of local volumes.
- 2 When using the local volume set feature, the Local Storage Operator does not support the use of logical volume management (LVM) devices.

b. Create the local volume set object:

```
$ oc apply -f local-volume-set.yaml
```

c. Verify that the local persistent volumes were dynamically provisioned based on the storage class:

```
$ oc get pv
```

### Example output

NAME	CAPACITY	ACCESS MODES	RECLAIM POLICY	STATUS
CLAIM STORAGECLASS		REASON AGE		
local-pv-1cec77cf	100Gi	RWO	Delete	Available
storageclass	88m			example-
local-pv-2ef7cd2a	100Gi	RWO	Delete	Available
storageclass	82m			example-
local-pv-3fa1c73	100Gi	RWO	Delete	Available
storageclass	48m			example-



### NOTE

Results are deleted after they are removed from the node. Symlinks must be manually removed.

## 4.10.7. Using tolerations with Local Storage Operator pods

Taints can be applied to nodes to prevent them from running general workloads. To allow the Local Storage Operator to use tainted nodes, you must add tolerations to the **Pod** or **DaemonSet** definition. This allows the created resources to run on these tainted nodes.

You apply tolerations to the Local Storage Operator pod through the **LocalVolume** resource and apply taints to a node through the node specification. A taint on a node instructs the node to repel all pods that do not tolerate the taint. Using a specific taint that is not on other pods ensures that the Local Storage Operator pod can also run on that node.



### IMPORTANT

Taints and tolerations consist of a key, value, and effect. As an argument, it is expressed as **key=value:effect**. An operator allows you to leave one of these parameters empty.



## Prerequisites

- The Local Storage Operator is installed.
- Local disks are attached to OpenShift Container Platform nodes with a taint.
- Tainted nodes are expected to provision local storage.

## Procedure

To configure local volumes for scheduling on tainted nodes:

1. Modify the YAML file that defines the **Pod** and add the **LocalVolume** spec, as shown in the following example:

```
apiVersion: "local.storage.openshift.io/v1"
kind: "LocalVolume"
metadata:
  name: "local-disks"
  namespace: "openshift-local-storage"
spec:
  tolerations:
    - key: localstorage 1
      operator: Equal 2
      value: "localstorage" 3
  storageClassDevices:
    - storageClassName: "localblock-sc"
      volumeMode: Block 4
      devicePaths: 5
        - /dev/xvdg
```

- 1** Specify the key that you added to the node.
- 2** Specify the **Equal** operator to require the **key/value** parameters to match. If operator is **Exists**, the system checks that the key exists and ignores the value. If operator is **Equal**, then the key and value must match.
- 3** Specify the value **local** of the tainted node.
- 4** The volume mode, either **Filesystem** or **Block**, defining the type of the local volumes.
- 5** The path containing a list of local storage devices to choose from.

2. Optional: To create local persistent volumes on only tainted nodes, modify the YAML file and add the **LocalVolume** spec, as shown in the following example:

```
spec:
  tolerations:
    - key: node-role.kubernetes.io/master
      operator: Exists
```

The defined tolerations will be passed to the resulting daemon sets, allowing the diskmaker and provisioner pods to be created for nodes that contain the specified taints.

## 4.10.8. Local Storage Operator Metrics

OpenShift Container Platform provides the following metrics for the Local Storage Operator:

- **iso\_discovery\_disk\_count**: total number of discovered devices on each node
- **iso\_lvset\_provisioned\_PV\_count**: total number of PVs created by **LocalVolumeSet** objects
- **iso\_lvset\_unmatched\_disk\_count**: total number of disks that Local Storage Operator did not select for provisioning because of mismatching criteria
- **iso\_lvset\_orphaned\_symlink\_count**: number of devices with PVs that no longer match **LocalVolumeSet** object criteria
- **iso\_lv\_orphaned\_symlink\_count**: number of devices with PVs that no longer match **LocalVolume** object criteria
- **iso\_lv\_provisioned\_PV\_count**: total number of provisioned PVs for **LocalVolume**

To use these metrics, be sure to:

- Enable support for monitoring when installing the Local Storage Operator.
- When upgrading to OpenShift Container Platform 4.9 or later, enable metric support manually by adding the **operator-metering=true** label to the namespace.

For more information about metrics, see [Managing metrics](#).

## 4.10.9. Deleting the Local Storage Operator resources

### 4.10.9.1. Removing a local volume or local volume set

Occasionally, local volumes and local volume sets must be deleted. While removing the entry in the resource and deleting the persistent volume is typically enough, if you want to reuse the same device path or have it managed by a different storage class, then additional steps are needed.



#### NOTE

The following procedure outlines an example for removing a local volume. The same procedure can also be used to remove symlinks for a local volume set custom resource.

#### Prerequisites

- The persistent volume must be in a **Released** or **Available** state.



#### WARNING

Deleting a persistent volume that is still in use can result in data loss or corruption.

## Procedure

1. Edit the previously created local volume to remove any unwanted disks.

a. Edit the cluster resource:

```
$ oc edit localvolume <name> -n openshift-local-storage
```

b. Navigate to the lines under **devicePaths**, and delete any representing unwanted disks.

2. Delete any persistent volumes created.

```
$ oc delete pv <pv-name>
```

3. Delete directory and included symlinks on the node.



### WARNING

The following step involves accessing a node as the root user. Modifying the state of the node beyond the steps in this procedure could result in cluster instability.

```
$ oc debug node/<node-name> -- chroot /host rm -rf /mnt/local-storage/<sc-name> 1
```

**1** The name of the storage class used to create the local volumes.

### 4.10.9.2. Uninstalling the Local Storage Operator

To uninstall the Local Storage Operator, you must remove the Operator and all created resources in the **openshift-local-storage** project.



### WARNING

Uninstalling the Local Storage Operator while local storage PVs are still in use is not recommended. While the PVs will remain after the Operator's removal, there might be indeterminate behavior if the Operator is uninstalled and reinstalled without removing the PVs and local storage resources.

## Prerequisites


- Access to the OpenShift Container Platform web console.

## Procedure

1. Delete any local volume resources installed in the project, such as **localvolume**, **localvolumeset**, and **localvolumediscovery**:

```
$ oc delete localvolume --all --all-namespaces
$ oc delete localvolumeset --all --all-namespaces
$ oc delete localvolumediscovery --all --all-namespaces
```

2. Uninstall the Local Storage Operator from the web console.
  - a. Log in to the OpenShift Container Platform web console.
  - b. Navigate to **Operators** → **Installed Operators**.
  - c. Type **Local Storage** into the filter box to locate the Local Storage Operator.

- d. Click the Options menu  at the end of the Local Storage Operator.
- e. Click **Uninstall Operator**.
- f. Click **Remove** in the window that appears.

3. The PVs created by the Local Storage Operator will remain in the cluster until deleted. After these volumes are no longer in use, delete them by running the following command:

```
$ oc delete pv <pv-name>
```

4. Delete the **openshift-local-storage** project:

```
$ oc delete project openshift-local-storage
```

## 4.11. PERSISTENT STORAGE USING NFS

OpenShift Container Platform clusters can be provisioned with persistent storage using NFS. Persistent volumes (PVs) and persistent volume claims (PVCs) provide a convenient method for sharing a volume across a project. While the NFS-specific information contained in a PV definition could also be defined directly in a **Pod** definition, doing so does not create the volume as a distinct cluster resource, making the volume more susceptible to conflicts.

### Additional resources

- [Mounting NFS shares](#)

### 4.11.1. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. To provision NFS volumes, a list of NFS servers and export paths are all that is required.

### Procedure


1. Create an object definition for the PV:

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 ❶
spec:
  capacity:
    storage: 5Gi ❷
  accessModes:
    - ReadWriteOnce ❸
  nfs: ❹
    path: /tmp ❺
    server: 172.17.0.2 ❻
  persistentVolumeReclaimPolicy: Retain ❼

```

- ❶ The name of the volume. This is the PV identity in various **oc <command> pod** commands.
- ❷ The amount of storage allocated to this volume.
- ❸ Though this appears to be related to controlling access to the volume, it is actually used similarly to labels and used to match a PVC to a PV. Currently, no access rules are enforced based on the **accessModes**.
- ❹ The volume type being used, in this case the **nfs** plugin.
- ❺ The path that is exported by the NFS server.
- ❻ The hostname or IP address of the NFS server.
- ❼ The reclaim policy for the PV. This defines what happens to a volume when released.



#### NOTE

Each NFS volume must be mountable by all schedulable nodes in the cluster.

2. Verify that the PV was created:

```
$ oc get pv
```

#### Example output

```

NAME      LABELS   CAPACITY  ACCESSMODES  STATUS   CLAIM REASON  AGE
pv0001   <none>   5Gi      RWO          Available             31s

```

3. Create a persistent volume claim that binds to the new PV:

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: nfs-claim1
spec:
  accessModes:

```

```
- ReadWriteOnce 1
resources:
  requests:
    storage: 5Gi 2
  volumeName: pv0001
  storageClassName: ""
```

- 1** The access modes do not enforce security, but rather act as labels to match a PV to a PVC.
- 2** This claim looks for PVs offering **5Gi** or greater capacity.

4. Verify that the persistent volume claim was created:

```
$ oc get pvc
```

#### Example output

```
NAME      STATUS  VOLUME  CAPACITY  ACCESS MODES  STORAGECLASS  AGE
nfs-claim1 Bound   pv0001  5Gi      RWO           2m
```

### 4.11.2. Enforcing disk quotas

You can use disk partitions to enforce disk quotas and size constraints. Each partition can be its own export. Each export is one PV. OpenShift Container Platform enforces unique names for PVs, but the uniqueness of the NFS volume's server and path is up to the administrator.

Enforcing quotas in this way allows the developer to request persistent storage by a specific amount, such as 10Gi, and be matched with a corresponding volume of equal or greater capacity.

### 4.11.3. NFS volume security

This section covers NFS volume security, including matching permissions and SELinux considerations. The user is expected to understand the basics of POSIX permissions, process UIDs, supplemental groups, and SELinux.

Developers request NFS storage by referencing either a PVC by name or the NFS volume plugin directly in the **volumes** section of their **Pod** definition.

The **/etc/exports** file on the NFS server contains the accessible NFS directories. The target NFS directory has POSIX owner and group IDs. The OpenShift Container Platform NFS plugin mounts the container's NFS directory with the same POSIX ownership and permissions found on the exported NFS directory. However, the container is not run with its effective UID equal to the owner of the NFS mount, which is the desired behavior.

As an example, if the target NFS directory appears on the NFS server as:

```
$ ls -lZ /opt/nfs -d
```

#### Example output

```
drwxrws---. nfsnobody 5555 unconfined_u:object_r:usr_t:s0 /opt/nfs
```

```
$ id nfsnobody
```

### Example output

```
uid=65534(nfsnobody) gid=65534(nfsnobody) groups=65534(nfsnobody)
```

Then the container must match SELinux labels, and either run with a UID of **65534**, the **nfsnobody** owner, or with **5555** in its supplemental groups to access the directory.



#### NOTE

The owner ID of **65534** is used as an example. Even though NFS's **root\_squash** maps **root**, uid **0**, to **nfsnobody**, uid **65534**, NFS exports can have arbitrary owner IDs. Owner **65534** is not required for NFS exports.

#### 4.11.3.1. Group IDs

The recommended way to handle NFS access, assuming it is not an option to change permissions on the NFS export, is to use supplemental groups. Supplemental groups in OpenShift Container Platform are used for shared storage, of which NFS is an example. In contrast, block storage such as iSCSI uses the **fsGroup** SCC strategy and the **fsGroup** value in the **securityContext** of the pod.



#### NOTE

To gain access to persistent storage, it is generally preferable to use supplemental group IDs versus user IDs.

Because the group ID on the example target NFS directory is **5555**, the pod can define that group ID using **supplementalGroups** under the **securityContext** definition of the pod. For example:

```
spec:
  containers:
  - name:
    ...
    securityContext: ①
      supplementalGroups: [5555] ②
```

- ① **securityContext** must be defined at the pod level, not under a specific container.
- ② An array of GIDs defined for the pod. In this case, there is one element in the array. Additional GIDs would be comma-separated.

Assuming there are no custom SCCs that might satisfy the pod requirements, the pod likely matches the **restricted** SCC. This SCC has the **supplementalGroups** strategy set to **RunAsAny**, meaning that any supplied group ID is accepted without range checking.

As a result, the above pod passes admissions and is launched. However, if group ID range checking is desired, a custom SCC is the preferred solution. A custom SCC can be created such that minimum and maximum group IDs are defined, group ID range checking is enforced, and a group ID of **5555** is allowed.

**NOTE**

To use a custom SCC, you must first add it to the appropriate service account. For example, use the **default** service account in the given project unless another has been specified on the **Pod** specification.

**4.11.3.2. User IDs**

User IDs can be defined in the container image or in the **Pod** definition.

**NOTE**

It is generally preferable to use supplemental group IDs to gain access to persistent storage versus using user IDs.

In the example target NFS directory shown above, the container needs its UID set to **65534**, ignoring group IDs for the moment, so the following can be added to the **Pod** definition:

```
spec:
  containers: ①
  - name:
    ...
    securityContext:
      runAsUser: 65534 ②
```

① Pods contain a **securityContext** definition specific to each container and a pod's **securityContext** which applies to all containers defined in the pod.

② **65534** is the **nfsnobody** user.

Assuming that the project is **default** and the SCC is **restricted**, the user ID of **65534** as requested by the pod is not allowed. Therefore, the pod fails for the following reasons:

- It requests **65534** as its user ID.
- All SCCs available to the pod are examined to see which SCC allows a user ID of **65534**. While all policies of the SCCs are checked, the focus here is on user ID.
- Because all available SCCs use **MustRunAsRange** for their **runAsUser** strategy, UID range checking is required.
- **65534** is not included in the SCC or project's user ID range.

It is generally considered a good practice not to modify the predefined SCCs. The preferred way to fix this situation is to create a custom SCC. A custom SCC can be created such that minimum and maximum user IDs are defined, UID range checking is still enforced, and the UID of **65534** is allowed.

**NOTE**

To use a custom SCC, you must first add it to the appropriate service account. For example, use the **default** service account in the given project unless another has been specified on the **Pod** specification.



### 4.11.3.3. SELinux

Red Hat Enterprise Linux (RHEL) and Red Hat Enterprise Linux CoreOS (RHCOS) systems are configured to use SELinux on remote NFS servers by default.

For non-RHEL and non-RHCOS systems, SELinux does not allow writing from a pod to a remote NFS server. The NFS volume mounts correctly but it is read-only. You will need to enable the correct SELinux permissions by using the following procedure.

#### Prerequisites

- The **container-selinux** package must be installed. This package provides the **virt\_use\_nfs** SELinux boolean.

#### Procedure

- Enable the **virt\_use\_nfs** boolean using the following command. The **-P** option makes this boolean persistent across reboots.

```
# setsebool -P virt_use_nfs 1
```

### 4.11.3.4. Export settings

To enable arbitrary container users to read and write the volume, each exported volume on the NFS server should conform to the following conditions:

- Every export must be exported using the following format:

```
/<example_fs> *(rw,root_squash)
```

- The firewall must be configured to allow traffic to the mount point.
  - For NFSv4, configure the default port **2049** (**nfs**).

#### NFSv4

```
# iptables -I INPUT 1 -p tcp --dport 2049 -j ACCEPT
```

- For NFSv3, there are three ports to configure: **2049** (**nfs**), **20048** (**mountd**), and **111** (**portmapper**).

#### NFSv3

```
# iptables -I INPUT 1 -p tcp --dport 2049 -j ACCEPT
```

```
# iptables -I INPUT 1 -p tcp --dport 20048 -j ACCEPT
```

```
# iptables -I INPUT 1 -p tcp --dport 111 -j ACCEPT
```

- The NFS export and directory must be set up so that they are accessible by the target pods. Either set the export to be owned by the container's primary UID, or supply the pod group access using **supplementalGroups**, as shown in the group IDs above.

#### 4.11.4. Reclaiming resources

NFS implements the OpenShift Container Platform **Recyclable** plugin interface. Automatic processes handle reclamation tasks based on policies set on each persistent volume.

By default, PVs are set to **Retain**.

Once claim to a PVC is deleted, and the PV is released, the PV object should not be reused. Instead, a new PV should be created with the same basic volume details as the original.

For example, the administrator creates a PV named **nfs1**:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: nfs1
spec:
  capacity:
    storage: 1Mi
  accessModes:
    - ReadWriteMany
  nfs:
    server: 192.168.1.1
    path: "/"
```

The user creates **PVC1**, which binds to **nfs1**. The user then deletes **PVC1**, releasing claim to **nfs1**. This results in **nfs1** being **Released**. If the administrator wants to make the same NFS share available, they should create a new PV with the same NFS server details, but a different PV name:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: nfs2
spec:
  capacity:
    storage: 1Mi
  accessModes:
    - ReadWriteMany
  nfs:
    server: 192.168.1.1
    path: "/"
```

Deleting the original PV and re-creating it with the same name is discouraged. Attempting to manually change the status of a PV from **Released** to **Available** causes errors and potential data loss.

#### 4.11.5. Additional configuration and troubleshooting


Depending on what version of NFS is being used and how it is configured, there may be additional configuration steps needed for proper export and security mapping. The following are some that may apply:

<p>NFSv4 mount incorrectly shows all files with ownership of <b>nobody:nobody</b></p>	<ul style="list-style-type: none"> <li>● Could be attributed to the ID mapping settings, found in <b>/etc/idmapd.conf</b> on your NFS.</li> <li>● See <a href="#">this Red Hat Solution</a>.</li> </ul>
<p>Disabling ID mapping on NFSv4</p>	<ul style="list-style-type: none"> <li>● On both the NFS client and server, run: <pre># echo 'Y' &gt; /sys/module/nfsd/parameters/nfs4_disable_idmapping</pre> </li> </ul>

## 4.12. RED HAT OPENSIFT DATA FOUNDATION

Red Hat OpenShift Data Foundation is a provider of agnostic persistent storage for OpenShift Container Platform supporting file, block, and object storage, either in-house or in hybrid clouds. As a Red Hat storage solution, Red Hat OpenShift Data Foundation is completely integrated with OpenShift Container Platform for deployment, management, and monitoring.

Red Hat OpenShift Data Foundation provides its own documentation library. The complete set of Red Hat OpenShift Data Foundation documentation is available at [https://access.redhat.com/documentation/en-us/red\\_hat\\_openshift\\_data\\_foundation](https://access.redhat.com/documentation/en-us/red_hat_openshift_data_foundation).



### IMPORTANT

OpenShift Data Foundation on top of Red Hat Hyperconverged Infrastructure (RHHI) for Virtualization, which uses hyperconverged nodes that host virtual machines installed with OpenShift Container Platform, is not a supported configuration. For more information about supported platforms, see the [Red Hat OpenShift Data Foundation Supportability and Interoperability Guide](#).

## 4.13. PERSISTENT STORAGE USING VMWARE VSPHERE VOLUMES

OpenShift Container Platform allows use of VMware vSphere's Virtual Machine Disk (VMDK) volumes. You can provision your OpenShift Container Platform cluster with persistent storage using VMware vSphere. Some familiarity with Kubernetes and VMware vSphere is assumed.

VMware vSphere volumes can be provisioned dynamically. OpenShift Container Platform creates the disk in vSphere and attaches this disk to the correct image.



### NOTE

OpenShift Container Platform provisions new volumes as independent persistent disks that can freely attach and detach the volume on any node in the cluster. Consequently, you cannot back up volumes that use snapshots, or restore volumes from snapshots. See [Snapshot Limitations](#) for more information.

The Kubernetes persistent volume framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.

Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. Persistent volume claims are specific to a project or namespace and can be requested by users.



### IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision vSphere storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.

#### Additional resources

- [VMware vSphere](#)

### 4.13.1. Dynamically provisioning VMware vSphere volumes

Dynamically provisioning VMware vSphere volumes is the recommended method.

#### 4.13.2. Prerequisites

- An OpenShift Container Platform cluster installed on a VMware vSphere version that meets the requirements for the components that you use. See [Installing a cluster on vSphere](#) for information about vSphere version support.

You can use either of the following procedures to dynamically provision these volumes using the default storage class.

##### 4.13.2.1. Dynamically provisioning VMware vSphere volumes using the UI

OpenShift Container Platform installs a default storage class, named **thin**, that uses the **thin** disk format for provisioning volumes.

#### Prerequisites

- Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform.

#### Procedure

1. In the OpenShift Container Platform console, click **Storage** → **Persistent Volume Claims**
2. In the persistent volume claims overview, click **Create Persistent Volume Claim**
3. Define the required options on the resulting page.
  - a. Select the **thin** storage class.

- b. Enter a unique name for the storage claim.
  - c. Select the access mode to determine the read and write access for the created storage claim.
  - d. Define the size of the storage claim.
4. Click **Create** to create the persistent volume claim and generate a persistent volume.

#### 4.13.2.2. Dynamically provisioning VMware vSphere volumes using the CLI

OpenShift Container Platform installs a default StorageClass, named **thin**, that uses the **thin** disk format for provisioning volumes.

##### Prerequisites

- Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform.

##### Procedure (CLI)

1. You can define a VMware vSphere PersistentVolumeClaim by creating a file, **pvc.yaml**, with the following contents:

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: pvc 1
spec:
  accessModes:
  - ReadWriteOnce 2
resources:
  requests:
    storage: 1Gi 3
```

- 1** A unique name that represents the persistent volume claim.
- 2** The access mode of the persistent volume claim. With **ReadWriteOnce**, the volume can be mounted with read and write permissions by a single node.
- 3** The size of the persistent volume claim.

2. Enter the following command to create the **PersistentVolumeClaim** object from the file:

```
$ oc create -f pvc.yaml
```

#### 4.13.3. Statically provisioning VMware vSphere volumes

To statically provision VMware vSphere volumes you must create the virtual machine disks for reference by the persistent volume framework.

##### Prerequisites

- Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform.

## Procedure

1. Create the virtual machine disks. Virtual machine disks (VMDKs) must be created manually before statically provisioning VMware vSphere volumes. Use either of the following methods:
  - Create using **vmkfstools**. Access ESX through Secure Shell (SSH) and then use following command to create a VMDK volume:

```
$ vmkfstools -c <size> /vmfs/volumes/<datastore-name>/volumes/<disk-name>.vmdk
```


- Create using **vmware-diskmanager**:

```
$ shell vmware-vdiskmanager -c -t 0 -s <size> -a lsilogic <disk-name>.vmdk
```

2. Create a persistent volume that references the VMDKs. Create a file, **pv1.yaml**, with the **PersistentVolume** object definition:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv1 1
spec:
  capacity:
    storage: 1Gi 2
  accessModes:
    - ReadWriteOnce
  persistentVolumeReclaimPolicy: Retain
  vsphereVolume: 3
    volumePath: "[datastore1] volumes/myDisk" 4
    fsType: ext4 5
```

- 1** The name of the volume. This name is how it is identified by persistent volume claims or pods.
- 2** The amount of storage allocated to this volume.
- 3** The volume type used, with **vsphereVolume** for vSphere volumes. The label is used to mount a vSphere VMDK volume into pods. The contents of a volume are preserved when it is unmounted. The volume type supports VMFS and VSAN datastore.
- 4** The existing VMDK volume to use. If you used **vmkfstools**, you must enclose the datastore name in square brackets, **[ ]**, in the volume definition, as shown previously.
- 5** The file system type to mount. For example, ext4, xfs, or other file systems.



### IMPORTANT

Changing the value of the fsType parameter after the volume is formatted and provisioned can result in data loss and pod failure.

3. Create the **PersistentVolume** object from the file:

```
$ oc create -f pv1.yaml
```

4. Create a persistent volume claim that maps to the persistent volume you created in the previous step. Create a file, **pvc1.yaml**, with the **PersistentVolumeClaim** object definition:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc1 1
spec:
  accessModes:
    - ReadWriteOnce 2
  resources:
    requests:
      storage: "1Gi" 3
  volumeName: pv1 4
```

- 1 A unique name that represents the persistent volume claim.
- 2 The access mode of the persistent volume claim. With ReadWriteOnce, the volume can be mounted with read and write permissions by a single node.
- 3 The size of the persistent volume claim.
- 4 The name of the existing persistent volume.

5. Create the **PersistentVolumeClaim** object from the file:

```
$ oc create -f pvc1.yaml
```

#### 4.13.3.1. Formatting VMware vSphere volumes


Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that the volume contains a file system that is specified by the **fsType** parameter value in the **PersistentVolume** (PV) definition. If the device is not formatted with the file system, all data from the device is erased, and the device is automatically formatted with the specified file system.

Because OpenShift Container Platform formats them before the first use, you can use unformatted vSphere volumes as PVs.

# CHAPTER 5. USING CONTAINER STORAGE INTERFACE (CSI)

## 5.1. CONFIGURING CSI VOLUMES

The Container Storage Interface (CSI) allows OpenShift Container Platform to consume storage from storage back ends that implement the [CSI interface](#) as persistent storage.




**NOTE**

OpenShift Container Platform 4.11 supports version 1.5.0 of the [CSI specification](#).

### 5.1.1. CSI Architecture

CSI drivers are typically shipped as container images. These containers are not aware of OpenShift Container Platform where they run. To use CSI-compatible storage back end in OpenShift Container Platform, the cluster administrator must deploy several components that serve as a bridge between OpenShift Container Platform and the storage driver.

The following diagram provides a high-level overview about the components running in pods in the OpenShift Container Platform cluster.



It is possible to run multiple CSI drivers for different storage back ends. Each driver needs its own external controllers deployment and daemon set with the driver and CSI registrar.

#### 5.1.1.1. External CSI controllers

External CSI Controllers is a deployment that deploys one or more pods with five containers:

- The snapshotter container watches **VolumeSnapshot** and **VolumeSnapshotContent** objects and is responsible for the creation and deletion of **VolumeSnapshotContent** object.



- The resizer container is a sidecar container that watches for **PersistentVolumeClaim** updates and triggers **ControllerExpandVolume** operations against a CSI endpoint if you request more storage on **PersistentVolumeClaim** object.
- An external CSI attacher container translates **attach** and **detach** calls from OpenShift Container Platform to respective **ControllerPublish** and **ControllerUnpublish** calls to the CSI driver.
- An external CSI provisioner container that translates **provision** and **delete** calls from OpenShift Container Platform to respective **CreateVolume** and **DeleteVolume** calls to the CSI driver.
- A CSI driver container

The CSI attacher and CSI provisioner containers communicate with the CSI driver container using UNIX Domain Sockets, ensuring that no CSI communication leaves the pod. The CSI driver is not accessible from outside of the pod.



#### NOTE

**attach**, **detach**, **provision**, and **delete** operations typically require the CSI driver to use credentials to the storage backend. Run the CSI controller pods on infrastructure nodes so the credentials are never leaked to user processes, even in the event of a catastrophic security breach on a compute node.



#### NOTE

The external attacher must also run for CSI drivers that do not support third-party **attach** or **detach** operations. The external attacher will not issue any **ControllerPublish** or **ControllerUnpublish** operations to the CSI driver. However, it still must run to implement the necessary OpenShift Container Platform attachment API.

### 5.1.1.2. CSI driver daemon set

The CSI driver daemon set runs a pod on every node that allows OpenShift Container Platform to mount storage provided by the CSI driver to the node and use it in user workloads (pods) as persistent volumes (PVs). The pod with the CSI driver installed contains the following containers:

- A CSI driver registrar, which registers the CSI driver into the **openshift-node** service running on the node. The **openshift-node** process running on the node then directly connects with the CSI driver using the UNIX Domain Socket available on the node.
- A CSI driver.

The CSI driver deployed on the node should have as few credentials to the storage back end as possible. OpenShift Container Platform will only use the node plugin set of CSI calls such as **NodePublish/NodeUnpublish** and **NodeStage/NodeUnstage**, if these calls are implemented.

### 5.1.2. CSI drivers supported by OpenShift Container Platform

OpenShift Container Platform installs certain CSI drivers by default, giving users storage options that are not possible with in-tree volume plugins.

To create CSI-provisioned persistent volumes that mount to these supported storage assets, OpenShift Container Platform installs the necessary CSI driver Operator, the CSI driver, and the required storage class by default. For more details about the default namespace of the Operator and driver, see the documentation for the specific CSI Driver Operator.

The following table describes the CSI drivers that are installed with OpenShift Container Platform and which CSI features they support, such as volume snapshots, cloning, and resize.

**Table 5.1. Supported CSI drivers and features in OpenShift Container Platform**

CSI driver	CSI volume snapshots	CSI cloning	CSI resize
AliCloud Disk	■	-	■
AWS EBS	■	-	■
AWS EFS	-	-	-
Google Cloud Platform (GCP) persistent disk (PD)	■	■	■
IBM VPC Block	-	-	■
Microsoft Azure Disk	■	■	■
Microsoft Azure Stack Hub	■	■	■
Microsoft Azure File	-	-	■
OpenStack Cinder	■	■	■
OpenShift Data Foundation	■	■	■
OpenStack Manila	■	-	-
Red Hat Virtualization (oVirt)	-	-	■
VMware vSphere	■ <sup>[1]</sup>	-	■ <sup>[2]</sup>

1.

- Requires vSphere version 7.0 Update 3 or later for both vCenter Server and ESXi.
- Does not support fileshare volumes.

2.

- Offline volume expansion: minimum required vSphere version is 6.7 Update 3 P06
- Online volume expansion: minimum required vSphere version is 7.0 Update 2.



### IMPORTANT

If your CSI driver is not listed in the preceding table, you must follow the installation instructions provided by your CSI storage vendor to use their supported CSI features.

### 5.1.3. Dynamic provisioning

Dynamic provisioning of persistent storage depends on the capabilities of the CSI driver and underlying storage back end. The provider of the CSI driver should document how to create a storage class in OpenShift Container Platform and the parameters available for configuration.

The created storage class can be configured to enable dynamic provisioning.

#### Procedure

- Create a default storage class that ensures all PVCs that do not require any special storage class are provisioned by the installed CSI driver.

```
# oc create -f - << EOF
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: <storage-class> 1
  annotations:
    storageclass.kubernetes.io/is-default-class: "true"
provisioner: <provisioner-name> 2
parameters:
EOF
```

1 The name of the storage class that will be created.

2 The name of the CSI driver that has been installed

### 5.1.4. Example using the CSI driver

The following example installs a default MySQL template without any changes to the template.

#### Prerequisites

- The CSI driver has been deployed.
- A storage class has been created for dynamic provisioning.

#### Procedure

- Create the MySQL template:

```
# oc new-app mysql-persistent
```

### Example output

```
--> Deploying template "openshift/mysql-persistent" to project default
...
```

```
# oc get pvc
```


### Example output

NAME	STATUS	VOLUME	CAPACITY
ACCESS MODES	STORAGECLASS	AGE	
mysql	Bound	kubernetes-dynamic-pv-3271ffc4e1811e8	1Gi
RWO	cinder	3s	

## 5.2. CSI INLINE EPHEMERAL VOLUMES

Container Storage Interface (CSI) inline ephemeral volumes allow you to define a **Pod** spec that creates inline ephemeral volumes when a pod is deployed and delete them when a pod is destroyed.

This feature is only available with supported Container Storage Interface (CSI) drivers.



### IMPORTANT

CSI inline ephemeral volumes is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see [Technology Preview Features Support Scope](#).

### 5.2.1. Overview of CSI inline ephemeral volumes

Traditionally, volumes that are backed by Container Storage Interface (CSI) drivers can only be used with a **PersistentVolume** and **PersistentVolumeClaim** object combination.

This feature allows you to specify CSI volumes directly in the **Pod** specification, rather than in a **PersistentVolume** object. Inline volumes are ephemeral and do not persist across pod restarts.

#### 5.2.1.1. Support limitations

By default, OpenShift Container Platform supports CSI inline ephemeral volumes with these limitations:

- Support is only available for CSI drivers. In-tree and FlexVolumes are not supported.
- The Shared Resource CSI Driver supports inline ephemeral volumes as a Technology Preview feature.

- Community or storage vendors provide other CSI drivers that support these volumes. Follow the installation instructions provided by the CSI driver provider.

CSI drivers might not have implemented the inline volume functionality, including **Ephemeral** capacity. For details, see the CSI driver documentation.



## IMPORTANT

Shared Resource CSI Driver is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see [Technology Preview Features Support Scope](#).

### 5.2.2. Embedding a CSI inline ephemeral volume in the pod specification

You can embed a CSI inline ephemeral volume in the **Pod** specification in OpenShift Container Platform. At runtime, nested inline volumes follow the ephemeral lifecycle of their associated pods so that the CSI driver handles all phases of volume operations as pods are created and destroyed.

#### Procedure

1. Create the **Pod** object definition and save it to a file.
2. Embed the CSI inline ephemeral volume in the file.

#### my-csi-app.yaml

```
kind: Pod
apiVersion: v1
metadata:
  name: my-csi-app
spec:
  containers:
  - name: my-frontend
    image: busybox
    volumeMounts:
    - mountPath: "/data"
      name: my-csi-inline-vol
    command: [ "sleep", "1000000" ]
  volumes: ❶
  - name: my-csi-inline-vol
    csi:
      driver: inline.storage.kubernetes.io
      volumeAttributes:
        foo: bar
```


- ❶ The name of the volume that is used by pods.

3. Create the object definition file that you saved in the previous step.

```
$ oc create -f my-csi-app.yaml
```

## 5.3. SHARED RESOURCE CSI DRIVER OPERATOR

As a cluster administrator, you can use the Shared Resource CSI Driver in OpenShift Container Platform to provision inline ephemeral volumes that contain the contents of **Secret** or **ConfigMap** objects. This way, pods and other Kubernetes types that expose volume mounts, and OpenShift Container Platform Builds can securely use the contents of those objects across potentially any namespace in the cluster. To accomplish this, there are currently two types of shared resources: a **SharedSecret** custom resource for **Secret** objects, and a **SharedConfigMap** custom resource for **ConfigMap** objects.



### IMPORTANT

The Shared Resource CSI Driver is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see [Technology Preview Features Support Scope](#).



### NOTE

To enable the Shared Resource CSI Driver, you must [enable features using feature gates](#)

### 5.3.1. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### 5.3.2. Sharing secrets across namespaces

To share a secret across namespaces in a cluster, you create a **SharedSecret** custom resource (CR) instance for the **Secret** object that you want to share.

#### Prerequisites

You must have permission to perform the following actions:

- Create instances of the **sharedsecrets.sharedresource.openshift.io** custom resource definition (CRD) at a cluster-scoped level.
- Manage roles and role bindings across the namespaces in the cluster to control which users can get, list, and watch those instances.
- Manage roles and role bindings to control whether the service account specified by a pod can mount a Container Storage Interface (CSI) volume that references the **SharedSecret** CR instance you want to use.

- Access the namespaces that contain the Secrets you want to share.

### Procedure

- Create a **SharedSecret** CR instance for the **Secret** object you want to share across namespaces in the cluster:

```
$ oc apply -f - <<EOF
apiVersion: sharedresource.openshift.io/v1alpha1
kind: SharedSecret
metadata:
  name: my-share
spec:
  secretRef:
    name: <name of secret>
    namespace: <namespace of secret>
EOF
```

### 5.3.3. Using a SharedSecret instance in a pod

To access a **SharedSecret** custom resource (CR) instance from a pod, you grant a given service account RBAC permissions to use that **SharedSecret** CR instance.

#### Prerequisites

- You have created a **SharedSecret** CR instance for the secret you want to share across namespaces in the cluster.
- You must have permission to perform the following actions
  - Create build configs and start builds.
  - Discover which **SharedSecret** CR instances are available by entering the **oc get sharedsecrets** command and getting a non-empty list back.
  - Determine if the **builder** service accounts available to you in your namespace are allowed to use the given **SharedSecret** CR instance. That is, you can run **oc adm policy who-can use <identifier of specific SharedSecret>** to see if the **builder** service account in your namespace is listed.



#### NOTE

If neither of the last two prerequisites in this list are met, create, or ask someone to create, the necessary role-based access control (RBAC) so that you can discover **SharedSecret** CR instances and enable service accounts to use **SharedSecret** CR instances.

### Procedure

1. Grant a given service account RBAC permissions to use the **SharedSecret** CR instance in its pod by using **oc apply** with YAML content:

**NOTE**

Currently, **kubectl** and **oc** have hard-coded special case logic restricting the **use** verb to roles centered around pod security. Therefore, you cannot use **oc create role ...** to create the role needed for consuming **SharedSecret** CR instances.

```
$ oc apply -f - <<EOF
apiVersion: rbac.authorization.k8s.io/v1
kind: Role
metadata:
  name: shared-resource-my-share
  namespace: my-namespace
rules:
  - apiGroups:
    - sharedresource.openshift.io
    resources:
    - sharedsecrets
    resourceNames:
    - my-share
    verbs:
    - use
EOF
```

2. Create the **RoleBinding** associated with the role by using the **oc** command:

```
$ oc create rolebinding shared-resource-my-share --role=shared-resource-my-share --
serviceaccount=my-namespace:builder
```

3. Access the **SharedSecret** CR instance from a pod:

```
$ oc apply -f - <<EOF
kind: Pod
apiVersion: v1
metadata:
  name: my-app
  namespace: my-namespace
spec:
  serviceAccountName: default

# containers omitted .... Follow standard use of 'volumeMounts' for referencing your shared
resource volume

  volumes:
  - name: my-csi-volume
    csi:
      readOnly: true
      driver: csi.sharedresource.openshift.io
      volumeAttributes:
        sharedSecret: my-share
EOF
```

### 5.3.4. Sharing a config map across namespaces



To share a config map across namespaces in a cluster, you create a **SharedConfigMap** custom resource (CR) instance for that config map.

## Prerequisites

You must have permission to perform the following actions:

- Create instances of the **sharedconfigmaps.sharedresource.openshift.io** custom resource definition (CRD) at a cluster-scoped level.
- Manage roles and role bindings across the namespaces in the cluster to control which users can get, list, and watch those instances.
- Manage roles and role bindings across the namespaces in the cluster to control which service accounts in pods that mount your Container Storage Interface (CSI) volume can use those instances.
- Access the namespaces that contain the Secrets you want to share.

## Procedure

1. Create a **SharedConfigMap** CR instance for the config map that you want to share across namespaces in the cluster:

```
$ oc apply -f - <<EOF
apiVersion: sharedresource.openshift.io/v1alpha1
kind: SharedConfigMap
metadata:
  name: my-share
spec:
  configMapRef:
    name: <name of configmap>
    namespace: <namespace of configmap>
EOF
```

### 5.3.5. Using a SharedConfigMap instance in a pod

#### Next steps

To access a **SharedConfigMap** custom resource (CR) instance from a pod, you grant a given service account RBAC permissions to use that **SharedConfigMap** CR instance.

#### Prerequisites

- You have created a **SharedConfigMap** CR instance for the config map that you want to share across namespaces in the cluster.
- You must have permission to perform the following actions:
  - Create build configs and start builds.
  - Discover which **SharedConfigMap** CR instances are available by entering the **oc get sharedconfigmaps** command and getting a non-empty list back.
  - Determine if the **builder** service accounts available to you in your namespace are allowed to use the given **SharedSecret** CR instance. That is, you can run **oc adm policy who-can use**

<identifier of specific **SharedSecret**> to see if the **builder** service account in your namespace is listed.



## NOTE

If neither of the last two prerequisites in this list are met, create, or ask someone to create, the necessary role-based access control (RBAC) so that you can discover **SharedConfigMap** CR instances and enable service accounts to use **SharedConfigMap** CR instances.

## Procedure

1. Grant a given service account RBAC permissions to use the **SharedConfigMap** CR instance in its pod by using **oc apply** with YAML content.



## NOTE

Currently, **kubectl** and **oc** have hard-coded special case logic restricting the **use** verb to roles centered around pod security. Therefore, you cannot use **oc create role ...** to create the role needed for consuming a **SharedConfigMap** CR instance.

```
$ oc apply -f - <<EOF
apiVersion: rbac.authorization.k8s.io/v1
kind: Role
metadata:
  name: shared-resource-my-share
  namespace: my-namespace
rules:
- apiGroups:
  - sharedresource.openshift.io
  resources:
  - sharedconfigmaps
  resourceName:
  - my-share
  verbs:
  - use
EOF
```

2. Create the **RoleBinding** associated with the role by using the **oc** command:

```
oc create rolebinding shared-resource-my-share --role=shared-resource-my-share --
serviceaccount=my-namespace:builder
```

3. Access the **SharedConfigMap** CR instance from a pod:

```
$ oc apply -f - <<EOF
kind: Pod
apiVersion: v1
metadata:
  name: my-app
  namespace: my-namespace
spec:
  serviceAccountName: default
```

```
# containers omitted .... Follow standard use of 'volumeMounts' for referencing your shared
resource volume

volumes:
- name: my-csi-volume
  csi:
    readOnly: true
    driver: csi.sharedresource.openshift.io
    volumeAttributes:
      sharedConfigMap: my-share

EOF
```

### 5.3.6. Additional support limitations for the Shared Resource CSI Driver

The Shared Resource CSI Driver has the following noteworthy limitations:

- The driver is subject to the limitations of Container Storage Interface (CSI) inline ephemeral volumes.
- The value of the **readOnly** field must be **true**. Otherwise, on volume provisioning during pod startup, the driver returns an error to the kubelet. This limitation is in keeping with proposed best practices for the upstream Kubernetes CSI Driver to apply SELinux labels to associated volumes.
- The driver ignores the **FSType** field because it only supports **tmpfs** volumes.
- The driver ignores the **NodePublishSecretRef** field. Instead, it uses **SubjectAccessReviews** with the **use** verb to evaluate whether a pod can obtain a volume that contains **SharedSecret** or **SharedConfigMap** custom resource (CR) instances.

### 5.3.7. Additional details about VolumeAttributes on shared resource pod volumes

The following attributes affect shared resource pod volumes in various ways:

- The **refreshResource** attribute in the **volumeAttributes** properties.
- The **refreshResources** attribute in the Shared Resource CSI Driver configuration.
- The **sharedSecret** and **sharedConfigMap** attributes in the **volumeAttributes** properties.

#### 5.3.7.1. The refreshResource attribute

The Shared Resource CSI Driver honors the **refreshResource** attribute in **volumeAttributes** properties of the volume. This attribute controls whether updates to the contents of the underlying **Secret** or **ConfigMap** object are copied to the volume **after** the volume is initially provisioned as part of pod startup. The default value of **refreshResource** is **true**, which means that the contents are updated.



## IMPORTANT

If the Shared Resource CSI Driver configuration has disabled the refreshing of both the shared **SharedSecret** and **SharedConfigMap** custom resource (CR) instances, then the **refreshResource** attribute in the **volumeAttribute** properties has no effect. The intent of this attribute is to disable refresh for specific volume mounts when refresh is generally allowed.

### 5.3.7.2. The **refreshResources** attribute

You can use a global switch to enable or disable refreshing of shared resources. This switch is the **refreshResources** attribute in the **csi-driver-shared-resource-config** config map for the Shared Resource CSI Driver, which you can find in the **openshift-cluster-csi-drivers** namespace. If you set this **refreshResources** attribute to **false**, none of the **Secret** or **ConfigMap** object-related content stored in the volume is updated after the initial provisioning of the volume.



## IMPORTANT

Using this Shared Resource CSI Driver configuration to disable refreshing affects all the cluster's volume mounts that use the Shared Resource CSI Driver, regardless of the **refreshResource** attribute in the **volumeAttributes** properties of any of those volumes.

### 5.3.7.3. Validation of **volumeAttributes** before provisioning a shared resource volume for a pod

In the **volumeAttributes** of a single volume, you must set either a **sharedSecret** or a **sharedConfigMap** attribute to the value of a **SharedSecret** or a **SharedConfigMap** CS instance. Otherwise, when the volume is provisioned during pod startup, a validation checks the **volumeAttributes** of that volume and returns an error to the kubelet under the following conditions:

- Both **sharedSecret** and **sharedConfigMap** attributes have specified values.
- Neither **sharedSecret** nor **sharedConfigMap** attributes have specified values.
- The value of the **sharedSecret** or **sharedConfigMap** attribute does not correspond to the name of a **SharedSecret** or **SharedConfigMap** CR instance on the cluster.

### 5.3.8. Integration between shared resources, Insights Operator, and OpenShift Container Platform Builds

Integration between shared resources, Insights Operator, and OpenShift Container Platform Builds makes using Red Hat subscriptions (RHEL entitlements) easier in OpenShift Container Platform Builds.

Previously, in OpenShift Container Platform 4.9.x and earlier, you manually imported your credentials and copied them to each project or namespace where you were running builds.

Now, in OpenShift Container Platform 4.10 and later, OpenShift Container Platform Builds can use Red Hat subscriptions (RHEL entitlements) by referencing shared resources and the simple content access feature provided by Insights Operator:

- The simple content access feature imports your subscription credentials to a well-known **Secret** object. See the links in the following "Additional resources" section.
- The cluster administrator creates a **SharedSecret** custom resource (CR) instance around that **Secret** object and grants permission to particular projects or namespaces. In particular, the

cluster administrator gives the **builder** service account permission to use that **SharedSecret** CR instance.

- Builds that run within those projects or namespaces can mount a CSI Volume that references the **SharedSecret** CR instance and its entitled RHEL content.

#### Additional resources

- [Importing simple content access certificates with Insights Operator](#)
- [Adding subscription entitlements as a build secret](#)

## 5.4. CSI VOLUME SNAPSHOTS

This document describes how to use volume snapshots with supported Container Storage Interface (CSI) drivers to help protect against data loss in OpenShift Container Platform. Familiarity with [persistent volumes](#) is suggested.

### 5.4.1. Overview of CSI volume snapshots

A *snapshot* represents the state of the storage volume in a cluster at a particular point in time. Volume snapshots can be used to provision a new volume.

OpenShift Container Platform supports Container Storage Interface (CSI) volume snapshots by default. However, a specific CSI driver is required.

With CSI volume snapshots, a cluster administrator can:

- Deploy a third-party CSI driver that supports snapshots.
- Create a new persistent volume claim (PVC) from an existing volume snapshot.
- Take a snapshot of an existing PVC.
- Restore a snapshot as a different PVC.
- Delete an existing volume snapshot.

With CSI volume snapshots, an app developer can:

- Use volume snapshots as building blocks for developing application- or cluster-level storage backup solutions.
- Rapidly rollback to a previous development version.
- Use storage more efficiently by not having to make a full copy each time.

Be aware of the following when using volume snapshots:

- Support is only available for CSI drivers. In-tree and FlexVolumes are not supported.
- OpenShift Container Platform only ships with select CSI drivers. For CSI drivers that are not provided by an OpenShift Container Platform Driver Operator, it is recommended to use the CSI drivers provided by [community or storage vendors](#). Follow the installation instructions furnished by the CSI driver provider.

- CSI drivers may or may not have implemented the volume snapshot functionality. CSI drivers that have provided support for volume snapshots will likely use the **csi-external-snapshotter** sidecar. See documentation provided by the CSI driver for details.

## 5.4.2. CSI snapshot controller and sidecar

OpenShift Container Platform provides a snapshot controller that is deployed into the control plane. In addition, your CSI driver vendor provides the CSI snapshot sidecar as a helper container that is installed during the CSI driver installation.

The CSI snapshot controller and sidecar provide volume snapshotting through the OpenShift Container Platform API. These external components run in the cluster.

The external controller is deployed by the CSI Snapshot Controller Operator.

### 5.4.2.1. External controller

The CSI snapshot controller binds **VolumeSnapshot** and **VolumeSnapshotContent** objects. The controller manages dynamic provisioning by creating and deleting **VolumeSnapshotContent** objects.

### 5.4.2.2. External sidecar

Your CSI driver vendor provides the **csi-external-snapshotter** sidecar. This is a separate helper container that is deployed with the CSI driver. The sidecar manages snapshots by triggering **CreateSnapshot** and **DeleteSnapshot** operations. Follow the installation instructions provided by your vendor.

## 5.4.3. About the CSI Snapshot Controller Operator

The CSI Snapshot Controller Operator runs in the **openshift-cluster-storage-operator** namespace. It is installed by the Cluster Version Operator (CVO) in all clusters by default.

The CSI Snapshot Controller Operator installs the CSI snapshot controller, which runs in the **openshift-cluster-storage-operator** namespace.

### 5.4.3.1. Volume snapshot CRDs

During OpenShift Container Platform installation, the CSI Snapshot Controller Operator creates the following snapshot custom resource definitions (CRDs) in the **snapshot.storage.k8s.io/v1** API group:

#### **VolumeSnapshotContent**

A snapshot taken of a volume in the cluster that has been provisioned by a cluster administrator. Similar to the **PersistentVolume** object, the **VolumeSnapshotContent** CRD is a cluster resource that points to a real snapshot in the storage back end.

For manually pre-provisioned snapshots, a cluster administrator creates a number of **VolumeSnapshotContent** CRDs. These carry the details of the real volume snapshot in the storage system.

The **VolumeSnapshotContent** CRD is not namespaced and is for use by a cluster administrator.

#### **VolumeSnapshot**

Similar to the **PersistentVolumeClaim** object, the **VolumeSnapshot** CRD defines a developer request for a snapshot. The CSI Snapshot Controller Operator runs the CSI snapshot controller,

which handles the binding of a **VolumeSnapshot** CRD with an appropriate **VolumeSnapshotContent** CRD. The binding is a one-to-one mapping.

The **VolumeSnapshot** CRD is namespaced. A developer uses the CRD as a distinct request for a snapshot.

### VolumeSnapshotClass

Allows a cluster administrator to specify different attributes belonging to a **VolumeSnapshot** object. These attributes may differ among snapshots taken of the same volume on the storage system, in which case they would not be expressed by using the same storage class of a persistent volume claim.

The **VolumeSnapshotClass** CRD defines the parameters for the **csi-external-snapshotter** sidecar to use when creating a snapshot. This allows the storage back end to know what kind of snapshot to dynamically create if multiple options are supported.

Dynamically provisioned snapshots use the **VolumeSnapshotClass** CRD to specify storage-provider-specific parameters to use when creating a snapshot.

The **VolumeSnapshotContentClass** CRD is not namespaced and is for use by a cluster administrator to enable global configuration options for their storage back end.

## 5.4.4. Volume snapshot provisioning

There are two ways to provision snapshots: dynamically and manually.

### 5.4.4.1. Dynamic provisioning

Instead of using a preexisting snapshot, you can request that a snapshot be taken dynamically from a persistent volume claim. Parameters are specified using a **VolumeSnapshotClass** CRD.

### 5.4.4.2. Manual provisioning


As a cluster administrator, you can manually pre-provision a number of **VolumeSnapshotContent** objects. These carry the real volume snapshot details available to cluster users.

## 5.4.5. Creating a volume snapshot

When you create a **VolumeSnapshot** object, OpenShift Container Platform creates a volume snapshot.

### Prerequisites

- Logged in to a running OpenShift Container Platform cluster.
- A PVC created using a CSI driver that supports **VolumeSnapshot** objects.
- A storage class to provision the storage back end.
- No pods are using the persistent volume claim (PVC) that you want to take a snapshot of.



### NOTE

Do not create a volume snapshot of a PVC if a pod is using it. Doing so might cause data corruption because the PVC is not quiesced (paused). Be sure to first tear down a running pod to ensure consistent snapshots.

## Procedure

To dynamically create a volume snapshot:

1. Create a file with the **VolumeSnapshotClass** object described by the following YAML:

### volumesnapshotclass.yaml

```
apiVersion: snapshot.storage.k8s.io/v1
kind: VolumeSnapshotClass
metadata:
  name: csi-hostpath-snap
driver: hostpath.csi.k8s.io 1
deletionPolicy: Delete
```

- 1** The name of the CSI driver that is used to create snapshots of this **VolumeSnapshotClass** object. The name must be the same as the **Provisioner** field of the storage class that is responsible for the PVC that is being snapshotted.



### NOTE

Depending on the driver that you used to configure persistent storage, additional parameters might be required. You can also use an existing **VolumeSnapshotClass** object.

2. Create the object you saved in the previous step by entering the following command:

```
$ oc create -f volumesnapshotclass.yaml
```

3. Create a **VolumeSnapshot** object:

### volumesnapshot-dynamic.yaml

```
apiVersion: snapshot.storage.k8s.io/v1
kind: VolumeSnapshot
metadata:
  name: mysnap
spec:
  volumeSnapshotClassName: csi-hostpath-snap 1
  source:
    persistentVolumeClaimName: myclaim 2
```

- 1** The request for a particular class by the volume snapshot. If the **volumeSnapshotClassName** setting is absent and there is a default volume snapshot class, a snapshot is created with the default volume snapshot class name. But if the field is absent and no default volume snapshot class exists, then no snapshot is created.
- 2** The name of the **PersistentVolumeClaim** object bound to a persistent volume. This defines what you want to create a snapshot of. Required for dynamically provisioning a snapshot.

4. Create the object you saved in the previous step by entering the following command:



```
$ oc create -f volumesnapshot-dynamic.yaml
```

To manually provision a snapshot:

1. Provide a value for the **volumeSnapshotContentName** parameter as the source for the snapshot, in addition to defining volume snapshot class as shown above.

### volumesnapshot-manual.yaml

```
apiVersion: snapshot.storage.k8s.io/v1
kind: VolumeSnapshot
metadata:
  name: snapshot-demo
spec:
  source:
    volumeSnapshotContentName: mycontent ❶
```

- ❶ The **volumeSnapshotContentName** parameter is required for pre-provisioned snapshots.

2. Create the object you saved in the previous step by entering the following command:

```
$ oc create -f volumesnapshot-manual.yaml
```

### Verification

After the snapshot has been created in the cluster, additional details about the snapshot are available.

1. To display details about the volume snapshot that was created, enter the following command:

```
$ oc describe volumesnapshot mysnap
```

The following example displays details about the **mysnap** volume snapshot:

### volumesnapshot.yaml

```
apiVersion: snapshot.storage.k8s.io/v1
kind: VolumeSnapshot
metadata:
  name: mysnap
spec:
  source:
    persistentVolumeClaimName: myclaim
    volumeSnapshotClassName: csi-hostpath-snap
status:
  boundVolumeSnapshotContentName: snapcontent-1af4989e-a365-4286-96f8-
  d5dcd65d78d6 ❶
  creationTime: "2020-01-29T12:24:30Z" ❷
  readyToUse: true ❸
  restoreSize: 500Mi
```

- ❶ The pointer to the actual storage content that was created by the controller.
- ❷ The time when the snapshot was created. The snapshot contains the volume content that

was available at this indicated time.

- 3 If the value is set to **true**, the snapshot can be used to restore as a new PVC. If the value is set to **false**, the snapshot was created. However, the storage back end needs to perform additional tasks to make the snapshot usable so that it can be restored as a new volume. For example, Amazon Elastic Block Store data might be moved to a different, less expensive location, which can take several minutes.

2. To verify that the volume snapshot was created, enter the following command:

```
$ oc get volumesnapshotcontent
```

The pointer to the actual content is displayed. If the **boundVolumeSnapshotContentName** field is populated, a **VolumeSnapshotContent** object exists and the snapshot was created.

3. To verify that the snapshot is ready, confirm that the **VolumeSnapshot** object has **readyToUse: true**.

### 5.4.6. Deleting a volume snapshot

You can configure how OpenShift Container Platform deletes volume snapshots.

#### Procedure

1. Specify the deletion policy that you require in the **VolumeSnapshotClass** object, as shown in the following example:

#### volumesnapshotclass.yaml

```
apiVersion: snapshot.storage.k8s.io/v1
kind: VolumeSnapshotClass
metadata:
  name: csi-hostpath-snap
driver: hostpath.csi.k8s.io
deletionPolicy: Delete 1
```

- 1 When deleting the volume snapshot, if the **Delete** value is set, the underlying snapshot is deleted along with the **VolumeSnapshotContent** object. If the **Retain** value is set, both the underlying snapshot and **VolumeSnapshotContent** object remain. If the **Retain** value is set and the **VolumeSnapshot** object is deleted without deleting the corresponding **VolumeSnapshotContent** object, the content remains. The snapshot itself is also retained in the storage back end.

2. Delete the volume snapshot by entering the following command:

```
$ oc delete volumesnapshot <volumesnapshot_name>
```


#### Example output

```
volumesnapshot.snapshot.storage.k8s.io "mysnapshot" deleted
```

- If the deletion policy is set to **Retain**, delete the volume snapshot content by entering the following command:

```
$ oc delete volumesnapshotcontent <volumesnapshotcontent_name>
```

- Optional: If the **VolumeSnapshot** object is not successfully deleted, enter the following command to remove any finalizers for the leftover resource so that the delete operation can continue:



### IMPORTANT

Only remove the finalizers if you are confident that there are no existing references from either persistent volume claims or volume snapshot contents to the **VolumeSnapshot** object. Even with the **--force** option, the delete operation does not delete snapshot objects until all finalizers are removed.

```
$ oc patch -n $PROJECT volumesnapshot/$NAME --type=merge -p '{"metadata": {"finalizers":null}}'
```

### Example output

```
volumesnapshotclass.snapshot.storage.k8s.io "csi-ocs-rbd-snapclass" deleted
```

The finalizers are removed and the volume snapshot is deleted.

## 5.4.7. Restoring a volume snapshot

The **VolumeSnapshot** CRD content can be used to restore the existing volume to a previous state.

After your **VolumeSnapshot** CRD is bound and the **readyToUse** value is set to **true**, you can use that resource to provision a new volume that is pre-populated with data from the snapshot. .Prerequisites \* Logged in to a running OpenShift Container Platform cluster. \* A persistent volume claim (PVC) created using a Container Storage Interface (CSI) driver that supports volume snapshots. \* A storage class to provision the storage back end. \* A volume snapshot has been created and is ready to use.

### Procedure

- Specify a **VolumeSnapshot** data source on a PVC as shown in the following:

#### pvc-restore.yaml

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: myclaim-restore
spec:
  storageClassName: csi-hostpath-sc
  dataSource:
    name: mysnap 1
    kind: VolumeSnapshot 2
    apiGroup: snapshot.storage.k8s.io 3
  accessModes:
    - ReadWriteOnce
```

```
resources:
  requests:
    storage: 1Gi
```

- 1 Name of the **VolumeSnapshot** object representing the snapshot to use as source.
- 2 Must be set to the **VolumeSnapshot** value.
- 3 Must be set to the **snapshot.storage.k8s.io** value.

2. Create a PVC by entering the following command:

```
$ oc create -f pvc-restore.yaml
```

3. Verify that the restored PVC has been created by entering the following command:

```
$ oc get pvc
```

A new PVC such as **myclaim-restore** is displayed.

## 5.5. CSI VOLUME CLONING

Volume cloning duplicates an existing persistent volume to help protect against data loss in OpenShift Container Platform. This feature is only available with supported Container Storage Interface (CSI) drivers. You should be familiar with [persistent volumes](#) before you provision a CSI volume clone.

### 5.5.1. Overview of CSI volume cloning

A Container Storage Interface (CSI) volume clone is a duplicate of an existing persistent volume at a particular point in time.

Volume cloning is similar to volume snapshots, although it is more efficient. For example, a cluster administrator can duplicate a cluster volume by creating another instance of the existing cluster volume.

Cloning creates an exact duplicate of the specified volume on the back-end device, rather than creating a new empty volume. After dynamic provisioning, you can use a volume clone just as you would use any standard volume.

No new API objects are required for cloning. The existing **dataSource** field in the **PersistentVolumeClaim** object is expanded so that it can accept the name of an existing PersistentVolumeClaim in the same namespace.

#### 5.5.1.1. Support limitations

By default, OpenShift Container Platform supports CSI volume cloning with these limitations:

- The destination persistent volume claim (PVC) must exist in the same namespace as the source PVC.
- Cloning is supported with a different Storage Class.
  - Destination volume can be the same for a different storage class as the source.
  - You can use the default storage class and omit **storageClassName** in the **spec**.

- Support is only available for CSI drivers. In-tree and FlexVolumes are not supported.
- CSI drivers might not have implemented the volume cloning functionality. For details, see the CSI driver documentation.

## 5.5.2. Provisioning a CSI volume clone

When you create a cloned persistent volume claim (PVC) API object, you trigger the provisioning of a CSI volume clone. The clone pre-populates with the contents of another PVC, adhering to the same rules as any other persistent volume. The one exception is that you must add a **dataSource** that references an existing PVC in the same namespace.

### Prerequisites

- You are logged in to a running OpenShift Container Platform cluster.
- Your PVC is created using a CSI driver that supports volume cloning.
- Your storage back end is configured for dynamic provisioning. Cloning support is not available for static provisioners.

### Procedure

To clone a PVC from an existing PVC:

1. Create and save a file with the **PersistentVolumeClaim** object described by the following YAML:

#### pvc-clone.yaml

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-1-clone
  namespace: mynamespace
spec:
  storageClassName: csi-cloning 1
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 5Gi
  dataSource:
    kind: PersistentVolumeClaim
    name: pvc-1
```

- 1** The name of the storage class that provisions the storage back end. The default storage class can be used and **storageClassName** can be omitted in the spec.

2. Create the object you saved in the previous step by running the following command:

```
$ oc create -f pvc-clone.yaml
```

A new PVC **pvc-1-clone** is created.

- Verify that the volume clone was created and is ready by running the following command:

```
$ oc get pvc pvc-1-clone
```

The **pvc-1-clone** shows that it is **Bound**.

You are now ready to use the newly cloned PVC to configure a pod.

- Create and save a file with the **Pod** object described by the YAML. For example:

```
kind: Pod
apiVersion: v1
metadata:
  name: mypod
spec:
  containers:
  - name: myfrontend
    image: dockerfile/nginx
    volumeMounts:
    - mountPath: "/var/www/html"
      name: mypd
  volumes:
  - name: mypd
    persistentVolumeClaim:
      claimName: pvc-1-clone 1
```

- The cloned PVC created during the CSI volume cloning operation.

The created **Pod** object is now ready to consume, clone, snapshot, or delete your cloned PVC independently of its original **dataSource** PVC.

## 5.6. CSI AUTOMATIC MIGRATION

In-tree storage drivers that are traditionally shipped with OpenShift Container Platform are being deprecated and replaced by their equivalent Container Storage Interface (CSI) drivers. OpenShift Container Platform provides automatic migration for certain supported in-tree volume plugins to their equivalent CSI drivers.

### 5.6.1. Overview

Volumes that are provisioned by using in-tree storage plugins, and that are supported by this feature, are migrated to their counterpart Container Storage Interface (CSI) drivers. This process does not perform any data migration; OpenShift Container Platform only translates the persistent volume object in memory. As a result, the translated persistent volume object is not stored on disk, nor is its contents changed.

The following in-tree to CSI drivers are supported:

**Table 5.2. CSI automatic migration feature supported in-tree/CSI drivers**

In-tree/CSI drivers	Support level	CSI auto migration enabled automatically?
<ul style="list-style-type: none"> <li>● Azure Disk</li> <li>● OpenStack Cinder</li> </ul>	Generally available (GA)	Yes. For more information, see " <i>Automatic migration of in-tree volumes to CSI</i> ".
<ul style="list-style-type: none"> <li>● Amazon Web Services (AWS) Elastic Block Storage (EBS)</li> <li>● Azure File</li> <li>● Google Compute Engine Persistent Disk (in-tree) and Google Cloud Platform Persistent Disk (CSI)</li> <li>● VMware vSphere</li> </ul>	Technology Preview (TP)	No. To enable, see " <i>Manually enabling CSI automatic migration</i> ".

CSI automatic migration should be seamless. This feature does not change how you use all existing API objects: for example, **PersistentVolumes**, **PersistentVolumeClaims**, and **StorageClasses**.

Enabling CSI automatic migration for in-tree persistent volumes (PVs) or persistent volume claims (PVCs) does not enable any new CSI driver features, such as snapshots or expansion, if the original in-tree storage plugin did not support it.

#### Additional resources

- [Automatic migration of in-tree volumes to CSI](#)
- [Manually enabling CSI automatic migration](#)

### 5.6.2. Automatic migration of in-tree volumes to CSI

OpenShift Container Platform supports automatic and seamless migration for the following in-tree volume types to their Container Storage Interface (CSI) driver counterpart:

- Azure Disk
- OpenStack Cinder

CSI migration for these volume types is considered generally available (GA), and requires no manual intervention.

For new OpenShift Container Platform 4.11, and later, installations, the default storage class is the CSI storage class. All volumes provisioned using this storage class are CSI persistent volumes (PVs).

For clusters upgraded from 4.10, and earlier, to 4.11, and later, the CSI storage class is created, and is set as the default if no default storage class was set prior to the upgrade. In the very unlikely case that there is a storage class with the same name, the existing storage class remains unchanged. Any existing in-tree

storage classes remain, and might be necessary for certain features, such as volume expansion to work for existing in-tree PVs. While storage class referencing to the in-tree storage plugin will continue working, we recommend that you switch the default storage class to the CSI storage class.

### 5.6.3. Manually enabling CSI automatic migration

If you want to test Container Storage Interface (CSI) migration in development or staging OpenShift Container Platform clusters, you must manually enable in-tree to CSI migration for the following in-tree volume types:

- AWS Elastic Block Storage (EBS)
- Google Compute Engine Persistent Disk (GCE-PD)
- VMware vSphere Disk
- Azure File



#### IMPORTANT

CSI automatic migration for the preceding in-tree volume plugins and CSI driver pairs is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of Red Hat Technology Preview features, see [Technology Preview Features Support Scope](#).

After migration, the default storage class remains the in-tree storage class.

CSI automatic migration will be enabled by default for all storage in-tree plugins in a future OpenShift Container Platform release, so it is highly recommended that you test it now and report any issues.



#### NOTE

Enabling CSI automatic migration drains, and then restarts, all nodes in the cluster in sequence. This might take some time.

#### Procedure

- Enable feature gates (see *Nodes* → *Working with clusters* → *Enabling features using feature gates*).



#### IMPORTANT

After turning on Technology Preview features using feature gates, they cannot be turned off. As a result, cluster upgrades are prevented.

The following configuration example enables CSI automatic migration for all CSI drivers supported by this feature that are currently in Technology Preview (TP) status:

```
apiVersion: config.openshift.io/v1
```



```

kind: FeatureGate
metadata:
  name: cluster
spec:
  featureSet: TechPreviewNoUpgrade 1
  ...

```

- 1** Enables automatic migration for AWS EBS, GCP, Azure File, and VMware vSphere.

You can specify CSI automatic migration for a selected CSI driver by setting **CustomNoUpgrade featureSet** and for **featuregates** to one of the following:

- CSIMigrationAWS
- CSIMigrationAzureFile
- CSIMigrationGCE
- CSIMigrationvSphere

The following configuration example enables automatic migration to the AWS EBS CSI driver only:

```

apiVersion: config.openshift.io/v1
kind: FeatureGate
metadata:
  name: cluster
spec:
  featureSet: CustomNoUpgrade
  customNoUpgrade:
    enabled:
      - CSIMigrationAWS 1
  ...

```

- 1** Enables automatic migration for AWS EBS only.

### Additional resources

- [Enabling features using feature gates](#)

## 5.7. ALICLOUD DISK CSI DRIVER OPERATOR

### 5.7.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for Alibaba AliCloud Disk Storage.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.

To create CSI-provisioned PVs that mount to AliCloud Disk storage assets, OpenShift Container Platform installs the AliCloud Disk CSI Driver Operator and the AliCloud Disk CSI driver, by default, in the **openshift-cluster-csi-drivers** namespace.

- The *AliCloud Disk CSI Driver Operator* provides a storage class ( **alicloud-disk**) that you can use to create persistent volume claims (PVCs). The AliCloud Disk CSI Driver Operator supports dynamic volume provisioning by allowing storage volumes to be created on demand, eliminating the need for cluster administrators to pre-provision storage.
- The *AliCloud Disk CSI driver* enables you to create and mount AliCloud Disk PVs.

## 5.7.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### Additional resources

- [Configuring CSI volumes](#)

## 5.8. AWS ELASTIC BLOCK STORE CSI DRIVER OPERATOR

### 5.8.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for AWS Elastic Block Store (EBS).

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a Container Storage Interface (CSI) Operator and driver.

To create CSI-provisioned PVs that mount to AWS EBS storage assets, OpenShift Container Platform installs the AWS EBS CSI Driver Operator and the AWS EBS CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- The *AWS EBS CSI Driver Operator* provides a StorageClass by default that you can use to create PVCs. You also have the option to create the AWS EBS StorageClass as described in [Persistent storage using AWS Elastic Block Store](#).
- The *AWS EBS CSI driver* enables you to create and mount AWS EBS PVs.



### NOTE

If you installed the AWS EBS CSI Operator and driver on an OpenShift Container Platform 4.5 cluster, you must uninstall the 4.5 Operator and driver before you update to OpenShift Container Platform 4.11.

### 5.8.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.



## IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision AWS EBS storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.

For information about dynamically provisioning AWS EBS persistent volumes in OpenShift Container Platform, see [Persistent storage using AWS Elastic Block Store](#).

### Additional resources

- [Persistent storage using AWS Elastic Block Store](#)
- [Configuring CSI volumes](#)

## 5.9. AWS ELASTIC FILE SERVICE CSI DRIVER OPERATOR

### 5.9.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for AWS Elastic File Service (EFS).

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.

After installing the AWS EFS CSI Driver Operator, OpenShift Container Platform installs the AWS EFS CSI Operator and the AWS EFS CSI driver by default in the **openshift-cluster-csi-drivers** namespace. This allows the AWS EFS CSI Driver Operator to create CSI-provisioned PVs that mount to AWS EFS assets.

- The *AWS EFS CSI Driver Operator*, after being installed, does not create a storage class by default to use to create persistent volume claims (PVCs). However, you can manually create the AWS EFS **StorageClass**. The AWS EFS CSI Driver Operator supports dynamic volume provisioning by allowing storage volumes to be created on-demand. This eliminates the need for cluster administrators to pre-provision storage.
- The *AWS EFS CSI driver* enables you to create and mount AWS EFS PVs.



## NOTE

AWS EFS only supports regional volumes, not zonal volumes.

### 5.9.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### 5.9.3. Installing the AWS EFS CSI Driver Operator

The AWS EFS CSI Driver Operator is not installed in OpenShift Container Platform by default. Use the following procedure to install and configure the AWS EFS CSI Driver Operator in your cluster.

#### Prerequisites

- Access to the OpenShift Container Platform web console.

#### Procedure

To install the AWS EFS CSI Driver Operator from the web console:

1. Log in to the web console.
2. Install the AWS EFS CSI Operator:
  - a. Click **Operators** → **OperatorHub**.
  - b. Locate the AWS EFS CSI Operator by typing **AWS EFS CSI** in the filter box.
  - c. Click the **AWS EFS CSI Driver Operator** button.



#### IMPORTANT

Be sure to select the **AWS EFS CSI Driver Operator** and not the **AWS EFS Operator**. The **AWS EFS Operator** is a community Operator and is not supported by Red Hat.

- d. On the **AWS EFS CSI Driver Operator** page, click **Install**.
  - e. On the **Install Operator** page, ensure that:
    - **All namespaces on the cluster (default)** is selected.
    - **Installed Namespace** is set to **openshift-cluster-csi-drivers**.
  - f. Click **Install**.  
After the installation finishes, the AWS EFS CSI Operator is listed in the **Installed Operators** section of the web console.
3. If you are using AWS EFS with AWS Security Token Service (STS), you must configure the AWS EFS CSI Driver with STS. For more information, see "Configuring AWS EFS CSI Driver with STS".
  4. Install the AWS EFS CSI Driver:
    - a. Click **administration** → **CustomResourceDefinitions** → **ClusterCSIDriver**.
    - b. On the **Instances** tab, click **Create ClusterCSIDriver**.

c. Use the following YAML file:

```
apiVersion: operator.openshift.io/v1
kind: ClusterCSIDriver
metadata:
  name: efs.csi.aws.com
spec:
  managementState: Managed
```

d. Click **Create**.

e. Wait for the following Conditions to change to a "true" status:

- AWSEFSDriverCredentialsRequestControllerAvailable
- AWSEFSDriverNodeServiceControllerAvailable
- AWSEFSDriverControllerServiceControllerAvailable

#### Additional resources

- [Configuring AWS EFS CSI Driver with STS](#)

### 5.9.4. Configuring AWS EFS CSI Driver Operator with Security Token Service

This procedure explains how to configure the AWS EFS CSI Driver Operator with OpenShift Container Platform on AWS Security Token Service (STS).

Perform this procedure after installing the AWS EFS CSI Operator, but before installing the AWS EFS CSI driver as part of *Installing the AWS EFS CSI Driver Operator* procedure. If you perform this procedure after installing the driver and creating volumes, your volumes will fail to mount into pods.

#### Prerequisites

- AWS account credentials

#### Procedure

To configure the AWS EFS CSI Driver Operator with STS:

1. Extract the CCO utility (**ccoctl**) binary from the OpenShift Container Platform release image, which you used to install the cluster with STS. For more information, see "Configuring the Cloud Credential Operator utility".
2. Create and save an EFS **CredentialsRequest** YAML file, such as shown in the following example, and then place it in the **credrequests** directory:

#### Example

```
apiVersion: cloudcredential.openshift.io/v1
kind: CredentialsRequest
metadata:
  name: openshift-aws-efs-csi-driver
  namespace: openshift-cloud-credential-operator
spec:
  providerSpec:
```

```

apiVersion: cloudcredential.openshift.io/v1
kind: AWSProviderSpec
statementEntries:
- action:
  - elasticfilesystem:*
  effect: Allow
  resource: '*'
secretRef:
  name: aws-efs-cloud-credentials
  namespace: openshift-cluster-csi-drivers
serviceAccountNames:
- aws-efs-csi-driver-operator
- aws-efs-csi-driver-controller-sa

```

3. Run the **ccoctl** tool to generate a new IAM role in AWS, and create a YAML file for it in the local file system (**<path\_to\_ccoctl\_output\_dir>/manifests/openshift-cluster-csi-drivers-aws-efs-cloud-credentials-credentials.yaml**).

```

$ ccoctl aws create-iam-roles --name=<name> --region=<aws_region> --credentials-requests-dir=<path_to_directory_with_list_of_credentials_requests>/credrequests --identity-provider-arn=arn:aws:iam::<aws_account_id>:oidc-provider/<name>-oidc.s3.<aws_region>.amazonaws.com

```

- **name=<name>** is the name used to tag any cloud resources that are created for tracking.
- **region=<aws\_region>** is the AWS region where cloud resources are created.
- **dir=<path\_to\_directory\_with\_list\_of\_credentials\_requests>/credrequests** is the directory containing the EFS CredentialsRequest file in previous step.
- **<aws\_account\_id>** is the AWS account ID.

### Example

```

$ ccoctl aws create-iam-roles --name my-aws-efs --credentials-requests-dir credrequests --identity-provider-arn arn:aws:iam::123456789012:oidc-provider/my-aws-efs-oidc.s3.us-east-2.amazonaws.com

```

### Example output

```

2022/03/21 06:24:44 Role arn:aws:iam::123456789012:role/my-aws-efs -openshift-cluster-csi-drivers-aws-efs-cloud- created
2022/03/21 06:24:44 Saved credentials configuration to: /manifests/openshift-cluster-csi-drivers-aws-efs-cloud-credentials-credentials.yaml
2022/03/21 06:24:45 Updated Role policy for Role my-aws-efs-openshift-cluster-csi-drivers-aws-efs-cloud-

```

4. Create the AWS EFS cloud credentials and secret:

```

$ oc create -f <path_to_ccoctl_output_dir>/manifests/openshift-cluster-csi-drivers-aws-efs-cloud-credentials-credentials.yaml

```

### Example

```
$ oc create -f /manifests/openshift-cluster-csi-drivers-aws-efs-cloud-credentials-credentials.yaml
```

### Example output

```
secret/aws-efs-cloud-credentials created
```

### Additional resources

- [Installing the AWS EFS CSI Driver Operator](#)
- [Configuring the Cloud Credential Operator utility](#)

## 5.9.5. Creating the AWS EFS storage class

Storage classes are used to differentiate and delineate storage levels and usages. By defining a storage class, users can obtain dynamically provisioned persistent volumes.

The *AWS EFS CSI Driver Operator*, after being installed, does not create a storage class by default. However, you can manually create the AWS EFS storage class.

### 5.9.5.1. Creating the AWS EFS storage class using the console

#### Procedure

1. In the OpenShift Container Platform console, click **Storage** → **StorageClasses**.
2. On the **StorageClasses** page, click **Create StorageClass**.
3. On the **StorageClass** page, perform the following steps:
  - a. Enter a name to reference the storage class.
  - b. Optional: Enter the description.
  - c. Select the reclaim policy.
  - d. Select **efs.csi.aws.com** from the **Provisioner** drop-down list.
  - e. Optional: Set the configuration parameters for the selected provisioner.
4. Click **Create**.

### 5.9.5.2. Creating the AWS EFS storage class using the CLI

#### Procedure

- Create a **StorageClass** object:

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: efs-sc
provisioner: efs.csi.aws.com
```

parameters:

```
provisioningMode: efs-ap 1
fileSystemId: fs-a5324911 2
directoryPerms: "700" 3
gidRangeStart: "1000" 4
gidRangeEnd: "2000" 5
basePath: "/dynamic_provisioning" 6
```

- 1** **provisioningMode** must be **efs-ap** to enable dynamic provisioning.
- 2** **fileSystemId** must be the ID of the EFS volume created manually.
- 3** **directoryPerms** is the default permission of the root directory of the volume. In this example, the volume is accessible only by the owner.
- 4** **gidRangeStart** and **gidRangeEnd** set the range of POSIX Group IDs (GIDs) that are used to set the GID of the AWS access point. If not specified, the default range is 50000-7000000. Each provisioned volume, and thus AWS access point, is assigned a unique GID from this range.
- 6** **basePath** is the directory on the EFS volume that is used to create dynamically provisioned volumes. In this case, a PV is provisioned as `"/dynamic_provisioning/<random uuid>"` on the EFS volume. Only the subdirectory is mounted to pods that use the PV.



#### NOTE

A cluster admin can create several **StorageClass** objects, each using a different EFS volume.

### 5.9.6. Creating and configuring access to EFS volumes in AWS

This procedure explains how to create and configure EFS volumes in AWS so that you can use them in OpenShift Container Platform.

#### Prerequisites

- AWS account credentials

#### Procedure

To create and configure access to an EFS volume in AWS:

1. On the AWS console, open <https://console.aws.amazon.com/efs>.
2. Click **Create file system**
  - Enter a name for the file system.
  - For **Virtual Private Cloud (VPC)** select your OpenShift Container Platform's virtual private cloud (VPC).
  - Accept default settings for all other selections.
3. Wait for the volume and mount targets to finish being fully created:



- a. Go to <https://console.aws.amazon.com/efs#/file-systems>.
  - b. Click your volume, and on the **Network** tab wait for all mount targets to become available (~1-2 minutes).
4. On the **Network** tab, copy the Security Group ID (you will need this in the next step).
  5. Go to <https://console.aws.amazon.com/ec2/v2/home#SecurityGroups>, and find the Security Group used by the EFS volume.
  6. On the **Inbound rules** tab, click **Edit inbound rules**, and then add a new rule with the following settings to allow OpenShift Container Platform nodes to access EFS volumes :
    - **Type:** NFS
    - **Protocol:** TCP
    - **Port range:** 2049
    - **Source:** Custom/IP address range of your nodes (for example: "10.0.0.0/16")  
This step allows OpenShift Container Platform to use NFS ports from the cluster.
  7. Save the rule.

### 5.9.7. Dynamic provisioning for AWS EFS

The AWS EFS CSI Driver supports a different form of dynamic provisioning than other CSI drivers. It provisions new PVs as subdirectories of a pre-existing EFS volume. The PVs are independent of each other. However, they all share the same EFS volume. When the volume is deleted, all PVs provisioned out of it are deleted too. The EFS CSI driver creates an AWS Access Point for each such subdirectory. Due to AWS AccessPoint limits, you can only dynamically provision 1000 PVs from a single **StorageClass**/EFS volume.



#### IMPORTANT

Note that **PVC.spec.resources** is not enforced by EFS.

In the example below, you request 5 GiB of space. However, the created PV is limitless and can store any amount of data (like petabytes). A broken application, or even a rogue application, can cause significant expenses when it stores too much data on the volume.

Using monitoring of EFS volume sizes in AWS is strongly recommended.

#### Prerequisites

- You have created AWS EFS volumes.
- You have created the AWS EFS storage class.

#### Procedure

To enable dynamic provisioning:

- Create a PVC (or StatefulSet or Template) as usual, referring to the **StorageClass** created above.

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: test
spec:
  storageClassName: efs-sc
  accessModes:
    - ReadWriteMany
resources:
  requests:
    storage: 5Gi

```

If you have problems setting up dynamic provisioning, see [AWS EFS troubleshooting](#).

### Additional resources

- [Creating and configuring access to AWS EFS volume\(s\)](#)
- [Creating the AWS EFS storage class](#)

## 5.9.8. Creating static PVs with AWS EFS

It is possible to use an AWS EFS volume as a single PV without any dynamic provisioning. The whole volume is mounted to pods.

### Prerequisites

- You have created AWS EFS volumes.

### Procedure

- Create the PV using the following YAML file:

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: efs-pv
spec:
  capacity: 1
  storage: 5Gi
  volumeMode: Filesystem
  accessModes:
    - ReadWriteMany
    - ReadWriteOnce
  persistentVolumeReclaimPolicy: Retain
  csi:
    driver: efs.csi.aws.com
    volumeHandle: fs-ae66151a 2
    volumeAttributes:
      encryptInTransit: "false" 3

```

- 1** **spec.capacity** does not have any meaning and is ignored by the CSI driver. It is used only when binding to a PVC. Applications can store any amount of data to the volume.

- 2 **volumeHandle** must be the same ID as the EFS volume you created in AWS. If you are providing your own access point, **volumeHandle** should be **<EFS volume ID>::<access**
- 3 If desired, you can disable encryption in transit. Encryption is enabled by default.

If you have problems setting up static PVs, see [AWS EFS troubleshooting](#).

### 5.9.9. AWS EFS security

The following information is important for AWS EFS security.

When using access points, for example, by using dynamic provisioning as described earlier, Amazon automatically replaces GIDs on files with the GID of the access point. In addition, EFS considers the user ID, group ID, and secondary group IDs of the access point when evaluating file system permissions. EFS ignores the NFS client's IDs. For more information about access points, see <https://docs.aws.amazon.com/efs/latest/ug/efs-access-points.html>.

As a consequence, EFS volumes silently ignore FSGroup; OpenShift Container Platform is not able to replace the GIDs of files on the volume with FSGroup. Any pod that can access a mounted EFS access point can access any file on it.

Unrelated to this, encryption in transit is enabled by default. For more information, see <https://docs.aws.amazon.com/efs/latest/ug/encryption-in-transit.html>.

### 5.9.10. AWS EFS troubleshooting

The following information provides guidance on how to troubleshoot issues with AWS EFS:

- The AWS EFS Operator and CSI driver run in namespace **openshift-cluster-csi-drivers**.
- To initiate gathering of logs of the AWS EFS Operator and CSI driver, run the following command:

```
$ oc adm must-gather
[must-gather ] OUT Using must-gather plugin-in image: quay.io/openshift-release-
dev/ocp-v4.0-art-
dev@sha256:125f183d13601537ff15b3239df95d47f0a604da2847b561151fedd699f5e3a5
[must-gather ] OUT namespace/openshift-must-gather-xm4wq created
[must-gather ] OUT clusterrolebinding.rbac.authorization.k8s.io/must-gather-2bd8x
created
[must-gather ] OUT pod for plug-in image quay.io/openshift-release-dev/ocp-v4.0-art-
dev@sha256:125f183d13601537ff15b3239df95d47f0a604da2847b561151fedd699f5e3a5
created
```

- To show AWS EFS Operator errors, view the **ClusterCSIDriver** status:

```
$ oc get clustercsidriver efs.csi.aws.com -o yaml
```

- If a volume cannot be mounted to a pod (as shown in the output of the following command):

```
$ oc describe pod
...
Type      Reason      Age   From          Message
----      -
-----
```

```

Normal Scheduled 2m13s default-scheduler Successfully assigned default/efs-app to
ip-10-0-135-94.ec2.internal
Warning FailedMount 13s kubelet MountVolume.Setup failed for volume "pvc-
d7c097e6-67ec-4fae-b968-7e7056796449" : rpc error: code = DeadlineExceeded desc =
context deadline exceeded 1
Warning FailedMount 10s kubelet Unable to attach or mount volumes: unmounted
volumes=[persistent-storage], unattached volumes=[persistent-storage kube-api-access-
9j477]: timed out waiting for the condition

```

- 1** Warning message indicating volume not mounted.

This error is frequently caused by AWS dropping packets between an OpenShift Container Platform node and AWS EFS.

Check that the following are correct:

- AWS firewall and Security Groups
- Networking: port number and IP addresses

### 5.9.11. Uninstalling the AWS EFS CSI Driver Operator

All EFS PVs are inaccessible after uninstalling the AWS EFS CSI Driver Operator.

#### Prerequisites

- Access to the OpenShift Container Platform web console.

#### Procedure

To uninstall the AWS EFS CSI Driver Operator from the web console:

1. Log in to the web console.
2. Stop all applications that use AWS EFS PVs.
3. Delete all AWS EFS PVs:
  - a. Click **Storage** → **PersistentVolumeClaims**.
  - b. Select each PVC that is in use by the AWS EFS CSI Driver Operator, click the drop-down menu on the far right of the PVC, and then click **Delete PersistentVolumeClaims**.
4. Uninstall the AWS EFS CSI Driver:



#### NOTE

Before you can uninstall the Operator, you must remove the CSI driver first.

- a. Click **administration** → **CustomResourceDefinitions** → **ClusterCSIDriver**.
- b. On the **Instances** tab, for **efs.csi.aws.com**, on the far left side, click the drop-down menu, and then click **Delete ClusterCSIDriver**.
- c. When prompted, click **Delete**.

5. Uninstall the AWS EFS CSI Operator:
  - a. Click **Operators** → **Installed Operators**.
  - b. On the **Installed Operators** page, scroll or type AWS EFS CSI into the **Search by name** box to find the Operator, and then click it.
  - c. On the upper, right of the **Installed Operators > Operator details** page, click **Actions** → **Uninstall Operator**.
  - d. When prompted on the **Uninstall Operator** window, click the **Uninstall** button to remove the Operator from the namespace. Any applications deployed by the Operator on the cluster need to be cleaned up manually.  
After uninstalling, the AWS EFS CSI Driver Operator is no longer listed in the **Installed Operators** section of the web console.



#### NOTE

Before you can destroy a cluster (**openshift-install destroy cluster**), you must delete the EFS volume in AWS. An OpenShift Container Platform cluster cannot be destroyed when there is an EFS volume that uses the cluster's VPC. Amazon does not allow deletion of such a VPC.

### 5.9.12. Additional resources

- [Configuring CSI volumes](#)

## 5.10. AZURE DISK CSI DRIVER OPERATOR

### 5.10.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for Microsoft Azure Disk Storage.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.


To create CSI-provisioned PVs that mount to Azure Disk storage assets, OpenShift Container Platform installs the Azure Disk CSI Driver Operator and the Azure Disk CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- The *Azure Disk CSI Driver Operator* provides a storage class named **managed-csi** that you can use to create persistent volume claims (PVCs). The Azure Disk CSI Driver Operator supports dynamic volume provisioning by allowing storage volumes to be created on-demand, eliminating the need for cluster administrators to pre-provision storage.
- The *Azure Disk CSI driver* enables you to create and mount Azure Disk PVs.

### 5.10.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.



## IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision Azure Disk storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in later versions of OpenShift Container Platform.

### 5.10.3. Creating a storage class with storage account type

Storage classes are used to differentiate and delineate storage levels and usages. By defining a storage class, you can obtain dynamically provisioned persistent volumes.

When creating a storage class, you can designate the storage account type. This corresponds to your Azure storage account SKU tier. Valid options are **Standard\_LRS**, **Premium\_LRS**, **StandardSSD\_LRS**, **UltraSSD\_LRS**, **Premium\_ZRS**, and **StandardSSD\_ZRS**. For information about finding your Azure SKU tier, see [SKU Types](#).

ZRS has some region limitations. For information about these limitations, see [ZRS limitations](#).

#### Prerequisites

- Access to an OpenShift Container Platform cluster with administrator rights

#### Procedure

Use the following steps to create a storage class with a storage account type.

1. Create a storage class designating the storage account type using a YAML file similar to the following:

```
$ oc create -f - << EOF
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: <storage-class> 1
provisioner: disk.csi.azure.com
parameters:
  skuName: <storage-class-account-type> 2
reclaimPolicy: Delete
volumeBindingMode: WaitForFirstConsumer
allowVolumeExpansion: true
EOF
```

- 1** Storage class name.

- 2 Storage account type. This corresponds to your Azure storage account SKU tier: `Standard\_LRS`, **Premium\_LRS**, **StandardSSD\_LRS**, **UltraSSD\_LRS**,

2. Ensure that the storage class was created by listing the storage classes:

```
$ oc get storageclass
```

#### Example output

```
$ oc get storageclass
NAME          PROVISIONER          RECLAIMPOLICY  VOLUMEBINDINGMODE
ALLOWVOLUMEEXPANSION  AGE
azurefile-csi  file.csi.azure.com  Delete         Immediate         true          68m
managed-csi (default)  disk.csi.azure.com  Delete         WaitForFirstConsumer  true          68m
sc-prem-zrs     disk.csi.azure.com  Delete         WaitForFirstConsumer  true          4m25s 1
```

- 1 New storage class with storage account type.

### 5.10.4. Machine sets that deploy machines with ultra disks using PVCs

You can create a machine set running on Azure that deploys machines with ultra disks. Ultra disks are high-performance storage that are intended for use with the most demanding data workloads.

Both the in-tree plugin and CSI driver support using PVCs to enable ultra disks. You can also deploy machines with ultra disks as data disks without creating a PVC.

#### Additional resources

- [Microsoft Azure ultra disks documentation](#)
- [Machine sets that deploy machines on ultra disks using in-tree PVCs](#)
- [Machine sets that deploy machines on ultra disks as data disks](#)

#### 5.10.4.1. Creating machines with ultra disks by using machine sets

You can deploy machines with ultra disks on Azure by editing your machine set YAML file.

#### Prerequisites

- Have an existing Microsoft Azure cluster.

#### Procedure

1. Copy an existing Azure **MachineSet** custom resource (CR) and edit it by running the following command:

```
$ oc edit machineset <machine-set-name>
```

where **<machine-set-name>** is the machine set that you want to provision machines with ultra disks.

2. Add the following lines in the positions indicated:

```

apiVersion: machine.openshift.io/v1beta1
kind: MachineSet
...
spec:
...
template:
...
spec:
  metadata:
    ...
    labels:
      ...
      disk: ultrasssd 1
      ...
  providerSpec:
    value:
      ...
      ultraSSDCapability: Enabled 2
      ...

```

- 1 Specify a label to use to select a node that is created by this machine set. This procedure uses **disk.ultrasssd** for this value.
- 2 These lines enable the use of ultra disks.

3. Create a machine set using the updated configuration by running the following command:

```
$ oc create -f <machine-set-name>.yaml
```

4. Create a storage class that contains the following YAML definition:

```

apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: ultra-disk-sc 1
parameters:
  cachingMode: None
  diskIopsReadWrite: "2000" 2
  diskMbpsReadWrite: "320" 3
  kind: managed
  skuName: UltraSSD_LRS
provisioner: disk.csi.azure.com 4
reclaimPolicy: Delete
volumeBindingMode: WaitForFirstConsumer 5

```

- 1 Specify the name of the storage class. This procedure uses **ultra-disk-sc** for this value.
- 2 Specify the number of IOPS for the storage class.



- 3 Specify the throughput in MBps for the storage class.
  - 4 For Azure Kubernetes Service (AKS) version 1.21 or later, use **disk.csi.azure.com**. For earlier versions of AKS, use **kubernetes.io/azure-disk**.
  - 5 Optional: Specify this parameter to wait for the creation of the pod that will use the disk.
5. Create a persistent volume claim (PVC) to reference the **ultra-disk-sc** storage class that contains the following YAML definition:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: ultra-disk 1
spec:
  accessModes:
  - ReadWriteOnce
  storageClassName: ultra-disk-sc 2
resources:
  requests:
    storage: 4Gi 3
```

- 1 Specify the name of the PVC. This procedure uses **ultra-disk** for this value.
  - 2 This PVC references the **ultra-disk-sc** storage class.
  - 3 Specify the size for the storage class. The minimum value is **4Gi**.
6. Create a pod that contains the following YAML definition:

```
apiVersion: v1
kind: Pod
metadata:
  name: nginx-ultra
spec:
  nodeSelector:
    disk: ultrassd 1
  containers:
  - name: nginx-ultra
    image: alpine:latest
    command:
    - "sleep"
    - "infinity"
  volumeMounts:
  - mountPath: "/mnt/azure"
    name: volume
  volumes:
  - name: volume
    persistentVolumeClaim:
      claimName: ultra-disk 2
```

- 1 Specify the label of the machine set that enables the use of ultra disks. This procedure uses **disk.ultrassd** for this value.

- 2 This pod references the **ultra-disk** PVC.

## Verification

1. Validate that the machines are created by running the following command:

```
$ oc get machines
```

The machines should be in the **Running** state.

2. For a machine that is running and has a node attached, validate the partition by running the following command:

```
$ oc debug node/<node-name> -- chroot /host lsblk
```

In this command, **oc debug node/<node-name>** starts a debugging shell on the node **<node-name>** and passes a command with **--**. The passed command **chroot /host** provides access to the underlying host OS binaries, and **lsblk** shows the block devices that are attached to the host OS machine.

## Next steps

- To use an ultra disk from within a pod, create workload that uses the mount point. Create a YAML file similar to the following example:

```
apiVersion: v1
kind: Pod
metadata:
  name: ssd-benchmark1
spec:
  containers:
  - name: ssd-benchmark1
    image: nginx
    ports:
    - containerPort: 80
      name: "http-server"
    volumeMounts:
    - name: lun0p1
      mountPath: "/tmp"
  volumes:
  - name: lun0p1
    hostPath:
      path: /var/lib/lun0p1
      type: DirectoryOrCreate
  nodeSelector:
    disktype: ultrasdd
```

### 5.10.4.2. Troubleshooting resources for machine sets that enable ultra disks

Use the information in this section to understand and recover from issues you might encounter.

#### 5.10.4.2.1. Unable to mount a persistent volume claim backed by an ultra disk

If there is an issue mounting a persistent volume claim backed by an ultra disk, the pod becomes stuck in the **ContainerCreating** state and an alert is triggered.

For example, if the **additionalCapabilities.ultraSSDEnabled** parameter is not set on the machine that backs the node that hosts the pod, the following error message appears:

```
StorageAccountType UltraSSD_LRS can be used only when additionalCapabilities.ultraSSDEnabled is set.
```

- To resolve this issue, describe the pod by running the following command:

```
$ oc -n <stuck_pod_namespace> describe pod <stuck_pod_name>
```

### 5.10.5. Additional resources

- [Persistent storage using Azure Disk](#)
- [Configuring CSI volumes](#)

## 5.11. AZURE FILE CSI DRIVER OPERATOR

### 5.11.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) by using the Container Storage Interface (CSI) driver for Microsoft Azure File Storage.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.

To create CSI-provisioned PVs that mount to Azure File storage assets, OpenShift Container Platform installs the Azure File CSI Driver Operator and the Azure File CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- The *Azure File CSI Driver Operator* provides a storage class that is named **azurefile-csi** that you can use to create persistent volume claims (PVCs).
- The *Azure File CSI driver* enables you to create and mount Azure File PVs. The Azure File CSI driver supports dynamic volume provisioning by allowing storage volumes to be created on-demand, eliminating the need for cluster administrators to pre-provision storage.

Azure File CSI Driver Operator does not support:

- Virtual hard disks (VHD)
- Network File System (NFS): OpenShift Container Platform does not deploy a NFS-backed storage class.
- Running on nodes with FIPS mode enabled.

For more information about supported features, see [Supported CSI drivers and features](#).

### 5.11.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### Additional resources

- [Persistent storage using Azure File](#)
- [Configuring CSI volumes](#)

## 5.12. AZURE STACK HUB CSI DRIVER OPERATOR

### 5.12.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for Azure Stack Hub Storage. Azure Stack Hub, which is part of the Azure Stack portfolio, allows you to run apps in an on-premises environment and deliver Azure services in your datacenter.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.

To create CSI-provisioned PVs that mount to Azure Stack Hub storage assets, OpenShift Container Platform installs the Azure Stack Hub CSI Driver Operator and the Azure Stack Hub CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- The *Azure Stack Hub CSI Driver Operator* provides a storage class ( **managed-csi**), with "Standard\_LRS" as the default storage account type, that you can use to create persistent volume claims (PVCs). The Azure Stack Hub CSI Driver Operator supports dynamic volume provisioning by allowing storage volumes to be created on-demand, eliminating the need for cluster administrators to pre-provision storage.
- The *Azure Stack Hub CSI driver* enables you to create and mount Azure Stack Hub PVs.

### 5.12.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### 5.12.3. Additional resources

- [Configuring CSI volumes](#)

## 5.13. GCP PD CSI DRIVER OPERATOR

### 5.13.1. Overview

OpenShift Container Platform can provision persistent volumes (PVs) using the Container Storage Interface (CSI) driver for Google Cloud Platform (GCP) persistent disk (PD) storage.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a Container Storage Interface (CSI) Operator and driver.

To create CSI-provisioned persistent volumes (PVs) that mount to GCP PD storage assets, OpenShift Container Platform installs the GCP PD CSI Driver Operator and the GCP PD CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- **GCP PD CSI Driver Operator.** By default, the Operator provides a storage class that you can use to create PVCs. You also have the option to create the GCP PD storage class as described in [Persistent storage using GCE Persistent Disk](#).
- **GCP PD driver.** The driver enables you to create and mount GCP PD PVs.



### IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision GCP PD storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.

### 5.13.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### 5.13.3. GCP PD CSI driver storage class parameters

The Google Cloud Platform (GCP) persistent disk (PD) Container Storage Interface (CSI) driver uses the CSI **external-provisioner** sidecar as a controller. This is a separate helper container that is deployed with the CSI driver. The sidecar manages persistent volumes (PVs) by triggering the **CreateVolume** operation.

The GCP PD CSI driver uses the **csi.storage.k8s.io/fstype** parameter key to support dynamic provisioning. The following table describes all the GCP PD CSI storage class parameters that are supported by OpenShift Container Platform.

**Table 5.3. CreateVolume Parameters**

Parameter	Values	Default	Description
-----------	--------	---------	-------------

Parameter	Values	Default	Description
<b>type</b>	<b>pd-ssd</b> or <b>pd-standard</b>	<b>pd-standard</b>	Allows you to choose between standard PVs or solid-state-drive PVs.
<b>replication-type</b>	<b>none</b> or <b>regional-pd</b>	<b>none</b>	Allows you to choose between zonal or regional PVs.
<b>disk-encryption-kms-key</b>	Fully qualified resource identifier for the key to use to encrypt new disks.	Empty string	Uses customer-managed encryption keys (CMEK) to encrypt new disks.

#### 5.13.4. Creating a custom-encrypted persistent volume

When you create a **PersistentVolumeClaim** object, OpenShift Container Platform provisions a new persistent volume (PV) and creates a **PersistentVolume** object. You can add a custom encryption key in Google Cloud Platform (GCP) to protect a PV in your cluster by encrypting the newly created PV.

For encryption, the newly attached PV that you create uses customer-managed encryption keys (CMEK) on a cluster by using a new or existing Google Cloud Key Management Service (KMS) key.

##### Prerequisites

- You are logged in to a running OpenShift Container Platform cluster.
- You have created a Cloud KMS key ring and key version.

For more information about CMEK and Cloud KMS resources, see [Using customer-managed encryption keys \(CMEK\)](#).


##### Procedure

To create a custom-encrypted PV, complete the following steps:

1. Create a storage class with the Cloud KMS key. The following example enables dynamic provisioning of encrypted volumes:

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: csi-gce-pd-cmek
provisioner: pd.csi.storage.gke.io
volumeBindingMode: "WaitForFirstConsumer"
allowVolumeExpansion: true
parameters:
  type: pd-standard
  disk-encryption-kms-key: projects/<key-project-id>/locations/<location>/keyRings/<key-ring>/cryptoKeys/<key> 1
```

- 1 This field must be the resource identifier for the key that will be used to encrypt new disks. Values are case-sensitive. For more information about providing key ID values, see [Retrieving a resource's ID](#) and [Getting a Cloud KMS resource ID](#).



#### NOTE

You cannot add the **disk-encryption-kms-key** parameter to an existing storage class. However, you can delete the storage class and recreate it with the same name and a different set of parameters. If you do this, the provisioner of the existing class must be **pd.csi.storage.gke.io**.

2. Deploy the storage class on your OpenShift Container Platform cluster using the **oc** command:

```
$ oc describe storageclass csi-gce-pd-cmek
```

#### Example output

```
Name:          csi-gce-pd-cmek
IsDefaultClass: No
Annotations:   None
Provisioner:   pd.csi.storage.gke.io
Parameters:    disk-encryption-kms-key=projects/key-project-
id/locations/location/keyRings/ring-name/cryptoKeys/key-name,type=pd-standard
AllowVolumeExpansion: true
MountOptions:  none
ReclaimPolicy: Delete
VolumeBindingMode: WaitForFirstConsumer
Events:        none
```

3. Create a file named **pvc.yaml** that matches the name of your storage class object that you created in the previous step:

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: podpvc
spec:
  accessModes:
    - ReadWriteOnce
  storageClassName: csi-gce-pd-cmek
resources:
  requests:
    storage: 6Gi
```



#### NOTE

If you marked the new storage class as default, you can omit the **storageClassName** field.

4. Apply the PVC on your cluster:

```
$ oc apply -f pvc.yaml
```

- Get the status of your PVC and verify that it is created and bound to a newly provisioned PV:

```
$ oc get pvc
```

#### Example output

NAME	STATUS	VOLUME	CAPACITY	ACCESS MODES
podpvc	Bound	pvc-e36abf50-84f3-11e8-8538-42010a800002	10Gi	RWO
gce-pd-cmek	9s			csi-



#### NOTE

If your storage class has the **volumeBindingMode** field set to **WaitForFirstConsumer**, you must create a pod to use the PVC before you can verify it.

Your CMEK-protected PV is now ready to use with your OpenShift Container Platform cluster.

#### Additional resources

- [Persistent storage using GCE Persistent Disk](#)
- [Configuring CSI volumes](#)

## 5.14. IBM VPC BLOCK CSI DRIVER OPERATOR

### 5.14.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for IBM Virtual Private Cloud (VPC) Block Storage.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.

To create CSI-provisioned PVs that mount to IBM VPC Block storage assets, OpenShift Container Platform installs the IBM VPC Block CSI Driver Operator and the IBM VPC Block CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- The *IBM VPC Block CSI Driver Operator* provides three storage classes named **ibmc-vpc-block-10iops-tier** (default), **ibmc-vpc-block-5iops-tier**, and **ibmc-vpc-block-custom** for different tiers that you can use to create persistent volume claims (PVCs). The IBM VPC Block CSI Driver Operator supports dynamic volume provisioning by allowing storage volumes to be created on demand, eliminating the need for cluster administrators to pre-provision storage.
- The *IBM VPC Block CSI driver* enables you to create and mount IBM VPC Block PVs.

### 5.14.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.



CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### Additional resources

- [Configuring CSI volumes](#)

## 5.15. OPENSTACK CINDER CSI DRIVER OPERATOR

### 5.15.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for OpenStack Cinder.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a Container Storage Interface (CSI) Operator and driver.

To create CSI-provisioned PVs that mount to OpenStack Cinder storage assets, OpenShift Container Platform installs the OpenStack Cinder CSI Driver Operator and the OpenStack Cinder CSI driver in the **openshift-cluster-csi-drivers** namespace.

- The *OpenStack Cinder CSI Driver Operator* provides a CSI storage class that you can use to create PVCs.
- The *OpenStack Cinder CSI driver* enables you to create and mount OpenStack Cinder PVs.

For OpenShift Container Platform, automatic migration from OpenStack Cinder in-tree to the CSI driver is available as a Technology Preview (TP) feature. With migration enabled, volumes provisioned using the existing in-tree plugin are automatically migrated to use the OpenStack Cinder CSI driver. For more information, see [CSI automatic migration feature](#).

### 5.15.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.



#### IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision Cinder storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.

### 5.15.3. Making OpenStack Cinder CSI the default storage class

The OpenStack Cinder CSI driver uses the **cinder.csi.openstack.org** parameter key to support dynamic provisioning.

To enable OpenStack Cinder CSI provisioning in OpenShift Container Platform, it is recommended that you overwrite the default in-tree storage class with **standard-csi**. Alternatively, you can create the persistent volume claim (PVC) and specify the storage class as "standard-csi".

In OpenShift Container Platform, the default storage class references the in-tree Cinder driver. However, with CSI automatic migration enabled, volumes created using the default storage class actually use the CSI driver.

#### Procedure

Use the following steps to apply the **standard-csi** storage class by overwriting the default in-tree storage class.

1. List the storage class:

```
$ oc get storageclass
```

#### Example output

```
NAME                PROVISIONER          RECLAIMPOLICY  VOLUMEBINDINGMODE
ALLOWVOLUMEEXPANSION  AGE
standard(default)    cinder.csi.openstack.org  Delete         WaitForFirstConsumer  true
46h
standard-csi         kubernetes.io/cinder     Delete         WaitForFirstConsumer  true
46h
```

2. Change the value of the annotation **storageclass.kubernetes.io/is-default-class** to **false** for the default storage class, as shown in the following example:

```
$ oc patch storageclass standard -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class": "false"}}}'
```

3. Make another storage class the default by adding or modifying the annotation as **storageclass.kubernetes.io/is-default-class=true**.

```
$ oc patch storageclass standard-csi -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class": "true"}}}'
```

4. Verify that the PVC is now referencing the CSI storage class by default:

```
$ oc get storageclass
```

#### Example output

```
NAME                PROVISIONER          RECLAIMPOLICY  VOLUMEBINDINGMODE
ALLOWVOLUMEEXPANSION  AGE
standard            kubernetes.io/cinder     Delete         WaitForFirstConsumer  true
```

```
46h
standard-csi(default) cinder.csi.openstack.org Delete WaitForFirstConsumer true
46h
```

- Optional: You can define a new PVC without having to specify the storage class:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: cinder-claim
spec:
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 1Gi
```

A PVC that does not specify a specific storage class is automatically provisioned by using the default storage class.

- Optional: After the new file has been configured, create it in your cluster:

```
$ oc create -f cinder-claim.yaml
```

### Additional resources

- [Configuring CSI volumes](#)

## 5.16. OPENSTACK MANILA CSI DRIVER OPERATOR

### 5.16.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for the [OpenStack Manila](#) shared file system service.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a Container Storage Interface (CSI) Operator and driver.

To create CSI-provisioned PVs that mount to Manila storage assets, OpenShift Container Platform installs the Manila CSI Driver Operator and the Manila CSI driver by default on any OpenStack cluster that has the Manila service enabled.

- The *Manila CSI Driver Operator* creates the required storage class that is needed to create PVCs for all available Manila share types. The Operator is installed in the **openshift-cluster-csi-drivers** namespace.
- The *Manila CSI driver* enables you to create and mount Manila PVs. The driver is installed in the **openshift-manila-csi-driver** namespace.

### 5.16.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### 5.16.3. Manila CSI Driver Operator limitations

The following limitations apply to the Manila Container Storage Interface (CSI) Driver Operator:

#### Only NFS is supported

OpenStack Manila supports many network-attached storage protocols, such as NFS, CIFS, and CEPHFS, and these can be selectively enabled in the OpenStack cloud. The Manila CSI Driver Operator in OpenShift Container Platform only supports using the NFS protocol. If NFS is not available and enabled in the underlying OpenStack cloud, you cannot use the Manila CSI Driver Operator to provision storage for OpenShift Container Platform.

#### Snapshots are not supported if the back end is CephFS-NFS

To take snapshots of persistent volumes (PVs) and revert volumes to snapshots, you must ensure that the Manila share type that you are using supports these features. A Red Hat OpenStack administrator must enable support for snapshots (**share type extra-spec snapshot\_support**) and for creating shares from snapshots (**share type extra-spec create\_share\_from\_snapshot\_support**) in the share type associated with the storage class you intend to use.

#### FSGroups are not supported

Since Manila CSI provides shared file systems for access by multiple readers and multiple writers, it does not support the use of FSGroups. This is true even for persistent volumes created with the ReadWriteOnce access mode. It is therefore important not to specify the **fsType** attribute in any storage class that you manually create for use with Manila CSI Driver.



#### IMPORTANT

In Red Hat OpenStack Platform 16.x and 17.x, the Shared File Systems service (Manila) with CephFS through NFS fully supports serving shares to OpenShift Container Platform through the Manila CSI. However, this solution is not intended for massive scale. Be sure to review important recommendations in [CephFS NFS Manila-CSI Workload Recommendations for Red Hat OpenStack Platform](#).

### 5.16.4. Dynamically provisioning Manila CSI volumes

OpenShift Container Platform installs a storage class for each available Manila share type.

The YAML files that are created are completely decoupled from Manila and from its Container Storage Interface (CSI) plugin. As an application developer, you can dynamically provision ReadWriteMany (RWX) storage and deploy pods with applications that safely consume the storage using YAML manifests.

You can use the same pod and persistent volume claim (PVC) definitions on-premise that you use with OpenShift Container Platform on AWS, GCP, Azure, and other platforms, with the exception of the storage class reference in the PVC definition.



#### NOTE

Manila service is optional. If the service is not enabled in Red Hat OpenStack Platform (RHOSP), the Manila CSI driver is not installed and the storage classes for Manila are not created.

## Prerequisites

- RHOSP is deployed with appropriate Manila share infrastructure so that it can be used to dynamically provision and mount volumes in OpenShift Container Platform.

## Procedure (UI)

To dynamically create a Manila CSI volume using the web console:

1. In the OpenShift Container Platform console, click **Storage** → **Persistent Volume Claims**
2. In the persistent volume claims overview, click **Create Persistent Volume Claim**
3. Define the required options on the resulting page.
  - a. Select the appropriate storage class.
  - b. Enter a unique name for the storage claim.
  - c. Select the access mode to specify read and write access for the PVC you are creating.



### IMPORTANT

Use RWX if you want the persistent volume (PV) that fulfills this PVC to be mounted to multiple pods on multiple nodes in the cluster.

4. Define the size of the storage claim.
5. Click **Create** to create the persistent volume claim and generate a persistent volume.

## Procedure (CLI)

To dynamically create a Manila CSI volume using the command-line interface (CLI):

1. Create and save a file with the **PersistentVolumeClaim** object described by the following YAML:

### pvc-manila.yaml

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-manila
spec:
  accessModes: 1
  - ReadWriteMany
resources:
  requests:
    storage: 10Gi
  storageClassName: csi-manila-gold 2
```

- 1** Use RWX if you want the persistent volume (PV) that fulfills this PVC to be mounted to multiple pods on multiple nodes in the cluster.
- 2** The name of the storage class that provisions the storage back end. Manila storage classes are provisioned by the Operator and have the **csi-manila-** prefix.

2. Create the object you saved in the previous step by running the following command:

```
$ oc create -f pvc-manila.yaml
```

A new PVC is created.

3. To verify that the volume was created and is ready, run the following command:

```
$ oc get pvc pvc-manila
```

The **pvc-manila** shows that it is **Bound**.

You can now use the new PVC to configure a pod.

### Additional resources

- [Configuring CSI volumes](#)

## 5.17. RED HAT VIRTUALIZATION CSI DRIVER OPERATOR

### 5.17.1. Overview

OpenShift Container Platform is capable of provisioning persistent volumes (PVs) using the Container Storage Interface (CSI) driver for Red Hat Virtualization (RHV).

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a Container Storage Interface (CSI) Operator and driver.


To create CSI-provisioned PVs that mount to RHV storage assets, OpenShift Container Platform installs the oVirt CSI Driver Operator and the oVirt CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- The *oVirt CSI Driver Operator* provides a default **StorageClass** object that you can use to create Persistent Volume Claims (PVCs).
- The *oVirt CSI driver* enables you to create and mount oVirt PVs.

### 5.17.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.



#### NOTE

The oVirt CSI driver does not support snapshots.

### 5.17.3. Red Hat Virtualization (RHV) CSI driver storage class

OpenShift Container Platform creates a default object of type **StorageClass** named **ovirt-csi-sc** which is used for creating dynamically provisioned persistent volumes.

To create additional storage classes for different configurations, create and save a file with the **StorageClass** object described by the following sample YAML:

### ovirt-storageclass.yaml

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: <storage_class_name> ❶
  annotations:
    storageclass.kubernetes.io/is-default-class: "<boolean>" ❷
provisioner: csi.ovirt.org
allowVolumeExpansion: <boolean> ❸
reclaimPolicy: Delete ❹
volumeBindingMode: Immediate ❺
parameters:
  storageDomainName: <rhv-storage-domain-name> ❻
  thinProvisioning: "<boolean>" ❼
  csi.storage.k8s.io/fstype: <file_system_type> ❽
```

- ❶ Name of the storage class.
- ❷ Set to **false** if the storage class is the default storage class in the cluster. If set to **true**, the existing default storage class must be edited and set to **false**.
- ❸ **true** enables dynamic volume expansion, **false** prevents it. **true** is recommended.
- ❹ Dynamically provisioned persistent volumes of this storage class are created with this reclaim policy. This default policy is **Delete**.
- ❺ Indicates how to provision and bind **PersistentVolumeClaims**. When not set, **VolumeBindingImmediate** is used. This field is only applied by servers that enable the **VolumeScheduling** feature.
- ❻ The RHV storage domain name to use.
- ❼ If **true**, the disk is thin provisioned. If **false**, the disk is preallocated. Thin provisioning is recommended.
- ❽ Optional: File system type to be created. Possible values: **ext4** (default) or **xfs**.

#### 5.17.4. Creating a persistent volume on RHV

When you create a **PersistentVolumeClaim** (PVC) object, OpenShift Container Platform provisions a new persistent volume (PV) and creates a **PersistentVolume** object.

##### Prerequisites

- You are logged in to a running OpenShift Container Platform cluster.
- You provided the correct RHV credentials in **ovirt-credentials** secret.
- You have installed the oVirt CSI driver.

- You have defined at least one storage class.

## Procedure

- If you are using the web console to dynamically create a persistent volume on RHV:
  1. In the OpenShift Container Platform console, click **Storage** → **Persistent Volume Claims**
  2. In the persistent volume claims overview, click **Create Persistent Volume Claim**
  3. Define the required options on the resulting page.
  4. Select the appropriate **StorageClass** object, which is **ovirt-csi-sc** by default.
  5. Enter a unique name for the storage claim.
  6. Select the access mode. Currently, RWO (ReadWriteOnce) is the only supported access mode.
  7. Define the size of the storage claim.
  8. Select the Volume Mode:
    - Filesystem**: Mounted into pods as a directory. This mode is the default.
    - Block**: Block device, without any file system on it
  9. Click **Create** to create the **PersistentVolumeClaim** object and generate a **PersistentVolume** object.
- If you are using the command-line interface (CLI) to dynamically create a RHV CSI volume:
  1. Create and save a file with the **PersistentVolumeClaim** object described by the following sample YAML:

### pvc-ovirt.yaml

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-ovirt
spec:
  storageClassName: ovirt-csi-sc 1
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: <volume size> 2
      volumeMode: <volume mode> 3

```

- 1 Name of the required storage class.
- 2 Volume size in GiB.
- 3 Supported options:
  - **Filesystem**: Mounted into pods as a directory. This mode is the default.



- **Block:** Block device, without any file system on it.
2. Create the object you saved in the previous step by running the following command:

```
$ oc create -f pvc-ovirt.yaml
```

3. To verify that the volume was created and is ready, run the following command:

```
$ oc get pvc pvc-ovirt
```

The **pvc-ovirt** shows that it is Bound.

### Additional resources

- [Configuring CSI volumes](#)
- [Dynamic Provisioning](#)

## 5.18. VMWARE VSPHERE CSI DRIVER OPERATOR

### 5.18.1. Overview

OpenShift Container Platform can provision persistent volumes (PVs) using the Container Storage Interface (CSI) VMware vSphere driver for Virtual Machine Disk (VMDK) volumes.

Familiarity with [persistent storage](#) and [configuring CSI volumes](#) is recommended when working with a CSI Operator and driver.

To create CSI-provisioned persistent volumes (PVs) that mount to vSphere storage assets, OpenShift Container Platform installs the vSphere CSI Driver Operator and the vSphere CSI driver by default in the **openshift-cluster-csi-drivers** namespace.

- **vSphere CSI Driver Operator:** The Operator provides a storage class, called **thin-csi**, that you can use to create persistent volumes claims (PVCs). The vSphere CSI Driver Operator supports dynamic volume provisioning by allowing storage volumes to be created on-demand, eliminating the need for cluster administrators to pre-provision storage.
- **vSphere CSI driver:** The driver enables you to create and mount vSphere PVs. In OpenShift Container Platform 4.11, the driver version is 2.5.1. The vSphere CSI driver supports all of the file systems supported by the underlying Red Hat Core OS release, including XFS and Ext4. For more information about supported file systems, see [Overview of available file systems](#).



## IMPORTANT

OpenShift Container Platform defaults to using an in-tree (non-CSI) plugin to provision vSphere storage.

In future OpenShift Container Platform versions, volumes provisioned using existing in-tree plugins are planned for migration to their equivalent CSI driver. CSI automatic migration should be seamless. Migration does not change how you use all existing API objects, such as persistent volumes, persistent volume claims, and storage classes. For more information about migration, see [CSI automatic migration](#).

After full migration, in-tree plugins will eventually be removed in future versions of OpenShift Container Platform.



## NOTE

The vSphere CSI Driver supports dynamic and static provisioning. When using static provisioning in the PV specifications, do not use the key **storage.kubernetes.io/csiProvisionerIdentity** in **csi.volumeAttributes** because this key indicates dynamically provisioned PVs.

### 5.18.2. About CSI

Storage vendors have traditionally provided storage drivers as part of Kubernetes. With the implementation of the Container Storage Interface (CSI), third-party providers can instead deliver storage plugins using a standard interface without ever having to change the core Kubernetes code.

CSI Operators give OpenShift Container Platform users storage options, such as volume snapshots, that are not possible with in-tree volume plugins.

### 5.18.3. vSphere storage policy

The vSphere CSI Driver Operator storage class uses vSphere's storage policy. OpenShift Container Platform automatically creates a storage policy that targets datastore configured in cloud configuration:

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: thin-csi
provisioner: csi.vsphere.vmware.com
parameters:
  StoragePolicyName: "$openshift-storage-policy-xxxx"
volumeBindingMode: WaitForFirstConsumer
allowVolumeExpansion: false
reclaimPolicy: Delete
```

### 5.18.4. ReadWriteMany vSphere volume support

If the underlying vSphere environment supports the vSAN file service, then vSphere Container Storage Interface (CSI) Driver Operator installed by OpenShift Container Platform supports provisioning of ReadWriteMany (RWX) volumes. If vSAN file service is not configured, then ReadWriteOnce (RWO) is the only access mode available. If you do not have vSAN file service configured, and you request RWX, the volume fails to get created and an error is logged.

For more information about configuring the vSAN file service in your environment, see [vSAN File Service](#).

You can request RWX volumes by making the following persistent volume claim (PVC):

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: myclaim
spec:
  resources:
    requests:
      storage: 1Gi
  accessModes:
    - ReadWriteMany
  storageClassName: thin-csi
```

Requesting a PVC of the RWX volume type should result in provisioning of persistent volumes (PVs) backed by the vSAN file service.

### 5.18.5. VMware vSphere CSI Driver Operator requirements

To install the vSphere CSI Driver Operator, the following requirements must be met:

- VMware vSphere version 7.0 Update 1 or later
- Virtual machines of hardware version 15 or later
- No third-party vSphere CSI driver already installed in the cluster

#### IMPORTANT

If a third-party vSphere CSI driver is present in the cluster, OpenShift Container Platform does not overwrite it. If you continue with the third-party vSphere CSI driver when upgrading to the next major version of OpenShift Container Platform, the **oc** CLI prompts you with the following message:

```
VSphereCSIDriverOperatorCRUpgradeable: VMwareVSphereControllerUpgradeable:
found existing unsupported csi.vsphere.vmware.com driver
```

The previous message informs you that Red Hat does not support the third-party vSphere CSI driver during an OpenShift Container Platform upgrade operation. You can choose to ignore this message and continue with the upgrade operation.

To remove a third-party CSI driver, see [Removing a third-party vSphere CSI Driver](#).

### 5.18.6. Removing a third-party vSphere CSI Driver Operator

OpenShift Container Platform 4.11 includes a built-in version of the vSphere Container Storage Interface (CSI) Operator Driver that is supported by Red Hat.

If you have installed a vSphere CSI driver provided by the community or another vendor, which is considered a third-party vSphere CSI driver, and you continue with upgrading to the next major version of OpenShift Container Platform, the **oc** CLI prompts you with the following message:

VSphereCSIDriverOperatorCRUpgradeable: VMwareVSphereControllerUpgradeable:  
found existing unsupported csi.vsphere.vmware.com driver

The previous message informs you that Red Hat does not support the third-party vSphere CSI driver during an OpenShift Container Platform upgrade operation. You can choose to ignore this message and continue with the upgrade operation.

The instructions outlined in the procedure show how to uninstall a third-party vSphere CSI Driver. Consult the vendor's or community provider's uninstall guide for more detailed instructions on removing the driver and its components.



### IMPORTANT

When removing a third-party vSphere CSI driver, you do not need to delete the associated persistent volume (PV) objects. Data loss typically does not occur, but Red Hat does not take any responsibility if data loss does occur.

After you have removed the third-party vSphere CSI Driver from the OpenShift Container Platform cluster, installation of Red Hat's vSphere CSI Operator Driver automatically resumes. If you had existing vSphere CSI PV objects, their lifecycle is now managed by Red Hat's vSphere CSI Operator Driver.

### Procedure

1. Delete the third-party vSphere CSI Driver (VMware vSphere Container Storage Plugin) Deployment and Daemonset objects.
2. Delete the configmap and secret objects that were installed previously with the third-party vSphere CSI Driver.
3. Delete the third-party vSphere CSI driver **CSIDriver** object:

```
~ $ oc delete CSIDriver csi.vsphere.vmware.com
```

```
csidriver.storage.k8s.io "csi.vsphere.vmware.com" deleted
```

After you have removed the third-party vSphere CSI Driver from the OpenShift Container Platform cluster, installation of Red Hat's vSphere CSI Driver Operator automatically resumes, and any conditions that could block upgrades to OpenShift Container Platform 4.11, or later, are automatically removed. If you had existing vSphere CSI PV objects, their lifecycle is now managed by Red Hat's vSphere CSI Driver Operator.

### 5.18.7. Additional resources

- [Configuring CSI volumes](#)

## CHAPTER 6. GENERIC EPHEMERAL VOLUMES

### 6.1. OVERVIEW

Generic ephemeral volumes are a type of ephemeral volume that can be provided by all storage drivers that support persistent volumes and dynamic provisioning. Generic ephemeral volumes are similar to **emptyDir** volumes in that they provide a per-pod directory for scratch data, which is usually empty after provisioning.

Generic ephemeral volumes are specified inline in the pod spec and follow the pod's lifecycle. They are created and deleted along with the pod.

Generic ephemeral volumes have the following features:

- Storage can be local or network-attached.
- Volumes can have a fixed size that pods are not able to exceed.
- Volumes might have some initial data, depending on the driver and parameters.
- Typical operations on volumes are supported, assuming that the driver supports them, including snapshotting, cloning, resizing, and storage capacity tracking.



#### NOTE

Generic ephemeral volumes do not support offline snapshots and resize.

Due to this limitation, the following Container Storage Interface (CSI) drivers do not support the following features for generic ephemeral volumes:

- Azure Disk CSI driver does not support resize.
- Cinder CSI driver does not support snapshot.

### 6.2. LIFECYCLE AND PERSISTENT VOLUME CLAIMS

The parameters for a volume claim are allowed inside a volume source of a pod. Labels, annotations, and the whole set of fields for persistent volume claims (PVCs) are supported. When such a pod is created, the ephemeral volume controller then creates an actual PVC object (from the template shown in the *Creating generic ephemeral volumes* procedure) in the same namespace as the pod, and ensures that the PVC is deleted when the pod is deleted. This triggers volume binding and provisioning in one of two ways:

- Either immediately, if the storage class uses immediate volume binding. With immediate binding, the scheduler is forced to select a node that has access to the volume after it is available.
- When the pod is tentatively scheduled onto a node (**WaitForFirstConsumervolume** binding mode). This volume binding option is recommended for generic ephemeral volumes because then the scheduler can choose a suitable node for the pod.

In terms of resource ownership, a pod that has generic ephemeral storage is the owner of the PVCs that provide that ephemeral storage. When the pod is deleted, the Kubernetes garbage collector deletes the PVC, which then usually triggers deletion of the volume because the default reclaim policy of storage

classes is to delete volumes. You can create quasi-ephemeral local storage by using a storage class with a reclaim policy of retain: the storage outlives the pod, and in this case, you must ensure that volume clean-up happens separately. While these PVCs exist, they can be used like any other PVC. In particular, they can be referenced as data source in volume cloning or snapshotting. The PVC object also holds the current status of the volume.

### Additional resources

- [Creating generic ephemeral volumes](#)

## 6.3. SECURITY

Enabling the generic ephemeral volume feature allows users to create persistent volume claims (PVCs) indirectly if they can create pods, even if they do not have permission to create PVCs directly. Cluster administrators must be aware of this. If this does not fit their security model, they should use an admission webhook that rejects objects like pods that have a generic ephemeral volume.


The normal namespace quota for PVCs still applies, so even if users are allowed to use this new mechanism, they cannot use it to circumvent other policies.

## 6.4. PERSISTENT VOLUME CLAIM NAMING

Automatically created persistent volume claims (PVCs) are named by a combination of the pod name and the volume name, with a hyphen (-) in the middle. This naming convention also introduces a potential conflict between different pods, and between pods and manually created PVCs.

For example: a pod "pod-a" with volume "scratch" and another pod with name "pod" and volume: "a-scratch" both end up with the same PVC name: "pod-a-scratch".

Such conflicts are detected, and a PVC is only used for an ephemeral volume if it was created for the pod. This check is based on the ownership relationship. An existing PVC is not overwritten or modified, but this does not resolve the conflict because without the right PVC, the pod cannot start.



### IMPORTANT

Be careful when naming pods and volumes inside the same namespace so that naming conflicts do not occur.

## 6.5. CREATING GENERIC EPHEMERAL VOLUMES

### Procedure

1. Create the **pod** object definition and save it to a file.
2. Include the generic ephemeral volume information in the file.

#### my-example-pod-with-generic-vols.yaml

```
kind: Pod
apiVersion: v1
metadata:
  name: my-app
spec:
```

```
containers:
- name: my-frontend
  image: busybox:1.28
  volumeMounts:
  - mountPath: "/mnt/storage"
    name: data
  command: [ "sleep", "1000000" ]
volumes:
- name: data 1
  ephemeral:
  volumeClaimTemplate:
  metadata:
  labels:
  type: my-app-ephvol
  spec:
  accessModes: [ "ReadWriteOnce" ]
  storageClassName: "gp2-csi"
  resources:
  requests:
  storage: 1Gi
```

**1** Generic ephemeral volume claim

## CHAPTER 7. EXPANDING PERSISTENT VOLUMES

### 7.1. ENABLING VOLUME EXPANSION SUPPORT

Before you can expand persistent volumes, the **StorageClass** object must have the **allowVolumeExpansion** field set to **true**.

#### Procedure

- Edit the **StorageClass** object and add the **allowVolumeExpansion** attribute by running the following command:

```
$ oc edit storageclass <storage_class_name> 1
```

- 1 Specifies the name of the storage class.

The following example demonstrates adding this line at the bottom of the storage class configuration.

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
...
parameters:
  type: gp2
  reclaimPolicy: Delete
  allowVolumeExpansion: true 1
```

- 1 Setting this attribute to **true** allows PVCs to be expanded after creation.

### 7.2. EXPANDING CSI VOLUMES

You can use the Container Storage Interface (CSI) to expand storage volumes after they have already been created.

CSI volume expansion does not support the following:

- Recovering from failure when expanding volumes
- Shrinking

#### Prerequisites

- The underlying CSI driver supports resize.
- Dynamic provisioning is used.
- The controlling **StorageClass** object has **allowVolumeExpansion** set to **true** (see [Enabling volume expansion support](#)).

#### Procedure



1. For the persistent volume claim (PVC), set **.spec.resources.requests.storage** to the desired new size.
2. Watch the **status.conditions** field of the PVC to see if the resize has completed. OpenShift Container Platform adds the **Resizing** condition to the PVC during expansion, which is removed after expansion completes.

### 7.3. EXPANDING FLEXVOLUME WITH A SUPPORTED DRIVER

When using FlexVolume to connect to your back-end storage system, you can expand persistent storage volumes after they have already been created. This is done by manually updating the persistent volume claim (PVC) in OpenShift Container Platform.

FlexVolume allows expansion if the driver is set with **RequiresFSResize** to **true**. The FlexVolume can be expanded on pod restart.

Similar to other volume types, FlexVolume volumes can also be expanded when in use by a pod.

#### Prerequisites

- The underlying volume driver supports resize.
- The driver is set with the **RequiresFSResize** capability to **true**.
- Dynamic provisioning is used.
- The controlling **StorageClass** object has **allowVolumeExpansion** set to **true**.

#### Procedure

- To use resizing in the FlexVolume plugin, you must implement the **ExpandableVolumePlugin** interface using these methods:

##### **RequiresFSResize**

If **true**, updates the capacity directly. If **false**, calls the **ExpandFS** method to finish the filesystem resize.

##### **ExpandFS**

If **true**, calls **ExpandFS** to resize filesystem after physical volume expansion is done. The volume driver can also perform physical volume resize together with filesystem resize.



#### IMPORTANT

Because OpenShift Container Platform does not support installation of FlexVolume plugins on control plane nodes, it does not support control-plane expansion of FlexVolume.

### 7.4. EXPANDING LOCAL VOLUMES

You can manually expand persistent volumes (PVs) and persistent volume claims (PVCs) created by using the local storage operator (LSO).

#### Procedure

1. Expand the underlying devices, and ensure that appropriate capacity is available on these devices.
2. Update the corresponding PV objects to match the new device sizes by editing the **.spec.capacity** field of the PV.
3. For the storage class that is used for binding the PVC to PVet, set **allowVolumeExpansion:true**.
4. For the PVC, set **.spec.resources.requests.storage** to match the new size.

Kubelet should automatically expand the underlying file system on the volume, if necessary, and update the status field of the PVC to reflect the new size.

## 7.5. EXPANDING PERSISTENT VOLUME CLAIMS (PVCS) WITH A FILE SYSTEM

Expanding PVCs based on volume types that need file system resizing, such as GCE PD, EBS, and Cinder, is a two-step process. This process involves expanding volume objects in the cloud provider, and then expanding the file system on the actual node.

Expanding the file system on the node only happens when a new pod is started with the volume.

### Prerequisites

- The controlling **StorageClass** object must have **allowVolumeExpansion** set to **true**.

### Procedure

1. Edit the PVC and request a new size by editing **spec.resources.requests**. For example, the following expands the **ebs** PVC to 8 Gi.

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: ebs
spec:
  storageClass: "storageClassWithFlagSet"
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 8Gi 1
```

- 1 Updating **spec.resources.requests** to a larger amount will expand the PVC.

2. After the cloud provider object has finished resizing, the PVC is set to **FileSystemResizePending**. Check the condition by entering the following command:

```
$ oc describe pvc <pvc_name>
```

3. When the cloud provider object has finished resizing, the **PersistentVolume** object reflects the newly requested size in **PersistentVolume.Spec.Capacity**. At this point, you can create or recreate a new pod from the PVC to finish the file system resizing. Once the pod is running, the

newly requested size is available and the **FileSystemResizePending** condition is removed from the PVC.

## 7.6. RECOVERING FROM FAILURE WHEN EXPANDING VOLUMES

If expanding underlying storage fails, the OpenShift Container Platform administrator can manually recover the persistent volume claim (PVC) state and cancel the resize requests. Otherwise, the resize requests are continuously retried by the controller without administrator intervention.

### Procedure

1. Mark the persistent volume (PV) that is bound to the PVC with the **Retain** reclaim policy. This can be done by editing the PV and changing **persistentVolumeReclaimPolicy** to **Retain**.
2. Delete the PVC. This will be recreated later.
3. To ensure that the newly created PVC can bind to the PV marked **Retain**, manually edit the PV and delete the **claimRef** entry from the PV specs. This marks the PV as **Available**.
4. Re-create the PVC in a smaller size, or a size that can be allocated by the underlying storage provider.
5. Set the **volumeName** field of the PVC to the name of the PV. This binds the PVC to the provisioned PV only.
6. Restore the reclaim policy on the PV.

## CHAPTER 8. DYNAMIC PROVISIONING

### 8.1. ABOUT DYNAMIC PROVISIONING

The **StorageClass** resource object describes and classifies storage that can be requested, as well as provides a means for passing parameters for dynamically provisioned storage on demand.

**StorageClass** objects can also serve as a management mechanism for controlling different levels of storage and access to the storage. Cluster Administrators (**cluster-admin**) or Storage Administrators (**storage-admin**) define and create the **StorageClass** objects that users can request without needing any detailed knowledge about the underlying storage volume sources.

The OpenShift Container Platform persistent volume framework enables this functionality and allows administrators to provision a cluster with persistent storage. The framework also gives users a way to request those resources without having any knowledge of the underlying infrastructure.

Many storage types are available for use as persistent volumes in OpenShift Container Platform. While all of them can be statically provisioned by an administrator, some types of storage are created dynamically using the built-in provider and plugin APIs.

### 8.2. AVAILABLE DYNAMIC PROVISIONING PLUGINS

OpenShift Container Platform provides the following provisioner plugins, which have generic implementations for dynamic provisioning that use the cluster's configured provider's API to create new storage resources:

Storage type	Provisioner plugin name	Notes
Red Hat OpenStack Platform (RHOSP) Cinder	<b>kubernetes.io/cinder</b>	
RHOSP Manila Container Storage Interface (CSI)	<b>manila.csi.openstack.org</b>	Once installed, the OpenStack Manila CSI Driver Operator and ManilaDriver automatically create the required storage classes for all available Manila share types needed for dynamic provisioning.
AWS Elastic Block Store (EBS)	<b>kubernetes.io/aws-ebs</b>	For dynamic provisioning when using multiple clusters in different zones, tag each node with <b>Key=kubernetes.io/cluster/&lt;cluster_name&gt;,Value=&lt;cluster_id&gt;</b> where <b>&lt;cluster_name&gt;</b> and <b>&lt;cluster_id&gt;</b> are unique per cluster.
Azure Disk	<b>kubernetes.io/azure-disk</b>	

Storage type	Provisioner plugin name	Notes
Azure File	<b>kubernetes.io/azure-file</b>	The <b>persistent-volume-binder</b> service account requires permissions to create and get secrets to store the Azure storage account and keys.
GCE Persistent Disk (gcePD)	<b>kubernetes.io/gce-pd</b>	In multi-zone configurations, it is advisable to run one OpenShift Container Platform cluster per GCE project to avoid PVs from being created in zones where no node in the current cluster exists.
VMware vSphere	<b>kubernetes.io/vsphere-volume</b>	



### IMPORTANT

Any chosen provisioner plugin also requires configuration for the relevant cloud, host, or third-party provider as per the relevant documentation.

## 8.3. DEFINING A STORAGE CLASS

**StorageClass** objects are currently a globally scoped object and must be created by **cluster-admin** or **storage-admin** users.



### IMPORTANT

The Cluster Storage Operator might install a default storage class depending on the platform in use. This storage class is owned and controlled by the operator. It cannot be deleted or modified beyond defining annotations and labels. If different behavior is desired, you must define a custom storage class.

The following sections describe the basic definition for a **StorageClass** object and specific examples for each of the supported plugin types.

### 8.3.1. Basic StorageClass object definition

The following resource shows the parameters and default values that you use to configure a storage class. This example uses the AWS ElasticBlockStore (EBS) object definition.

#### Sample StorageClass definition

```
kind: StorageClass 1
apiVersion: storage.k8s.io/v1 2
metadata:
  name: <storage-class-name> 3
  annotations: 4
```

```

storageclass.kubernetes.io/is-default-class: 'true'
...
provisioner: kubernetes.io/aws-ebs 5
parameters: 6
  type: gp2
...

```

- 1** (required) The API object type.
- 2** (required) The current apiVersion.
- 3** (required) The name of the storage class.
- 4** (optional) Annotations for the storage class.
- 5** (required) The type of provisioner associated with this storage class.
- 6** (optional) The parameters required for the specific provisioner, this will change from plugin to plugin.

### 8.3.2. Storage class annotations

To set a storage class as the cluster-wide default, add the following annotation to your storage class metadata:

```
storageclass.kubernetes.io/is-default-class: "true"
```

For example:

```

apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  annotations:
    storageclass.kubernetes.io/is-default-class: "true"
...

```

This enables any persistent volume claim (PVC) that does not specify a specific storage class to automatically be provisioned through the default storage class. However, your cluster can have more than one storage class, but only one of them can be the default storage class.



#### NOTE

The beta annotation **storageclass.beta.kubernetes.io/is-default-class** is still working; however, it will be removed in a future release.

To set a storage class description, add the following annotation to your storage class metadata:

```
kubernetes.io/description: My Storage Class Description
```

For example:

```
apiVersion: storage.k8s.io/v1
```

```
kind: StorageClass
metadata:
  annotations:
    kubernetes.io/description: My Storage Class Description
  ...
```

### 8.3.3. RHOSP Cinder object definition

#### cinder-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: <storage-class-name> 1
provisioner: kubernetes.io/cinder
parameters:
  type: fast 2
  availability: nova 3
  fsType: ext4 4
```

- 1 Name of the storage class. The persistent volume claim uses this storage class for provisioning the associated persistent volumes.
- 2 Volume type created in Cinder. Default is empty.
- 3 Availability Zone. If not specified, volumes are generally round-robined across all active zones where the OpenShift Container Platform cluster has a node.
- 4 File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is **ext4**.

### 8.3.4. RHOSP Manila Container Storage Interface (CSI) object definition

Once installed, the OpenStack Manila CSI Driver Operator and ManilaDriver automatically create the required storage classes for all available Manila share types needed for dynamic provisioning.

### 8.3.5. AWS Elastic Block Store (EBS) object definition

#### aws-ebs-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: <storage-class-name> 1
provisioner: kubernetes.io/aws-ebs
parameters:
  type: io1 2
  iopsPerGB: "10" 3
```

```
encrypted: "true" 4
kmsKeyId: keyvalue 5
fsType: ext4 6
```

- 1** (required) Name of the storage class. The persistent volume claim uses this storage class for provisioning the associated persistent volumes.
- 2** (required) Select from **io1**, **gp2**, **sc1**, **st1**. The default is **gp2**. See the [AWS documentation](#) for valid Amazon Resource Name (ARN) values.
- 3** Optional: Only for **io1** volumes. I/O operations per second per GiB. The AWS volume plugin multiplies this with the size of the requested volume to compute IOPS of the volume. The value cap is 20,000 IOPS, which is the maximum supported by AWS. See the [AWS documentation](#) for further details.
- 4** Optional: Denotes whether to encrypt the EBS volume. Valid values are **true** or **false**.
- 5** Optional: The full ARN of the key to use when encrypting the volume. If none is supplied, but **encrypted** is set to **true**, then AWS generates a key. See the [AWS documentation](#) for a valid ARN value.
- 6** Optional: File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is **ext4**.

### 8.3.6. Azure Disk object definition

#### azure-advanced-disk-storageclass.yaml

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: <storage-class-name> 1
provisioner: kubernetes.io/azure-disk
volumeBindingMode: WaitForFirstConsumer 2
allowVolumeExpansion: true
parameters:
  kind: Managed 3
  storageaccounttype: Premium_LRS 4
reclaimPolicy: Delete
```

- 1** Name of the storage class. The persistent volume claim uses this storage class for provisioning the associated persistent volumes.
- 2** Using **WaitForFirstConsumer** is strongly recommended. This provisions the volume while allowing enough storage to schedule the pod on a free worker node from an available zone.
- 3** Possible values are **Shared** (default), **Managed**, and **Dedicated**.





## IMPORTANT

Red Hat only supports the use of **kind: Managed** in the storage class.

With **Shared** and **Dedicated**, Azure creates unmanaged disks, while OpenShift Container Platform creates a managed disk for machine OS (root) disks. But because Azure Disk does not allow the use of both managed and unmanaged disks on a node, unmanaged disks created with **Shared** or **Dedicated** cannot be attached to OpenShift Container Platform nodes.

- 4 Azure storage account SKU tier. Default is empty. Note that Premium VMs can attach both **Standard\_LRS** and **Premium\_LRS** disks, Standard VMs can only attach **Standard\_LRS** disks, Managed VMs can only attach managed disks, and unmanaged VMs can only attach unmanaged disks.
  - a. If **kind** is set to **Shared**, Azure creates all unmanaged disks in a few shared storage accounts in the same resource group as the cluster.
  - b. If **kind** is set to **Managed**, Azure creates new managed disks.
  - c. If **kind** is set to **Dedicated** and a **storageAccount** is specified, Azure uses the specified storage account for the new unmanaged disk in the same resource group as the cluster. For this to work:
    - The specified storage account must be in the same region.
    - Azure Cloud Provider must have write access to the storage account.
  - d. If **kind** is set to **Dedicated** and a **storageAccount** is not specified, Azure creates a new dedicated storage account for the new unmanaged disk in the same resource group as the cluster.

### 8.3.7. Azure File object definition

The Azure File storage class uses secrets to store the Azure storage account name and the storage account key that are required to create an Azure Files share. These permissions are created as part of the following procedure.

#### Procedure

1. Define a **ClusterRole** object that allows access to create and view secrets:

```
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRole
metadata:
  # name: system:azure-cloud-provider
  name: <persistent-volume-binder-role> 1
rules:
- apiGroups: [""]
  resources: ['secrets']
  verbs: ['get','create']
```

- 1 The name of the cluster role to view and create secrets.

2. Add the cluster role to the service account:

```
$ oc adm policy add-cluster-role-to-user <persistent-volume-binder-role>
system:serviceaccount:kube-system:persistent-volume-binder
```

3. Create the Azure File **StorageClass** object:

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: <azure-file> 1
provisioner: kubernetes.io/azure-file
parameters:
  location: eastus 2
  skuName: Standard_LRS 3
  storageAccount: <storage-account> 4
reclaimPolicy: Delete
volumeBindingMode: Immediate
```

- 1 Name of the storage class. The persistent volume claim uses this storage class for provisioning the associated persistent volumes.
- 2 Location of the Azure storage account, such as **eastus**. Default is empty, meaning that a new Azure storage account will be created in the OpenShift Container Platform cluster's location.
- 3 SKU tier of the Azure storage account, such as **Standard\_LRS**. Default is empty, meaning that a new Azure storage account will be created with the **Standard\_LRS** SKU.
- 4 Name of the Azure storage account. If a storage account is provided, then **skuName** and **location** are ignored. If no storage account is provided, then the storage class searches for any storage account that is associated with the resource group for any accounts that match the defined **skuName** and **location**.

### 8.3.7.1. Considerations when using Azure File

The following file system features are not supported by the default Azure File storage class:

- Symlinks
- Hard links
- Extended attributes
- Sparse files
- Named pipes

Additionally, the owner user identifier (UID) of the Azure File mounted directory is different from the process UID of the container. The **uid** mount option can be specified in the **StorageClass** object to define a specific user identifier to use for the mounted directory.

The following **StorageClass** object demonstrates modifying the user and group identifier, along with enabling symlinks for the mounted directory.

```

kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: azure-file
mountOptions:
  - uid=1500 1
  - gid=1500 2
  - mfsymlinks 3
provisioner: kubernetes.io/azure-file
parameters:
  location: eastus
  skuName: Standard_LRS
reclaimPolicy: Delete
volumeBindingMode: Immediate

```

- 1 Specifies the user identifier to use for the mounted directory.
- 2 Specifies the group identifier to use for the mounted directory.
- 3 Enables symlinks.

### 8.3.8. GCE PersistentDisk (gcePD) object definition

#### gce-pd-storageclass.yaml

```

apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: <storage-class-name> 1
provisioner: kubernetes.io/gce-pd
parameters:
  type: pd-standard 2
  replication-type: none
volumeBindingMode: WaitForFirstConsumer
allowVolumeExpansion: true
reclaimPolicy: Delete

```

- 1 Name of the storage class. The persistent volume claim uses this storage class for provisioning the associated persistent volumes.
- 2 Select either **pd-standard** or **pd-ssd**. The default is **pd-standard**.

### 8.3.9. VMware vSphere object definition

#### vsphere-storageclass.yaml

```

kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: <storage-class-name> 1

```

```
provisioner: kubernetes.io/vsphere-volume 2
```

```
parameters:
```

```
  diskformat: thin 3
```

- 1** Name of the storage class. The persistent volume claim uses this storage class for provisioning the associated persistent volumes.
- 2** For more information about using VMware vSphere with OpenShift Container Platform, see the [VMware vSphere documentation](#).
- 3** **diskformat: thin, zeroedthick** and **eagerzeroedthick** are all valid disk formats. See vSphere docs for additional details regarding the disk format types. The default value is **thin**.

## 8.4. CHANGING THE DEFAULT STORAGE CLASS

Use the following process to change the default storage class. For example you have two defined storage classes, **gp2** and **standard**, and you want to change the default storage class from **gp2** to **standard**.

1. List the storage class:

```
$ oc get storageclass
```

### Example output

NAME	TYPE
gp2 (default)	kubernetes.io/aws-ebs <b>1</b>
standard	kubernetes.io/aws-ebs

- 1** **(default)** denotes the default storage class.

2. Change the value of the **storageclass.kubernetes.io/is-default-class** annotation to **false** for the default storage class:

```
$ oc patch storageclass gp2 -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class": "false"}}}'
```

3. Make another storage class the default by setting the **storageclass.kubernetes.io/is-default-class** annotation to **true**:

```
$ oc patch storageclass standard -p '{"metadata": {"annotations": {"storageclass.kubernetes.io/is-default-class": "true"}}}'
```

4. Verify the changes:

```
$ oc get storageclass
```

### Example output

NAME	TYPE
gp2	kubernetes.io/aws-ebs
standard (default)	kubernetes.io/aws-ebs