



# **Red Hat 3scale 2-saas**

## **Accounts**

For Use with Red Hat 3scale 2-saas



# Red Hat 3scale 2-saas Accounts

---

For Use with Red Hat 3scale 2-saas

## Legal Notice

Copyright © 2018 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## Abstract

This guide documents account management with Red Hat 3scale 2-saas.


## Table of Contents

<b>CHAPTER 1. ACCOUNT CONFIGURATION</b>	<b>3</b>
1.1. STEP 1: ADD YOUR COMPANY INFORMATION	3
1.2. STEP 2: SELECT YOUR PREFERRED TIME ZONE	3
<b>CHAPTER 2. SINGLE SIGN ON FOR ADMIN PORTAL</b>	<b>4</b>
2.1. STEP 1: ENABLE RED HAT SSO OR AUTH0 MEMBER AUTHENTICATION	4
2.1.1. RH SSO Prerequisites	4
2.1.2. Auth0 Prerequisites	4
2.1.3. Enable SSO	4
2.2. STEP 2: USING SSO WITH 3SCALE	5
<b>CHAPTER 3. INVITING USERS AND MANAGING RIGHTS</b>	<b>6</b>
3.1. STEP 1: NAVIGATE TO USER ADMINISTRATION	6
3.2. STEP 2: SEND AN INVITATION	6
3.3. STEP 3: ACCEPT THE INVITATION	7
3.4. STEP 4: GIVE NEW USERS RIGHTS	7
<b>CHAPTER 4. NOTIFICATIONS</b>	<b>9</b>
4.1. TYPES OF NOTIFICATIONS	9
4.2. VISIBILITY	9
4.3. SUBSCRIBING TO NOTIFICATIONS BY EMAIL	9
4.4. WEB NOTIFICATIONS	9
<b>CHAPTER 5. PERSONAL SETTINGS</b>	<b>11</b>
5.1. TYPES OF SETTINGS	11
<b>CHAPTER 6. TOKENS</b>	<b>12</b>
6.1. ACCESS TOKENS	12
6.2. CREATING ACCESS TOKENS	12
6.3. USING ACCESS TOKENS	13
6.3.1. Service tokens	13



# CHAPTER 1. ACCOUNT CONFIGURATION

After creating your account, update basic information about your company. Set your location, contact information and add your company logo to the admin dashboard.



## NOTE

The account view is only visible to admins (and not to members).

## 1.1. STEP 1: ADD YOUR COMPANY INFORMATION

Once you've created your new account, click on the gear icon in the top navigation bar, and then on **Account** → **Overview** and click on *Edit* in the **Details** item. Fill in the information for your account.

RED HAT 3SCALE API MANAGEMENT Account Settings

Overview

Personal

Users

Integrate

Export

### Overview

#### Provider API key

Use this key when calling 3scale's API to authenticate yourself. This key should be kept secret between you and 3scale and never passed to other people.

We strongly suggest using [service tokens](#) to authenticate against the Service Management API and [access tokens](#) to authenticate against the Account Management API, the Analytics API and the Billing API. Their custom/limited access scopes make them inherently more secure than using this provider API key.

XXXXXXXX

#### Account Details [Edit](#)

Organization/Group Name Provider Name

Time Zone UTC

[Edit account](#)

The address you write here is what we use for billing purposes (if you are on a paid plan) and also what your user will see on your invoices if you're using the billing and payments modules.

## 1.2. STEP 2: SELECT YOUR PREFERRED TIME ZONE

On the same page you can also select the time zone you'd like to use on all system displays. This setting affects analytics graphs. However, billing cycle calculations are made according to UTC time.

## CHAPTER 2. SINGLE SIGN ON FOR ADMIN PORTAL

This guide provides information about how to configure and use single sign on with the 3scale admin portal

### 2.1. STEP 1: ENABLE RED HAT SSO OR AUTH0 MEMBER AUTHENTICATION

3scale supports single sign on (SSO) authentication for your members and admins.

The admin portal supports the following SSO providers, each which support a number of identity brokering and member federation options:

- [Red Hat SSO \(RH SSO\)](#)
- [Auth0](#)



#### NOTE

You can enable multiple SSO member authentication types

Only users that have been added to RH SSO or Auth0 will be able to access your 3scale admin portal through SSO. If you want to further restrict the access by either roles or user groups you should refer to the corresponding step by step tutorials on the [RH SSO](#) or [Auth0](#) support portals.

Once you have established SSO through your chosen provider, you must configure it and enable it on the 3scale admin portal.

#### 2.1.1. RH SSO Prerequisites

- An RH SSO instance and realm configured as described under the [Configuring Red Hat Single Sign-On](#) section of the developer portal documentation
- A 3scale Enterprise account

#### 2.1.2. Auth0 Prerequisites

- An Auth0 Subscription and account
- A 3scale Enterprise account

#### 2.1.3. Enable SSO

As an administrator, perform the following steps in the 3scale admin panel to enable RH SSO or Auth0:

1. Ensure your preferred SSO provider, highlighted in the prerequisites, has been properly configured
2. Navigate to SSO Integrations in the Account Settings:
  - Click the gear icon in the upper right corner of the page
  - Navigate to **Account Settings (gear icon) > Users > SSO Integrations**, and click **New SSO Integration**.



3. Select your SSO provider from the dropdown list
4. Enter the required information, provided when you configured your SSO:
  - Client
  - Client Secret
  - Realm or Site
5. Click **Create Authentication Provider**

**NOTE**

If, during testing, you encounter a callback URL mismatch, add the callback URL shown in the error message to your Auth0 allowed callback URLs.

## 2.2. STEP 2: USING SSO WITH 3SCALE

Once you have configured SSO, members can sign on using the account credentials in connected IdPs.

Follow these steps to log in to the 3scale Admin portal using SSO:

1. Navigate to your 3scale login page:

`https://<organization>-admin.3scale.net/p/login`

2. Authorize 3scale with your IdP
3. If necessary, complete sign up by entering any needed information

Once you successfully sign up, you will have a member account under the API provider organization, and you will be automatically logged in.


## CHAPTER 3. INVITING USERS AND MANAGING RIGHTS

In order to share the workload of administering your APIs, you may wish to invite team members from your organization to access the 3scale Admin Portal. In this tutorial, you'll see how to that and what types of roles and rights are available. **Note:** The 'invite' feature is only available for Pro and Enterprise customers.

We'll walk you through how to give access rights to the 3scale Admin Portal to one or more team members.

### 3.1. STEP 1: NAVIGATE TO USER ADMINISTRATION


On the Admin Portal top navigation bar, click on the gear icon. Then, navigate to **Users > Listing** from the left side menu.



When we refer to users, we're talking about members of your team. The 3scale Admin Portal has two types of users:

- **Admins:** Which have full access to all areas and services, and can invite other members (if your plan allows it).
- **Members:** Which have limited access to areas of the product (e.g. Analytics, Developer Portal) and, if you're an enterprise customer, also to services.

From the menu, click on the *Invite user* link.



### 3.2. STEP 2: SEND AN INVITATION

You can find invitations in **Users > Invitations**.

RED HAT 3SCALE API MANAGEMENT Account Settings ▾

Overview

Personal >

Users ▾

Listing

Invitations

SSO Integrations

## Invite a New Team Member

Send invitation to

Email address of a colleague or friend you want to invite to this account

**Email address**

Enter the email address of the person you want to invite and click send. An invitation email will be sent to the address you entered. If the email doesn't arrive, make sure it didn't get marked as spam.

### 3.3. STEP 3: ACCEPT THE INVITATION

Your new administrator or member must click the link in the invitation email and complete the form to complete the process. Once the form is submitted, their account will be activated.

### 3.4. STEP 4: GIVE NEW USERS RIGHTS

There are two main type of rights you can give to members of your team:

- **By area:** Such as analytics, billing, or developer administration.
- **By service:** Choose which services to give access to members amongst all of your services.  
**Note:** This feature is only available for enterprise customers.

To give a new user rights, edit the new user by selecting them from the user menu and clicking on *Edit*.

Changing their rights to "admin" will give them full access to control the dashboard.

Changing their rights to "member" will give you the option of choosing which areas and services the team member has access to.

RED HAT 3SCALE API MANAGEMENT Account Settings ▾

Overview

Personal >

Users ▾

Listing

Invitations

SSO Integrations

Integrate >

Export

This user can access

☒ Developer Portal

☒ Billing

☐ Settings

**Select areas**

☒ Developer Accounts -- Applications

☐ Analytics

☐ Integration & Application Plans

☐ All current and future APIs

**Select services**

☒ Echo API

☐ Scratch API

Integration & Application Plans

Analytics

Applications

Giving members access to certain areas of the 3scale Admin Portal will give them access only to the equivalent API:

- **Developer accounts — Applications:** Gives access to the Account management API

- Analytics: Gives access to the Analytics API
- Billing: Gives access to the Billing API

## CHAPTER 4. NOTIFICATIONS

Notifications are sent to admins and members to make it easier to parse developer activity (new account

### 4.1. TYPES OF NOTIFICATIONS

There are different types of notifications:

- Accounts
- Billing
- Applications
- Service subscriptions
- Usage alerts

### 4.2. VISIBILITY

Admin users have access to all notifications.


Member users have access only to notifications of the areas they have been given access to. For example, a member will only have access to notifications related to billing if they have access to the billing section.

For **enterprise accounts**, member users will only have access to notifications regarding activity of the services they have been granted access to.

### 4.3. SUBSCRIBING TO NOTIFICATIONS BY EMAIL

Subscriptions are personal and can only be modified by the person receiving those notifications. To edit your subscriptions:

1. Navigate to **Account Settings (gear icon) > Personal > Notification Preferences**
2. Check the notifications you would like to receive.



The screenshot shows the Red Hat 3Scale API Management interface. The top navigation bar includes the Red Hat 3Scale logo, 'API MANAGEMENT', and 'Account Settings' with a dropdown arrow. A sidebar on the left contains links: Overview, Personal (selected), Personal Details, Tokens, Notification Preferences (active), Users, Integrate, and Export. The main content area is titled 'Notification Preferences' and includes a description: 'Events originate from interactions with the 3scale interface & the 3scale API. They can be triggered by developers, you, your team & 3scale. You will only receive API-related notifications for those APIs that you have access to.' Below this, under the 'ACCOUNTS' heading, there is a list of notification types with checkboxes: 'New account created' (checked), 'Account plan change request' (checked), 'Account deleted' (checked), and 'New messages' (checked). Each item has a brief description of when the notification is sent.

### 4.4. WEB NOTIFICATIONS

In addition to email notifications, these can be found in your Dashboard:

RED HAT 3SCALE API MANAGEMENT

Dashboard

AUDIENCE

5 ACCOUNTS (2 PLANS)

6 APPS

BILLING

PORTAL (2 DRAFTS)

0 MESSAGES

0 Signups

last 30 days

-100%

vs. previous 30 days

Potential Upgrades

Accounts that hit their Usage Limits in the last 30 days

In order to show Potential Upgrades, add 1 or more usage limits to your [Application Plans](#).

Furthermore, [Web Alerts for Admins of this Account of 100% \(and up\)](#) should be enabled for service(s) with usage limits.

TODAY

metro from Metro signed up

Metro's App created on Echo API

tester from tester inc signed up

tester inc's App created on Echo API

barba papa's App created on Echo API

barbapapa from barba papa signed up

Feasible Inc. has subscribed to your service Echo API

feasible from Feasible Inc. signed up

Feasible Inc.'s App created on Echo API

All APIs

## CHAPTER 5. PERSONAL SETTINGS

In Personal settings you can edit your preferences as a team member. If you're an admin, you will also be able to edit the account preferences. For that, check out the [account configuration](#) tutorial.

### 5.1. TYPES OF SETTINGS

There are 3 types of settings you can edit from here

- **Personal Details:** Name, email, password, etc.
- **Tokens:** Create access tokens to authenticate against the 3scale APIs – Billing, Account Management, and Analytics – and try them out using our ActiveDocs (interactive documentation). Learn more about [3scale tokens](#).
- **Notification Preferences:** Select which notifications you'd like to receive. Note: If you're an enterprise customer, and if you are a member, these are filtered by area and service. This means you'll only be able to subscribe to notifications re: areas and services you've been given access to. More on [notification preferences here](#).

**RED HAT 3SCALE** API MANAGEMENT Account Settings

**Personal Details**

USER INFORMATION

Username  
admin

Email  
admin@3scale.poc-sd.staging.3sca.net

New Password

PROVIDE YOUR CURRENT PASSWORD AND UPDATE YOUR PERSONAL DETAILS

Current password

Any other active session(s) for this user account will be terminated when you update your personal details to be sure it's you and not somebody else trying to lock you out of your account.

Update Details

## CHAPTER 6. TOKENS

In this tutorial you'll learn about 3scale tokens: what are they, how they work, and how to create them.

3scale has two types of tokens: **Access tokens** (created by the user) and **Service tokens** (automatically created when you create a new service in 3scale).

### 6.1. ACCESS TOKENS


Access tokens allow API provider admins and members to authenticate against the 3scale APIs – Billing, Account management, and Analytics – and try them out using our [ActiveDocs](#) (interactive documentation).

An access token may provide either read and write access, or read only.

An important thing to take into account is how access tokens work, which is according to the member's rights. Admins can create tokens to authenticate against all three 3scale APIs. Members will be limited by their permissions to access the different parts of the Admin Portal. For example, if a member doesn't have access to the Billing area, they won't be able to create a token to authenticate against the Billing API.


### 6.2. CREATING ACCESS TOKENS

Access tokens can be created on the tokens page. To access the tokens page, click on the gear icon in the upper right corner of the page, and then navigate to **Personal > Tokens**.



Click on **Add Access Token** and choose a name, scope, and permissions.





The screenshot shows the 'RED HAT 3SCALE API MANAGEMENT' header with a dark navigation sidebar on the left. The sidebar contains links for Overview, Personal (selected), Personal Details, Tokens, Notification Preferen..., Users, Integrate, and Export. The main content area is titled 'New Access Token' and contains a form with the following fields:

- Name:** A text input field.
- Scopes:** A section with three checkboxes:
  - ☐ Billing API
  - ☐ Account Management API
  - ☐ Analytics API
- Permission:** A dropdown menu currently showing 'Read Only'.

Note that if you are a member, you might not see all the APIs – just the ones you’ve been given access to by the admin of your account.

You can create as many access tokens as you need, but take into account that for security reasons, they won’t be stored on 3scale. When you create a new token, you’ll be alerted to save the token so you can then use it to make requests to the 3scale API. If you lose a token, we recommend that you delete it – which will disable it and render it invalid – then create a new one.

## 6.3. USING ACCESS TOKENS

When using your access token to make calls to the 3scale APIs the results will be filtered by the services you have access to.


For example, when deploying APIcast self-managed, you’ll need an access token so your APIcast API gateway can pull the configuration of the service using the Account Management API.

The way it works is if your organization has set up three services on 3scale, and as a member, you have access to Service 1, but not 2 and 3, and you also have access to the Account Management API, when you create a token and make a request to the Account Management API you will only get the applications which are using Service 1.




Following the same example, if you have access to the Account Management API, but access to zero services, when making a call, you’ll get "access denied" error.

### 6.3.1. Service tokens

Service tokens are used to authenticate against 3scale Service Management API. Service tokens are generated automatically when a new service is created in 3scale, and are unique per service. They are shared among the users of the 3scale account. You can find the service tokens for the services that the user has access to in the Admin portal: **Account Settings (gear icon) > Personal > Tokens**

 RED HAT 3SCALE API MANAGEMENT

Account Settings ▾



Overview

Personal ▾

Personal Details

Tokens

Notification Preferen...


Users >

Integrate >

Export

Full RW

Billing API, Account Management API, and Analytics API

Read & Write 

### Service Tokens

Service tokens let you authenticate against the Service Management API. Service tokens are auto generated, unique per service and shared between the users of this account. Use Service Tokens from within the [3scale API docs](#).

Service name	Scope	Permission	Token
Echo API	Service management API	Read & Write	xxxxxxx
Scratch API	Service management API	Read & Write	xxxxxxx
camel-rest-sql	Service management API	Read & Write	xxxxxxx
well that's a nice name	Service management API	Read & Write	xxxxxxx
Test	Service management API	Read & Write	xxxxxxx