



# **Red Hat Gluster Storage 3.4**

## **Monitoring Guide**

Monitoring Gluster Cluster



# Red Hat Gluster Storage 3.4 Monitoring Guide

---

Monitoring Gluster Cluster

Rakesh Ghatvisave

Red Hat Customer Content Services

[rghatvis@redhat.com](mailto:rghatvis@redhat.com)

## Legal Notice

Copyright © 2018 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## Abstract

This guide provides essential information on how to import a Gluster cluster using Red Hat Gluster Storage Web Administration and how to monitor your Gluster cluster health, performance, and status. The monitoring and metrics visualization is provided by the Grafana monitoring platform which is integrated into the Web Administration interface.

## Table of Contents

<b>CHAPTER 1. OVERVIEW</b>	<b>4</b>
<b>CHAPTER 2. IMPORT CLUSTER</b>	<b>5</b>
2.1. IMPORTING CLUSTER	5
2.1.1. Troubleshooting Import Cluster	8
2.1.2. Volume Profiling	8
<b>CHAPTER 3. CLUSTER EXPANSION</b>	<b>12</b>
3.1. UNMANAGING CLUSTER	14
3.2. TROUBLESHOOTING CLUSTER EXPANSION	16
<b>CHAPTER 4. MONITORING AND METRICS</b>	<b>17</b>
<b>CHAPTER 5. MONITORING DASHBOARD AND CONCEPTS</b>	<b>18</b>
5.1. DASHBOARD SELECTOR	18
5.2. DASHBOARD PANELS	18
5.3. DASHBOARD ROWS	20
5.4. DASHBOARD COLOR CODES	21
<b>CHAPTER 6. MONITORING DASHBOARD FEATURES</b>	<b>22</b>
6.1. DASHBOARD SEARCH	22
6.2. DASHBOARD TIME RANGE	22
6.3. DASHBOARD SHARING	23
<b>CHAPTER 7. MONITORING DASHBOARD NAVIGATION</b>	<b>24</b>
7.1. CLUSTER VIEW DASHBOARD	24
7.2. HOSTS VIEW DASHBOARD	24
7.3. VOLUME VIEW DASHBOARD	25
7.4. BRICK VIEW DASHBOARD	25
<b>CHAPTER 8. MONITORING CLUSTER METRICS</b>	<b>26</b>
8.1. CLUSTER LEVEL DASHBOARD	26
8.1.1. Monitoring and Viewing Cluster Health	26
8.1.1.1. Health and Snapshots	26
8.1.1.2. Hosts, Volumes and Bricks	26
8.1.1.3. Geo-Replication Session	27
8.1.1.4. Health Panel Descriptions	28
8.1.2. Monitoring and Viewing Cluster Performance	28
8.1.3. Top Consumers	31
8.1.4. Monitoring and Viewing Cluster Status	33
8.2. HOST LEVEL DASHBOARD	36
8.2.1. Monitoring and Viewing Health and Status	36
8.2.2. Monitoring and Viewing Performance	38
8.2.2.1. Memory and CPU Utilization	38
8.2.2.2. Capacity and Disk Load	41
8.2.2.3. Network	45
8.2.3. Host Dashboard Metric Units	47
8.3. VOLUME LEVEL DASHBOARD	48
8.3.1. Monitoring and Viewing Health	48
8.3.2. Monitoring and Viewing Performance	52
8.3.3. Monitoring File Operations	57
8.3.4. Volume Dashboard Metric Units	59
8.4. BRICK LEVEL DASHBOARD	60

8.4.1. Monitoring and Viewing Brick Status	60
8.4.2. Monitoring and Viewing Brick Performance	60
8.4.3. Brick Dashboard Metric Units	66
<b>CHAPTER 9. USERS AND ROLES ADMINISTRATION .....</b>	<b>68</b>
9.1. USER ROLES	68
9.2. CONFIGURING ROLES	68
9.2.1. Editing Users	69
9.2.2. Disabling Notifications and Deleting User	70
<b>CHAPTER 10. ALERTS AND NOTIFICATIONS .....</b>	<b>72</b>
10.1. TYPES OF ALERTS	72
10.2. LIST OF ALERTS	72
10.3. ALERTS NOTIFICATIONS DRAWER	73
10.4. SMTP NOTIFICATIONS CONFIGURATION	74
10.5. SNMPV3 NOTIFICATION CONFIGURATION	75



## CHAPTER 1. OVERVIEW

Red Hat Gluster Storage Web Administration provides visual monitoring and metrics infrastructure for Red Hat Gluster Storage 3.4 and is the primary method to monitor your Red Hat Gluster Storage environment. The Red Hat Gluster Storage Web Administration is based on the Tendrl upstream project and utilizes Ansible automation for installation. The key goal of Red Hat Gluster Storage Web Administration is to provide deep metrics and visualization of Red Hat Storage Gluster clusters and the associated physical storage elements such as storage nodes, volumes, and bricks.

### Key Features

1. Monitoring dashboards for Clusters, Hosts, Volumes, and Bricks
2. Top-level list views of Clusters, Hosts, and Volumes
3. SNMPv3 Configuration and alerting
4. User Management
5. Importing Gluster cluster



## CHAPTER 2. IMPORT CLUSTER


You can import and start managing a cluster once Web Administration is installed and ready. For installation instructions, see the [Installing Web Administration](#) chapter of the Red Hat Gluster Storage Web Administration Quick Start Guide.

### 2.1. IMPORTING CLUSTER

The following procedure outlines the steps to import a Gluster cluster.

#### Procedure. Importing Cluster

1. Log in to the Web Administration interface. Enter the username and password, and click **Log In**.



#### NOTE

The default username is **admin** and the default password is **adminuser**.

Figure 2.1. Login Page

2. In the default landing interface, a list of all the clusters ready to be imported is displayed. Locate the cluster to be imported and click **Import**.

Figure 2.2. Import Cluster

	Cluster Version	Managed	Hosts	
? 0354fa28-78b4-47c4-a960-4aa1130d8771	RHGS 3.4.0	No	6	Import

3. Enter a user-friendly Cluster name. By default, the **Enable for all volumes** option is selected.

**Figure 2.3. Cluster name**

[Clusters](#) » Import Cluster

## Import Cluster

Cluster Name

Only alphanumeric and underscore characters are allowed.

Ensure all hosts in the cluster are listed below, then click Import to begin importing the cluster.

### Volume Profiling

- ☒ Enable for all volumes
- ☐ Disable for all volumes
- ☐ Keep current configuration

Discovered Host(s)

Name ▾

*Filter by Name*

---

6 of 6 Discovered - Hosts -



### NOTE

If the cluster name is not provided, the system will assign a randomly generated uuid as a cluster name. However, it is advisable to enter a user-friendly cluster name to easily locate the cluster from the clusters list.

4. Click **Import** to continue.

## 6 of 6 Discovered - Hosts -

Host ^
tendrl-usm1-gl1.example.org
tendrl-usm1-gl2.example.org
tendrl-usm1-gl3.example.org
tendrl-usm1-gl4.example.org
tendrl-usm1-gl5.example.org
tendrl-usm1-gl6.example.org

1. The cluster import request is submitted. To view the task progress, click **View Task Progress**.

Figure 2.4. Task Detail



### Import Cluster Task Submitted

An import cluster task has been submitted. You will be notified when processing is complete and the cluster is ready for use.

2. Navigate to the **All Clusters** interface view. The Cluster is successfully imported and ready for use.


Figure 2.5. Cluster Ready

Clusters

Name ▾

Name ▾ ↓↑ A Z

1 Cluster

	ClusterA	Cluster Version	Managed	Hosts	Volumes	Alerts	Volume Profiling	Ready to Use
		RHGS 3.4.0	Yes	6	3	1	Enabled	

2.1.1. Troubleshooting Import Cluster

Scenario: The Import cluster UI button is disabled after a failed cluster import operation.

In this scenario, when cluster import fails, the Import button is disabled.

Resolution

Resolve the issue by investigating why the import cluster operation failed. To see details of the failed operation, navigate to the **All Clusters** interface of the Web Administration environment. In the clusters list, locate the cluster that you attempted to import and click on **View Details** next to the **Import Failed** status label.

Examine the reason of the failed cluster import operation and resolve the issue. After resolving the issue, unmanage the cluster and then reimport the cluster. For unmanaging cluster instructions, navigate to the [Unmanaging Cluster](#) section of this Guide.

2.1.2. Volume Profiling

Volume profiling enables additional telemetry information to be collected on a per volume basis for a given cluster, which helps in troubleshooting, capacity planning, and performance tuning.

Volume profiling can be enabled or disabled on a per cluster basis and per volume basis when a cluster is actively managed and monitored using the Web Administration interface.



**NOTE**

Enabling volume profiling results in richer set of metrics being collected which may cause performance degradation to occur as system resources, for example, CPU and memory, may get used for volume profiling data collection.

Volume Profiling at Cluster Level

To enable or disable volume profiling at cluster level:

- 1. Log in to the Web Administration interface
- 2. From the Clusters list, locate the cluster to disable Volume Profiling.




**NOTE**

Clusters list is the default landing interface after login and the Interface switcher is on **All Clusters**.

3. At the right-hand side, next to the Dashboard button, click the vertical ellipsis.
4. An inline menu is opened. Click **Disable Profiling** or **Enable Profiling** depending on the current state. In the example screen below, Volume Profiling option is enabled. Click **Disable Profiling** to disable.

**Figure 2.6. Disable Volume Profiling**



5. The disable profiling task is submitted and processed. After processing, Volume Profiling is successfully disabled.

**Figure 2.7. Disable Volume Profiling**


Hosts	Volumes	Alerts	Volume Profiling
4	1	0	Disabled

### Volume Profiling at Volume Level

To enable or disable volume profiling at Volume level:


1. Log in to the Web Administration interface and select the specific cluster from the Interface switcher drop-down.
2. After selecting the specific cluster, the left vertical navigation pane is exposed.
3. From the navigation pane, click **Volumes**. The Volumes view is displayed listing all the Volumes part of the cluster.

Figure 2.8. Volumes View




4. Locate the volume and click **Disable Profiling** or **Enable Profiling** depending on the current state. In the example screen below, Volume Profiling is enabled. To disable volume profiling, click **Disable Profiling**.

Figure 2.9. Disable Volume Profiling



5. The disable profiling task is submitted and processed. After processing, Volume Profiling is successfully disabled.

Figure 2.10. Disable Volume Profiling



Volume Profiling Metrics

When volume profiling is disabled, the following metrics will not be displayed in the Grafana Dashboard. Based on the metrics required to view, enable or disable volume profiling accordingly.

For detailed information on Volume Profiling, see the [Monitoring Red Hat Gluster Storage Gluster Workload](#) chapter of the Red Hat Gluster Storage Administration Guide.

Table 2.1. Volume Profiling Metrics

Grafana Dashboard Level	Dashboard Section	Panel and Metrics
Cluster Dashboard	At-a-glance	IOPS
Host Dashboard	At-a-glance	Brick IOPS
Volume Dashboard	Performance	IOPS
Volume Dashboard	Profiling Information	File Operations For Locks
Volume Dashboard	Profiling Information	Top File Operations

Grafana Dashboard Level	Dashboard Section	Panel and Metrics
Volume Dashboard	Profiling Information	File Operations for Read/Write
Volume Dashboard	Profiling Information	File Operations for Inode Operations
Volume Dashboard	Profiling Information	File Operations for Entry Operations
Brick Dashboard	At-a-glance	IOPS

## CHAPTER 3. CLUSTER EXPANSION


To expand an existing Gluster cluster already imported and managed by the Web Administration environment, perform the following sequence of actions:

### Create New Nodes

Before initiating cluster expansion in the Web Administration interface, create new Gluster storage nodes to be imported in Web Administration. For detailed instructions, see the [Expanding Volumes](#) section in the *Red Hat Gluster Storage Administration Guide*

### New Alert

After successfully expanding the cluster with new nodes, an alert is generated in the Notifications panel of the Web Administration interface as displayed in the following screen:



In this screen, new peers represents new storage nodes that were created in the previous cluster expansion process.

### New Event

Additionally, a new Event is also generated about the availability of new storage nodes for expansion as displayed in the following screen:



### Running Tendrl-ansible installation for new nodes



After the storage nodes are identified by Web Administration, run `tendr1-ansible` installation by adding the new hosts in the inventory file. For detailed installation instructions, see the [Installing Web Administration](#) chapter in the Red Hat Gluster Storage Web Administration Quick Start Guide.

## Cluster Expansion in Web Administration


After `tendr1-ansible` is executed, the expand cluster option becomes available in the Web Administration interface. Follow these instructions to expand the cluster:

### Procedure. Expanding Cluster

1. Log in to the Web Administration interface and click **All Clusters** interface from the interface selector drop-down.
2. In the Clusters view, locate the cluster to be expanded. It will be labelled as **Expansion required**.

<b>Alerts</b>	<b>Volume Profiling</b>	<b>Expansion required</b>
3	Enabled	

3. At the far right of the cluster row, click the vertical ellipsis and then click **Expand**.



4. The available hosts to be added are listed. Click **Expand**.

**Expand Cluster**

ClusterA will be expanded by importing the new hosts listed below. Further actions will not be allowed on this cluster until expansion is complete.

Name ▾

Filter by Name

**2 Hosts Discovered**

Host ^	Address
tendrl-usm1-gl5.example.org	10.37.169.27
tendrl-usm1-gl6.example.org	10.37.169.224

Cancel

**Expand**

5. The cluster expansion task is submitted.

Expanding Cluster. [View Details](#)

6. The cluster is successfully expanded and ready for use.

Cluster Version	Managed	Hosts	Volumes	Alerts	Volume Profiling	Ready to Use
RHGS 3.4.0	Yes	6	1	3	Enabled	

### 3.1. UNMANAGING CLUSTER


The following are the reasons to unmanage a cluster:

1. Import cluster fails
2. Removal of a cluster that is no longer under management and used for monitoring
3. A way to remove orphaned cluster entries


#### Unmanage a cluster from Web Administration

To unmanage a cluster:


1. Log in to the Web Administration interface and select the All Clusters view from drop-down.
2. Locate the cluster from the list of imported clusters. At the far right of the cluster row, click the vertical ellipsis and then click **Unmanage**.



3. A confirmation box appears. Click **Unmanage** to proceed.



4. The unmanage cluster task is submitted. To view the task progress, click **View Task Progress**.



5. The status shows **Completed** after the unmanage task is successfully completed.

[All Clusters](#) » [Tasks](#) »  [UnmanageCluster: 0c6e2c22-a581-4175-a331-afccb03e507f](#)

Time Submitted: 18 Jun 2018 17:14:17

Status:  Completed**NOTE**

After a cluster is unmanaged, it will not reappear immediately for reimport in the Web Administration environment. When the cluster is unmanaged, the tendrl-node-agent service undergoes synchronization with the nodes in the cluster. Based on the number of nodes in the cluster, expect a delay ranging from 60 seconds to a few minutes for the unmanaged cluster to reappear in the Web Administration environment.

## 3.2. TROUBLESHOOTING CLUSTER EXPANSION

### Scenario: Cluster Expansion task failed

In this scenario, the cluster expansion task fails.

#### Resolution

If cluster expansion fails, check if tendrl-ansible was executed successfully and ensure the node agents are correctly configured. If cluster expansion failed due to errors, resolve the errors on affected nodes and re-initiate the Expand Cluster action.

To verify tendrl-ansible execution steps, see the [Web Administration Installation](#) section of the Red Hat Gluster Storage Web Administration Quick Start Guide.

For detailed instructions on expanding cluster, navigate to the [Cluster Expansion](#) section of this Guide.

## CHAPTER 4. MONITORING AND METRICS

Gluster Web Administration provides deep metrics and visualization of Gluster clusters, the physical server nodes and the storage elements (disks) through the Grafana open-source monitoring platform.


## CHAPTER 5. MONITORING DASHBOARD AND CONCEPTS

The Monitoring Dashboard provides high level visual information on health, performance and utilization of cluster wide resources.

### 5.1. DASHBOARD SELECTOR

The Dashboard Selector is the primary navigation tool to move between different dashboards.

Figure 5.1. Dashboard Selector




### 5.2. DASHBOARD PANELS

The Dashboard is composed of individual visualization blocks displaying different metrics and statistics termed as Panels. The panels exhibit different data based on the current status of the cluster component. Panels can be dragged and dropped and rearranged on the Dashboard.

The following are the types of panels available to visualize monitoring data:

1. **Single Status Panel:** The status panel displays the aggregated value of a series in e a single number data. For example, the Health, volume, snapshots are Singlestat panels.


Figure 5.2. Single Status Panel Example



2. **Multiple Status Panel:** The Multiple status panel displays multiple values of a data source. The multiple status panel displays:

- The severity of the component
- If the component is disabled
- Extra data in the panel about the component

Figure 5.3. Multiple Status Panel Example




**NOTE**

If a multiple status panel displays **Invalid Number** as a status for a component, it indicates there is no data available to display from the time series database.

3. **Graph Panel:** The Graph panel allows to visualize unrestrained amounts of metrics. The Connection Trend and the Throughput Trend are examples of Graph panel.

**Figure 5.4. Graph Panel Example**



4. **Table Panel:** The Graph panel allows to visualize unrestrained amounts of metrics. The Connection Trend and the Throughput Trend are examples of Graph panel.

**Figure 5.5. Table Panel Example**

CPU Utilization by Host	
Host Name	Utilization ▾
tendrl-usm1-gl3_example_org	7.8%
tendrl-usm1-gl1_example_org	6.5%
tendrl-usm1-gl2_example_org	6.5%
tendrl-usm1-gl4_example_org	5.5%
tendrl-usm1-gl6_example_org	4.7%

## 5.3. DASHBOARD ROWS



A row is a logical divider in a given Dashboard. The panels of the dashboard are arranged and organized in rows to give a streamlined look and visual.

## 5.4. DASHBOARD COLOR CODES

The Dashboard panels text displays the following color codes to represent health status information:


- **Green:** Healthy
- **Orange:** Degraded
- **Red:** Unhealthy, Down, or Unavailable

## CHAPTER 6. MONITORING DASHBOARD FEATURES

### 6.1. DASHBOARD SEARCH

You can search the available dashboards by the dashboard name. The available filters to search a particular dashboard are starred and tags. The dashboard search functionality is accessed through the dashboard selector, located at the top of the Grafana interface.


Figure 6.1. Dashboard Search



### 6.2. DASHBOARD TIME RANGE

The Grafana interface provides time range management of the the data being visualized. You can change the time range for a graph to view the data at different points in time

At the top right, you can access the master Dashboard time picker. It shows the currently selected time range and the refresh interval.



Clicking the master Dashboard time picker, toggles a menu for time range controls.



## Time range

The time range filter allows to mix both explicit and relative time ranges. The explicit time range format is **YYYY-MM-DD HH:MM:SS**.

## Quick Range

Quick ranges are preset values to choose a relative time.


## Refreshing every

When enabled, auto-refresh will reload the dashboard at the specified time range.

## 6.3. DASHBOARD SHARING

The Dashboard Selector is the primary navigation tool to move between different dashboards.

**Figure 6.2. Dashboard Selector**



## CHAPTER 7. MONITORING DASHBOARD NAVIGATION

To access the Monitoring Dashboard, follow these steps:


1. Log in to the Web Administration interface at <http://web-admin-server.example.com>.
2. In the default Cluster view, locate the cluster and click **Launch Dashboard**.
3. The Cluster dashboard showing the aggregated metrics view is opened in a new window.

### 7.1. CLUSTER VIEW DASHBOARD

The Cluster view dashboard allows the Gluster Administrator to:

- View at-a-glance information about the Gluster cluster that includes health and status information, key performance indicators such as IOPS, throughput, etc, and alerts that can highlight attention to potential issues in the cluster, host, volume, and brick.
- Compare a metric such as IOPS, CPU, Memory, Network Load across hosts within the cluster.
- Compare utilization across bricks within a volume, for example, IOPS, capacity, etc.


**Figure 7.1. Cluster View Dashboard**



### 7.2. HOSTS VIEW DASHBOARD

The Host view Dashboard allows the Gluster Administrator to:


- View at-a-glance information about the Gluster host that includes health and status information, key performance indicators such as IOPS, throughput, etc and alerts that highlights attention to potential issues in the host, volume, brick, and disk.
- Compare one or more metrics such as IOPS, CPU, Memory, Network Load across bricks within the host.
- Compare utilization such as IOPS, capacity, etc across bricks within a host.



## 7.3. VOLUME VIEW DASHBOARD

The Volume view Dashboard allows the Gluster Administrator to:


- View at-a-glance information about the Gluster Volume that includes health and status information, key performance indicators that highlights attention to potential issues in the volume, brick, and disk.



## 7.4. BRICK VIEW DASHBOARD

The Brick view dashboard allows the Gluster Administrator to:

- View at-a-glance information about the Gluster brick that includes health and status information, key performance indicators such as IOPS, throughput, latency, etc and alerts that can highlight attention to potential issues in the brick and underlying disks.
- Look at performance by brick to address diagnosing of RAID 6 disk failure/rebuild/degradation poor performance on one brick.



## CHAPTER 8. MONITORING CLUSTER METRICS

### 8.1. CLUSTER LEVEL DASHBOARD


This is the default dashboard of the Monitoring interface that shows the overview of the selected cluster.

#### 8.1.1. Monitoring and Viewing Cluster Health

To monitor the Cluster health status and the metrics associated with it, view the panels in the Cluster Dashboard. For detailed panel descriptions and health indicators, see **Table 7.1. Cluster Health Panel Descriptions**.

##### 8.1.1.1. Health and Snapshots

The **Health** panel displays the overall health of the selected cluster and the **Snapshots** panel shows the active number of snapshots.



##### 8.1.1.2. Hosts, Volumes and Bricks


The Hosts, Volumes, and Bricks panels displays status information. The following is an example screen displaying the respective status information.



- **Hosts:** In total, there are 3 online Hosts
- **Volumes:** In total, there are 9 Volumes
- **Bricks:** In total, there are 44 Bricks

#### 8.1.1.3. Geo-Replication Session

The Geo-Replication Session panel displays geo-replication session information from a given cluster, including the total number of geo-replication session and a count of geo-replication sessions by status.



### 8.1.1.4. Health Panel Descriptions

The following table lists the Panels and the descriptions.

**Table 8.1. Cluster Health Panel Descriptions**

Panel	Description	Health Indicator
Health	The Health panel displays the overall health of the selected cluster, which is either <b>Healthy</b> or <b>Unhealthy</b>	Green: Healthy Red: Unhealthy Orange: Degraded
Snapshots	The Snapshots panel displays the count of the active snapshots	
Hosts	The Hosts panel displays host status information including the total number of hosts and a count of hosts by status	
Volume	The Volumes panel displays volume status information for the selected cluster, including the total number of volumes and a count of volumes by status	
Bricks	The Bricks panel displays brick status information for the selected cluster, including the total number of bricks in the cluster, and a count of bricks by status	
Geo-Replication Session	The Geo-Replication Session panel displays geo-replication session information from a given cluster, including the total number of geo-replication session and a count of geo-replication sessions by status	


### 8.1.2. Monitoring and Viewing Cluster Performance

Cluster performance metrics can be monitored by the data displayed in the following panels.

#### Connection Trend


The Connection Trend panel displays the total number of client connections to bricks in the volumes for the selected cluster over a period of time. Typical statistics may look like this:





## IOPS

The IOPS panel displays IOPS for the selected cluster over a period of time. IOPS is based on the aggregated brick level read and write operations collected using *gluster volume profileinfo*.



## Capacity Utilization and Capacity Available

The **Capacity Utilization** panel displays the capacity utilized across all volumes for the selected cluster.

The **Capacity Available** panel displays the available capacity across all volumes for the selected cluster.

## Capacity Utilization



## Capacity Available

**31.7**  
**GiB**

### Weekly Growth Rate

The Weekly Growth Rate panel displays the forecasted weekly growth rate for capacity utilization computed based on daily capacity utilization.

## Weekly Growth Rate


**6.0**

**MB**

### Weeks Remaining


The Weeks Remaining panel displays the estimated time remaining in weeks till volumes reach full

capacity based on the forecasted Weekly Growth Rate.



### Throughput Trend

The Throughput Trend panel displays the network throughput for the selected cluster over a period of time.



### 8.1.3. Top Consumers

The Top Consumers panels displays the highest capacity utilization by the cluster resources.

To view the top consumers of the cluster:

1. In the Cluster level dashboard, at the bottom, click **Top Consumers** to expand the menu.

> **Top Consumers**

> **Status**

### Top 5 Utilization By Bricks

The Top 5 Utilization By Bricks panel displays the bricks with the highest capacity utilization.

Top 5 Utilization by Bricks	
Bricks	Utilization ▼
tendrl-usm1-gl2_example_org:/mnt/brick_beta_arbiter_2/2	0.1%
tendrl-usm1-gl2_example_org:/mnt/brick_beta_arbiter_1/1	0.1%
tendrl-usm1-gl1_example_org:/mnt/brick_beta_arbiter_3/3	0.1%
tendrl-usm1-gl1_example_org:/mnt/brick_beta_arbiter_2/2	0.1%
tendrl-usm1-gl1_example_org:/mnt/brick_beta_arbiter_1/1	0.1%

### Top 5 Utilization by Volume

The Top 5 Utilization By Volumes panel displays the volumes with the highest capacity utilization.

CPU Utilization by Host	
Host Name	Utilization ▼
tendrl-usm1-gl3_example_org	7.8%
tendrl-usm1-gl1_example_org	6.6%
tendrl-usm1-gl2_example_org	6.6%
tendrl-usm1-gl4_example_org	6.0%
tendrl-usm1-gl5_example_org	5.0%

### CPU Utilization by Host

The CPU Utilization by Host panel displays the CPU utilization of each node in the cluster.

### CPU Utilization by Host

Host Name	Utilization
dhcp41-255_lab_eng_blr_redhat_com	4.8%
dhcp42-11_lab_eng_blr_redhat_com	4.6%


### Memory Utilization By Host

The Memory Utilization by Hosts panel displays memory utilization of each node in the cluster.

Memory Utilization by Host	
Host Name	Utilization ▾
tendr1-usm1-gl1_example_org	6.2%
tendr1-usm1-gl2_example_org	6.1%
tendr1-usm1-gl3_example_org	6.0%
tendr1-usm1-gl4_example_org	6.0%
tendr1-usm1-gl5_example_org	5.6%

### Ping Latency Trend

The Ping Latency Trend panel displays the ping latency for each host in a given cluster.



#### 8.1.4. Monitoring and Viewing Cluster Status

To view the status of the overall cluster:

1. In the Cluster level dashboard, at the bottom, click **Status** to expand the menu.

› Top Consumers

› Status

2. The Volume, Host, and Brick status are displayed in the panels.

#### ▼ Status

Volume Status	
Volume Name	Status ▾
volume_gama_disperse_4_plus_2x2	0

Host Status	
Host Name	Status ▾
ci-usb4-gl6_usmqe_lab_eng_blr_redhat_com	0
ci-usb4-gl5_usmqe_lab_eng_blr_redhat_com	0
ci-usb4-gl4_usmqe_lab_eng_blr_redhat_com	0
ci-usb4-gl3_usmqe_lab_eng_blr_redhat_com	0
ci-usb4-gl2_usmqe_lab_eng_blr_redhat_com	0

Brick Status	
Brick Name	Status ▾
ci-usb4-gl6_usmqe_lab_eng_blr_redhat_com/mnt/brick_gama_disperse	0
ci-usb4-gl6_usmqe_lab_eng_blr_redhat_com/mnt/brick_gama_disperse	0
ci-usb4-gl5_usmqe_lab_eng_blr_redhat_com/mnt/brick_gama_disperse	0

### Volume Status

The Volume Status panel displays the status code of each volume for the selected cluster.


Volume Status	
Volume Name	Status
volume_gama_disperse_4_plus_2x2	0

The volume status is displayed in numerals and colors. The following are the corresponding status of the numerals.

- 0 = Up
- 3 = Up (Degraded)
- 4 = Up (Partial)
- 5 = Unknown
- 8 = Down

### Host Status

The Host Status panel displays the status code of each host for the selected cluster.



Host Name	Status
ci-usm4-gl1_usmqe_lab_eng_blr_redhat_com	0
ci-usm4-gl2_usmqe_lab_eng_blr_redhat_com	0
ci-usm4-gl3_usmqe_lab_eng_blr_redhat_com	0
ci-usm4-gl4_usmqe_lab_eng_blr_redhat_com	0
ci-usm4-gl5_usmqe_lab_eng_blr_redhat_com	0

The Host status is displayed in numeric codes:

- 0 = Up
- 8 = Down

### Brick Status

The Brick Status panel displays the status code of each brick for the selected cluster.

Brick Status	
Brick Name	Status
ci-usm4- gl6_usmqe_lab_eng_blr_redhat_com:/mnt/brick_gama_disperse_2/2	1
ci-usm4- gl6_usmqe_lab_eng_blr_redhat_com:/mnt/brick_gama_disperse_1/1	1
ci-usm4- gl5_usmqe_lab_eng_blr_redhat_com:/mnt/brick_gama_disperse_2/2	1
ci-usm4-	1

The Brick status is displayed in numeric codes:

- 1 = Started
- 10 = Stopped

## 8.2. HOST LEVEL DASHBOARD


### 8.2.1. Monitoring and Viewing Health and Status

To monitor the Cluster Hosts status and the metrics associated with it, navigate to the Hosts Level Dashboard and view the panels.

#### Health

The Health panel displays the overall health for a given host.





### Bricks and Bricks Status

The Bricks panel displays brick status information for a given host, including the total number of bricks in the host, and a count of bricks by status.



The Brick Status panel displays the status code of each brick for a given host.

Brick Status	
Brick Path	Status ▼
/root/bricks/v3	1
/root/bricks/v22	1
/root/bricks/v2	1


- 1 = Started
- 10 = Stopped

## 8.2.2. Monitoring and Viewing Performance

### 8.2.2.1. Memory and CPU Utilization


#### Memory Available

The Memory Available panel displays the sum of memory free and memory cached.



#### Memory Utilization

The Memory Utilization panel displays memory utilization percentage for a given host that includes buffers and caches used by the kernel over a period of time.



- **Buffered:** Amount of memory used for buffering, mostly for I/O operations
- **Cached:** Memory used for caching disk data for reads, memory-mapped files or tmpfs data
- **Slab Rec:** Amount of reclaimable memory used for slab kernel allocations
- **Slab Unrecl:** Amount of unreclaimable memory used for slab kernel allocations
- **Used:** Amount of memory used, calculated as Total - Free (Unused Memory) - Buffered - Cache
- **Total:** Total memory used


### Swap Free

The Swap Free panel displays the available swap space in percent for a given host.




### Swap Utilization

The Swap Utilization panel displays the used swap space in percent for a given host.




### CPU Utilization

The CPU utilization panel displays the CPU utilization for a given host over a period of time.



### IOPS


The IOPS panel displays IOPS for a given host over a period of time. IOPS is based on the aggregated brick level read and write operations.



### 8.2.2.2. Capacity and Disk Load

#### Total Brick Capacity Utilization Trend


The Total Brick Capacity Utilization Trend panel displays the capacity utilization for all bricks on a given for a period of time.



#### Total Brick Capacity Utilization

The Total Brick Capacity Utilization panel displays the current percent capacity utilization for a given host.

### Total Brick Capacity Utilization



### Total Brick Capacity Available

The Total Brick Capacity Available panel displays the current available capacity for a given host.

### Total Brick Capacity Available

**32.8 GiB**

### Weekly Growth Rate

The Weekly Growth Rate panel displays the forecasted weekly growth rate for capacity utilization computed based on daily capacity utilization.

**Weekly Growth Rate****4.9 GB****Weeks Remaining**

The Weeks Remaining panel displays the estimated time remaining in weeks till host capacity reaches full capacity based on the forecasted Weekly Growth Rate.

**Weeks Remaining****7****Brick Utilization**

The Brick Utilization panel displays the utilization of each brick for a given host.

<b>Brick Utilization</b>	
<b>Brick Path</b>	<b>Utilization ▼</b>
/mnt/brick_gama_disperse_2/2	0.2%
/mnt/brick_gama_disperse_1/1	0.2%

## Brick Capacity

The Brick Capacity panel displays the total capacity of each brick for a given host.

Brick Capacity	
Brick Path	Capacity ▼
/mnt/brick_gama_disperse_2/2	19.9 GiB
/mnt/brick_gama_disperse_1/1	19.9 GiB


## Brick Capacity Used

The Brick Capacity Used panel displays the used capacity of each brick for a given host.

Brick Capacity Used	
Brick Path	Capacity ▼
/mnt/brick_gama_disperse_2/2	33.0 MiB
/mnt/brick_gama_disperse_1/1	33.0 MiB

## Disk Load


The Disk Load panel shows the host's aggregated read and writes from/to disks over a period of time.



## Disk Operation


The Disk Operations panel shows the host's aggregated read and writes disk operations over a period of time.





## Disk IO


The Disk IO panel shows the host's aggregated I/O time over a period of time.



## 8.2.2.3. Network


### Throughput

The Throughput panel displays the network throughput for a given host over a period of time.




### Dropped Packets Per Second

The Dropped Packets Per Second panel displays dropped network packets for the host over a period of time. Typically, dropped packets indicates network congestion, for example, the queue on the switch port your host is connected to is full and packets are dropped because it cannot transmit data fast enough.



### Errors Per Second

The Errors Per Second panel displays network errors for a given host over a period of time. Typically, the errors indicate issues that occurred while transmitting packets due to carrier errors (duplex mismatch, faulty cable), fifo errors, heartbeat errors, and window errors, CRC errors too short frames, and/or too long frames. In short, errors typically result from faulty hardware, and/or speed mismatch.



### 8.2.3. Host Dashboard Metric Units

The following table shows the metrics and their corresponding measurement units.

**Table 8.2. Host Dashboard Metric Units**

Metrics	Units
Memory Available	Megabyte/Gigabyte/Terabyte
Memory Utilization	Percentage %
Swap free	Percentage %
Swap Utilization	Percentage %
CPU Utilization	Percentage %
Total Brick Capacity Utilization	Percentage %
Total Brick Capacity	MB/GB/TB
Weekly Growth Rate	MB/GB/TB
Disk Load	kbps
Disk IO	millisecond ms
Network Throughput	kbps

## 8.3. VOLUME LEVEL DASHBOARD

The Volume view dashboard allows the Gluster Administrator to:

- View at-a-glance information about the Gluster volume that includes health and status information, key performance indicators such as IOPS, throughput, etc, and alerts that can highlight attention to potential issues in the volume, brick, and disk.
- Compare 1 or more metrics such as IOPS, CPU, Memory, Network Load across bricks within the volume.
- Compare utilization such as IOPS, capacity, etc, across bricks within a volume.
- View performance metrics by brick (within a volume) to address diagnosing of failure, rebuild, degradation, and poor performance on one brick.

When all the Gluster storage nodes are shut down or offline, Time to live (TTL) will delete the volume details from etcd as per the TTL value measured in seconds. The TTL value for volumes is set based on the number of volumes and bricks in the system. The formula to calculate the TTL value to delete volume details is:

**Time to Live (seconds) = synchronization interval (60 seconds) + number of volumes \* 20 + number of bricks \* 10 + 160.**

### In Web Administration environment

- Cluster will show status as unhealthy and all hosts will be marked as down
- No display of Volumes and Bricks
- The Events view will reflect the relevant status


### In Grafana Dashboard

- In Cluster level Dashboard, the Host, Volumes, and Bricks panels reflects the relevant updated counts with status.
- In Cluster, Volume, and Brick level dashboards, some panels will be marked as N/A, indicating no data is available.

### 8.3.1. Monitoring and Viewing Health


#### Health

The Health panel displays the overall health for a given volume.



### Snapshots

The Snapshots panel displays the count of active snapshots for the selected cluster.



### Brick Status

The Brick Status panel displays the status code of each brick for a given volume.

Brick Status	
Brick Path	Status
dhcp42-11_lab_eng_blr_redhat_com:/root/bricks/v22	1
dhcp42-11_lab_eng_blr_redhat_com:/root/bricks/v2	1
dhcp41-255_lab_eng_blr_redhat_com:/root/bricks/v22	1
dhcp41-255_lab_eng_blr_redhat_com:/root/bricks/v2	1

- 1 = Started
- 10 = Stopped


### Bricks

The Bricks panel displays brick status information for a given volume, including the total number of bricks in the volume, and a count of bricks by status.



### Subvolumes

The Subvolumes panel displays subvolume status information for a given volume.



### Geo-Replication Sessions

The Geo-Replication Session panel displays geo-replication session information from a given volumes, including the total number of geo-replication session and a count of geo-replication sessions by status.

## *Geo-Replication Sessions*

Total - 0

Created - 0

Up - 0

Partial - 0

Paused - 0

Stopped - 0

Down - 0

### **Rebalance**

The Rebalance panel displays rebalance progress information for a given volume, which is applicable when rebalancing is underway.

## *Rebalance*

Rebalanced

Files - 0

MB Size - 0

Skipped - 0

Failure - 0

### **Rebalance Status:**

The Rebalance Status panel displays the status of rebalancing for a given volume, which is applicable when rebalancing is underway.

**Rebalance  
Status**


**Not**

**Started**

### 8.3.2. Monitoring and Viewing Performance

#### Capacity Utilization

The Capacity Utilization panel displays the used capacity for a given volume.



#### Capacity Available

The Capacity Available panel displays the available capacity for a given volume.



**Capacity  
Available**

**21.3**

**GiB**

### Weekly Growth Rate

The Weekly Growth Rate panel displays the forecasted weekly growth rate for capacity utilization computed based on daily capacity utilization.


**Weekly Growth  
Rate**

**3.8**

**MB**


### Weeks Remaining

The Weeks Remaining panel displays the estimated time remaining in weeks till volume reaches full capacity based on the forecasted Weekly Growth Rate.




### Capacity Utilization Trend

The Capacity Utilization Trend panel displays the volume capacity utilization over a period of time.




### Inode Utilization

The Inode Utilization panel displays inodes used for bricks in the volume over a period of time.




### Inode Available

The Inode Available panel displays inodes free for bricks in the volume.




### Throughput

The Throughput panel displays volume throughput based on brick-level read and write operations fetched using *gluster volume profile*.



### LVM Thin Pool Metadata %


The LVM Thin Pool Metadata % panel displays the utilization of LVM thin pool metadata for a given volume. Monitoring the utilization of LVM thin pool metadata and data usage is important to ensure they do not run out of space. If the data space is exhausted, I/O operations are either queued or failing based on the configuration. If metadata space is exhausted, you will observe error I/O's until the LVM pool is taken offline and repair is performed to fix potential inconsistencies. Moreover, due to the metadata transaction being aborted and the pool doing caching there might be uncommitted (to disk) I/O operations that were acknowledged to the upper storage layers (file system) so those layers will need to have checks/repairs performed as well.



### LVM Thin Pool Data Usage %

The LVM Thin Pool Data Usage % panel displays the LVM thin pool data usage for a given volume. Monitoring the utilization of LVM thin pool metadata and data usage is important to ensure they do not run out of space. If the data space is exhausted, I/O operations are either queued or failing based on

the configuration. If metadata space is exhausted, you will observe error I/O's until the LVM pool is taken offline and repair is performed to fix potential inconsistencies. Moreover, due to the metadata transaction being aborted and the pool doing caching there might be uncommitted (to disk) I/O operations that were acknowledged to the upper storage layers (file system) so those layers will need to have checks/repairs performed as well.



### 8.3.3. Monitoring File Operations

#### Top File Operations

The Top File Operations panel displays the top 5 FOP (file operations) with the highest % latency, wherein the % latency is the fraction of the FOP response time that is consumed by the FOP.

Top File Operations	
File Operations	% Latency ▼
LOOKUP	16.00
GETXATTR	9.00
READDIR	8.00
STATFS	4.00
OPENDIR	4.00


#### File Operations for Locks Trend

The File Operations for Locks Trend panel displays the average latency, maximum latency, call rate for each FOP for Locks over a period of time.




### File Operations for Read/Write

The File Operations for Read/Write panel displays the average latency, maximum latency, call rate for each FOP for Read/Write Operations over a period of time.




### File Operations for Inode Operations

The File Operations for Inode Operations panel displays the average latency, maximum latency, call rate for each FOP for Inode Operations over a period of time.



### File Operations for Entry Operations

The File Operations for Entry Operations panel displays the average latency, maximum latency, call rate for each FOP for Entry Operations over a period of time.



### 8.3.4. Volume Dashboard Metric Units

The following table shows the metrics and their corresponding measurement units.

**Table 8.3. Volume Dashboard Metric Units**


Metrics	Units
Capacity Utilization	Percentage %
Capacity Available	Megabyte/Gigabyte/Terabyte
Weekly Growth Rate	Megabyte/Gigabyte/Terabyte
Capacity Utilization Trend	Percentage %
Inode Utilization	Percentage %
Lvm Thin Pool Metadata	Percentage %
Lvm Thin Pool Data Usage	Percentage %

Metrics	Units
File Operations for Locks Trend	MB/GB/TB
File Operations for Read/Write	K
File Operations for Inode Operation Trend	K
File Operations for Entry Operations	K

## 8.4. BRICK LEVEL DASHBOARD

### 8.4.1. Monitoring and Viewing Brick Status

The Status panel displays the status for a given brick.




### 8.4.2. Monitoring and Viewing Brick Performance

#### Capacity Utilization


The Capacity Utilization panel displays the percentage of capacity utilization for a given brick.






### Capacity Available

The Capacity Available panel displays the available capacity for a given volume.




### Capacity Utilization Trend

The Capacity Utilization Trend panel displays the brick capacity utilization over a period of time.




### Weekly Growth Rate

The Weekly Growth Rate panel displays the forecasted weekly growth rate for capacity utilization computed based on daily capacity utilization.




### Weeks Remaining

The Weeks Remaining panel displays the estimated time remaining in weeks till brick reaches full capacity based on the forecasted Weekly Growth Rate.



## Healing

The Healing panel displays healing information for a given volume based on healinfo.




### NOTE

The Healing panel will not show any data for volumes without replica.

## Inode Utilization

The Inode Utilization panel displays inodes used for a given brick over a period of time.




## Inode Available

The Inode Available panel displays inodes free for a given brick.

**Inode Available****6507980**


### LVM Thin Pool Metadata %

The LVM Thin Pool Metadata % panel displays the utilization of LVM thin pool metadata for a given brick. Monitoring the utilization of LVM thin pool metadata and data usage is important to ensure they don't run out of space. If the data space is exhausted, I/O operations are either queued or failing based on the configuration. If metadata space is exhausted, you will observe error I/O's until the LVM pool is taken offline and repair is performed to fix potential inconsistencies. Moreover, due to the metadata transaction being aborted and the pool doing caching there might be uncommitted (to disk) I/O operations that were acknowledged to the upper storage layers (file system) so those layers will need to have checks/repairs performed as well.

**LVM Thin Pool Meta Data %**


### LVM Thin Pool Data Usage %

The LVM Thin Pool Data Usage % panel displays the LVM thin pool data usage for a given brick. Monitoring the utilization of LVM thin pool metadata and data usage is important to ensure they don't run out of space. If the data space is exhausted, I/O operations are either queued or failing based on the configuration. If metadata space is exhausted, you will observe error I/O's until the LVM pool is taken offline and repair is performed to fix potential inconsistencies. Moreover, due to the metadata transaction being aborted and the pool doing caching there might be uncommitted (to disk) I/O operations that were acknowledged to the upper storage layers (file system) so those layers will need to have repairs performed as well.




## Throughput

The Throughput panel displays brick-level read and write operations fetched using “gluster volume profile.”




## IOPS

The IOPS panel displays IOPS for a brick over a period of time. IOPS is based on brick level read and write operations.



### Latency

The Latency panel displays latency for a brick over a period of time. Latency is based on the average amount of time a brick spends doing a read or write operation.



### 8.4.3. Brick Dashboard Metric Units

The following table shows the metrics and their corresponding measurement units.

**Table 8.4. Brick Dashboard Metric Units**

Metrics	Units
Capacity Utilization	Percentage %
Capacity Available	Megabyte/Gigabyte/Terabyte
Weekly Growth Rate	Megabyte/Gigabyte/Terabyte
Capacity Utilization Trend	Percentage %
Inode Utilization	Percentage %
Lvm Thin Pool Metadata	Percentage %
Lvm Thin Pool Data Usage	Percentage %
Disk Throughput	Percentage %

## CHAPTER 9. USERS AND ROLES ADMINISTRATION

### 9.1. USER ROLES

There are three user roles available for Web Administration.

1. **Admin:** The Admin role gives complete rights to the user to manage all Web Administration operations.
2. **Normal User:** The Normal User role authorizes the user to perform operations such as importing cluster and enabling or disabling volume profiling but restricts managing users and other administrative operations.
3. **Read-only User:** Read-only: The Read-only User role authorizes the user to only view and monitor cluster-wide metrics and readable data. The user can launch Grafana dashboards from the Web Administration interface but is restricted to perform any storage operations. This role is suited for users performing monitoring tasks.

### 9.2. CONFIGURING ROLES


To add and configure a new user, follow these steps:

1. Log In the Web Administration interface and in navigation pane, click **Admin > Users**.
2. The users list is displayed. To add a new user, click **Add** at the right-hand side.

User ID ▾

Filter by Use

Add

User ID	Name	Role	Notification	Email	Actions
admin	Admin	Admin	 Disabled	admin@tendrl.org	<div>Edit</div> <div>⋮</div>

3. Enter the user information in the given fields. To enable or disable email notifications, toggle the **ON-OFF** button.

Add a new local user. All user information will be stored internally in Tendrl.

User ID	<input type="text" value="Normal"/>		
Name	<input type="text" value="John Smith"/>		
Email	<input type="text" value="jsmith@org.com"/>	Email Notifications	<div style="border: 1px solid #ccc; padding: 2px 10px; background-color: #007bff; color: white; display: inline-block;">ON</div>
Password	<input type="password" value="....."/>		
Confirm Password	<input type="password" value="....."/>		





4. Select a **Role** from the available three roles and click **Save**.



- Select a Role
- ☐ **Admin**  
The Admin role permits the user to manage Tendrl and all storage operations.
  - ☒ **Normal User**  
The Normal user role permits the user to provision storage but cannot manage the Tendrl applications.
  - ☐ **Read-only User**  
The Read-only user role permits the user to access Tendrl in read-only mode, which means the user cannot actively manage storage. This role is ideal for users interested in monitoring the storage.

**Save** **Cancel**





5. The new user is successfully created.

User ID	Name	Role	Notification	Email	Actions	
admin	Admin	Admin	 Disabled	admin@tendrl.org	<b>Edit</b>	
administrator	John Smith	Normal	 Enabled	jsmith@org.com	<b>Edit</b>	

### 9.2.1. Editing Users

To edit an existing user:

1. Navigate to the user view by clicking **Admin > Users** from the interface navigation.
2. Locate the user to be edited and click **Edit** at the right-hand side.

User ID	Name	Role	Notification	Email	Actions	
admin	Admin	Admin	 Disabled	admin@tendrl.org	<b>Edit</b>	
administrator	John Smith	Normal	 Enabled	jsmith@org.com	<b>Edit</b>	

3. Edit the required information and click **Save**.

User ID      Normal

Name     

Email            Email Notifications      ON

New Password     

Confirm Password     

Save Cancel

## 9.2.2. Disabling Notifications and Deleting User

### Enabling and Disabling Notifications

To enable notifications:

1. Navigate to the user view by clicking **Admin > Users** from the interface navigation.

User ID	Name	Role	Notification	Email	Actions
admin	Admin	Admin	Disabled	admin@tendrl.org	<span>Edit</span> <span>⋮</span>
administrator	John Smith	Normal	Enabled	jsmith@org.com	<span>Edit</span> <span>⋮</span>

2. Click the vertical elipsis next to the Edit button and click **Disable Email Notification** from the callout menu.

Email	Actions
admin@tendrl.org	<span>Edit</span> <span>⋮</span>
jsmith@org.com	<span>Edit</span> <span>⋮</span>

Disable Email Notification  
Delete User

3. Email notification is successfully disabled for the user.



Email notification is now disabled for Normal.



## Users

User ID ▾ *Filter by User ID*

Add

User ID	Name	Role	Notification	Email	Actions
admin	Admin	Admin	Disabled	admin@tendr1.org	<div>Edit</div> <div>⋮</div>
Normal	John Smith	Normal	Disabled	jsmith@org.com	<div>Edit</div> <div>⋮</div>

### Deleting User

To delete an existing user:

1. Navigate to the user view by clicking **Admin > Users** from the interface navigation.
2. Locate the user to be deleted and click the vertical elipsis next to the Edit button. A callout menu opens, click **Delete User**.

Email	Actions
admin@tendr1.org	<div>Edit</div> <div>⋮</div>
jsmith@org.com	<div>Edit</div> <div>⋮</div>

Disable Email Notification  
Delete User

3. A confirmation box appears. Click **Delete**.

Delete User



This action will permanently remove user **Normal**. Click Delete to continue.

Cancel

Delete

## CHAPTER 10. ALERTS AND NOTIFICATIONS

Alerts are current problems and critical conditions that occur in the system and notified to the user. The Grafana monitoring platform generates alerts based on severity levels.

You can configure alerts via SMTP and SNMP protocols. SMTP configuration will send email alerts to users that have email notifications enabled. SNMPv3 configuration will send SNMP trap alerts to the Alerts notifications drawer of the Web Administration environment.

### 10.1. TYPES OF ALERTS

The alerts triggered by the dashboard are classified in the following categories:

- **Status alerts :** Alerts arising when a cluster resource undergoes a change of state. For example, Healthy to Unhealthy.
- **Utilization alerts:** Alerts arising after a cluster resource exceed the set threshold and after it reverts to the normal state. For example, when the Host CPU utilization is breached, an alert is triggered notifying the user about the event.

### 10.2. LIST OF ALERTS

The list of Web Administration alerts are given in the tables below.

#### Status Alerts

Table 10.1. Status Alerts

Alert	System Resource(s)
volume status	Volume and Cluster
volume state	Volume and Cluster
brick status	Volume, Host, and Cluster
peer status	Cluster
rebalance status	Volume and Cluster
Geo-Replication status	Cluster
quorum of volume lost	Volume and Cluster
quorum of volume regained	Volume and Cluster
svc connected	Cluster
svc disconnected	Cluster

Alert	System Resource(s)
minimum number of bricks not up in EC subvolume	Volume and Cluster
minimum number of bricks up in EC subvolume	Volume and Cluster
afr quorum met for subvolume	Volume and Cluster
afr quorum fail for subvolume	Volume and Cluster
afr subvolume up	Volume and Cluster
afr subvolume down	Volume and Cluster

### Utilization Alerts

**Table 10.2. Utilization Alerts**


Alert	System Resource
cpu utilization	Host
memory utilization	host
swap utilization	host
volume utilization	Volume and Cluster
brick utilization	Volume and Cluster

## 10.3. ALERTS NOTIFICATIONS DRAWER




Alerts drawer is a notification indicator embedded in the Web Administration interface to display the system wide alerts.

### Accessing Alerts Drawer



1. To access the Alerts drawer, log in the Web Administration interface. In the default landing interface, locate and click on the interactive bell icon on the header bar at the top right-hand side.




2. The drawer is opened displaying the number of alerts generated.

Alerts ×


**3 Alerts**
 1
 2

---




Cluster:ClusterA is unhealthy  
28 Aug 2018 13:59:23

---



Volume:volume\_beta\_arbiter\_2\_plus\_1x2 is down  
28 Aug 2018 13:59:22

---



Peer tendrl-usm1-gl1.example.org in cluster ClusterA is  
Connected  
28 Aug 2018 13:59:18

To filter alerts, click on the status icon at the right.

 2  4

## 10.4. SMTP NOTIFICATIONS CONFIGURATION

Tendrl-ansible installs and configures tendrl-notifier. After the tendrl-notifier file is configured, configure SMTP email notifications:

1. Open the `/etc/tendrl/notifier/email.conf.yaml` file.
2. Update the parameters:

```
email_id = <The sender email id>
email_smtp_server = <The smtp server>
email_smtp_port = <The smtp port>
```

3. If the SMTP server supports only authenticated email, follow the template in the `/etc/tendr1/notifier/email_auth.conf.yaml` file and accordingly enable the following:

```
auth = <ssl/tls>

email_pass = <password corresponding to email_id for
authenticating to smtp server>
```

4. Restart the `tendr1-notifier` service:

```
systemctl restart tendr1-notifier
```

## 10.5. SNMPV3 NOTIFICATION CONFIGURATION

### Configure SNMP

Tendr1-ansible installs and configures `tendr1-notifier`. After the `tendr1-notifier` file is configured, configure SNMPv3 trap notifications:

1. Open the `tendr1-notifier` configuration file:

```
# cat /etc/tendr1/notifier/snmp.conf.yaml
```

2. Update the parameters in the file for v3 trap alerts:

```
For v3_endpoint:
# For more hosts you can add more entry with endpoint2, endpoint3,
etc
endpoint1:

# Name or IP address of the remote SNMP host.
  host_ip: <Receiving machine ip>
# Name of the user on the host that connects to the agent.
  username: <Username of receiver>
# Enables the agent to receive packets from the host.
  auth_key: <md5 password>
# The private user password
  priv_key: <des password>

# For v2_endpoint:

# For more hosts you can add more entry with endpoint2, endpoint3,
etc

endpoint1:
# Name or IP address of the remote SNMP host.
  host_ip: <Receiving machine ip>
  community: <community name>
```

3. Restart the `tendr1-notifier` service:

```
systemctl restart tendr1-notifier
```

